
ETSITS 129 002 V6.17.0 (2010-07)

Technical Specification

Digital cellular telecommunications system (Phase 2+); Universal Mobile Telecommunications System (UMTS); Mobile Application Part (MAP) specification (3GPP TS 29.002 version 6.17.0 Release 6)



Reference RTS/TSGC-0429002v6h0 Keywords GSM, UMTS

ETSI

650 Route des Lucioles F-06921 Sophia Antipolis Cedex - FRANCE

Tel.: +33 4 92 94 42 00 Fax: +33 4 93 65 47 16

Siret N° 348 623 562 00017 - NAF 742 C Association à but non lucratif enregistrée à la Sous-Préfecture de Grasse (06) N° 7803/88

Important notice

Individual copies of the present document can be downloaded from: <u>http://www.etsi.org</u>

The present document may be made available in more than one electronic version or in print. In any case of existing or perceived difference in contents between such versions, the reference version is the Portable Document Format (PDF). In case of dispute, the reference shall be the printing on ETSI printers of the PDF version kept on a specific network drive within ETSI Secretariat.

Users of the present document should be aware that the document may be subject to revision or change of status.

Information on the current status of this and other ETSI documents is available at

http://portal.etsi.org/tb/status/status.asp

If you find errors in the present document, please send your comment to one of the following services: http://portal.etsi.org/chaircor/ETSI_support.asp

Copyright Notification

No part may be reproduced except as authorized by written permission. The copyright and the foregoing restriction extend to reproduction in all media.

© European Telecommunications Standards Institute 2010. All rights reserved.

DECTTM, **PLUGTESTS**TM, **UMTS**TM, **TIPHON**TM, the TIPHON logo and the ETSI logo are Trade Marks of ETSI registered for the benefit of its Members.

3GPP[™] is a Trade Mark of ETSI registered for the benefit of its Members and of the 3GPP Organizational Partners. **LTE**[™] is a Trade Mark of ETSI currently being registered

for the benefit of its Members and of the 3GPP Organizational Partners.

GSM® and the GSM logo are Trade Marks registered and owned by the GSM Association.

Intellectual Property Rights

IPRs essential or potentially essential to the present document may have been declared to ETSI. The information pertaining to these essential IPRs, if any, is publicly available for **ETSI members and non-members**, and can be found in ETSI SR 000 314: "Intellectual Property Rights (IPRs); Essential, or potentially Essential, IPRs notified to ETSI in respect of ETSI standards", which is available from the ETSI Secretariat. Latest updates are available on the ETSI Web server (http://webapp.etsi.org/IPR/home.asp).

Pursuant to the ETSI IPR Policy, no investigation, including IPR searches, has been carried out by ETSI. No guarantee can be given as to the existence of other IPRs not referenced in ETSI SR 000 314 (or the updates on the ETSI Web server) which are, or may be, or may become, essential to the present document.

Foreword

This Technical Specification (TS) has been produced by ETSI 3rd Generation Partnership Project (3GPP).

The present document may refer to technical specifications or reports using their 3GPP identities, UMTS identities or GSM identities. These should be interpreted as being references to the corresponding ETSI deliverables.

The cross reference between GSM, UMTS, 3GPP and ETSI identities can be found under http://webapp.etsi.org/key/queryform.asp.

Contents

Intelle	ctual Property Rights	2
Forew	ord	2
Forew	ord	26
1	Scope	27
2	References	27
3	Abbreviations	32
4	Void	33
	Overload and compatibility overview	
5.1	Overload control	
5.1.1	Overload control for MSC (outside MAP)	
5.1.2	Overload control for MAP entities	
5.1.3	Congestion control for Signalling System No. 7	
5.2	Compatibility	
5.2.1	General	
5.2.2	Strategy for selecting the Application Context (AC) version	
5.2.2.1	Proposed method	
5.2.2.1		
5.2.2.3		
	•	
6	Requirements concerning the use of SCCP and TC	39
6.1	Use of SCCP	39
6.1.1	SCCP Class	39
6.1.2	Sub-System Number (SSN)	39
6.1.3	SCCP addressing	
6.1.3.1	Introduction	40
6.1.3.2	The Mobile-services Switching Centre (MSC)	42
6.1.3.2	· · · · · · · · · · · · · · · · · · ·	
6.1.3.2		
6.1.3.2	The state of the s	
6.1.3.2		
6.1.3.3		
6.1.3.3		
6.1.3.3		
6.1.3.3		
6.1.3.3	1 0 1	
6.1.3.3		
6.1.3.3		
6.1.3.3		
6.1.3.3		
6.1.3.4		
6.1.3.4		
6.1.3.4		
6.1.3.5	1	
6.1.3.6		
6.1.3.7		
6.1.3.8		
6.1.3.9		
6.1.3.1		
6.1.3.1	· · · · · · · · · · · · · · · · · · ·	
6.1.3.1		
6.1.3.1		
6.1.3.1		
6.1.3.1		
0.1.5.1	1 Summary table	40

6.2	Use of TC	49
7 (General on MAP services	49
7.1	Terminology and definitions	
7.2	Modelling principles	
7.3	Common MAP services	
7.3.1	MAP-OPEN service	51
7.3.2	MAP-CLOSE service	54
7.3.3	MAP-DELIMITER service	54
7.3.4	MAP-U-ABORT service	
7.3.5	MAP-P-ABORT service	
7.3.6	MAP-NOTICE service	56
7.3.7	void	57
7.3.8	void	57
7.3.9	void	57
7.3.10	void	57
7.4	Sequencing of services	57
7.5	General rules for mapping of services onto TC	58
7.5.1	Mapping of common services	
7.5.2	Mapping of user specific services	59
7.6	Definition of parameters	
7.6.1	Common parameters	
7.6.1.1	Invoke Id	
7.6.1.2	Linked Id	
7.6.1.3	Provider error	
7.6.1.4	User error	
7.6.2	Numbering and identification parameters	
7.6.2.1	IMSI	
7.6.2.2	TMSI	
7.6.2.3	IMEI	
7.6.2.3a		
7.6.2.4	Previous location area Id	
7.6.2.5	Stored location area Id	
7.6.2.6	Current location area Id	
7.6.2.7	Target location area Id	
7.6.2.8	Target cell Id A Target RNC Id	
7.6.2.8 <i>F</i> 7.6.2.9	Void	
7.6.2.9 7.6.2.10		
7.6.2.10		
7.6.2.11		
7.6.2.13		
7.6.2.14		
7.6.2.15		
7.6.2.16		
7.6.2.17		
7.6.2.18		
7.6.2.19		
7.6.2.19	C	
7.6.2.20		
7.6.2.21	Handover number	65
7.6.2.22	2 Forwarded-to number	66
7.6.2.22	E	
7.6.2.22	E 11	66
7.6.2.23		66
7.6.2.24		
7.6.2.25		
7.6.2.26	č ,	
7.6.2.27		
7.6.2.28		
7.6.2.29		
7 6 2 30	Location Information	66

7.6.2.30a	Location Information for GPRS	66
7.6.2.31	GMSC Address	66
7.6.2.32	VMSC Address	67
7.6.2.33	Group Id	
7.6.2.34	North American Equal Access preferred Carrier Id	67
7.6.2.35	Void	67
7.6.2.36	Void	67
7.6.2.37	Serving cell Id	67
7.6.2.38	SGSN number	67
7.6.2.39	SGSN address	67
7.6.2.40	GGSN address	67
7.6.2.41	GGSN number	67
7.6.2.42	APN	
7.6.2.43	Network Node number	67
7.6.2.44	PDP-Type	67
7.6.2.45	PDP-Address	68
7.6.2.46	Additional number	68
7.6.2.47	P-TMSI	68
7.6.2.48	B-subscriber number	68
7.6.2.49	B-subscriber subaddress	68
7.6.2.50	LMU Number	68
7.6.2.51	MLC Number	
7.6.2.52	Multicall Bearer Information	68
7.6.2.53	Multiple Bearer Requested	
7.6.2.54	Multiple Bearer Not Supported	
7.6.2.55	PDP-Charging Characteristics	68
7.6.2.56	Selected RAB ID	
7.6.2.57	RAB ID	68
7.6.2.58	gsmSCF Address	68
7.6.2.59	V-GMLC Address	69
7.6.2.60	Void	
7.6.2.61	H-GMLC Address	
7.6.2.62	PPR Address	
7.6.2.63	Routeing Number	
7.6.2.64	Additional V-GMLC Address	
7.6.3	Subscriber management parameters	
7.6.3.1	Category	
7.6.3.2	Equipment status	
7.6.3.2a	BMUEF	
7.6.3.3	Extensible Bearer service	
7.6.3.4	Extensible Teleservice	
7.6.3.5	Extensible Basic Service Group	
7.6.3.6	GSM bearer capability	
7.6.3.7	Subscriber Status	
7.6.3.8	CUG Outgoing Access indicator	
7.6.3.9	Operator Determined Barring General Data	
7.6.3.10	ODB HPLMN Specific Data	
7.6.3.11 7.6.3.12	Regional Subscription Data	
	Regional Subscription Response	
7.6.3.13		
7.6.3.14	Extensible SS-Info	
7.6.3.15	Extensible forwarding information	
7.6.3.16 7.6.3.17	Extensible forwarding feature	
7.6.3.17 7.6.3.18	Extensible Forwarding Options	
7.6.3.18 7.6.3.19	Extensible No reply condition timer	
7.6.3.19	Extensible No reply condition timer Extensible Call barring information	
7.6.3.20 7.6.3.21	Extensible Call barring information	
7.6.3.21	CUG info	
7.6.3.23	CUG subscription	
7.6.3.24	CUG interlock	
7.0.3.24	CUG index	7/

7.6.3.26	CUG feature	
7.6.3.27	Inter CUG options	
7.6.3.28	Intra CUG restrictions	
7.6.3.29	Extensible SS-Data	
7.6.3.30	Subscriber State	
7.6.3.31	Requested Info	
7.6.3.31A	Requested Domain	
7.6.3.32	Suppression of Announcement	
7.6.3.33	Suppress T-CSI	
7.6.3.34	GMSC CAMEL Subscription Info	
7.6.3.35	VLR CAMEL Subscription Info	
7.6.3.36	Supported CAMEL Phases in the VLR	
7.6.3.36A	Supported CAMEL Phases in the SGSN	
7.6.3.36B	Offered CAMEL4 CSIs in the VLR	
7.6.3.36C 7.6.3.36D	Offered CAMEL4 CSIs in the SGSN	
7.6.3.36E	Offered CAMEL4 CSIs	
7.6.3.36E	Offered CAMEL4 CSIs in Interrogating node Offered CAMEL4 CSIs in VMSC	
7.6.3.36G	Offered CAMEL4 CSIS III VIMSC Offered CAMEL4 Functionalities	
7.6.3.36H	Supported CAMEL Phases	
7.6.3.36I	Supported CAMEL Phases in interrogating node	
7.6.3.37	CUG Subscription Flag	
7.6.3.38	CAMEL Subscription Info Withdraw	
7.6.3.39	Voice Group Call Service (VGCS) Data	
7.6.3.40	Voice Broadcast Service (VBS) Data	
7.6.3.41	ISDN bearer capability	
7.6.3.42	Lower layer Compatibility	
7.6.3.43	High Layer Compatibility	
7.6.3.44	Alerting Pattern	
7.6.3.45	GPRS Subscription Data Withdraw	77
7.6.3.46	GPRS Subscription Data	77
7.6.3.47	QoS-Subscribed	77
7.6.3.48	VPLMN address allowed	
7.6.3.49	Roaming Restricted In SGSN Due To Unsupported Feature	
7.6.3.50	Network Access Mode	
7.6.3.51	Mobile Not Reachable Reason	
7.6.3.52	Cancellation Type	
7.6.3.53	All GPRS Data	
7.6.3.54	Complete Data List Included	
7.6.3.55 7.6.3.56	LSA Information	
7.6.3.57	SoLSA support indicator	
7.6.3.58	LSA Information Withdraw	
7.6.3.59	LMU Indicator	
7.6.3.60	LCS Information	
7.6.3.61	GMLC List	
7.6.3.62	LCS Privacy Exception List	
7.6.3.62A	Additional LCS Privacy Exception List	
7.6.3.63	LCS Privacy Exception Parameters	
7.6.3.64	External Client List	
7.6.3.65	Internal Client List	79
7.6.3.65A	MO-LR List	80
7.6.3.65B	Privacy Notification to MS User	
7.6.3.65C	GMLC List Withdraw	
7.6.3.65D	Service Type List	
7.6.3.66	IST Alert Timer	
7.6.3.67	Call Termination Indicator	
7.6.3.68	IST Information Withdraw	
7.6.3.69	IST Support Indicator	
7.6.3.70	Super-Charger Supported In HLR.	
7.6.3.71 7.6.3.72	Super-Charger Supported In Serving Network Entity	
1.0.3.14	Age illuleaul	

7.6.3.73	GPRS enhancements support indicator	
7.6.3.74	Extension QoS-Subscribed	
7.6.3.75	SGSN CAMEL Subscription Info	
7.6.3.75A	Extension-2 QoS-Subscribed	
7.6.3.76	MO-SMS-CSI	
7.6.3.76a	MT-SMS-CSI	
7.6.3.77	GPRS-CSI	
7.6.3.78	CAMEL subscription info	
7.6.3.83	Call Barring Data	
7.6.3.84	Call Forwarding Data	
7.6.3.85	ODB Data	
7.6.3.86	Requested Subscription Info	
7.6.3.87	CS Allocation/Retention priority	
7.6.3.88	ODB Info	
7.6.3.89 7.6.3.90	Suppress VT-CSI	
7.6.3.90	gsmSCF Initiated Call	
7.6.3.91	Call barring support indicator	
7.6.3.93	MNP Info Result	
7.6.3.94	Allowed Services	
7.6.3.95	Unavailability Cause	
7.6.3.96	MNP Requested Info	
7.6.3.97	Access Restriction Data	
	pplementary services parameters	
7.6.4.1	SS-Code	
7.6.4.1A	SS-Code 2	
7.6.4.2	SS-Status	
7.6.4.3	SS-Data	84
7.6.4.4	Override Category	84
7.6.4.5	CLI Restriction Option	84
7.6.4.6	Forwarding Options	85
7.6.4.7	No reply condition timer	
	- Void	
7.6.4.15	Forwarding information	
7.6.4.16	Forwarding feature	
7.6.4.17	Void	
7.6.4.18	Call barring information	
7.6.4.19	Call barring feature	
7.6.4.20 7.6.4.21	New password	
7.6.4.21 7.6.4.22	Current password	
7.6.4.23	Void	
7.6.4.24	SS-Info	
	55-mo	
7.6.4.36	USSD Data Coding Scheme	
7.6.4.37	USSD String	
7.6.4.38	Bearer service	
7,6,4.38A	Bearer Service 2	
7.6.4.39	Teleservice	
7.6.4.39A	Teleservice 2	87
7.6.4.40	Basic Service Group	87
7.6.4.41	eMLPP information	87
7.6.4.42	SS-event	88
7.6.4.43	SS-event data	
7.6.4.44	LCS Privacy Exceptions	
7.6.4.45	Mobile Originating Location Request (MO-LR)	
7.6.4.46	NbrUser	
7.6.4.47	MC Subscription Data	
7.6.4.48	MC Information	
7.6.4.49	CCBS Request State	
7.6.4.50	Basic Service Group 2	
7.6.5 Ca	ll parameters	85

Call reference number	
Interrogation type	89
OR interrogation	89
OR capability	89
Forwarding reason	
Forwarding interrogation required	90
O-CSI	90
D-CSI	90
T-CSI	90
VT-CSI	90
O-IM-CSI	90
D-IM-CSI	90
VT-IM-CSI	90
Void	91
Number Portability Status	91
· · · · · · · · · · · · · · · · · · ·	
1 0 0 11	
Encryption Information	97
Encryption Information	
Radio Resource Information	92
Radio Resource Information	92 92
Radio Resource Information	
Radio Resource Information Radio Resource List Chosen Radio Resource Information Key Status	
Radio Resource Information Radio Resource List Chosen Radio Resource Information Key Status Selected UMTS Algorithms	92 92 92 92 92 92
Radio Resource Information Radio Resource List Chosen Radio Resource Information Key Status Selected UMTS Algorithms Allowed GSM Algorithms	92 92 92 92 92 92
Radio Resource Information Radio Resource List Chosen Radio Resource Information Key Status Selected UMTS Algorithms Allowed GSM Algorithms Allowed UMTS Algorithms	92 92 92 92 92 92 92
Radio Resource Information Radio Resource List Chosen Radio Resource Information Key Status Selected UMTS Algorithms Allowed GSM Algorithms Allowed UMTS Algorithms Selected GSM Algorithms	92 92 92 92 92 92 92 92
Radio Resource Information Radio Resource List Chosen Radio Resource Information Key Status Selected UMTS Algorithms Allowed GSM Algorithms Allowed UMTS Algorithms Selected GSM Algorithm Iu-Currently Used Codec	92 92 92 92 92 92 92 92
Radio Resource Information Radio Resource List Chosen Radio Resource Information Key Status Selected UMTS Algorithms Allowed GSM Algorithms Allowed UMTS Algorithms Selected GSM Algorithm Iu-Currently Used Codec Iu-Supported Codecs List	92 92 92 92 92 92 92 92 92 92
Radio Resource Information Radio Resource List Chosen Radio Resource Information Key Status Selected UMTS Algorithms Allowed GSM Algorithms Allowed UMTS Algorithms Selected GSM Algorithm Iu-Currently Used Codec Iu-Supported Codecs List Iu-Available Codecs List	92 92 92 92 92 92 92 92 92 92
Radio Resource Information Radio Resource List Chosen Radio Resource Information Key Status Selected UMTS Algorithms Allowed GSM Algorithms Allowed UMTS Algorithms Selected GSM Algorithm Iu-Currently Used Codec Iu-Supported Codecs List Iu-Available Codecs List Iu-Selected Codec	92 92 92 92 92 92 92 92 93 93
Radio Resource Information Radio Resource List Chosen Radio Resource Information Key Status Selected UMTS Algorithms Allowed GSM Algorithms Allowed UMTS Algorithms Selected GSM Algorithm Iu-Currently Used Codec Iu-Supported Codecs List Iu-Available Codecs List Iu-Selected Codec RAB Configuration Indicator	92 92 92 92 92 92 92 92 92 92 92 92 92 9
Radio Resource Information Radio Resource List Chosen Radio Resource Information Key Status Selected UMTS Algorithms Allowed GSM Algorithms Allowed UMTS Algorithms Selected GSM Algorithm Iu-Currently Used Codec Iu-Supported Codecs List Iu-Available Codecs List Iu-Selected Codec RAB Configuration Indicator UESBI-Iu	92 92 92 92 92 92 92 92 92 92 92 92 92 9
Radio Resource Information Radio Resource List Chosen Radio Resource Information Key Status Selected UMTS Algorithms Allowed GSM Algorithms Allowed UMTS Algorithms Selected GSM Algorithm Iu-Currently Used Codec Iu-Supported Codecs List Iu-Available Codecs List Iu-Selected Codec RAB Configuration Indicator UESBI-Iu Alternative Channel Type	92 92 92 92 92 92 92 92 92 92 92 92 92 9
Radio Resource Information Radio Resource List Chosen Radio Resource Information Key Status Selected UMTS Algorithms Allowed GSM Algorithms Allowed UMTS Algorithms Selected GSM Algorithm Iu-Currently Used Codec Iu-Supported Codecs List Iu-Available Codecs List Iu-Selected Codec RAB Configuration Indicator UESBI-Iu Alternative Channel Type Authentication parameters	92 92 92 92 92 92 92 92 92 92 92 92 92 9
Radio Resource Information Radio Resource List Chosen Radio Resource Information Key Status Selected UMTS Algorithms Allowed GSM Algorithms Allowed UMTS Algorithms Selected GSM Algorithm Iu-Currently Used Codec Iu-Supported Codecs List Iu-Available Codecs List Iu-Available Codecs List Iu-Selected Codec RAB Configuration Indicator UESBI-Iu Alternative Channel Type Authentication parameters Authentication set list	92 92 92 92 92 92 92 92 92 92 92 92 92 9
Radio Resource Information Radio Resource List Chosen Radio Resource Information Key Status Selected UMTS Algorithms Allowed GSM Algorithms Allowed UMTS Algorithms Selected GSM Algorithm Iu-Currently Used Codec Iu-Supported Codecs List Iu-Available Codecs List Iu-Available Codecs List Iu-Selected Codec RAB Configuration Indicator UESBI-Iu Alternative Channel Type Authentication parameters Authentication set list Rand	92 92 92 92 92 92 92 92 92 92 92 92 92 9
Radio Resource Information Radio Resource List Chosen Radio Resource Information Key Status Selected UMTS Algorithms Allowed GSM Algorithms Allowed UMTS Algorithms Selected GSM Algorithm Iu-Currently Used Codec Iu-Supported Codecs List Iu-Available Codecs List Iu-Available Codecs List Iu-Selected Codec RAB Configuration Indicator UESBI-Iu Alternative Channel Type Authentication parameters Authentication set list Rand Sres	92 92 92 92 92 92 92 92 92 92 92 92 92 9
Radio Resource Information Radio Resource List Chosen Radio Resource Information Key Status Selected UMTS Algorithms Allowed GSM Algorithms Allowed UMTS Algorithms Selected GSM Algorithm Iu-Currently Used Codec Iu-Supported Codecs List Iu-Available Codecs List Iu-Available Codecs List Iu-Selected Codec RAB Configuration Indicator UESBI-Iu Alternative Channel Type Authentication parameters Authentication set list Rand Sres Kc	92 92 92 92 92 92 92 92 92 92 92 92 92 9
Radio Resource Information Radio Resource List Chosen Radio Resource Information Key Status Selected UMTS Algorithms Allowed GSM Algorithms Allowed UMTS Algorithms Selected GSM Algorithm Iu-Currently Used Codec Iu-Supported Codecs List Iu-Available Codecs List Iu-Available Codecs List Iu-Selected Codec RAB Configuration Indicator UESBI-Iu Alternative Channel Type Authentication parameters Authentication set list Rand Sres Kc Xres	92 92 92 92 92 92 92 92 92 92 92 92 92 9
Radio Resource Information Radio Resource List Chosen Radio Resource Information Key Status Selected UMTS Algorithms Allowed GSM Algorithms Allowed UMTS Algorithms Selected GSM Algorithm Iu-Currently Used Codec Iu-Supported Codecs List Iu-Available Codecs List Iu-Selected Codec RAB Configuration Indicator UESBI-Iu Alternative Channel Type Authentication parameters Authentication set list Rand Sres Kc Xres Ck	92 92 92 92 92 92 92 92 92 92 92 92 92 9
Radio Resource Information Radio Resource List Chosen Radio Resource Information Key Status Selected UMTS Algorithms Allowed GSM Algorithms Allowed UMTS Algorithms Selected GSM Algorithm Iu-Currently Used Codec Iu-Supported Codecs List Iu-Available Codecs List Iu-Selected Codec RAB Configuration Indicator UESBI-Iu Alternative Channel Type Authentication parameters Authentication set list Rand Sres Kc Xres Ck Ik	92 92 92 92 92 92 92 92 92 92 92 92 92 9
Radio Resource Information Radio Resource List Chosen Radio Resource Information Key Status Selected UMTS Algorithms Allowed GSM Algorithms Allowed UMTS Algorithms Selected GSM Algorithm Iu-Currently Used Codec Iu-Supported Codecs List Iu-Available Codecs List Iu-Available Codecs List Iu-Selected Codec RAB Configuration Indicator UESBI-Iu Alternative Channel Type Authentication parameters Authentication set list Rand Sres Kc Xres Ck Ik Autn	92 92 92 92 92 92 92 92 92 92 92 92 92 9
Radio Resource Information Radio Resource List Chosen Radio Resource Information Key Status Selected UMTS Algorithms Allowed GSM Algorithms Allowed UMTS Algorithms Selected GSM Algorithm Iu-Currently Used Codec Iu-Supported Codecs List Iu-Available Codecs List Iu-Available Codec RAB Configuration Indicator UESBI-Iu Alternative Channel Type Authentication parameters Authentication set list Rand Sres Kc Xres Ck Ik Autn Cksn	92 92 92 92 92 92 92 92 92 92 92 92 92 9
Radio Resource List Chosen Radio Resource Information Key Status Selected UMTS Algorithms Allowed GSM Algorithms Allowed UMTS Algorithms Selected GSM Algorithms Iu-Currently Used Codec Iu-Supported Codecs List Iu-Available Codecs List Iu-Available Codec List Iu-Selected Codec RAB Configuration Indicator UESBI-Iu Alternative Channel Type Authentication parameters Authentication set list Rand Sres Kc Xres Ck Ik Autn. Cksn Ksi	92 92 92 92 92 92 92 92 92 92 92 92 92 9
Radio Resource List Chosen Radio Resource Information Key Status Selected UMTS Algorithms Allowed GSM Algorithms Allowed UMTS Algorithms Selected GSM Algorithms Iu-Currently Used Codec Iu-Supported Codecs List Iu-Available Codecs List Iu-Selected Codec RAB Configuration Indicator UESBI-Iu Alternative Channel Type Authentication parameters Authentication set list Rand Sres Kc Xres Ck Ik Autn Cksn Ksi Auts	92 92 92 92 92 92 92 92 92 92 92 92 92 9
Radio Resource Information Radio Resource List Chosen Radio Resource Information Key Status Selected UMTS Algorithms Allowed GSM Algorithms Allowed UMTS Algorithms Selected GSM Algorithm Iu-Currently Used Codec Iu-Supported Codecs List Iu-Available Codecs List Iu-Available Codecs List Iu-Selected Codec RAB Configuration Indicator UESBI-Iu Alternative Channel Type Authentication parameters Authentication set list Rand Sres Kc Xres Ck Ik Autn Cksn Ksi Auts Ciphering mode	92 92 92 92 92 92 92 92 92 92 92 92 92 9
Radio Resource Information Radio Resource List Chosen Radio Resource Information Key Status Selected UMTS Algorithms Allowed GSM Algorithms Allowed UMTS Algorithms Selected GSM Algorithm Iu-Currently Used Codec Iu-Supported Codecs List Iu-Available Codecs List Iu-Available Codecs List Iu-Selected Codec RAB Configuration Indicator UESBI-Iu Alternative Channel Type Authentication parameters Authentication set list Rand Sres Kc Xres Ck Ik Autn Cksn Ksi Auts Ciphering mode Current Security Context	92 92 92 92 92 92 92 92 92 92 92 92 92 9
Radio Resource List	92 92 92 92 92 92 92 92 92 92 92 93 93 93 93 93 93 93 94 94 94
Radio Resource Information Radio Resource List Chosen Radio Resource Information Key Status Selected UMTS Algorithms Allowed GSM Algorithms Allowed UMTS Algorithms Selected GSM Algorithm Iu-Currently Used Codec Iu-Supported Codecs List Iu-Available Codecs List Iu-Available Codecs List Iu-Selected Codec RAB Configuration Indicator UESBI-Iu Alternative Channel Type Authentication parameters Authentication set list Rand Sres Kc Xres Ck Ik Autn Cksn Ksi Auts Ciphering mode Current Security Context	92 92 92 92 92 92 92 92 92 92 92 92 93 93 93 93 93 93 93 94 94 94 94
	Interrogation type OR interrogation OR capability Forwarding reason. Forwarding interrogation required O-CSI D-CSI T-CSI VT-CSI O-IM-CSI D-IM-CSI VT-IM-CSI Void Void Void Void CCBS Feature UU Data Number Portability Status Pre-paging supported Radio parameters 6.3 Void. GERAN Classmark BSSMAP Service Handover BSSMAP Service Handover HO-Number Not Required Integrity Protection Information

7.6.8.1	SM-RP-DA	
7.6.8.2	SM-RP-OA	
7.6.8.3	MWD status	
7.6.8.4	SM-RP-UI	
7.6.8.5	SM-RP-PRI	95
7.6.8.6	SM Delivery Outcome	
7.6.8.7	More Messages To Send	95
7.6.8.8	Alert Reason	
7.6.8.9	Absent Subscriber Diagnostic SM	96
7.6.8.10	Alert Reason Indicator	96
7.6.8.11	Additional SM Delivery Outcome	96
7.6.8.12	Additional Absent Subscriber Diagnostic SM	96
7.6.8.13	Delivery Outcome Indicator	
7.6.8.14	GPRS Node Indicator	
7.6.8.15	GPRS Support Indicator	
7.6.8.16	SM-RP-MTI	
7.6.8.17	SM-RP-SMEA	
7.6.9	Access and signalling system related parameters	
7.6.9.1	AN-apdu	
7.6.9.2	CM service type	
7.6.9.3	Access connection status	
7.6.9.4	External Signal Information	
7.6.9.5	Access signalling information	
7.6.9.6	Location update type	
7.6.9.7	Protocol ID	
7.6.9.7 7.6.9.8	Network signal information	
	Network signal information 2	
7.6.9.8A	<u> </u>	
7.6.9.9	Call Info	
7.6.9.10	Additional signal info	
7.6.10	System operations parameters	
7.6.10.1	Network resources	
7.6.10.2	Trace reference	
7.6.10.2A	Trace reference 2	
7.6.10.3	Trace type	
7.6.10.4	Additional network resources	
7.6.10.5	Trace depth list	
7.6.10.6	Trace NE type list	
7.6.10.7	Trace interface list	
7.6.10.8	Trace event list	
7.6.10.9	Trace support indicator	
7.6.10.10	Trace Propagation List	
7.6.11	Location Service Parameters	
7.6.11.1	Age of Location Estimate	
7.6.11.2	Deferred MT-LR Response Indicator	
7.6.11.3	Deferred MT-LR Data	100
7.6.11.4	LCS Client ID	
7.6.11.5	LCS Event	101
7.6.11.7	LCS Priority	101
7.6.11.8	LCS QoS	
7.6.11.9	CS LCS Not Supported by UE	101
7.6.11.10	PS LCS Not Supported by UE	101
7.6.11.11	Location Estimate	101
7.6.11.11A	GERAN Positioning Data	
7.6.11.11B	UTRAN Positioning Data	102
7.6.11.12	Location Type	
7.6.11.13	NA-ESRD	
7.6.11.14	NA-ESRK	
7.6.11.15	LCS Service Type Id	
7.6.11.16	Privacy Override	
7.6.11.17	Supported LCS Capability Sets	
7.6.11.18	LCS Codeword	
7.6.11.10	NA_FSRK Request	102

7.6.11.20	Supported GAD Shapes	103
7.6.11.21	Additional Location Estimate	
7.6.11.22	Cell Id Or SAI	103
7.6.11.23	LCS-Reference Number	103
7.6.11.24	LCS Privacy Check	
7.6.11.25	Additional LCS Capability Sets	
7.6.11.26	Area Event Info	
7.6.11.27	Accuracy Fulfilment Indicator	
7.6.12	void	
7.7	Representation of a list of a basic parameter in service-primitives	
0 14	•	
	bility services	
8.1	Location management services	
8.1.1	Void	
8.1.1.1	Void	
8.1.1.2	Void	
8.1.1.3	Void	
8.1.2	MAP_UPDATE_LOCATION service	
8.1.2.1	Definition	
8.1.2.2	Service primitives	
8.1.2.3	Parameter definitions and use	
8.1.3	MAP_CANCEL_LOCATION service	
8.1.3.1	Definition	
8.1.3.2	Service primitives	
8.1.3.3	Parameter definitions and use	
8.1.4	MAP_SEND_IDENTIFICATION service	
8.1.4.1	Definition	
8.1.4.2	Service primitives	
8.1.4.3	Parameter definitions and use	
8.1.5	Void	109
8.1.5.1	Void	
8.1.5.2	Void	
8.1.5.3	Void	
8.1.6	MAP_PURGE_MS service	
8.1.6.1	Definition	
8.1.6.2	Service primitives	
8.1.6.3	Parameter definitions and use	
8.1.7	MAP_UPDATE_GPRS_LOCATION service	
8.1.7.1	Definition	
8.1.7.2	Service primitives	
8.1.7.3	Parameter definitions and use	111
8.1.8	MAP-NOTE-MM-EVENT	113
8.1.8.1	Definition	113
8.1.8.2	Service primitives	113
8.1.8.3	Parameter use	114
8.2	Paging and search	115
8.2.1	MAP_PAGE service	115
8.2.1.1	Definition	115
8.2.1.2	Service primitives	115
8.2.1.3	Parameter definitions and use	115
8.2.2	MAP_SEARCH_FOR_MS service	116
8.2.2.1	Definition	116
8.2.2.2	Service primitives	116
8.2.2.3	Parameter definitions and use	116
8.3	Access management services	
8.3.1	MAP_PROCESS_ACCESS_REQUEST service	
8.3.1.1	Definition	
8.3.1.2	Service primitives	
8.3.1.3	Parameter definitions and use	
8.4	Handover services	118
8.4.1	MAP_PREPARE_HANDOVER service	118
8.4.1.1	Definition	118

8.4.1.2	Service primitives	119
8.4.1.3	Parameter use	119
8.4.2	MAP_SEND_END_SIGNAL service	123
8.4.2.1	Definition	123
8.4.2.2	Service primitives	123
8.4.2.3	Parameter use	123
8.4.3	MAP_PROCESS_ACCESS_SIGNALLING service	123
8.4.3.1	Definition	123
8.4.3.2	Service primitives	
8.4.3.3	Parameter use	
8.4.4	MAP_FORWARD_ACCESS_SIGNALLING service	
8.4.4.1	Definition	
8.4.4.2	Service primitives	
8.4.4.3	Parameter use	
8.4.5	MAP_PREPARE_SUBSEQUENT_HANDOVER service	
8.4.5.1	Definition	
8.4.5.2	Service primitives	
8.4.5.3	Parameter use	
8.4.6	MAP_ALLOCATE_HANDOVER_NUMBER service	
8.4.6.1	Definition	
8.4.6.2	Service primitives	
8.4.6.3	Parameter use	
8.4.7	MAP_SEND_HANDOVER_REPORT service	
8.4.7.1	Definition	
8.4.7.2	Service primitives	
8.4.7.3	Parameter use	
8.5	Authentication management services	
8.5.1	MAP_AUTHENTICATE service	
8.5.1.1	Definition	
8.5.1.2	Service primitives	
8.5.1.3	Parameter use	
8.5.2 8.5.2.1	MAP_SEND_AUTHENTICATION_INFO service	
8.5.2.1	Definition	
8.5.2.3	Parameter use	
8.5.3	MAP_AUTHENTICATION_FAILURE_REPORT service	
8.5.3.1	Definition	
8.5.3.2	Service primitives	
8.5.3.3	Parameter use	
8.6	Security management services	
8.6.1	MAP_SET_CIPHERING_MODE service	
8.6.1.1	Definitions	
8.6.1.2	Service primitives	
8.6.1.3	Parameter use	
8.7	International mobile equipment identities management services	
8.7.1	MAP_CHECK_IMEI service	
8.7.1.1	Definition	
8.7.1.2	Service primitives	
8.7.1.3	Parameter use	
8.7.2	MAP_OBTAIN_IMEI service	
8.7.2.1	Definition	135
8.7.2.2	Service primitives	135
8.7.2.3	Parameter use	
8.8	Subscriber management services	
8.8.1	MAP-INSERT-SUBSCRIBER-DATA service	136
8.8.1.1	Definition	
8.8.1.2	Service primitives	
8.8.1.3	Parameter use	
8.8.1.4	Basic service information related to supplementary services	
8.8.2	MAP-DELETE-SUBSCRIBER-DATA service	
8.8.2.1	Definition	
8822	Service primitives	147

8.8.2.3	Parameter use	
8.9	Identity management services	150
8.9.1	MAP-PROVIDE-IMSI service	150
8.9.1.1	Definition	150
8.9.1.2	Service primitives	150
8.9.1.3	Parameter use	151
8.9.2	MAP-FORWARD-NEW-TMSI service	
8.9.2.1	Definition	
8.9.2.2	Service primitives	
8.9.2.3	Parameter use	
8.10	Fault recovery services	
8.10.1	MAP RESET service	
8.10.1.1	Definition	
8.10.1.2	Service primitives	
8.10.1.2	Parameter definition and use	
8.10.1.3	MAP_FORWARD_CHECK_SS_INDICATION service	
8.10.2.1	Definition	
8.10.2.2	Service primitives	
8.10.2.3	Parameter definition and use	
8.10.3	MAP_RESTORE_DATA service	
8.10.3.1	Definition	
8.10.3.2	Service primitives	
8.10.3.3	Parameter definitions and use	
8.11	Subscriber Information services	
8.11.1	MAP-ANY-TIME-INTERROGATION service	
8.11.1.1	Definition	154
8.11.1.2	Service primitives	155
8.11.1.3	Parameter definition and use	155
8.11.2	MAP-PROVIDE-SUBSCRIBER-INFO service	
8.11.2.1	Definition	155
8.11.2.2	Service primitives	
8.11.2.3	Parameter definition and use	
8.11.3	MAP-ANY-TIME-SUBSCRIPTION-INTERROGATION service	
8.11.3.1	Definition	
8.11.3.2	Service primitives	
8.11.3.3	Parameter definition and use	
8.11.3.3	MAP-ANY-TIME-MODIFICATION service	
8.11.4.1	Definition	
8.11.4.2	Service primitives	
8.11.4.3	Parameter definition and use	
8.11.5	MAP-NOTE-SUBSCRIBER-DATA-MODIFIED service	
8.11.5.1	Definition	
8.11.5.2	Service primitives	
8.11.5.3	Parameter definition and use	159
9 O	peration and maintenance services	160
9 0 9.1		
	Subscriber tracing services	
9.1.1	MAP-ACTIVATE-TRACE-MODE service	
9.1.1.1	Definition	
9.1.1.2	Service primitives	
9.1.1.3	Parameter use	
9.1.2	MAP-DEACTIVATE-TRACE-MODE service	
9.1.2.1	Definition	
9.1.2.2	Service primitives	162
9.1.2.3	Parameter use	
9.1.3	MAP-TRACE-SUBSCRIBER-ACTIVITY service	162
9.1.3.1	Definition	162
9.1.3.2	Service primitives	162
9.1.3.3	Parameter use	
9.2	Other operation and maintenance services	
9.2.1	MAP-SEND-IMSI service	
9.2.1.1	Definition	163

9.2.1.2 9.2.1.3	1	
9.2.1.3		
10	Call handling services	
10.1	MAP_SEND_ROUTING_INFORMATION service	
10.1.1		
10.1.2	r	
10.1.3		
10.2	MAP_PROVIDE_ROAMING_NUMBER service	
10.2.1		
10.2.2	T	
10.2.3 10.3		
10.3	MAP_RESUME_CALL_HANDLING service Definition	
10.3.1		
10.3.2	*	
10.3.3	MAP_PREPARE_GROUP_CALL service	
10.4.1		
10.4.1		
10.4.3	1	
10.5	MAP PROCESS GROUP CALL SIGNALLING service	
10.5.1		
10.5.2		
10.5.3	1	
10.6	MAP FORWARD GROUP CALL SIGNALLING service	
10.6.1		
10.6.2		
10.6.3	Parameter definitions and use	177
10.7	MAP_SEND_GROUP_CALL_END_SIGNAL service	178
10.7.1	Definitions	178
10.7.2	Service primitives	178
10.7.3		
10.8	Void	
10.9	Void	
10.10		
10.10.		
10.10.2	1	
10.10.3		
10.11	MAP_STATUS_REPORT service	
10.11.		
10.11.2	- F	
10.11.3		
10.12		
10.12.		
10.12.3 10.12.3	1	
10.12.3		
10.13		
10.13.		
10.13.2	1	
10.13.		
10.14		
10.14.2		
10.14.3		
10.14.		
10.15.1	-	
10.15.2		
10.15.3	1	
11	Supplementary services related services	
11.1	MAP_REGISTER_SS service	
11.1.1	Definition	

11.1.2	Service primitives	184
11.1.3	Parameter use	184
11.2	MAP_ERASE_SS service	185
11.2.1	Definition	185
11.2.2	Service primitives	185
11.2.3	Parameter use	186
11.3	MAP_ACTIVATE_SS service	186
11.3.1	Definition	186
11.3.2	Service primitives	186
11.3.3	Parameter use	187
11.4	MAP_DEACTIVATE_SS service	188
11.4.1	Definitions	
11.4.2	Service primitives	188
11.4.3	Parameter use	188
11.5	MAP_INTERROGATE_SS service	189
11.5.1	Definitions	189
11.5.2	Service primitives	
11.5.3	Parameter use	190
11.6	Void	191
11.7	MAP_REGISTER_PASSWORD service	
11.7.1	Definitions	
11.7.2	Service primitives	
11.7.3	Parameter use	
11.8	MAP_GET_PASSWORD service	
11.8.1	Definitions	
11.8.2	Service primitives	
11.8.3	Parameter use	
11.9	MAP_PROCESS_UNSTRUCTURED_SS_REQUEST service	
11.9.1	Definitions	
11.9.2	Service primitives	
11.9.3	Parameter use	
11.10	MAP_UNSTRUCTURED_SS_REQUEST service	
11.10.1		
11.10.2		
11.10.3	•	
11.11	MAP_UNSTRUCTURED_SS_NOTIFY service	
11.11.1		
11.11.2		
11.11.3	•	
11.12	MAP_SS_INVOCATION_NOTIFY	
11.12.1		
11.12.2		
11.12.3	1	
11.13	MAP REGISTER CC ENTRY service	
11.13.1		
11.13.2		
11.13.3	*	
11.14	MAP ERASE CC ENTRY service	
11.14.1		
11.14.2		
11.14.3	1	
	Short message service management services	
12.1	MAP-SEND-ROUTING-INFO-FOR-SM service	
12.1.1	Definition	
12.1.2	Service primitives	
12.1.3	Parameter use	
12.2	MAP-MO-FORWARD-SHORT-MESSAGE service	
12.2.1	Definition	
12.2.2	Service primitives	
12.2.3	Parameter use	
12.3	MAP-REPORT-SM-DELIVERY-STATUS service	203

12.3.1	Definition	203
12.3.2	Service primitives	203
12.3.3	Parameter use	203
12.4	MAP-READY-FOR-SM service	204
12.4.1	Definition	204
12.4.2	Service primitives	205
12.4.3	Parameter use	205
12.5	MAP-ALERT-SERVICE-CENTRE service	205
12.5.1	Definition	205
12.5.2	Service primitives	206
12.5.3	Parameter use	
12.6	MAP-INFORM-SERVICE-CENTRE service	206
12.6.1	Definition	206
12.6.2	Service primitives	
12.6.3	Parameter use	
12.7	MAP-SEND-INFO-FOR-MT-SMS service	
12.7.1	Definition	
12.7.2	Service primitives	
12.7.3	Parameter use	
12.8	MAP-SEND-INFO-FOR-MO-SMS service	
12.8.1	Definition	
12.8.2	Service primitives	
12.8.3	Parameter use	
12.9 12.9.1	MAP-MT-FORWARD-SHORT-MESSAGE service Definition	
12.9.1	Service primitives	
12.9.2	Parameter use	
13	Network-Requested PDP Context Activation services	
13.1	MAP_SEND_ROUTING_INFO_FOR_GPRS service	
13.1.1	Definition	
13.1.2	Service primitives	
13.1.3	Parameter definition and use	
13.2	MAP_FAILURE_REPORT service	
13.2.1	Definition	
13.2.2	Service primitives	
13.2.3	Parameter definition and use	
13.3	MAP_NOTE_MS_PRESENT_FOR_GPRS service	
13.3.1	Definition Service primitives	
13.3.2 13.3.3	Parameter definition and use	
13A	Location Service Management Services	214
13A.1	MAP-SEND-ROUTING-INFO-FOR-LCS Service	
13A.1.1		
13A.1.2		
13A.1.3		
13A.2	MAP-PROVIDE-SUBSCRIBER-LOCATION Service	
13A.2.1		
13A.2.2		
13A.2.3		
13A.3	MAP-SUBSCRIBER-LOCATION-REPORT Service	
13A.3.1 13A.3.2		
13A.3.2 13A.3.3		
13A.3.3 13A.4	Void	
13A.4.1		
13A.4.2		
13A.4.3		
13A.5	Void	
13A.5.1		
13A.5.2	2 Void	222

13A.5.3	Void	
13A.6	Void	
13A.6.1	Void	
13A.6.2	Void	
13A.6.3	Void	
13A.7	Void	
13A.7.1	Void	
13A.7.2	Void	
13A.7.3	Void	
13A.8	Void	
13A.8.1	Void	
13A.8.2	Void	
13A.8.3	Void	
13A.9	Void	
13A.9.1	Void	
13A.9.2	Void	
13A.9.3	Void	223
14 G	eneral	223
14.1	Overview	223
14.2	Underlying services	223
14.3	Model	223
14.4	Conventions	223
15 E	lements of procedure	22/
15 E.	Handling of unknown operations	
15.1	Dialogue establishment	
15.2.1	Behaviour at the initiating side	
15.2.2	Behaviour at the responding side	
15.3	Dialogue continuation	
15.4 15.5	Load control	
15.5.1	Procedures for MAP specific services	
15.5.1	void	
15.5.2	Service invocation receipt	
15.5.4	void	
15.5.5	Handling of components received from TC	
15.5.5	SDL descriptions	
	•	
16 M	Sapping on to TC services	
16.1	Dialogue control	
16.1.1	Directly mapped parameters	
16.1.2	Use of other parameters of dialogue handling primitives	
16.1.2.1	Dialogue Id	
16.1.2.2	Application-context-name	
16.1.2.3	User information	
16.1.2.4	Component present	
16.1.2.5	Termination	
16.1.2.6	P-Abort-Cause	
16.1.2.7	Quality of service	
16.2	Service specific procedures	
16.2.1	Directly mapped parameters	
16.2.2	Use of other parameters of component handling primitives	
16.2.2.1	Dialogue Id	
16.2.2.2	Class	
16.2.2.3	Linked Id	
16.2.2.4	Operation	
16.2.2.5	Error	
16.2.2.6	Parameters	
16.2.2.7	Time out	
16.2.2.8	Last component	
16.2.2.9	Problem code	
16229	1 Manning to MAP User Error	263

16.2.2.9.2	Mapping to MAP Provider Error parameter	
16.2.2.9.3	Mapping to diagnostic parameter	264
17 Abstra	ct syntax of the MAP protocol	265
	neral	
	Encoding rules	
17.1.2	Use of TC	265
17.1.2.1	Use of Global Operation and Error codes defined outside MAP	266
17.1.3	Use of information elements defined outside MAP	266
	Compatibility considerations	
17.1.5	Structure of the Abstract Syntax of MAP	
17.1.6	Application Contexts	
	eration packages	
17.2.1 17.2.2	General aspects	
17.2.2	Packages specificationsLocation updating	
17.2.2.1	Location cancellation	
17.2.2.3	Roaming number enquiry	
17.2.2.4	Information retrieval	
17.2.2.5	Inter-VLR information retrieval	
17.2.2.6	IMSI retrieval	
17.2.2.7	Call control transfer.	
17.2.2.8	void	
17.2.2.9	Void	273
17.2.2.10	Interrogation	273
17.2.2.11	Void	273
17.2.2.12	Handover Control	
17.2.2.13	Subscriber Data management stand alone	
17.2.2.14	Equipment management	
17.2.2.15	Subscriber data management	
17.2.2.16	Location register restart	
17.2.2.17	Tracing stand-alone	
17.2.2.18	Functional SS handling	
17.2.2.19	Tracing	
17.2.2.20	Binding	
17.2.2.21 17.2.2.22	Unstructured SS handling	
17.2.2.22	Short message gateway services	
17.2.2.23	MT Short message relay services	
17.2.2.24	Void	
17.2.2.26	Message waiting data management	
17.2.2.27	Alerting	
17.2.2.28	Data restoration	
17.2.2.29	Purging	
17.2.2.30	Subscriber information enquiry	
17.2.2.31	Any time information enquiry	
17.2.2.32	Group Call Control	278
17.2.2.33	Void	278
17.2.2.34	Void	278
17.2.2.35	Gprs location updating	
17.2.2.36	Gprs Interrogation	
17.2.2.37	Failure reporting	
17.2.2.38	GPRS notifying	
17.2.2.39	Supplementary Service invocation notification	
17.2.2.40	Set Reporting State	
17.2.2.41	Status Report	
17.2.2.42	Remote User Free	
17.2.2.43	Call Completion	
17.2.2.44	Location service gateway services	
17.2.2.45 17.2.2.45A	Location service enquiry Location service reporting	
17.2.2.43A 17.2.2.46	Void	281 281

17.2.2.47	Void	
17.2.2.48	Void	281
17.2.2.49	IST Alerting	281
17.2.2.50	Service Termination	281
17.2.2.51	Mobility Management event notification	281
17.2.2.53	Subscriber Data modification notification	
17.2.2.54	Authentication Failure Report	
17.2.2.55	Resource Management	
17.2.2.33	Application contexts	
17.3.1	General aspects	
17.3.2	Application context definitions	
17.3.2.1	Void	
17.3.2.2	Location Updating	
17.3.2.3	Location Cancellation	
17.3.2.4	Roaming number enquiry	
17.3.2.5	Void	
17.3.2.6	Location Information Retrieval	
17.3.2.7	Call control transfer	285
17.3.2.8	void	285
17.3.2.9 -	17.3.2.10Void	285
17.3.2.11	Location registers restart	
17.3.2.12	Handover control	
17.3.2.13	IMSI Retrieval.	
17.3.2.14	Equipment Management	
17.3.2.14	Information retrieval	
	Inter-VLR information retrieval	
17.3.2.16		
17.3.2.17	Stand Alone Subscriber Data Management	
17.3.2.18	Tracing	
17.3.2.19	Network functional SS handling	
17.3.2.20	Network unstructured SS handling	
17.3.2.21	Short Message Gateway	
17.3.2.22	Mobile originating Short Message Relay	
17.3.2.23	Void	
17.3.2.24	Short message alert	
17.3.2.25	Short message waiting data management	289
17.3.2.26	Mobile terminating Short Message Relay	289
17.3.2.27	MS purging	290
17.3.2.28	Subscriber information enquiry	
17.3.2.29	Any time information enquiry	
17.3.2.30	Group Call Control	
17.3.2.31	Void	
17.3.2.32	Gprs Location Updating	
17.3.2.32	Gprs Location Information Retreival	
17.3.2.34	Failure Reporting	
17.3.2.34	GPRS Notifying	
17.3.2.36	Supplementary Service invocation notification	
17.3.2.37	Reporting	
17.3.2.38	Call Completion	
17.3.2.39	Location Service Gateway	
17.3.2.40	Location Service Enquiry	
17.3.2.41	Void	
17.3.2.42	Void	
17.3.2.43	Void	
17.3.2.44	IST Alerting	
17.3.2.45	Service Termination	293
17.3.2.46	Mobility Management event notification	
17.3.2.48	Subscriber Data modification notification	
17.3.2.49	Authentication Failure Report	
17.3.2.50	Resource Management	
17.3.3	ASN.1 Module for application-context-names	
17.3.3	MAP Dialogue Information	
1/4		

17.6	MAP operations and errors	301	
17.6.1	Mobile Service Operations	301	
17.6.2	Operation and Maintenance Operations	308	
17.6.3			
17.6.4			
17.6.5			
17.6.6	Errors		
17.6.7	Group Call operations		
17.6.8	Location service operations		
17.6.9	void		
17.0.9	MAP constants and data types		
17.7.1	Mobile Service data types		
17.7.2	Operation and maintenance data types		
17.7.3	Call handling data types		
17.7.4	Supplementary service data types		
17.7.5	Supplementary service codes		
17.7.6	Short message data types		
17.7.7	Error data types		
17.7.8	Common data types		
17.7.9	Teleservice Codes		
17.7.10	Bearer Service Codes		
17.7.11	Extension data types		
17.7.12	Group Call data types		
17.7.13	Location service data types		
17.7.14	void	410	
18 G	eneral on MAP user procedures	410	
18.1	Introduction		
18.2	Common aspects of user procedure descriptions		
18.2.1	General conventions		
18.2.2	Naming conventions		
18.2.3	Convention on primitives parameters		
18.2.3.1	Open service		
	*		
18.2.3.2	Close service		
18.2.4	Version handling at dialogue establishment		
18.2.4.1	Behaviour at the initiating side		
18.2.4.2	Behaviour at the responding side		
18.2.5	Abort Handling		
18.2.6	SDL conventions		
18.3	Interaction between MAP Provider and MAP Users	413	
19 M	Iobility procedures	414	
19.1	Location management Procedures		
19.1.1	Location updating		
19.1.1.1	General		
19.1.1.2	Procedures in the VLR		
19.1.1.3	Procedure in the PVLR		
19.1.1.4	Procedure in the SGSN		
19.1.1.4	Procedures in the HLR		
19.1.1.3	Location Cancellation		
19.1.2.1	General		
19.1.2.2	Procedure in the HLR		
19.1.2.3	Procedure in the VLR		
19.1.2.4	Procedure in the SGSN		
19.1.3	Void		
19.1.4	MS Purging		
19.1.4.1	General		
19.1.4.2	Procedure in the VLR		
19.1.4.3	Procedure in the SGSN	449	
19.1.4.4	Procedure in the HLR	450	
19.2	Handover procedures		
19.2.1	General	455	

19.2.2	Procedure in MSC-A	458
19.2.2.1	Basic handover	458
19.2.2.2	Handling of access signalling	459
19.2.2.3	Subsequent handover	
19.2.3	Procedure in MSC-B	
19.2.3.1	Basic handover	
19.2.3.2	Handling of access signalling	
19.2.3.3	Subsequent handover	
19.2.4	Macro Receive_Error_From_HO_CA	
19.2.5	Procedure in VLR-B	
19.3	Fault recovery procedures	
19.3.1	VLR fault recovery procedures	
19.3.1.1	General	
19.3.1.2	Procedure in the VLR	
19.3.1.2	Procedure in the HLR	
19.3.1.3	HLR fault recovery procedures	
19.3.2.1	General	
19.3.2.1	Procedure in the HLR	
19.3.2.2	Procedure in the VLR	
19.3.2.3		
19.3.2.4 19.4	Procedure in the SGSN	
	Mobility Management event notification procedure	
19.4.1	General	
19.4.2	Procedure in the VLR or SGSN	
19.4.3	Procedure in the gsmSCF	
19.4	HLR Insert Subscriber Data macros	
19.5.1	Macro Insert_Subs_Data_Framed_HLR	
19.5.2	Macro Insert_GPRS_Subs_Data_Framed_HLR	493
20 O	peration and maintenance procedures	496
20.1	General	
20.1.1	Tracing Co-ordinator for the VLR	
20.1.1	Tracing Co-ordinator for the SGSN	
20.1.2	Subscriber Data Management Co-ordinator for the VLR	
20.1.3	Subscriber Data Management Co-ordinator for the VEK	
20.1.4	Tracing procedures	
20.2.1	Subscriber tracing activation procedure	
20.2.1	Procedures in the HLR	
20.2.1.2	Procedure in the VLR	
20.2.1.3	Procedure in the SGSN	
20.2.2	Subscriber tracing deactivation procedure	
20.2.2.1	Procedures in the HLR	
20.2.2.2	Procedure in the VLR	
20.2.2.3	Procedure in the SGSN	
20.3	Subscriber data management procedures	
20.3.1	Subscriber deletion procedure	
20.3.1.1	Procedure in the HLR	
20.3.1.2	Procedure in the VLR	
20.3.1.3	Procedure in the SGSN	
20.3.2	Subscriber data modification procedure	
20.3.2.1	Procedure in the HLR	
20.3.2.2	Procedures in the VLR	
20.3.2.3	Procedures in the SGSN	
20.4	Subscriber Identity procedure	
20.4.1	Procedure in the VLR	533
20.4.2	Procedure in the HLR	533
21 0	all handling proceedures	F2/
	all handling procedures	
21.1	General	
21.2	Retrieval of routing information	
21.2.1	General	
21.2.2	Procedure in the GMSC	
21.2.9	Process in the gsmSCF	540

21.2.4	Procedure in the HLR	540		
21.2.5	Procedure in the VLR to provide a roaming number			
21.2.6	Procedure in the VLR to restore subscriber data	540		
21.2.7	Procedure in the VLR to provide subscriber information			
21.3	Transfer of call handling			
21.3.1	General	549		
21.3.2	Process in the VMSC	549		
21.3.3	Process in the GMSC	550		
21.4	Inter MSC Group Call Procedures	553		
21.4.1	General	553		
21.4.2	Process in the Anchor MSC	554		
21.4.3	Process in the Relay MSC			
21.5	Void	559		
21.6	CCBS: monitoring and reporting the status of the subscriber	559		
21.6.1	Reporting co-ordinator process in the VLR			
21.6.2	Setting the reporting state – stand-alone			
21.6.2.1	Process in the HLR	559		
21.6.2.2	Process in the VLR	559		
21.6.3	Status Reporting	559		
21.6.3.1	Process in the VLR			
21.6.3.2	Process in the HLR			
21.6.4	CCBS: Remote User Free			
21.6.4.1	Process in the HLR			
21.6.3.2	Process in the VLR			
21.7	Void			
21.8	Void			
21.9	Immediate Service Termination (IST)			
21.9.1	IST Alert			
21.9.1.1	Procedure in the MSC			
21.9.1.2	Procedure in the HLR			
21.9.2	IST Command			
21.9.2.1	Procedure in the HLR.			
21.9.2.2	Procedure in the MSC			
21.10	Resource Management			
21.10.1	General			
21.3.2	Process in the GMSC			
21.3.3	Process in the VMSC			
	upplementary services procedures			
22.1	Supplementary service co-ordinator processes	584		
22.1.1	Supplementary service co-ordinator process for the MSC			
22.1.2	Void			
22.1.3	Functional supplementary service co-ordinator process for the HLR			
22.1.4	Call completion supplementary service co-ordinator process for the HLR			
22.2	Registration procedure			
22.2.1	General			
22.2.2	Procedure in the MSC			
22.2.3	Procedure in the VLR			
22.2.4	Procedure in the HLR	590		
22.3	Erasure procedure	596		
22.3.1	General	596		
22.3.2	Procedure in the MSC			
22.3.3	Procedure in the VLR	597		
22.3.4	Procedure in the HLR	597		
22.4	Activation procedure	597		
22.4.1	General Genera	597		
22.4.2	Procedure in the MSC	598		
22.4.3	Procedure in the VLR	599		
22.4.4	Procedure in the HLR	599		
22.5	Deactivation procedure			
22.5.1	General			
22.5.2	Procedure in the MSC			

22.5.3	Procedures in the VLR	
22.5.4	Procedures in the HLR	
22.6	Interrogation procedure	606
22.6.1	General	606
22.6.2	Procedure in the MSC	607
22.6.3	Procedures in the VLR	607
22.6.4	Procedure in the HLR	608
22.7	Void	612
22.8	Password registration procedure	
22.8.1	General	
22.8.2	Procedure in the MSC	
22.8.3	Procedure in the VLR	
22.8.4	Procedure in the HLR	
22.9	Mobile Initiated USSD procedure	
22.9.1	General	
22.9.1	Procedure in the MSC	
22.9.2		
	Procedure in the VLR	
22.9.4		
22.9.5	Procedures in the gsmSCF/secondary HLR	
22.10	Network initiated USSD procedure	
22.10.1	General	
22.10.2	Procedure in the MSC	
22.10.3	Procedure in the VLR	
22.10.4	Procedure in the HLR	
22.10.5	Procedure in the gsmSCF or secondary HLR	
22.11	Common macros for clause 22	654
22.11.1	SS Password handling macros	654
22.11.2	Void	654
22.12	Supplementary Service Invocation Notification procedure	658
22.12.1	General	658
22.12.2	Procedure in the MSC	658
22.12.3	Procedure in the gsmSCF	
22.13	Activation of a CCBS request	
22.13.1	General	
22.13.1	Procedure in the VLR	
22.13.2	Procedure in the HLR	
22.13.3	Deactivation of a CCBS request	
22.14.1	General	
22.14.1	Procedure in the VLR	
22.14.2	Procedure in the HLR	
22.14.3	Flocedule III tile filk	004
23 S	hort message service procedures	667
23.1	General	
23.1.1	Mobile originated short message service Co-ordinator for the MSC	
23.1.2	Short message Gateway Co-ordinator for the HLR	
23.1.2	The mobile originated short message transfer procedure	
23.2.1	Procedure in the serving MSC	
23.2.1	Procedure in the VLR	
23.2.3	Procedure in the SGSN	
23.2.4	Procedure in the SMS Interworking MSC (SMS-IWMSC)	
23.3	The mobile terminated short message transfer procedure	
23.3.1	Procedure in the SMS-GMSC	
23.3.2	Procedure in the HLR	
23.3.3	Procedure in the Serving MSC	
23.3.4	Procedure in the VLR	
23.3.5	Procedure in the SGSN	
23.4	The Short Message Alert procedure	
23.4.1	Procedure in the Serving MSC – the MS has memory available	730
23.4.2	Procedures in the VLR	730
23.4.2.1	The Mobile Subscriber is present	730
23.4.2.2	The MS has memory available	
23 4 3	Procedures in the SGSN	731

23.4.3.	The Mobile Subscriber is present	731
23.4.3.	The Mobile Equipment has memory available	731
23.4.4	Procedure in the HLR	
23.4.5	Procedure in the SMS Interworking MSC	731
23.5	The SM delivery status report procedure	
23.5.1	Procedure in the SMS-GMSC	
23.5.2	Procedure in the HLR	
23.6	The macro Report_SM_Delivery_Stat_HLR	744
24	GPRS process description	747
24.1	Procedure for retrieval of routeing information for GPRS	747
24.1.1	Process in the GGSN	
24.1.1	Process in the HLR	
24.1.2	Procedure for reporting failure to establish a network requested PDP context	
24.2.1	Process in the GGSN	
24.2.1	Process in the HLR	
24.2.2	Procedure for reporting that an MS has become reachable for GPRS	
24.3.1	Process in the HLR	
24.3.1	Process in the GGSN for Note Ms Present For Gprs	
	•	
	CSE interrogation and control of subscriber data	
24A.1	General	
24A.2	Any Time Subscription Interrogation procedure	
24A.2.		
24A.2.	ϵ	
24A.2.		
24A.3	Any Time Modification procedure	
24A.3.		
24A.3.2	ϵ	
24A.3.		
24A.4	Subscriber Data Modification Notification procedure	
24A.4.		
24A.4.2		
24A.4.	8	
24A.5	Any Time Interrogation procedure	
	1 General	
24A.5.		
24A.5.		
24A.5.4	4 Procedure in the GMLC	770
24B	Location Services process description	776
24B.1	Routeing information retrieval procedure for LCS	77 <i>6</i>
24B.1.	1 General	776
24B.1.2		776
24B.1.3		
24B.2	Provide Subscriber Location procedure	
24B.2.		
24B.2.2		779
24B.2.3	Process in the MSC	779
24B.2.4		· · · · · · · · · · · · · · · · · · ·
24B.3	Subscriber Location Report procedure	783
24B.3.		
24B.3.2		
24B.3.3		
24B.3.4	4 Process in the GMLC	783
25	General macro description	787
25.1	MAP_OPEN handling macros	
25.1.1	Macro Receive_Open_Ind	
25.1.2	Macro Receive_Open_Cnf	
25.2	Macros to check the content of indication and confirmation primitives	
25.2.1	Macro Check_Indication	792
25 2 2	Macro Chack Confirmation	703

25.3	The page and search macros	
25.3.1	Macro PAGE_MSC	
25.3.2	Macro Search_For_MS_MSC	795
25.4	Macros for handling an Access Request	
25.4.1	Macro Process_Access_Request_MSC	798
25.4.2	Macro Process_Access_Request_VLR	
25.4.3	Macro Obtain_Identity_VLR	
25.4.4	Process Update_Location_Child_VLR	798
25.5	Authentication macros and processes	
25.5.1	Macro Authenticate_MSC	
25.5.2	Macro Authenticate_VLR	
25.5.3	Macro Obtain_Authent_Params_VLR	
25.5.4	Process Obtain_Authentication_Sets_VLR	
25.5.6	Process Obtain_Authent_Sets_SGSN	808
25.5.6	Process Obtain_Authent_Sets_HLR	
25.5.7	Authentication Failure Reporting	
25.5.7.1	General	
25.5.7.2		
25.5.7.3		
25.5.7.4		
25.6	IMEI Handling Macros	
25.6.1	Macro Check_IMEI_MSC	
25.6.2	Macro Check_IMEI_VLR	
25.6.3	Process Check_IMEI_SGSN	
25.6.4	Process Check_IMEI_EIR	
25.6.5	Macro Obtain_IMEI_MSC	
25.6.6	Macro Obtain_IMEI_VLR	
25.7	Insert Subscriber Data macros and processes	
25.7.1	Macro Insert_Subs_Data_VLR	
25.7.2	Macro Insert_Subs_Data_SGSN	
25.7.3	Process Insert_Subs_Data_Stand_Alone_HLR	
25.7.4	Process Insert_GPRS_Subs_Data_Stand_Alone_HLR	
25.7.5	Macro Wait_for_Insert_Subs_Data_Cnf	
25.7.6	Macro Wait_for_Insert_GPRS_Subs_Data_Cnf	
25.7.7	Process Send_Insert_Subs_Data_HLR	
25.8	Request IMSI Macros	
25.8.1	Macro Obtain_IMSI_MSC	
25.8.2	Macro Obtain_IMSI_VLR	
25.9	Tracing macros	
25.9.1	Macro Trace_Subscriber_Activity_MSC	
25.9.2	Macro Trace_Subscriber_Activity_VLR	
25.9.3	Macro Trace_Subscriber_Activity_SGSN	
25.9.4	Macro Activate_Tracing_VLR	
25.9.5	Macro Activate_Tracing_SGSN	
25.9.6	Macro Control_Tracing_With_VLR_HLR	
25.9.7	Macro Control_Tracing_With_SGSN_HLR	
25.10	Short Message Alert procedures	
25.10.1	Process Subscriber_Present_VLR	
25.10.2	Process SubscriberPresent_SGSN	
25.10.3	Macro Alert_Service_Centre_HLR	
25.10.4	Process Alert_SC_HLR	856
Annex .	A (informative): Cross-reference for abstract syntaxes of MAP	861
Annex 1	B (informative): Fully expanded ASN.1 sources for abstract syntaxes of I	MAP1101
B.1 F	Fully Expanded ASN.1 Source of MAP-Protocol/TCAPMessages	1101
B.2 F	Fully Expanded ASN.1 Source of MAP-DialogueInformation	1285
	C (informative): Message Segmentation Mechanisms	
C.1	SCCP segmentation	
C_2	TCAP segmentation	1200

C.2.1	Empty Begin		1290
C.2.2	Empty Continue	·	1290
C.2.3	TC-Result-NL		1290
C.3	MAP Segmentation		1291
C.3.1			
C.3.2	Invoke with exp	licit indication	1291
C.3.3	Result		1291
Annex 1	D (informative):	Void	1294
Annex E (informative):		tive): Change History	1295
History			1308

Foreword

This Technical Specification (TS) has been produced by the 3rd Generation Partnership Project (3GPP).

The present document specifies the Mobile Application Part (MAP), the requirements for the signalling system and procedures within the 3GPP system at application level.

The contents of the present document are subject to continuing work within the TSG and may change following formal TSG approval. Should the TSG modify the contents of the present document, it will be re-released by the TSG with an identifying change of release date and an increase in version number as follows:

Version x.y.z

where:

- x the first digit:
 - 1 presented to TSG for information;
 - 2 presented to TSG for approval;
 - 3 or greater indicates TSG approved document under change control.
- y the second digit is incremented for all changes of substance, i.e. technical enhancements, corrections, updates, etc.
- z the third digit is incremented when editorial only changes have been incorporated in the document.

1 Scope

It is necessary to transfer between entities of a Public Land Mobile Network (PLMN) information specific to the PLMN in order to deal with the specific behaviour of roaming Mobile Stations (MS)s. The Signalling System No. 7 specified by CCITT is used to transfer this information.

The present document describes the requirements for the signalling system and the procedures needed at the application level in order to fulfil these signalling needs.

Clauses 1 to 6 are related to general aspects such as terminology, mobile network configuration and other protocols required by MAP.

MAP consists of a set of MAP services that are provided to MAP service-users by a MAP service-provider.




Figure 1.1/1: Modelling principles

Clauses 7 to 13A of the present document describe the MAP services.

Clauses 14 to 17 define the MAP protocol specification and the behaviour of service provider (protocol elements to be used to provide MAP services, mapping on to TC service primitives, abstract syntaxes, etc.).

Clauses 18 to 25 describe the MAP user procedures that make use of MAP services.

2 References

The following documents contain provisions which, through reference in this text, constitute provisions of the present document.

- References are either specific (identified by date of publication, edition number, version number, etc.) or non-specific.
- For a specific reference, subsequent revisions do not apply.
- For a non-specific reference, the latest version applies. In the case of a reference to a 3GPP document (including a GSM document), a non-specific reference implicitly refers to the latest version of that document *in the same Release as the present document*.
- [1] 3GPP TS 21.905: "3G Vocabulary".
 [2] 3GPP TS 22.001: "Digital cellular telecommunications system (Phase 2+); Principles of telecommunication services supported by a Public Land Mobile Network (PLMN)".
 [3] 3GPP TS 22.002: "Bearer Services Supported by a Public Land Mobile Network (PLMN)".
 [4] 3GPP TS 22.003: "Circuit Teleservices Supported by a Public Land Mobile Network (PLMN)".
 [5] 3GPP TS 22.004: "General on Supplementary Services".
 [6] 3GPP TS 42.009: "Digital cellular telecommunications system (Phase 2+); Security aspects".
 [7] 3GPP TS 22.016: "International Mobile station Equipment Identities (IMEI)".

[8]	3GPP TS 22.041: "Operator Determined Barring".
[9]	3GPP TS 22.081: "Line identification supplementary services - Stage 1".
[10]	3GPP TS 22.082: "Call Forwarding (CF) supplementary services - Stage 1".
[11]	3GPP TS 22.083: "Call Waiting (CW) and Call Hold (HOLD) Supplementary Services - Stage 1".
[12]	3GPP TS 22.084: "Multi Party (MPTY) Supplementary Services - Stage 1".
[13]	3GPP TS 22.085: "Closed User Group (CUG) supplementary services - Stage 1".
[14]	3GPP TS 22.086: "Advice of charge (AoC) Supplementary Services - Stage 1".
[15]	3GPP TS 22.088: "Call Barring (CB) supplementary services - Stage 1".
[16]	3GPP TS 22.090: "Unstructured Supplementary Service Data (USSD); - Stage 1".
[17]	3GPP TS 23.003: "Numbering, addressing and identification".
[18]	Void
[19]	3GPP TS 23.007: "Restoration procedures".
[20]	3GPP TS 23.008: "Organisation of subscriber data".
[21]	3GPP TS 23.009: "Handover procedures".
[22]	3GPP TS 23.011: "Technical realization of Supplementary Services - General Aspects".
[23]	3GPP TS 23.012: "Location management procedures".
[24]	3GPP TS 43.020: "Security related network functions".
[25]	3GPP TS 23.038: "Alphabets and language".
[25a]	3GPP TS 23.039: "Interface protocols for the connection of Short Message Service Centres (SMSCs) to Short Message Entities (SMEs)".
[26]	3GPP TS 23.040: "Technical realization of the Short Message Service (SMS) Point to Point (PP)".
[26a]	3GPP TS 23.271: "Functional stage2 description of LCS".
[27]	3GPP TS 23.081: "Line Identification Supplementary Services - Stage 2".
[28]	3GPP TS 23.082: "Call Forwarding (CF) Supplementary Services - Stage 2".
[29]	$3 GPP\ TS\ 23.083;\ "Call\ Waiting\ (CW)\ and\ Call\ Hold\ (HOLD)\ Supplementary\ Services\ -\ Stage\ 2".$
[30]	3GPP TS 23.084: "Multi Party (MPTY) Supplementary Services - Stage 2".
[31]	3GPP TS 23.085: "Closed User Group (CUG) Supplementary Services - Stage 2".
[32]	3GPP TS 23.086: "Advice of Charge (AoC) Supplementary Services - Stage 2".
[33]	3GPP TS 23.088: "Call Barring (CB) Supplementary Services - Stage 2".
[34]	3GPP TS 23.090: "Unstructured Supplementary Services Data (USSD) - Stage 2".
[34a]	3GPP TS 33.200: "3G Security; Network domain security; MAP application layer security".
[35]	3GPP TS 24.008: "Mobile Radio Interface Layer 3 specification; Core Network Protocols - Stage 3".
[36]	3GPP TS 24.010: "Mobile radio interface layer 3 Supplementary Services specification - General aspects".
[37]	3GPP TS 24.011: "Point-to-Point (PP) Short Message Service (SMS) support on mobile radio interface".

[37a]	3GPP TS 44.071: "Location Services (LCS) – stage 3".
[38]	$3\mbox{GPP TS }24.080;$ "Mobile radio interface layer 3 supplementary services specification - Formats and coding".
[39]	3GPP TS 24.081: "Line identification supplementary services - Stage 3".
[40]	3GPP TS 24.082: "Call Forwarding (CF) Supplementary Services - Stage 3".
[41]	$3 GPP\ TS\ 24.083; "Call\ Waiting\ (CW)\ and\ Call\ Hold\ (HOLD)\ supplementary\ services\ -\ Stage\ 3".$
[42]	3GPP TS 24.084: "Multi Party (MPTY) Supplementary Services - Stage 3".
[43]	3GPP TS 24.085: "Closed User Group (CUG) Supplementary Services - Stage 3".
[44]	3GPP TS 24.086: "Advice of Charge (AoC) Supplementary Services - Stage 3".
[45]	3GPP TS 24.088: "Call Barring (CB) Supplementary Services - Stage 3".
[46]	3GPP TS 24.090: "Unstructured Supplementary Services Data - Stage 3".
[47]	3GPP TS 48.002: " Base Station System - Mobile-services Switching Centre (BSS - MSC) interface principles".
[48]	3GPP TS 48.006: "Signalling transport mechanism specification for the Base Station System - Mobile-services Switching Centre (BSS - MSC) interface".
[49]	3GPP TS 48.008: "Mobile Switching Centre - Base Station System (MSC - BSS) interface; Layer 3 specification".
[49a1]	3GPP TS 48.031: "Location Services (LCS); Serving Mobile Location Centre (SMLC) – Serving Mobile Location Centre (SMLC); SMLC Peer Protocol (SMLCPP)".
[49b]	3GPP TS 48.071: "Location Services (LCS); Serving Mobile Location Centre - Base Station System (SMLC - BSS) interface Layer 3 specification".
[50]	3GPP TS 49.001: "General network interworking scenarios".
[51]	3GPP TS 29.002: "Mobile Application Part (MAP) specification".
[52]	Void
[53]	Void
[54]	Void
[55]	3GPP TS 29.006: "Interworking between a Public Land Mobile Network (PLMN) and a Packet Switched Public Data Network/Integrated Services Digital Network (PSPDN/ISDN) for the support of Packet Switched data transmission services".
[56]	3GPP TS 29.007: "General requirements on interworking between the Public Land Mobile Network (PLMN) and the Integrated Services Digital Network (ISDN) or Public Switched Telephone Network (PSTN)".
[57]	3GPP TS 29.008: "Application of the Base Station System Application Part (BSSAP) on the E-interface".
[58]	3GPP TS 29.010: "Information element mapping between Mobile Station - Base Station System and BSS - Mobile-services Switching Centre (MS - BSS - MSC) Signalling procedures and the Mobile Application Part (MAP)".
[59]	3GPP TS 29.011: "Signalling interworking for Supplementary Services".
[59a]	3GPP TS 49.031: "Digital cellular telecommunications system (Phase 2+); Location Services (LCS); Base Station System Application Part LCS Extension (BSSAP-LE)".
[60]	Void

[61]	3GPP TS 52.008: " GSM Subscriber and Equipment Trace".
[62]	ETS 300 102-1 (1990): "Integrated Services Digital Network (ISDN); User-network interface layer 3 specifications for basic call control".
[63]	ETS 300 136 (1992): "Integrated Services Digital Network (ISDN); Closed User Group (CUG) supplementary service description".
[64]	ETS 300 138 (1992): "Integrated Services Digital Network (ISDN); Closed User Group (CUG) supplementary service Digital Subscriber Signalling System No.one (DSS1) protocol".
[65]	ETS 300 287: "Integrated Services Digital Network (ISDN); Signalling System No.7; Transaction Capabilities (TC) version 2".
[66]	ETR 060: "Signalling Protocols and Switching (SPS); Guide-lines for using Abstract Syntax Notation One (ASN.1) in telecommunication application protocols".
[66b]	ETR 091: "ETSI object identifier tree; Common domain Mobile domain"
[67]	ITU-T Recommendation E.164: " The international public telecommunication numbering plan".
[68]	ITU-T Recommendation E.212: " The international identification plan for mobile terminals and mobile users".
[69]	ITU-T Recommendation E.213: "Telephone and ISDN numbering plan for land mobile stations in public land mobile networks (PLMN) ".
[70]	ITU-T Recommendation E.214: " Structure of the land mobile global title for the signalling connection control part (SCCP) ".
[71]	ITU-T Recommendation Q.699: "Interworking between ISDN access and non-ISDN access over ISDN User Part of Signalling System No. 7".
[72]	ITU-T Recommendation Q.711: "Specifications of Signalling System No.7; Functional description of the Signalling Connection Control Part".
[73]	ITU-T Recommendation Q.712: "Definition and function of SCCP messages".
[74]	ITU-T Recommendation Q.713: "Specifications of Signalling System No.7; SCCP formats and codes".
[75]	ITU-T Recommendation Q.714: "Specifications of Signalling System No.7; Signalling Connection Control Part procedures".
[76]	ITU-T Recommendation Q.716: "Specifications of Signalling System No.7; Signalling connection control part (SCCP) performances".
[77]	ITU-T Recommendation Q.721 (1988): "Specifications of Signalling System No.7; Functional description of the Signalling System No.7 Telephone user part".
[78]	ITU-T Recommendation Q.722 (1988): "Specifications of Signalling System No.7; General function of Telephone messages and signals".
[79]	ITU-T Recommendation Q.723 (1988): "Specifications of Signalling System No.7; Formats and codes".
[80]	ITU-T Recommendation Q.724 (1988): "Specifications of Signalling System No.7; Signalling procedures".
[81]	ITU-T Recommendation Q.725 (1988): "Specifications of Signalling System No.7; Signalling performance in the telephone application".
[82]	ITU-T Recommendation Q.761 (1988): "Specifications of Signalling System No.7; Functional description of the ISDN user part of Signalling System No.7".
[83]	ITU-T Recommendation Q.762 (1988): "Specifications of Signalling System No.7; General function of messages and signals".

[84]	ITU-T Recommendation Q.763 (1988): "Specifications of Signalling System No.7; Formats and codes".
[85]	ITU-T Recommendation Q.764 (1988): "Specifications of Signalling System No.7; Signalling procedures".
[86]	ITU-T Recommendation Q.767: "Specifications of Signalling System No.7; Application of the ISDN user part of CCITT signalling System No.7 for international ISDN interconnections".
[87]	ITU-T Recommendation Q.771: "Specifications of Signalling System No.7; Functional description of transaction capabilities".
[88]	ITU-T Recommendation Q.772: "Specifications of Signalling System No.7; Transaction capabilities information element definitions".
[89]	ITU-T Recommendation Q.773: "Specifications of Signalling System No.7; Transaction capabilities formats and encoding".
[90]	ITU-T Recommendation Q.774: "Specifications of Signalling System No.7; Transaction capabilities procedures".
[91]	ITU-T Recommendation Q.775: "Specifications of Signalling System No.7; Guide-lines for using transaction capabilities".
[92]	ITU-T Recommendation X.200: "Reference Model of Open systems interconnection for CCITT Applications".
[93]	ITU-T Recommendation X.680: "Information technology – Abstract Syntax Notation One (ASN.1): Specification of basic notation".
[93b]	ITU-T Recommendation X.681: "Information technology – Abstract Syntax Notation One (ASN.1): Information object specification"
[94]	ITU-T Recommendation X.690: "Information technology – ASN.1 encoding rules: Specification of Basic Encoding Rules (BER), Canonical Encoding Rules (CER) and Distinguished Encoding Rules (DER)".
[95]	ITU-T Recommendation X.210: "Open systems interconnection layer service definition conventions".
[97]	3GPP TS 23.018: "Basic Call Handling".
[98]	3GPP TS 23.078: "Customised Applications for Mobile network Enhanced Logic (CAMEL) Phase 4 - Stage 2".
[99]	3GPP TS 23.079: "Support of Optimal Routeing (SOR) - Stage 2".
[100]	3GPP TS 43.068: "Voice Group Call Service (VGCS) - Stage 2".
[101]	3GPP TS 43.069: "Voice Broadcast service (VBS) - Stage 2".
[102]	ANSI T1.113: "Signaling System No. 7 (SS7) - ISDN User Part".
[103]	Void
[104]	3GPP TS 23.060: "General Packet Radio Service (GPRS) Description; Stage 2".
[105]	3GPP TS 29.060: "General Packet Radio Service (GPRS); GPRS Tunnelling Protocol (GTP) across the Gn and Gp Interface".
[106]	3GPP TS 29.018: "General Packet Radio Service (GPRS); Serving GPRS Support Node (SGSN) - Visitors Location Register (VLR); Gs interface layer 3 specification".
[107]	3GPP TS 23.093: "Technical Realization of Completion of Calls to Busy Subscriber (CCBS); Stage 2".
[108]	3GPP TS 23.066: "Support of Mobile Number Portability (MNP); Technical Realisation Stage 2".

[109]	ANSI T1.112 (1996): "Telecommunication – Signalling No. 7 - Signaling Connection Control Part (SCCP)".
[110]	3GPP TS 23.116: "Super-Charger Technical Realisation; Stage 2."
[111]	Void.
[112]	Void
[113]	Void
[114]	Void
[115]	Void
[116]	ITU-T Recommendation Q.850 (May 1998): "Usage of cause and location in the Digital Subscriber Signalling System No. 1 and the Signalling System No. 7 ISDN User Part".
[117]	3GPP TS 22.135: "Multicall; Service description; Stage 1".
[118]	3GPP TS 23.135: "Multicall supplementary service; Stage 2".
[119]	3GPP TS 24.135: "Multicall supplementary service; Stage 3".
[120]	3GPP TS 25.413: "UTRAN Iu Interface RANAP Signalling".
[121]	3GPP TS 29.202: "SS7 signalling transport in core network"
[122]	3GPP TS 23.032: "Universal Geographical Area Description (GAD)"
[123]	3GPP TS 22.071: "Location Services (LCS); Service description, Stage 1"
[124]	ITU-T Recommendation X.880: "Data networks and open system communication - Open System Interconnection - Service definitions - Remote operations: Concepts, model and notation".
[125]	3GPP TS 23.278: 'Customised Applications for Mobile Network Enhanced Logic (CAMEL) Phase 4 – Stage 2 IM CN Interworking (Rel-5)'
[126]	3GPP TS 23.172: "Technical realization of Circuit Switched (CS) multimedia service; UDI/RDI fallback and service modification"
[127]	3GPP TS 26.103: "Speech codec list for GSM and UMTS".
[128]	3GPP TS 23.141: "Presence Service; Architecture and Functional Description"
[129]	3GPP TS 23.094: "Follow Me (FM) – Stage 2"
[130]	3GPP TS 32.422: "Subscriber and equipment trace; Trace control and Configuration Management (CM)".
[131]	3GPP TS 32.421: "Subscriber and equipment trace: Trace concepts and requirements".
[132]	3GPP TS 32.422: "Subscriber and equipment trace; Trace control and Configuration Management".

3 Abbreviations

ADD Automatic Device Detection

All other abbreviations used in the present document are listed in 3GPP TS 21.905.

4 Void

5 Overload and compatibility overview

5.1 Overload control

There is a requirement for an overload/congestion control for all entities of the Public Land Mobile Network and the underlying Signalling System No. 7.

5.1.1 Overload control for MSC (outside MAP)

For the entity MSC the following two procedures (outside MAP) may be applied to control the processor load:

- ISDN
 CCITT Recommendation Q.764 (Automatic Congestion Control), applicable to reduce the mobile terminating traffic;
- BSSAP 3GPP TS 48.008 [49] (A-interface Flow Control), applicable to reduce the mobile originating traffic.

5.1.2 Overload control for MAP entities

For all MAP entities, especially the HLR, the following overload control method is applied.

If overload of a MAP entity is detected requests for certain MAP operations (see tables 5.1/1, 5.1/2, 5.1/3 and 5.1/4) may be ignored by the responder. The decision as to which MAP Operations may be ignored is made by the MAP service provider and is based upon the priority of the application context.

Since most of the affected MAP operations are supervised in the originating entity by TC timers (medium) an additional delay effect is achieved for the incoming traffic.

If overload levels are applicable in the Location Registers the MAP operations should be discarded taking into account the priority of their application context (see table 5.1/1 for HLR, table 5.1/2 for MSC/VLR, table 5.1/3 for the SGSN and table 5.1/4 for the SMLC; the lowest priority is discarded first).

The ranking of priorities given in the tables 5.1/1, 5.1/2, 5.1/3 and 5.1/4 is not normative. The tables can only be seen as a proposal that might be changed due to network operator/implementation matters.

Table 5.1/1: Priorities of Application Contexts for HLR as Responder

Priority high	Responder = HLR	Initiating Entity
, 0	Mobility Management	
	networkLocUp	VLR
	(updateLocation),	
	(restoreData/v2),	
	(sendParameters/v1)	9 9 9 1
	gprsLocationUpdate	SGSN
	(updateGPRSLocation/v3),	THE PAGGON
	infoRetrieval	VLR/SGSN
	(sendAuthenticationInfo/v2/v3),	
	(sendParameters/v1)	MSC
	istAlerting (istAlert/v3)	
	(purgeMS/v2/v3)	msPurging VLR
	msPurging	SGSN
	(purgeMS/v3)	30311
	Short Message Service	
	shortMsgGateway	GMSC
	(sendRoutingInfoforSM),	GMSC
	(reportSM-DeliveryStatus)	
	mwdMngt VLR/SGSN	
	(readyForSM/v2/v3),	
	(noteSubscriberPresent/v1)	
	Mobile Terminating Traffic	
	locInfoRetrieval	GMSC
	(sendRoutingInfo)	
	anyTimeEnquiry	gsmSCF
	(anyTimeInterrogation/v3)	-
	reporting	VLR
	(statusReport)	
	<u>Location Services</u>	
	locationSvcGateway	GMLC
	(sendRoutingInfoforLCS/v3)	
	Subscriber Controlled Inputs (Supplementary Services)	
	networkFunctionalSs	VLR
	(registerSS),	
	(eraseSS),	
	(activateSS),	
	(deactivateSS),	
	(interrogateSS),	
	(registerPassword),	
	(processUnstructuredSS-Data/v1),	
	(beginSubscriberActivity/v1)	
	callCompletion	VLR
	(registerCCEntry),	
	(eraseCCEntry)	MD
	networkUnstructuredSs	VLR
	(processUnstructuredSS-Request/v2) imsiRetrieval	VI D
		VLR
	(sendIMSI/v2) gprsLocationInfoRetrieval	GGSN/SGSN
	(sendRoutingInfoForGprs/v3/v4)	UGDIN/BUDIN
	(sendroutinginiororopis/v3/v4) failureReport	GGSN/SGSN
	(failureReport/v3)	GGDI4/DGDI4
	authenticationFailureReport	VLR/SGSN
	(authenticationFailureReport/v3)	V LIV SUSIN
	(authentication randre Report v5)	

NOTE: The application context name is the last component but one of the object identifier.

Operation names are given in brackets for information with "/vn" appended to vn only operations.

Table 5.1/3: Priorities of Application Contexts for SGSN as Responder

Responder = So	GSN	Initiating Entity
Priority high		
	Mobility and Location Register Management	
location	Cancel	HLR
	(cancelLocation v3)	
reset		HLR
	(reset)	
subscrib	erDataMngt	HLR
	(insertSubscriberData v3),	
	(deleteSubscriberData v3)	
tracing		HLR
	(activateTraceMode),	
	(deactivateTraceMode)	
	Short Message Service	
shortMs	gMT-Relay	MSC
	(MT-ForwardSM v3),	
	(forwardSM v1/v2)	
	Location Services	
location	SvcEnquiry	GMLC
locations	(provideSubscriberLocation v3)	OWILC
	(provides doscriber Location v3)	
	Network-Requested PDP context activation	
gprsNoti	_	HLR
gpisivou	(noteMsPresentForGprs v3),	TILK
	(notetrisi resonti oropis vo),	
	(Subscriber Location & State retrieval)	
subscrib	erInfoEnquiry	HLR
Subscrib	(provideSubscriberInformation/v3)	TIESK
Priority low		

NOTE: The application context name is the last component but one of the object identifier. Operation names are given in brackets for information with "/vn" appended to vn.

Table 5.1/2: Priorities of Application Contexts for MSC/VLR as Responder

	der = MSC/VLR	Initiating Entity
Priority high	Handover handoverControl (prepareHandover/v2/v3), (performHandover/v1)	MSC
	Group call and Broadcast call groupCallControl (prepareGroupCall/v3)	MSC
	Mobility and Location Register Management locationCancel (cancelLocation)	HLR
	reset (reset)	HLR
	immediateTermination	HLR
	(istCommand/v3) interVlrInfoRetrieval (sendIdentification/v2/v3),	VLR
	(sendParameters/v1) subscriberDataMngt (insertSubscriberData),	HLR
	(deleteSubscriberData) tracing (activateTraceMode), (deactivateTraceMode)	HLR
	Short Message Service shortMsgMO-Relay (MO-ForwardSM v3), (forwardSM v1/v2)	MSC/SGSN
	shortMsgMT-Relay (MT-ForwardSM v3),	MSC
	(forwardSM v1/v2) shortMsgAlert (alertServiceCentre/v2), (alertServiceCentreWithoutResult/v1)	HLR
	Mobile Terminating Traffic resourceMngt	GMSC
	(releaseResources) roamingNbEnquiry	HLR
	(provideRoamingNumber) callControlTransfer	MSC
	(resumeCallHandling) subscriberInfoEnquiry	HLR
	(provideSubscriberInformation/v3) reporting	HLR
	(remoteUserFree), (SetReportingState)	TILK
	Location Services locationSvcEnquiry (provideSubscriberLocation/v3)	GMLC
	<u>Network-Initiated USSD</u> networkUnstructuredSs (unstructuredSS-Request/v2), (unstructuredSS-Notify/v2)	HLR
Priority low	• ,	

NOTE: The application context name is the last component but one of the object identifier.

Operation names are given in brackets for information with "/vn" appended to vn only operations.

5.1.3 Congestion control for Signalling System No. 7

The requirements of SS7 Congestion control have to be taken into account as far as possible.

Means that could be applied to achieve the required traffic reductions are described in clauses 5.1.1 and 5.1.2.

5.2 Compatibility

5.2.1 General

The present document of the Mobile Application Part is designed in such a way that an implementation which conforms to it can also conform to the Mobile Application Part operational version 1 specifications, except on the MSC-VLR interface.

A version negotiation mechanism based on the use of an application-context-name is used to negotiate the protocol version used between two entities for supporting a MAP-user signalling procedure.

When starting a signalling procedure, the MAP-user supplies an application-context-name to the MAP-provider. This name refers to the set of application layer communication capabilities required for this dialogue. This refers to the required TC facilities (e.g. version 1 or 2) and the list of operation packages (i.e. set of operations) from which operations can be invoked during the dialogue.

A version one application-context-name may only be transferred to the peer user in a MAP-U-ABORT to an entity of version two or higher (i.e. to trigger a dialogue which involves only communication capabilities defined for MAP operational version 1).

If the proposed application-context-name can be supported by the responding entity the dialogue continues on this basis otherwise the dialogue is refused and the initiating user needs to start a new dialogue, which involves another application-context-name which requires less communication capabilities but provides similar functionality (if possible).

When a signalling procedure can be supported by several application contexts that differ by their version number, the MAP-User needs to select a name. It can either select the name that corresponds to the highest version it supports or follow a more specific strategy so that the number of protocol fallbacks due to version compatibility problems is minimised.

5.2.2 Strategy for selecting the Application Context (AC) version

A method should be used to minimise the number of protocol fall-backs which would occur sometimes if the highest supported AC-Name were always the one selected by GSM entities when initiating a dialogue. The following method is an example that can be used mainly at transitory phase stage when the network is one of mixed phase entities.

5.2.2.1 Proposed method

A table (table 1) may be set up by administrative action to define the highest application context (AC) version supported by each destination; a destination may be another node within the same or a different PLMN, or another PLMN considered as a single entity. The destination may be defined by an E.164 number or an E.214 number derived from an IMSI or in North America (World Zone 1) by an E.164 number or an IMSI (E.212 number). The table also includes the date when each destination is expected to be able to handle at least one AC of the latest version of the MAP protocol. When this date is reached, the application context supported by the node is marked as "unknown", which will trigger the use of table 2.

A second table (table 2) contains an entry for each destination that has an entry in table 1. For a given entity, the entry in table 2 may be a single application context version or a vector of different versions applying to different application contexts for that entity. Table 2 is managed as described in clause 5.2.2.2.

The data for each destination will go through the following states:

a) the version shown in table 1 is "version n-1", where 'n' is the highest version existing in this specification; table 2 is not used;

- b) the version shown in table 1 is "unknown"; table 2 is used, and maintained as described in clause 5.2.2.2;
- c) when the PLMN operator declares that an entity (single node or entire PLMN) has been upgraded to support all the MAP version n ACs defined for the relevant interface, the version shown in table 1 is set to "version n" by administrative action; table 2 is no longer used, and the storage space may be recovered.

5.2.2.2 Managing the version look-up table

WHEN it receives a MAP-OPEN ind the MAP-User determines the originating entity number either using the originating address parameter or the originating reference parameter or retrieving it from the subscriber data using the IMSI or the MSISDN.

IF the entity number is known:

THEN

It updates (if required) the associated list of highest supported ACs.

ELSE

It creates an entry for this entity and includes the received AC-name in the list of highest supported ACs.

WHEN starting a procedure, the originating MAP-user looks up its version control table.

IF the destination address is known and not timed-out.

THEN

It retrieves the appropriate AC-name and uses it

IF the dialogue is accepted by the peer

THEN

It does not modify the version control table

ELSE (this should never occur)

It starts a new dialogue with the common highest version supported (based on information implicitly or explicitly provided by the peer).

It replaces the old AC-name by the new one in the list of associated highest AC supported.

ELSE

It uses the AC-name that corresponds to the highest version it supports.

IF the dialogue is accepted by the peer.

THEN

It adds the destination node in its version control table and includes the AC-Name in the list of associated highest AC supported.

ELSE

It starts a new dialogue with the common highest version supported (based on information implicitly or explicitly provided by the peer).

IF the destination node was not known

THEN

It adds the destination node in its version control table and includes the new AC-Name in the list of associated highest AC supported.

ELSE

It replaces the old AC-name by the new one in the list of highest supported AC and reset the timer.

5.2.2.3 Optimising the method

A table look-up may be avoided in some cases if both the HLR and the VLR or both the HLR and the SGSN store for each subscriber the version of the AC-name used at location updating. Then:

- for procedures which make use of the same application-context, the same AC-name (thus the same version) can be selected (without any table look-up) when the procedure is triggered;
- for procedures which make use of a different application-context but which includes one of the packages used by the location updating AC, the same version can be selected (without any table look-up) when the procedure is triggered;

for HLR:

- Subscriber data modification (stand alone);

for VLR:

Data Restoration.

6 Requirements concerning the use of SCCP and TC

6.1 Use of SCCP

The Mobile Application Part (MAP) makes use of the services offered by the Signalling Connection Control Part (SCCP).

MAP supports the following SCCP versions:

- Signalling Connection Control Part, Signalling System no. 7 CCITT ("Blue Book SCCP");
- Signalling Connection Control Part, Signalling System no. 7 ITU-T Recommendation (07/96) Q.711 to Q.716 ("White Book SCCP"). Support of White Book SCCP at the receiving side shall be mandated from 00:01hrs, 1st July 2002(UTC). However, for signalling over the MAP E-interface to support inter-MSC handover/relocation, the support of White Book SCCP shall be mandated with immediate effect.

A White Book SCCP message will fail if any signalling point used in the transfer of the message does not support White Book SCCP. Therefore it is recommended that the originator of the White Book SCCP message supports a drop back mechanism or route capability determination mechanism to interwork with signalling points that are beyond the control of GSM/UMTS network operators.

In North America (World Zone 1) the national version of SCCP is used as specified in ANSI T1.112. Interworking between a PLMN in North America and a PLMN outside North America will involve an STP to translate between ANSI SCCP and ITU-T/CCITT SCCP.

The SCCP is identified as an MTP3-user and the transport of SCCP messages between two entities shall be accomplished according to the 3GPP TS 29.202 [121].

6.1.1 SCCP Class

MAP will only make use of the connectionless classes (0 or 1) of the SCCP.

6.1.2 Sub-System Number (SSN)

The Application Entities (AEs) defined for MAP consist of several Application Service Elements (ASEs) and are addressed by sub-system numbers (SSNs). The SSNs for MAP are specified in 3GPP TS 23.003 [17].

When the SGSN emulates MSC behaviour for processing messages (MAP-MO-FORWARD-SHORT-MESSAGE, MAP_CHECK_IMEI, MAP_SUBSCRIBER_LOCATION_REPORT) towards entities which do not support interworking to SGSNs, it shall use the MSC SSN in the calling party address instead of the SGSN SSN.

When present in the network, the Presence Network Agent emulates the behaviour of the GSM Service Control Function (gsm SCF) for processing of messages (MAP-NOTE-MM-EVENT, MAP-ANY-TIME-INTERROGATION and MAP-ANY-TIME-MODIFICATION).

6.1.3 SCCP addressing

6.1.3.1 Introduction

Within the GSM System there will be a need to communicate between entities within the same PLMN and in different PLMNs. Using the Mobile Application Part (MAP) for this function implies the use of Transaction Capabilities (TC) and the Signalling Connection Control Part (SCCP) of CCITT Signalling System No. 7.

Only the entities that should be addressed are described below. If the CCITT or ITU-T SCCP is used, the format and coding of address parameters carried by the SCCP for that purpose shall comply with CCITT Recommendation Q.713 with the following restrictions:

1) Intra-PLMN addressing

For communication between entities within the same PLMN, a MAP SSN shall always be included in the called and calling party addresses. All other aspects of SCCP addressing are network specific.

2) Inter-PLMN addressing

- a) Called Party Address
 - SSN indicator = 1 (MAP SSN always included);
 - Global title indicator = 0100 (Global title includes translation type, numbering plan, encoding scheme and nature of address indicator);
 - the translation type field will be coded "00000000" (Not used). For call related messages for non-optimal routed calls (as described in 3GPP TS 23.066 [108]) directed to another PLMN the translation type field may be coded "10000000" (CRMNP);
 - Routing indicator = 0 (Routing on global title);

b) Calling Party Address

- SSN indicator = 1 (MAP SSNs always included);
- Point code indicator = 0;
- Global title indicator = 0100 (Global title includes translation type, numbering plan, encoding scheme and nature of address indicator);
- Numbering Plan = 0001 (ISDN Numbering Plan, E.164; In Case of Inter-PLMN Signalling, the dialogue initiating entity and dialogue responding entity shall always include its own E.164 Global Title as Calling Party Address);
- the translation type field will be coded "00000000" (Not used);
- Routing indicator = 0 (Routing on Global Title).

If ANSI T1.112 SCCP is used, the format and coding of address parameters carried by the SCCP for that purpose shall comply with ANSI specification T1.112 with the following restrictions:

1) Intra-PLMN addressing

For communication between entities within the same PLMN, a MAP SSN shall always be included in the called and calling party addresses. All other aspects of SCCP addressing are network specific.

2) Inter-PLMN addressing

- a) Called Party Address
 - SSN indicator = 1 (MAP SSN always included);
 - Global title indicator = 0010 (Global title includes translation type);
 - the Translation Type (TT) field will be coded as follows:

TT = 9, if IMSI is included;

TT = 14, if MSISDN is included;

Or TT = 10, if Network Element is included. (If TT=10, then Number Portability GTT is not invoked, if TT=14, then Number Portability GTT may be invoked).

- Routing indicator = 0 (Routing on global title);
- b) Calling Party Address
 - SSN indicator = 1 (MAP SSNs always included);
 - Point code indicator = 0;
 - Global Title indicator = 0010 (Global title includes translation type);

TT = 9, if IMSI is included;

TT = 14, if MSISDN is included;

Or TT = 10, if Network Element is included. (If TT=10, then Number Portability GTT is not invoked, if TT=14, then Number Portability GTT may be invoked).

Routing indicator = 0 (Routing on Global Title).

If a Global Title translation is required for obtaining routeing information, one of the numbering plans E.164, E.212 and E.214 is applicable.

- E.212 numbering plan.

When CCITT or ITU-T SCCP is used, an E.212 number must not be included as Global Title in an SCCP UNITDATA message. The translation of an E.212 number into a Mobile Global Title is applicable in a dialogue initiating VLR, SGSN or GGSN if the routeing information towards the HLR is derived from the subscriber's IMSI. In World Zone 1 when ANSI SCCP is used, the IMSI (E.212 number) is used as a Global Title to address the HLR. When an MS moves from one VLR service area to another, the new VLR may derive the address of the previous VLR from the Location Area Identification provided by the MS in the location registration request. The PLMN where the previous VLR is located is identified by the E.212 numbering plan elements of the Location Area Identification, i.e. the Mobile Country Code (MCC) and the Mobile Network Code (MNC).

- E.214 and E.164 numbering plans.

When CCITT or ITU-T SCCP is used, only address information belonging to either E.214 or E.164 numbering plan is allowed to be included as Global Title in the Called and Calling Party Address. In World Zone 1 when ANSI SCCP is used, the IMSI (E.212 number) is used as a Global Title to address the HLR.

If the Calling Party Address associated with the dialogue initiating message contains a Global Title, the sending network entity shall include its E.164 entity number.

When receiving an SCCP UNITDATA message, SCCP shall accept either of the valid numbering plans in the Called Party Address and in the Calling Party Address.

When CCITT or ITU-T SCCP is used and an N-UNITDATA-REQUEST primitive from TC is received, SCCP shall accept an E.164 number or an E.214 number in the Called Address and in the Calling Address. In World Zone 1 when ANSI SCCP is used, the IMSI (E.212 number) is used instead of E.214 number.

The following clauses describe the method of SCCP addressing appropriate for each entity both for the simple intra-PLMN case and where an inter-PLMN communication is required. The following entities are considered:

- the Mobile-services Switching Centre (MSC);
- the Home location Register (HLR);
- the Visitor Location Register (VLR);
- the Gateway Mobile-services Switching Centre (GMSC);
- the GSM Service Control Function (gsmSCF);
- the Interworking Mobile-services Switching Centre (IWMSC);
- the Serving GPRS Support Node (SGSN);
- the Gateway GPRS Support Node (GGSN);
- the Gateway Mobile Location Centre (GMLC).

6.1.3.2 The Mobile-services Switching Centre (MSC)

There are several cases where it is necessary to address the MSC.

6.1.3.2.1 MSC interaction during handover or relocation

The address is derived from the target Cell id or from the target RNC id.

6.1.3.2.2 MSC for short message routing

When a short message has to be routed to an MS, the GMSC addresses the VMSC by an MSC identity received from the HLR that complies with E.164 rules.

For MS originating short message, the IWMSC address is derived from the Service Centre address.

6.1.3.2.3 MSC for location request routing

When a location request for a particular MS needs to be sent to the MS"s VMSC, the GMLC addresses the VMSC using an E.164 address received from the MS"s HLR.

6.1.3.2.4 MSC for LMU Control

When a control message has to be routed to an LMU from an SMLC, the SMLC addresses the serving MSC for the LMU using an E.164 address.

6.1.3.3 The Home Location Register (HLR)

There are several cases where the HLR has to be addressed.

6.1.3.3.1 During call set-up

When a call is initiated the HLR of the called mobile subscriber will be interrogated to discover the whereabouts of the MS. The addressing required by the SCCP will be derived from the MSISDN dialled by the calling subscriber. The dialled number will be translated into either an SPC, in the case of communications within a PLMN, or a Global Title if other networks are involved (i.e. if the communication is across a PLMN boundary).

If the calling subscriber is a fixed network subscriber, the interrogation can be initiated from the Gateway MSC of the home PLMN in the general case. If the topology of the network allows it, the interrogation could be initiated from any Signalling Point that has MAP capabilities, e.g. local exchange, outgoing International Switching Centre (ISC), etc.

6.1.3.3.2 Before location updating completion

When an MS registers for the first time in a VLR, the VLR has to initiate the update location dialogue with the MS's HLR and a preceding dialogue for authentication information retrieval if the authentication information must be retrieved from the HLR. When initiating either of these dialogues, the only data for addressing the HLR that the VLR has available is contained in the IMSI, and addressing information for SCCP must be derived from it. When continuing the established update location dialogue (as with any other dialogue), the VLR must derive the routeing information towards the HLR from the Calling Party Address received with the first responding CONTINUE message until the dialogue terminating message is received. This means that the VLR must be able to address the HLR based on:

- an E.214 Mobile Global Title originally derived by the VLR from the IMSI (when CCITT or ITU-T SCCP is used), or an E.212 number originally derived from IMSI (when ANSI SCCP is used, an IMSI); or
- an E.164 HLR address; or
- in the case of intra-PLMN signalling, an SPC.

When answering with Global Title to the VLR, the HLR shall insert its E.164 address in the Calling Party Address of the SCCP message containing the first responding CONTINUE message.

If the HLR is in the same PLMN as the VLR, local translation tables may exist to derive an SPC. For authentication information retrieval and location updating via the international PSTN/ISDN signalling network that requires the use of CCITT or ITU-T SCCP, the Global Title must be derived from the IMSI, using the principles contained in CCITT Recommendation E.214 and the Numbering Plan Indicator (NPI) value referenced by the SCCP Specifications. In World Zone 1 where the ANSI SCCP is used, IMSI (E.212 number) is used as Global Title. A summary of the translation from the IMSI (CCITT Recommendation E.212) to Mobile Global Title (described in CCITT Recommendation E.214) is shown below:

- E.212 Mobile Country Code translates to E.164 Country Code;
- E.212 Mobile Network Code translates to E.164 National Destination Code;
- E.212 Mobile Subscriber Identification Number (MSIN) is carried unchanged if within the E.164 number maximum length (15 digits). If the Mobile Global Title is more than 15 digits the number is truncated to 15 by deleting the least significant digits.

This translation will be done either at the application or at SCCP level in the VLR. The Mobile Global Title thus derived will be used to address the HLR.

If location updating is triggered by an MS that roams from one MSC Area into a different MSC Area served by the same VLR, the VLR shall address the HLR in the same way as if the MS registers for the first time in the VLR.

6.1.3.3.3 After location updating completion

In this case, the subscriber's basic MSISDN has been received from the HLR during the subscriber data retrieval procedure as well as the HLR number constituting a parameter of the MAP message indicating successful completion of the update location dialogue. From either of these E.164 numbers the address information for initiating dialogues with the roaming subscriber's HLR can be derived. Also the subscriber's IMSI may be used for establishing the routeing information towards the HLR. This may apply in particular if the dialogue with the HLR is triggered by subscriber controlled input.

Thus the SCCP address of the roaming subscriber's HLR may be an SPC, or it may be a Global title consisting of the E.164 MSISDN or the E.164 number allocated to the HLR or either the E.214 Mobile Global Title derived from the IMSI if CCITT or ITU-T SCCP is used, or the IMSI if ANSI SCCP is used (ANSI SCCP is used in World Zone 1).

6.1.3.3.4 VLR restoration

If a roaming number is requested by the HLR for an IMSI that has no data record in the interrogated VLR, the VLR provides the roaming number in the dialogue terminating message. Subsequently the VLR must retrieve the authentication data from the MS's HLR, if required, and must then trigger the restore data procedure. For this purpose, the VLR has to initiate in succession two independent dialogues with the MS's HLR. The MTP and SCCP address information needed for routeing towards the HLR can be derived from the IMSI received as a parameter of the MAP message requesting the roaming number. In this case, the IMSI received from the HLR in the roaming number request shall be processed in the same way as the IMSI that is received from an MS that registers for the first time within a VLR. Alternatively to the IMSI, the Calling Party Address associated with the roaming number request may be used to obtain the routeing information towards the HLR.

6.1.3.3.5 During Network-Requested PDP Context Activation

When receiving a PDP PDU the GGSN may interrogate the HLR of the MS for information retrieval. When initiating such a dialogue, the only data for addressing the HLR that the GGSN has available is contained in the IMSI, and addressing information must be derived from it. The IMSI is obtained from the IP address or the X.25 address in the incoming IP message by means of a translation table. This means that the GGSN shall be able to address the HLR based on an E.214, (if CCITT or ITU-T SCCP is used), or E.212 (if ANSI SCCP is used), Mobile Global Title originally derived by the GGSN from the IMSI in the case of inter-PLMN signalling. In the case of intra-PLMN signalling, an SPC may also be used.

If the HLR is in the same PLMN as the GGSN, local translation tables may exist to derive an SPC. For information retrieval via the international PSTN/ISDN signalling network, the Global title must be derived from the IMSI, using the principles contained in CCITT Recommendation E.214 and the Numbering Plan Indicator (NPI) value referenced by the SCCP Specifications. A summary of the translation from the IMSI (CCITT Recommendation E.212) to Mobile Global Title (described in CCITT Recommendation E.214) is shown below:

- E.212 Mobile Country Code translates to E.164 Country Code;
- E.212 Mobile Network Code translates to E.164 National Destination Code;
- E.212 Mobile Subscriber Identification Number (MSIN) is carried unchanged if within the E.164 number maximum length (15 digits). If the Mobile Global Title is more than 15 digits the number is truncated to 15 by deleting the least significant digits.

This translation will be done either at the application or at SCCP level in the GGSN. The Mobile Global Title thus derived will be used to address the HLR.

6.1.3.3.6 Before GPRS location updating completion

When an MS registers for the first time in an SGSN, the SGSN has to initiate the update location dialogue with the MS's HLR and a preceding dialogue for authentication information retrieval if the authentication information must be retrieved from the HLR. When initiating either of these dialogues, the only data for addressing the HLR that the SGSN has available is contained in the IMSI, and addressing information for SCCP must be derived from it. When continuing the established update location dialogue (as with any other dialogue), the SGSN must derive the routeing information towards the HLR from the Calling Party Address received with the first responding CONTINUE message until the dialogue terminating message is received. This means that the SGSN must be able to address the HLR based on:

- an E.214 (if CCITT or ITU-T SCCP is used) or E.212 (if ANSI SCCP is used) Mobile Global Title originally derived by the SGSN from the IMSI; or
- an E.164 HLR address; or
- in the case of intra-PLMN signalling, an SPC.

If the HLR is in the same PLMN as the SGSN, local translation tables may exist to derive an SPC. For authentication information retrieval and location updating via the international PSTN/ISDN signalling network, the Global title must be derived from the IMSI, using the principles contained in CCITT Recommendation E.214 and the Numbering Plan Indicator (NPI) value referenced by the SCCP Specifications. A summary of the translation from the IMSI (CCITT Recommendation E.212) to Mobile Global Title (described in CCITT Recommendation E.214) is shown below:

- E.212 Mobile Country Code translates to E.164 Country Code;

- E.212 Mobile Network Code translates to E.164 National Destination Code:
- E.212 Mobile Subscriber Identification Number (MSIN) is carried unchanged if within the E.164 number maximum length (15 digits). If the Mobile Global Title is more than 15 digits the number is truncated to 15 by deleting the least significant digits.

This translation will be done either at the application or at SCCP level in the SGSN. The Mobile Global Title thus derived will be used to address the HLR.

6.1.3.3.7 After GPRS location updating completion

In this case, the subscriber's Basic MSISDN has been received from the HLR during the subscriber data retrieval procedure as well as the HLR number constituting a parameter of the MAP message indicating successful completion of the update location dialogue. From either of these E.164 numbers the address information for initiating dialogues with the roaming subscriber's HLR can be derived. Also the subscriber's IMSI may be used for establishing the routeing information towards the HLR.

Thus the SCCP address of the roaming subscriber's HLR may be an SPC, or it may be a Global title consisting of the E.164 MSISDN or the E.164 number allocated to the HLR or the E.214 Mobile Global Title derived from the IMSI.

6.1.3.3.8 Query for a Location Request

For a location request from an external client, the GMLC needs to address the home HLR of the target MS to obtain the address of the target MS's serving MSC. The GMLC uses either the international E.164 MSISDN, the international E.214 number (if CCITT or ITU-T SCCP is used) or the international E.212 number (if ANSI SCCP is used) of the MS as means to route a query to the HLR.

6.1.3.4 The Visitor Location Register (VLR)

There are several cases when the VLR needs to be addressed.

6.1.3.4.1 Inter-VLR information retrieval

When an MS moves from one VLR service area to another, the new VLR may request the IMSI and authentication sets from the previous VLR. The new VLR derives the address of the previous VLR from the Location Area Identification provided by the MS in the location registration request.

6.1.3.4.2 HLR request

The HLR will only request information from a VLR if it is aware that one of its subscribers is in the VLR service area. This means that a location updating dialogue initiated by the VLR has been successfully completed, i.e. the HLR has indicated successful completion of the update location procedure to the VLR.

When initiating dialogues towards the VLR after successful completion of location updating, the routeing information used by the HLR is derived from the E.164 VLR number received as a parameter of the MAP message initiating the update location dialogue. If the VLR is in the same PLMN as the HLR, the VLR may be addressed directly by an SPC derived from the E.164 VLR number. For dialogues via the international PSTN/ISDN signalling network, presence of the E.164 VLR number in the Called Party Address is required.

6.1.3.5 The Interworking MSC (IWMSC) for Short Message Service

The IWMSC is the interface between the mobile network and the network to access to the Short Message Service Centre. This exchange has an E.164 address known in the SGSN or in the MSC.

6.1.3.6 The Equipment Identity Register (EIR)

The EIR address is either unique or could be derived from the IMEI. The type of address is not defined.

6.1.3.7 Void

6.1.3.8 The Serving GPRS Support Node (SGSN)

The HLR will initiate dialogues towards the SGSN if it is aware that one of its subscribers is in the SGSN serving area. This means that a GPRS location updating has been successfully completed, i.e., the HLR has indicated successful completion of the GPRS location update to the SGSN. The routeing information used by the HLR is derived form the E.164 SGSN number received as parameter of the MAP message initiating the GPRS update location procedure. If the SGSN is in the same PLMN as the HLR, the SGSN may be addressed directly by an SPC derived from the E.164 SGSN number. For dialogues via the international PSTN/ISDN signalling network, the presence of the E.164 SGSN number in the Called Party Address is required.

When the GMSC initiates dialogues towards the SGSN the SGSN (MAP) SSN (See 3GPP TS 23.003 [17]) shall be included in the called party address. The routeing information used by the GMSC is derived from the E.164 SGSN number received as a parameter of the MAP message initiating the forward short message procedure. If the GMSC does not support the GPRS functionality the MSC (MAP) SSN value shall be included in the called party address.

NOTE: Every VMSC and SGSN shall have uniquely identifiable application using E.164 numbers, for the purpose of SMS over GPRS when the GMSC does not support the GPRS functionality.

6.1.3.9 The Gateway GPRS Support Node (GGSN)

The GGSN provides interworking with external packet-switched networks, network screens and routing of the Network-Requested PDP Context activation. If a Network-Requested PDP Context activation fails, the HLR will alert the GGSN when the subscriber becomes reachable. The HLR will use the E.164 GGSN number received as parameter of the MAP message reporting the failure.

6.1.3.10 The Gateway MSC (GMSC) for Short Message Service

The GMSC provides interworking with the network to access the Short Message Service Centre, the mobile network and routing of Send Routing Info For SM. The GMSC has on E.164 address known in the HLR, SGSN or MSC.

6.1.3.10A Void

6.1.3.10A.1 Void

6.1.3.10A.2 Void

6.1.3.10B The Gateway Mobile Location Centre (GMLC)

The GMLC initiates location requests on behalf of external clients. The E.164 address of the GMLC is provided to an HLR when the GMLC requests a serving MSC address or SGSN address from the HLR for a target MS. The E.164 address of the GMLC is also provided to a serving MSC or SGSN when the GMLC requests the location of a target MS served by this MSC or SGSN.

6.1.3.11 Summary table

The following tables summarise the SCCP address used for invoke operations. As a principle, within a PLMN either an SPC or a GT may be used (network operation option), whereas when addressing an entity outside the PLMN the GT must be used. The address type mentioned in the table (e.g. MSISDN) is used as GT or to derive the SPC.

For a response, the originating address passed in the invoke is used as SCCP Called Party Address. For extra-PLMN addressing the own E.164 entity address is used as SCCP Calling Party Address; for intra-PLMN addressing an SPC derived from the entity number may be used instead. When using an SPC, the SPC may be taken directly from MTP.

Table 6.1/1

to from	fixed net work	HLR	VLR	MSC	EIR	gsmSCF	SGSN	GGSN
fixed network		E:GT T:MSISDN						
Home Location Register			I:SPC/GT E:GT T:VLR NUMBER			I:SPC/GT E:GT T:gsmSCF NUMBER	I:SPC/GT E:GT T:SGSN NUMBER	I:SPC/GT E:GT T:GGSN NUMBER
Visitor Location Register		I:SPC/GT E:GT T:MGT (outside World Zone 1)/MSISDN (World Zone 1/)HLR NUMBER (note)	I:SPC/GT E:GT T:VLR NUMBER		1	I:SPC/GT E:GT T:gsmSCF NUMBER		
mobile- services switching centre		I:SPC/GT E:GT T:MSISDN	I:SPC/GT E:GT T:VLR NUMBER	I:SPC/GT E:GT T:MSC NUMBER	I:SPC/GT E:GT T:EIR NUMBER	I:SPC/GT E:GT T:gsmSCF NUMBER	I:SPC/GT E:GT T:SGSN NUMBER	
gsm Service Control Function		I:SPC/GT E:GT T:MSISDN						
Serving GPRS Support Node		I:SPC/GT E:GT T:MGT/ MSISDN/HL R NUMBER		I:SPC/GT E:GT T:MSC NUMBER	I:SPC/GT E:GT T:EIR NUMBER	I:SPC/GT E:GT T:gsmSCF NUMBER		
Gateway GPRS Support Node		I:SPC/GT E:GT T:MGT						
Gateway Mobile Location Centre		I:SPC/GT E:GT T:MSISDN, MGT (outside World Zone 1) or IMSI (World Zone 1) (note)		I:SPC/GT E:GT T:MSC NUMBER	1		I:SPC/GT E:GT T:SGSN NUMBER	-

I: Intra-PLMN.
E: Extra (Inter)-PLMN.
T: Address Type.
GT: Global Title.

MGT: E.214 Mobile Global Title. SPC: Signalling Point Code.

NOTE: Signalling Point Code.

For initiating the location updating procedure and an authentication information retrieval from the HLR preceding it, the VLR has to derive the HLR address from the IMSI of the MS. The result can be an SPC or an E.214 Mobile Global Title if CCITT or ITU-T SCCP is used, or IMSI itself if ANSI SCCP is used (ANSI SCCP is used in World Zone 1). When continuing the established update location dialogue (as with any other dialogue) the VLR must derive the routeing information towards the HLR from the Calling Party Address received with the first responding CONTINUE message until the dialogue terminating message is received.

For transactions invoked by the VLR after update location completion, the VLR may derive the information for addressing the HLR from addresses received in the course of the update location procedure (MSISDN or HLR number) or from the IMSI.

When invoking the Restore Data procedure and an authentication information retrieval from the HLR preceding it, the VLR must derive the information for addressing the HLR from the address information received in association with the roaming number request. This may be either the IMSI received as a parameter of the MAP message requesting the Roaming Number or the Calling Party Address associated with the MAP message requesting the Roaming Number.

The gsmSCF shall be addressed using more than one Global Title number. The first Global Title number is used to address a gsmSCF for MAP. The second Global Title number is used to address a gsmSCF for CAP.

For querying the HLR to obtain the VMSC address to support location services, the GMLC has to derive the HLR address from either the MSISDN or IMSI of the target MS. When using the IMSI, the result can be an SPC or an E.214 Mobile Global Title if CCITT or ITU-T SCCP is used, or IMSI itself if ANSI SCCP is used (ANSI SCCP is used in World Zone 1).

Table 6.1/2

-			
to)		GMLC
fro	m		
fixed net	work		
Home Lo	cation		
Register			
Visitor Lo	ocation		
Register			
Mobile-se	ervices		I:SPC/GT
Switching	g Centre		E:GT
			T:MLC Number
gsm Serv			I:SPC/GT
Control F	unction		E:GT T:MSISDN
Serving			I:SPC/GT
GPRS			E:GT
Support			T:MLC Number
Node			
Gateway GPRS			
Support			
Node			
Gateway	Mohile		
Location			
1:	Intra-PLM	IN	
:: E:		er)-PLMN.	
T:	Address		
GT:	Global Ti		
MGT:		bile Global Title.	
SPC:		Point Code.	
<u> </u>	Orginaliing	j i din Odde.	

6.2 Use of TC

The Mobile Application part makes use of the services offered by the Transaction Capabilities (TC) of Signalling System No. 7. ETS 300 287, which is based on CCITT White Book Recommendations Q.771 to Q.775, should be consulted for the full specification of TC.

The MAP uses all the services provided by TC except the ones related to the unstructured dialogue facility.

From a modelling perspective, the MAP is viewed as a single Application Service Element. Further structuring of it is for further study.

Transaction Capabilities refers to a protocol structure above the network layer interface (i.e., the SCCP service interface) up to the application layer including common application service elements but not the specific application service elements using them.

TC is structured as a Component sub-layer above a Transaction sub-layer.

The Component sub-layer provides two types of application services: services for the control of end-to-end dialogues and services for Remote Operation handling. These services are accessed using the TC-Dialogue handling primitives and TC-Component handling primitives respectively.

Services for dialogue control include the ability to exchange information related to application-context negotiation as well as initialisation data.

Services for Remote Operation handling provide for the exchange of protocol data units invoking tasks (operations), and reporting their outcomes (results or errors) plus any non-application-specific protocol errors detected by the component sub-layer. The reporting of application-specific protocol errors by the TC user, as distinct from application process errors, is also provided. The Transaction sub-layer provides a simple end-to-end connection association service over which several related protocol data units (i.e. built by the Component Sub-Layer) can be exchanged. A Transaction termination can be prearranged (no indication provided to the TC user) or basic (indication provided).

7 General on MAP services

7.1 Terminology and definitions

The term service is used in clauses 7 to 12 as defined in CCITT Recommendation X.200. The service definition conventions of CCITT Recommendation X.210 are also used.

7.2 Modelling principles

MAP provides its users with a specified set of services and can be viewed by its users as a "black box" or abstract machine representing the MAP service-provider. The service interface can then be depicted as shown in figure 7.2/1.




Figure 7.2/1: Modelling principles

The MAP service-users interact with the MAP service-provider by issuing or receiving MAP service-primitives at the service interface.

A MAP service-user may receive services from several instances of the MAP service-provider at the same time. In such cases the overall procedure is synchronised by the service-user.

The MAP service-primitives are named using the following notation:

MAP-ServicePrimitiveName type

where **type** can be any of: request (req), indication (ind), response (rsp) or confirm (cnf). (In the user arrow diagrams type is not indicated in the case of req/ind and indicated as "ack" in the case of rsp/cnf).

The services are further classified as unconfirmed-service, confirmed-service and provider-initiated-service where the first two categories refer to whether or not the service is confirmed by the service-provider. The confirmation may or may not correspond to a response provided by the other service-user.

MAP services are also classified as common MAP services that are available to all MAP service-users, and MAP service-user specific services, which are services available to one or several, but not all, MAP service-users.

A MAP dialogue is defined as an exchange of information between two MAP users in order to perform a common task. A MAP dialogue will consist of one or several MAP services.

7.3 Common MAP services

All MAP service-users require access to services for performing basic application layer functions:

- for establishing and clearing MAP dialogues between peer MAP service-users;
- for accessing functions supported by layers below the applications layer;
- for reporting abnormal situations;
- for handling of different MAP versions;
- for testing whether or not a persistent MAP dialogue is still active at each side.

For these purposes the following common services are defined:

- MAP-OPEN service;
- MAP-CLOSE service;
- MAP-DELIMITER service;
- MAP-U-ABORT service;
- MAP-P-ABORT service;
- MAP-NOTICE service.

In defining the service-primitives the following convention is used for categorising parameters:

- M the inclusion of the parameter is mandatory. The M category can be used for any primitive type and specifies that the corresponding parameter must be present in the indicated primitive type;
- O the inclusion of the parameter is a service-provider option. The O category can be used in indication and confirm type primitives and is used for parameters that may optionally be included by the service-provider;
- U the inclusion of the parameter is a service-user option. The U category can be used in request and response type primitives. The inclusion of the corresponding parameter is the choice of the service-user;
- C the inclusion of the parameter is conditional. The C category can be used for the following purposes:
 - to indicate that if the parameter is received from another entity it must be included for the service being considered;
 - to indicate that the service user must decide whether to include the parameter, based on the context on which the service is used;

- to indicate that one of a number of mutually exclusive parameters must be included (e.g. parameters indicating a positive result versus parameters indicating a negative result);
- to indicate that a service user optional parameter (marked "U") or a conditional parameter (marked "C") presented by the service user in a request or response type primitive is to be presented to the service user in the corresponding indication or confirm type primitive;
- (=) when appended to one of the above, this symbol means that the parameter takes the same value as the parameter appearing immediately to its left;

blank the parameter is not present.

A primitive type may also be without parameters, i.e. no parameter is required with the primitive type; in this case the corresponding column of the table is empty.

7.3.1 MAP-OPEN service

This service is used for establishing a MAP dialogue between two MAP service-users. The service is a confirmed service with service primitives as shown in table 7.3/1.

Request Indication Response Confirm **Parameters** U Application context name Μ M(=)C(=)Destination address Μ M(=)Destination reference U C(=)U Originating address 0 U Originating reference C(=)Specific information U U C(=) C(=)Responding address U C(=) Result М M(=)

Table 7.3/1: Service-primitives for the MAP-OPEN service

Application context name:

Refuse-reason

Provider error

This parameter identifies the type of application context being established. If the dialogue is accepted the received application context name shall be echoed. In case of refusal of dialogue this parameter shall indicate the highest version supported.

С

C(=)

Destination address:

A valid SCCP address identifying the destination peer entity (see also clause 6). As an implementation option, this parameter may also, in the indication, be implicitly associated with the service access point at which the primitive is issued.

Destination-reference:

This parameter is a reference that refines the identification of the called process. It may be identical to Destination address but its value is to be carried at MAP level. Table 7.3/2 describes the MAP services using this parameter. Only these services are allowed to use it.

Table 7.3/2: Use of the destination reference

MAP service	Reference type	Use of the parameter
MAP-REGISTER-SS	IMSI	Subscriber identity
MAP-ERASE-SS	IMSI	Subscriber identity
MAP-ACTIVATE-SS	IMSI	Subscriber identity
MAD DE LORMANTE GO	T n rev	
MAP-DEACTIVATE-SS	IMSI	Subscriber identity
MAD INTEDDOCATE CC	IMCI	Calandian identita
MAP-INTERROGATE-SS	IMSI	Subscriber identity
MAP-REGISTER-PASSWORD	IMSI	Subscriber identity
WAI -REGISTER-I ASSWORD	IMBI	Subscriber identity
MAP-PROCESS-UNSTRUCTURED-	IMSI (note 1)	Subscriber identity
SS-REQUEST	(
MAP-UNSTRUCTURED-	IMSI (note 2)	Subscriber identity
SS-REQUEST		
	T	
MAP-UNSTRUCTURED-SS-NOTIFY	IMSI (note 2)	Subscriber identity
	T	
MAP-FORWARD-SHORT-MESSAGE	IMSI (note 3)	Subscriber identity
MAD DECICTED OC ENTERN	TMCI	G 1 21 21 24
MAP-REGISTER-CC-ENTRY	IMSI	Subscriber identity
MAP-ERASE-CC-ENTRY	IMSI	Subscriber identity
MAP-ERASE-CC-ENTRY	11/151	Subscriber identity

- NOTE 1: On the HLR HLR interface and on the HLR gsmSCF interface the Destination reference shall be either IMSI or MSISDN.
- NOTE 2: On the gsmSCF HLR interface and on the HLR HLR interface the Destination reference shall be either IMSI or MSISDN.
- NOTE 3: Only when the IMSI and the LMSI are received together from the HLR in the mobile terminated short message transfer.

Originating address:

A valid SCCP address identifying the requestor of a MAP dialogue (see also clause 6). As an implementation option, this parameter may also, in the request, be implicitly associated with the service access point at which the primitive is issued.

Originating-reference:

This parameter is a reference that refines the identification of the calling process. It may be identical to the Originating address but its value is to be carried at MAP level. Table 7.3/3 describes the MAP services using the parameter. Only these services are allowed to use it. Processing of the Originating-reference shall be performed according to the supplementary service descriptions and other service descriptions, e.g. operator determined barring. Furthermore the receiving entity may be able to use the value of the Originating-reference to screen the service indication.

Table 7.3/3: Use of the originating reference

MAP service	Reference type	Use of the parameter
MAP-REGISTER-SS	ISDN-Address-String	Originated entity address
MAP-ERASE-SS	ISDN-Address-String	Originated entity address
MAP-ACTIVATE-SS	ISDN-Address-String	Originated entity address
MAD DEACTIVATE GG	LIGDNI A 11 G. :	
MAP-DEACTIVATE-SS	ISDN-Address-String	Originated entity address
MAP-INTERROGATE-SS	ISDN-Address-String	Originated entity address
MAI-INTERROGATE-55	ISDIN-Address-String	Originated entity address
MAP-REGISTER-PASSWORD	ISDN-Address-String	Originated entity address
MAP-PROCESS-UNSTRUCTURED-	ISDN-Address-String	Originated entity address
SS-REQUEST		
MAD INCONTROL	IGDM A11 GO: ()	
MAP-UNSTRUCTURED- SS-REQUEST	ISDN-Address-String (note)	Originated entity address
MAP-UNSTRUCTURED-	ISDN-Address-String (note)	Originated entity address
SS-NOTIFY		
		,
MAP-REGISTER-CC-ENTRY	ISDN-Address-String	Originated entity address
ALLE TELLOT OF TAXABLE	Transit a :	
MAP-ERASE-CC-ENTRY	ISDN-Address-String	Originated entity address

NOTE: The Originating reference may be omitted.

Specific information:

This parameter may be used for passing any user specific information. Establishment and processing of the Specific information is not specified by GSM and shall be performed according to operator specific requirements.

Responding address:

An address identifying the responding entity. The responding address is included if required by the context (e.g. if it is different from the destination address).

Result:

This parameter indicates whether the peer accepts the dialogue.

Refuse reason:

This parameter is present only if the Result parameter indicates that the dialogue is refused. It takes one of the following values:

- Application-context-not-supported;
- Invalid-destination-reference;
- Invalid-originating-reference;
- No-reason-given;
- Remote node not reachable;
- Potential version incompatibility.

7.3.2 MAP-CLOSE service

This service is used for releasing a previously established MAP dialogue. The service may be invoked by either MAP service-user depending on rules defined within the service-user. The service is an unconfirmed service with parameters as shown in table 7.3/4.

Table 7.3/4: Service-primitives for the MAP-CLOSE service

Parameters	Request	Indication
Release method	M	
Specific Information	U	C(=)

Release method:

This parameter can take the following two values:

- normal release; in this case the primitive is mapped onto the protocol and sent to the peer;
- prearranged end; in this case the primitive is not mapped onto the protocol. Prearranged end is managed independently by the two users, i.e. only the request type primitive is required in this case.

Specific information:

This parameter may be used for passing any user specific information. Establishment and processing of the Specific information is not specified by GSM GSM and shall be performed according to operator specific requirements.

7.3.3 MAP-DELIMITER service

This service is used to explicitly request the transfer of the MAP protocol data units to the peer entities.

See also clause 7.4 and 7.5 for the detailed use of the MAP-DELIMITER service.

The service is an unconfirmed service with service-primitives as shown in table 7.3/5.

Table 7.3/5: Service-primitives for the MAP-DELIMITER service

Parameters	Request	Indication

7.3.4 MAP-U-ABORT service

This service enables the service-user to request the MAP dialogue to be aborted. The service is an unconfirmed service with service-primitives as shown in table 7.3/6.

Table 7.3/6: Service-primitives for the MAP-U-ABORT service

Parameters	Request	Indication
User reason	M	M(=)
Diagnostic information	U	C(=)
Specific information	U	C(=)

<u>User reason</u>:

This parameter can take the following values:

- resource limitation (congestion);
 - the requested user resource is unavailable due to congestion;
- resource unavailable;

the requested user resource is unavailable for reasons other than congestion;

- application procedure cancellation;
 - the procedure is cancelled for reasons detailed in the diagnostic information parameter;
- procedure error;
 - processing of the procedure is terminated for procedural reasons.

Diagnostic information:

This parameter may be used to give additional information for some of the values of the user-reason parameter:

Table 7.3/7: User reason and diagnostic information

User reason	Diagnostic information
Resource limitation (congestion)	-
Resource unavailable	Short term/long term problem
Application procedure cancellation	Handover cancellation/
	Radio Channel release/
	Network path release/
	Call release/
	Associated procedure failure/
	Tandem dialogue released/
	Remote operations failure
Procedure error	-

Specific information:

This parameter may be used for passing any user specific information. Establishment and processing of the Specific information is not specified by GSM and shall be performed according to operator specific requirements.

7.3.5 MAP-P-ABORT service

This service enables the MAP service-provider to abort a MAP dialogue. The service is a provider-initiated service with service-primitives as shown in table 7.3/8.

Table 7.3/8: Service-primitives for the MAP-P-ABORT service

Parameters	Indication
Provider reason	М
Source	М

Provider reason:

This parameter indicates the reason for aborting the MAP dialogue:

- provider malfunction;
- supporting dialogue/transaction released;
- resource limitation;
- maintenance activity;
- version incompatibility;
- abnormal MAP dialogue.

Source:

This parameter indicates the source of the abort. For Transaction Capabilities (TC) applications the parameter may take the following values:

- MAP problem;
- TC problem;
- network service problem.

Table 7.3/9: Values of provider reason and source parameters and examples of corresponding events

Provider reason	Source	Corresponding event
Provider	MAP	Malfunction at MAP level at peer entity
malfunction	TC	"Unrecognised message type" or
		"Badly formatted transaction portion" or
		"Incorrect transaction portion" received in TC-P-ABORT
		"Abnormal dialogue"
	Network service	Malfunction at network service level at peer entity
Supporting dialogue/		
transaction released		
	TC	"Unrecognised transaction ID" received in TC-ABORT
Resource	MAP	Congestion towards MAP peer service-user
limitation	TC	"Resource limitation" received in TC-P-ABORT
Maintenance	MAP	Maintenance at MAP peer service-user
activity	Network service	Maintenance at network peer service level
Abnormal MAP	MAP	MAP dialogue is not in accordance with specified
dialogue		application context
Version	TC	A Provider Abort indicating "No common dialogue portion"
incompatibility		is received in the dialogue initiated state

7.3.6 MAP-NOTICE service

This service is used to notify the MAP service-user about protocol problems related to a MAP dialogue not affecting the state of the protocol machines.

The service is a provider-initiated service with service-primitive as shown in table 7.3/10.

Table 7.3/10: Service-primitive for the MAP-NOTICE service

Parameters	Indication
Problem diagnostic	M

Problem diagnostic:

This parameter can take one of the following values:

- abnormal event detected by the peer;
- response rejected by the peer;
- abnormal event received from the peer;
- message cannot be delivered to the peer.

- 7.3.7 void
- 7.3.8 void
- 7.3.9 void
- 7.3.10 void

7.4 Sequencing of services

The sequencing of services is shown in figure 7.4/1 and is as follows:

Opening:

The MAP-OPEN service is invoked before any user specific service-primitive is accepted. The sequence may contain none, one or several user specific service-primitives. If no user specific service-primitive is contained between the MAP-OPEN and the MAP-DELIMITER primitives, then this will correspond to sending an empty Begin message in TC. If more than one user specific service-primitive is included, all are to be sent in the same Begin message. The sequence ends with a MAP-DELIMITER primitive.

Continuing:

This sequence may not be present in some MAP dialogues. If it is present, it ends with a MAP-DELIMITER primitive. If more than one user specific service-primitive is included, all are to be included in the same Continue message.

Closing:


The sequence can only appear after an opening sequence or a continuing sequence. The sequence may contain none, one or several user specific service-primitives if the MAP-CLOSE primitive specifies normal release. If no user specific service-primitive is included, then this will correspond to sending an empty End message in TC. If more than one user specific service-primitive is included, all are to be sent in the same End message. If prearranged end is specified, the sequence cannot contain any user specific service-primitive. The MAP-CLOSE primitive must be sent after all user specific service-primitives have been delivered to the MAP service-provider.

Aborting:

A MAP service-user can issue a MAP-U-ABORT primitive at any time after the MAP dialogue has been opened or as a response to an attempt to open a MAP dialogue.

The MAP service-provider may issue at any time a MAP-P-ABORT primitive towards a MAP service-user for which a MAP dialogue exists.

MAP-U-ABORT primitives and MAP-P-ABORT primitives terminate the MAP dialogue.






Figure 7.4/1: Sequencing of services

If the reason "resource unavailable (short term problem)" is indicated in the MAP-U-ABORT indication primitive, the MAP service-user may decide to attempt a new MAP dialogue establishment immediately.

Sequencing of user specific service-primitives is done by the MAP service-user and based on rules applicable for each MAP service-user instance.

A MAP-NOTICE indication primitive may be received at any time during the active period of a MAP dialogue.

7.5 General rules for mapping of services onto TC

7.5.1 Mapping of common services

Table 7.5/1 gives an overview of the mapping rules for mapping of common services onto TC-services. Table 7.5/2 gives the mapping rules for mapping of TC-services onto common services.

Protocol machine description is given in clauses 14 to 17.

Table 7.5/1: Mapping of common services onto TC services

MAP service-primitive	TC service-primitive		
MAP-OPEN request			
(+ any user specific service primitives)	TC-BEGIN request		
+ MAP-DELIMITER request	(+ component handling primitives)		
MAP-OPEN response			
(+ any user specific service primitives)	TC-CONTINUE request (note)		
+ MAP-DELIMITER request	(+ component handling primitives)		
(any user specific service primitives)	TC-CONTINUE request		
+ MAP-DELIMITER request	(+ component handling primitives)		
(any user specific service primitives)	TC-END request		
+ MAP-CLOSE request	(+ component handling primitives)		

	MAP-U-ABORT request	TC-U-ABORT request
NOTE:	Or TC-END if the MAP-CLOSE request has	s been received before the MAP-DELIMITER
	request.	

Table 7.5/2: Mapping of TC services onto common service

TC service-primitive	MAP service-primitive		
TC-BEGIN indication	MAP-OPEN indication		
(+ component handling primitives)	(+ user specific service primitives)		
	+ MAP-DELIMITER indication (note 1)		
TC-CONTINUE indication	First time:		
(+ component handling primitives)	MAP-OPEN confirm		
	(+ user specific service primitives)		
	+ MAP-DELIMITER indication (note 1)		
	Subsequent times:		
	Subsequent times:		
	(user specific service primitives)		
TO END indication	+ MAP-DELIMITER indication (note 1)		
TC-END indication	MAP-OPEN confirm (note 6)		
(+ component handling primitives)	(user specific service primitives)		
	+ MAP-CLOSE indication		
TC-U-ABORT indication	MAP-U-ABORT indication or		
	MAP-P-ABORT indication (note 2)		
	MAP-OPEN confirmation (note 3)		
TC-P-ABORT indication	MAP-P-ABORT indication (note 4)		
	MAP-OPEN confirmation (note 5)		
NOTE 1: It may not be necessary to present this p			
NOTE 2: The mapping depends on whether the To			
	ervice-provider or a MAP-user-abort-PDU from the		
remote MAP service-user.			
NOTE 3: Only if the opening sequence is pending and if the "Abort Reason" in the TC-U-ABORT indication			
is set to "Application Context Not Supported".			
NOTE 4: If the "Abort Reason" in the TC-P-ABORT indication is set to a value different from "Incorrect Transaction Portion".			
	and if the "Abort Reason" in the TC-P-ABORT indication		
NOTE 5: Only if the opening sequence is pending and if the "Abort Reason" in the TC-P-ABORT indication is set to "Incorrect Transaction Portion".			
NOTE 6: Only if opening sequence is pending.			

7.5.2 Mapping of user specific services

Table 7.5/3 gives the general mapping rules which apply to mapping of MAP user specific services onto TC services and table 7.5/4 gives the similar rules for mapping of TC services onto MAP user specific services. Detailed mapping is given in clauses 14 to 17.

Table 7.5/3: Mapping of MAP user specific services onto TC services

MAP service-primitive	TC-service-primitive
MAP-xx request	TC-INVOKE request
MAP-xx response	TC-RESULT-L request
(note 1)	TC-U-ERROR request
	TC-U-REJECT request
	TC-INVOKE request (note 2)

Table 7.5/4: Mapping of TC services onto MAP user specific services

TC-service-primitive	MAP service-primitive
TC-INVOKE indication	MAP-xx indication
TC-RESULT-L indication (note 4)	MAP-xx confirm
TC-U-ERROR indication	
TC-INVOKE indication (note 2)	

TC-L-CANCEL indication	
TC-U-REJECT indication	MAP-xx confirm or
TC-L-REJECT indication	MAP-NOTICE indication (note 3)
TC-R-REJECT indication	·

Notes to tables 7.5/3 and 7.5/4:

NOTE 1: The mapping is determined by parameters contained in the MAP-xx response primitive.

NOTE 2: This applies only to TC class 4 operations where the operation is used to pass a result of another class 2 or class 4 operation.

NOTE 3: The detailed mapping rules are given in clause 16.

NOTE 4: If RESULT-NL components are present they are mapped onto the same MAP-xx confirm.

7.6 Definition of parameters

7.6.1 Common parameters

The following set of parameters is used in several MAP service-primitives.

7.6.1.1 Invoke Id

This parameter identifies corresponding service primitives. The parameter is supplied by the MAP service-user and must be unique over each service-user/service-provider interface.

7.6.1.2 Linked Id

This parameter is used for linked services and it takes the value of the invoke Id of the service linked to.

7.6.1.3 Provider error

This parameter is used to indicate a protocol related type of error:

- duplicated invoke Id;
- not supported service;
- mistyped parameter;
- resource limitation;
- initiating release, i.e. the peer has already initiated release of the dialogue and the service has to be released;
- unexpected response from the peer;
- service completion failure;
- no response from the peer;
- invalid response received.

7.6.1.4 User error

This parameter can take values as follows:

NOTE: The values are grouped in order to improve readability; the grouping has no other significance.

a) Generic error:

- system failure, i.e. a task cannot be performed because of a problem in another entity. The type of entity or network resource may be indicated by use of the network resource parameter or additional network resource parameter;
- data missing, i.e. an optional parameter required by the context is missing;
- unexpected data value, i.e. the data type is formally correct but its value or presence is unexpected in the current context;
- resource limitation;
- initiating release, i.e. the receiving entity has started the release procedure;
- facility not supported, i.e. the requested facility is not supported by the PLMN with detailed reasons as follows:
 - Shape of location estimate not supported;
 - Needed LCS capability not supported in serving node;
- incompatible terminal, i.e. the requested facility is not supported by the terminal.

b) Identification or numbering problem:

- unknown subscriber, i.e. no such subscription exists;
- number changed, i.e. the subscription does not exist for that number any more;
- unknown MSC:
- unidentified subscriber, i.e. if the subscriber is not contained in the database and it has not or cannot be established whether or not a subscription exists;
- unallocated roaming number;
- unknown equipment;
- unknown location area.

c) Subscription problem:

- roaming not allowed, i.e. a location updating attempt is made in an area not covered by the subscription;
- illegal subscriber, i.e. illegality of the access has been established by use of authentication procedure;
- bearer service not provisioned;
- teleservice not provisioned;
- illegal equipment, i.e. the IMEI check procedure has shown that the IMEI is blacklisted or not whitelisted.

d) Handover problem:

- no handover number available, i.e. the VLR cannot allocate a number for handover or cannot allocate the required amount of numbers for relocation;
- subsequent handover failure, i.e. handover to a third MSC failed for some reason;
- target cell outside group call area.

e) Operation and maintenance problem:

- tracing buffer full, i.e. tracing cannot be performed because the tracing capacity is exceeded.

f) Call set-up problem:

- no roaming number available, i.e. a roaming number cannot be allocated because all available numbers are in use;

- absent subscriber, i.e. the subscriber has activated the detach service or the system detects the absence condition. This error may be qualified to indicate whether the subscriber was IMSI detached, in a restricted area or did not respond to paging;
- busy subscriber. This error may be qualified to indicate that the subscriber was busy due to CCBS and that CCBS is possible;
- no subscriber reply;
- forwarding violation, i.e. the call has already been forwarded the maximum number of times that is allowed;
- CUG reject, i.e. the call does not pass a CUG check; additional information may also be given in order to indicate rejection due to e.g. incoming call barred or non-CUG membership;
- call barred. Optionally, additional information may be included for indicating either that the call meets a barring condition set by the subscriber or that the call is barred for operator reasons. In the case of barring of Mobile Terminating Short Message, the additional information may indicate a barring condition due to "Unauthorised Message Originator";
- optimal routeing not allowed, i.e. the entity which sends the error does not support optimal routeing, or the HLR will not accept an optimal routeing interrogation from the GMSC, or the call cannot be optimally routed because it would contravene optimal routeing constraints;
- forwarding failed, i.e. the GMSC interrogated the HLR for forwarding information but the HLR returned an error.
- g) Supplementary services problem:
 - call barred;
 - illegal SS operation;
 - SS error status;
 - SS not available;
 - SS subscription violation;
 - SS incompatibility;
 - negative password check;
 - password registration failure;
 - Number of Password Attempts;
 - USSD Busy;
 - Unknown Alphabet;
 - short term denial;
 - long term denial.

For definition of these errors see 3GPP TS 24.080 [38].

- h) Short message problem:
 - SM delivery failure with detailed reason as follows:
 - memory capacity exceeded;
 - MS protocol error;
 - MS not equipped;
 - unknown service centre (SC);

- SC congestion;
- invalid SME address;
- subscriber is not an SC subscriber;
- and possibly detailed diagnostic information, coded as specified in 3GPP TS 23.040, under SMS-SUBMIT-REPORT and SMS-DELIVERY-REPORT. If the SM entity that returns the SM Delivery Failure error includes detailed diagnostic information, it shall be forwarded in the MAP_MO_FORWARD_SHORT_MESSAGE and in the MAP_MT_FORWARD_SHORT_MESSAGE response.
- message waiting list full, i.e. no further SC address can be added to the message waiting list.
- Subscriber busy for MT SMS, i.e. the mobile terminated short message transfer cannot be completed because:
 - another mobile terminated short message transfer is going on and the delivery node does not support message buffering; or
 - another mobile terminated short message transfer is going on and it is not possible to buffer the message for later delivery; or
 - the message was buffered but it is not possible to deliver the message before the expiry of the buffering time defined in 3GPP TS 23.040;
- Absent Subscriber SM, i.e. the mobile terminated short message transfer cannot be completed because the network cannot contact the subscriber. Diagnostic information regarding the reason for the subscriber's absence may be included with this error.
- i) Location services problem:
 - Unauthorised Requesting Network
 - Unauthorised LCS Client with detailed reasons as follows:
 - NoAdditional Information
 - Client not in MS Privacy Exception List
 - Call to Client not setup
 - Disallowed by Local Regulatory Requirements
 - Unauthorised Privacy Class
 - Unauthorised Call/Session Unrelated External Client
 - Unauthorised Call/Session Related External Client
 - Privacy override not applicable
 - Position method failure with detailed reasons as follows:
 - Congestion
 - Insufficient resources
 - Insufficient Measurement Data
 - Inconsistent Measurement Data
 - Location procedure not completed
 - QoS not attainable
 - Position Method Not Available in Network

- Position Method Not Available in Location Area
- Unknown or unreachable LCS Client.
- j) Problem detected by an application using secure transport:
 - Secure transport error. This error indicates that the application using secure transport returned an error. The parameter of the error indicates:
 - The protected payload, which carries the result of applying the protection function specified in 3GPP TS 33.200 to the encoding of the parameter of the original error.

7.6.1.5 All Information Sent

This parameter indicates to the receiving entity when the sending entity has sent all necessary information.

7.6.2 Numbering and identification parameters

7.6.2.1 IMSI

This parameter is the International Mobile Subscriber Identity defined in 3GPP TS 23.003 [17].

7.6.2.2 TMSI

This parameter is the Temporary Mobile Subscriber Identity defined in 3GPP TS 23.003 [17].

7.6.2.3 IMEI

This parameter is the International Mobile Equipment Identity defined in 3GPP TS 23.003 [17].

7.6.2.3a IMEISV

This parameter is the International Mobile Equipment Identity and Software Version Number defined in 3GPP TS 23.003 [17].

7.6.2.4 Previous location area Id

This parameter refers to the identity of the location area from which the subscriber has roamed.

7.6.2.5 Stored location area ld

This parameter refers to the location area where the subscriber is assumed to be located.

7.6.2.6 Current location area ld

This parameter is used to indicate the location area in which the subscriber is currently located.

7.6.2.7 Target location area ld

This parameter refers to the location area into which the subscriber intends to roam.

7.6.2.8 Target cell ld

This parameter refers to the identity of the cell to which a call has to be handed over.

7.6.2.8A Target RNC Id

This parameter refers to the identity of the RNC to which a call has to be relocated.

7.6.2.9 Void

7.6.2.10 Originating entity number

This parameter refers to an application layer identification of a system component in terms of its associated ISDN number.

7.6.2.11 MSC number

This parameter refers to the ISDN number of an MSC.

7.6.2.12 Target MSC number

This parameter refers to the ISDN number of an MSC to which a call has to be handed over.

7.6.2.13 HLR number

This parameter refers to the ISDN number of an HLR.

7.6.2.14 VLR number

This parameter refers to the ISDN number of a VLR.

7.6.2.15 HLR Id

This parameter refers to the identity of an HLR derived from the IMSI defined in CCITT Recommendation E.212.

7.6.2.16 LMSI

This parameter refers to a local identity allocated by the VLR to a given subscriber for internal management of data in the VLR. LMSI shall not be sent to the SGSN.

7.6.2.17 MS ISDN

This parameter refers to one of the ISDN numbers assigned to a mobile subscriber in accordance with CCITT Recommendation E.213.

7.6.2.18 OMC ld

This parameter refers to the identity of an Operation and Maintenance Centre.

7.6.2.19 Roaming number

This parameter refers to the roaming number as defined in CCITT Recommendation E.213.

7.6.2.19A Relocation Number List

This parameter refers to the number(s) used for routing one call or several calls between MSCs during relocation.

7.6.2.20 Void

7.6.2.21 Handover number

This parameter refers to the number used for routing a call between MSCs during handover.

7.6.2.22 Forwarded-to number

This parameter refers to the address to which a call is to be forwarded. A subaddress may be appended. For subscribers having an originating CAMEL Phase 2 or higher subscription, this address need not be in E.164 international format.

7.6.2.22A Long forwarded-to number

This parameter refers to the address to which a call is to be forwarded. A subaddress may be appended. For subscribers having an originating CAMEL Phase 2 or higher subscription this address need not be in international format.

7.6.2.22B Long FTN Supported

This parameter indicates that the sending entity supports Long Forwarded-to Numbers.

7.6.2.23 Forwarded-to subaddress

This parameter refers to the sub-address attached to the address to which a call is to be forwarded.

7.6.2.24 Called number

This parameter refers to a called party number as defined in CCITT Recommendation Q.767.

7.6.2.25 Calling number

This parameter refers to a calling party number as defined in CCITT Recommendation Q.767.

7.6.2.26 Originally dialled number

This parameter refers to the number dialled by the calling party in order to reach a mobile subscriber.

7.6.2.27 Service centre address

This parameter represents the address of a Short Message Service Centre.

7.6.2.28 Zone Code

This parameter is used to define location areas into which the subscriber is allowed or not allowed to roam (regional subscription). With a complete list of Zone Codes the VLR or the SGSN is able to determine for all its location areas whether roaming is allowed or not.

7.6.2.29 MSIsdn-Alert

This parameter refers to the MSISDN stored in a Message Waiting Data File in the HLR. It is used to alert the Service Centre when the MS is again attainable.

7.6.2.30 Location Information

This parameter indicates the location of the served subscriber as defined in 3GPP TS 23.018 [97].

7.6.2.30a Location Information for GPRS

This parameter indicates the location of the served subscriber as defined in 3GPP TS 23.078 [98].

7.6.2.31 GMSC Address

This parameter refers to the E.164 address of a GMSC.

7.6.2.32 VMSC Address

This parameter refers to the E.164 address of a VMSC.

7.6.2.33 Group ld

This parameter is used to describe groups a subscriber can be a member of. A subscriber can partake in all group calls (VBS/VGCS) where he subscribed to the respective groups.

7.6.2.34 North American Equal Access preferred Carrier Id

This parameter refers to the carrier identity preferred by the subscriber for calls requiring routing via an inter-exchange carrier. This identity is used at:

- outgoing calls: when the subscriber does not specify at call set-up a carrier identity;
- forwarded calls: when a call is forwarded by the subscriber;
- incoming calls: applicable to the roaming leg of the call.

7.6.2.35 Void

7.6.2.36 Void

7.6.2.37 Serving cell ld

This parameter indicates the cell currently being used by the served subscriber.

7.6.2.38 SGSN number

This parameter refers to the ISDN number of a SGSN.

7.6.2.39 SGSN address

This parameter refers to the IP-address of a SGSN. This parameter is defined in 3GPP TS 23.003 [17].

7.6.2.40 GGSN address

This parameter refers to the IP-address of a GGSN. This parameter is defined in 3GPP TS 23.003 [17].

7.6.2.41 GGSN number

This parameter refers to the ISDN number of a GGSN or the ISDN number of the protocol-converter if a protocol-converting GSN is used between the GGSN and the HLR.

7.6.2.42 APN

This parameter refers to the DNS name of a GGSN. This parameter is defined in 3GPP TS 23.060 [104].

7.6.2.43 Network Node number

This parameter refers either to the ISDN number of SGSN or to the ISDN number of MSC.

7.6.2.44 PDP-Type

This parameter indicates which type of protocol is used by the MS as defined in 3GPP TS 23.060 [104].

7.6.2.45 PDP-Address

This parameter indicates the address of the data protocol as defined in 3GPP TS 23.060 [104].

7.6.2.46 Additional number

This parameter can refer either to the SGSN number or to the MSC number.

7.6.2.47 P-TMSI

This parameter is the Packet Temporary Mobile Subscriber Identity defined in 3GPP TS 23.003 [17].

7.6.2.48 B-subscriber number

This parameter refers to the number of the destination B dialled by the A user. This may include a subaddress.

7.6.2.49 B-subscriber subaddress

This parameter refers to the sub-address attached to the destination B dialled by the A user.

7.6.2.50 LMU Number

This parameter refers to a local number assigned to an LMU by an SMLC.

7.6.2.51 MLC Number

This parameter refers to the ISDN (E.164) number of an MLC.

7.6.2.52 Multicall Bearer Information

This parameter refers to the number of simultaneous bearers supported per user by the serving network.

7.6.2.53 Multiple Bearer Requested

This parameter indicates whether multiple bearers are requested for a relocation.

7.6.2.54 Multiple Bearer Not Supported

This parameter indicates whether multiple bearers are supported.

7.6.2.55 PDP-Charging Characteristics

This parameter indicates the charging characteristics associated with a specific PDP context as defined in 3GPP TS 32.215.

7.6.2.56 Selected RAB ID

The selected radio access bearer to be kept at subsequent inter-MSC handover from UMTS to GSM.

7.6.2.57 RAB ID

This parameter indicates the radio access bearer identifier as defined in 3GPP TS 25.413. This parameter is used to relate the radio resources with the radio access bearers.

7.6.2.58 gsmSCF Address

This parameter refers to the ISDN number assigned to the gsmSCF address. In an IP Multimedia Core Network, the gsmSCF-address shall contain the IM-SSF address when the IM-SSF takes the role of the gsmSCF.

7.6.2.59 V-GMLC Address

This parameter refers to the IP address of a V-GMLC.

7.6.2.60 Void

7.6.2.61 H-GMLC Address

This parameter refers to the IP address of a H-GMLC.

7.6.2.62 PPR Address

This parameter refers to the IP address of a Privacy Profile Register.

7.6.2.63 Routeing Number

This parameter refers to a number used for routing purpose and identifying a network operator. See 3GPP TS 23.066 [108].

7.6.2.64 Additional V-GMLC Address

This parameter refers to the IP address of a V-GMLC.

7.6.3 Subscriber management parameters

7.6.3.1 Category

This parameter refers to the calling party category as defined in CCITT Recommendation Q.767.

7.6.3.2 Equipment status

This parameter refers to the status of the mobile equipment as defined in 3GPP TS 22.016 [7].

7.6.3.2a BMUEF

This parameter refers to the Bit Map of UE Faults and corresponds to the UESBI-Iu parameter defined in 3GPP TS 25.413 [120].

7.6.3.3 Extensible Bearer service

This parameter may refer to a single bearer service, a set of bearer services or to all bearer services as defined in 3GPP TS 22.002 [3]. This parameter is used only for subscriber profile management. Extensible Bearer service values include all values defined for a Bearer service parameter (7.6.4.38).

7.6.3.4 Extensible Teleservice

This parameter may refer to a single teleservice, a set of teleservices or to all teleservices as defined in 3GPP TS 22.003 [4]. This parameter is used only for subscriber profile management. Extensible Teleservice values include all values defined for a Teleservice parameter (7.6.4.39).

7.6.3.5 Extensible Basic Service Group

This parameter refers to the Basic Service Group either as an extensible bearer service (see clause 7.6.3.3) or an extensible teleservice (see clause 7.6.3.4). This parameter is used only for subscriber profile management. The null value (i.e. neither extensible bearer service nor extensible teleservice) is used to denote the group containing all extensible bearer services and all extensible teleservices.

7.6.3.6 GSM bearer capability

This parameter refers to the GSM bearer capability information element defined in 3GPP TS 24.008 [35].

7.6.3.7 Subscriber Status

This parameter refers to the barring status of the subscriber:

- service granted;
- Operator Determined Barring.

7.6.3.8 CUG Outgoing Access indicator

This parameter represents the Outgoing Access as defined in ETS 300 136.

7.6.3.9 Operator Determined Barring General Data

This parameter refers to the set of subscriber features that the network operator or the service provider can regulate. This set only includes those limitations that can be

- a) controlled in the VLR,
- b) controlled in the SGSN,
- c) controlled in the SGSN applied for short message transfer only,
- d) interrogated or modified by the gsmSCF:

ODB category	Controlled in the VLR	Controlled in the SGSN	Controlled in the SGSN applied for short message transfer only	Interrogatable and modifyable by the gsmSCF
All outgoing calls barred	X		X	X
International outgoing calls barred	X		X	X
International outgoing calls except those to the home PLMN country barred	X		X	X
Interzonal outgoing calls barred	X		X	X
Interzonal outgoing calls except those to the home PLMN country barred	X		X	X
Interzonal outgoing calls AND international outgoing calls except those directed to the home PLMN country barred	X		X	X
Premium rate (information) outgoing calls barred	X			X

		1	
Premium rate (entertainment) outgoing calls barred	X		X
Supplementary service access barred	X		X
Invocation of call transfer barred	X		X
Invocation of chargeable call transfer barred	X		X
Invocation of internationally chargeable call transfer barred	X		X
Invocation of interzonally chargeable call transfer barred	X		X
Invocation of call transfer where both legs are chargeable barred	X		X
Invocation of call transfer if there is already an ongoing transferred call for the served subscriber in the serving MSC/VLR barred	X		X
All packet Oriented Services barred		X	X
Roamer Access to HPLMN-AP barred		X	X
Roamer Access to VPLMN-AP barred		X	X
Outgoing calls when roaming outside the home PLMN country			Х
All incoming calls			X
Incoming calls when roaming outside the home PLMN country			X
Incoming calls when roaming outside the zone of the home PLMN country			Х
Roaming outside the home PLMN			X
Roaming outside the home PLMN country			X

- · · · · · · · · · · · · · · · · · · ·		1	
Registration of any call			X
forwarded-to number			
Registration of any			X
international call			
forwarded-to number			
forwarded-to flumber			
Registration of any			X
international call			
forwarded-to number			
except to a number			
within the HPLMN			
country			
Registration of any			X
inter-zone call			
forwarded-to number			
Registration of any			X
inter-zone call			
forwarded-to number			
except to a number			
within the HPLMN			
country			

7.6.3.10 ODB HPLMN Specific Data

This parameter refers to the set of subscriber features that the network operator or the service provider can regulate only when the subscriber is registered in the HPLMN. This set only includes those limitations that can be controlled in the VLR or in the SGSN:

- Operator Determined Barring Type 1;
- Operator Determined Barring Type 2;
- Operator Determined Barring Type 3;
- Operator Determined Barring Type 4.

7.6.3.11 Regional Subscription Data

This parameter defines the regional subscription area in which the subscriber is allowed to roam. It consists of a list of Zone Codes (see clause 7.6.2.28).

7.6.3.12 Regional Subscription Response

This parameter indicates either that the regional subscription data cannot be handled or that the current MSC or SGSN area is entirely restricted because of regional subscription.

7.6.3.13 Roaming Restriction Due To Unsupported Feature

This parameter defines that a subscriber is not allowed to roam in the current MSC area. It may be used by the HLR if a feature or service is indicated as unsupported by the VLR.

7.6.3.14 Extensible SS-Info

This parameter refers to all the information related to a supplementary service and is a choice between:

- extensible forwarding information (see clause 7.6.3.15);
- extensible call barring information (see clause 7.6.3.20);
- CUG info (see clause 7.6.3.22);
- extensible SS-Data (see clause 7.6.3.29).

7.6.3.15 Extensible forwarding information

This parameter represents the information related to each call forwarding service:

- the SS-Code of the relevant call forwarding service (see clause 7.6.4.1);
- if required, a list of extensible forwarding feature parameters (see clause 7.6.3.16).

The list may contain one item per Basic Service Group.

7.6.3.16 Extensible forwarding feature

This parameter applies to each combination of call forwarding service and Basic Service Group and contains the following information, as required:

extensible Basic Service Group (see clause 7.6.3.5);
extensible SS-Status (see clause 7.6.3.17);
forwarded-to number (see clause 7.6.2.22);
forwarded-to subaddress (see clause 7.6.2.23);
extensible forwarding options (see clause 7.6.3.18);
extensible no reply condition timer (see clause 7.6.4.19);
long forwarded-to number (see clause 7.6.2.22A).

If a number is required to define the forwarded-to destination then:

- If the VLR supports Long Forwarded-to Numbers then the long forwarded-to number shall be present and the forwarded-to number shall be absent;
- If the VLR does not support Long Forwarded-to Numbers then the forwarded-to number shall be present and the long forwarded-to number shall be absent.

7.6.3.17 Extensible SS-Status

This parameter refers to the state information of individual supplementary services as defined in 3GPP TS 23.011 [22].

7.6.3.18 Extensible Forwarding Options

This parameter refers to a set of forwarding options attached to a supplementary service. It contains the following information:

-	notification to forwarding party parameter);	(see 3GPP TS 22.082 [10] for the meaning of this
-	redirection notification to the forwarded-to party parameter);	(see 3GPP TS 22.082 [10] for the meaning of this
-	notification to calling party parameter);	(see 3GPP TS 22.082 [10] for the meaning of this
-	redirecting presentation parameter);	(see 3GPP TS 22.082 [10] for the meaning of this

- forwarding reason parameter).

(see 3GPP TS 22.082 [10] for the meaning of this

7.6.3.19 Extensible No reply condition timer

This parameter refers to the extensible no reply condition timer for call forwarding on no reply.

7.6.3.20 Extensible Call barring information

This parameter contains for each call barring service:

- SS-Code (see clause 7.6.4.1);

- a list of extensible call barring feature parameters (see clause 7.6.3.21).

The list may contain one item per Basic Service Group.

7.6.3.21 Extensible Call barring feature

This parameter gives the status of call barring services as applicable to each Basic Service Group. The parameter contains the following information:

- Extensible Basic Service Group (see clause 7.6.3.5);

provisioned SS-Status (see clause 7.6.3.17).

7.6.3.22 CUG info

This parameter refers to the overall information required for operation for each CUG:

- CUG subscriptionList;
- CUG featureList.

7.6.3.23 CUG subscription

This parameter refers to the set of basic information for each CUG defined in that subscription. The following information is stored:

- CUG index:
- CUG interlock;
- Intra CUG restrictions;
- Basic Service Group List.

7.6.3.24 CUG interlock

This parameter represents the CUG interlock code defined in ETS 300 138.

7.6.3.25 CUG index

This parameter represents the CUG index defined in ETS 300 138.

7.6.3.26 CUG feature

This parameter contains two parameters that are associated with the Basic Service Group. If the Basic Service Group Code is not present the feature applies to all Basic Services. The following parameters are included:

- Preferential CUG indicator:

- indicates which CUG index is to be used at outgoing call set-up using the associated Basic Service Group;
- Inter CUG Option:
 - describes whether it for the associated Basic Service Group is allowed to make calls outside the CUG and whether incoming calls are allowed;
- Basic Service Group.

See 3GPP TS 22.085 [13] for meaning of this parameter.

7.6.3.27 Inter CUG options

This parameter indicates the subscribers' ability to make and receive calls outside a specific closed user group. It takes any of the following values:

- CUG only facility (only calls within CUG are allowed);
- CUG with outgoing access (calls outside CUG allowed);
- CUG with incoming access (calls from outside CUG into CUG allowed);
- CUG with both incoming and outgoing access (all calls allowed).

7.6.3.28 Intra CUG restrictions

This parameter describes whether or not the subscriber is allowed to originate calls to or to receive calls from within the CUG. It can take any of the following values:

- no CUG restrictions;
- CUG incoming calls barred;
- CUG outgoing calls barred.

7.6.3.29 Extensible SS-Data

This parameter refers to the necessary set of information required in order to characterise one supplementary service:

-	SS-Code	(see clause 7.6.4.1);
-	Extensible SS-Status (if applicable)	(see clause 7.6.3.17);
-	Extensible Override subscription option (if applicable)	(see clause 7.6.3.30);
-	Extensible CLI Restriction (if applicable)	(see clause 7.6.3.31);
_	Extensible Basic Service Group Code	(see clause 7.6.3.5).

7.6.3.30 Subscriber State

This parameter indicates the state of the MS as defined in 3GPP TS 23.018 [97].

7.6.3.31 Requested Info

This parameter indicates the subscriber information being requested as defined in 3GPP TS 23.018 [97] and 3GPP TS 23.078 [98].

7.6.3.31A Requested Domain

This parameter indicates the domain (circuit switched, i.e. from the MSC/VLR, or packet switched, i.e. from the SGSN) from which the requested information should be retrieved.

7.6.3.32 Suppression of Announcement

This parameter indicates if the announcement or tones shall be suppressed as defined in 3GPP TS 23.078 [98].

7.6.3.33 Suppress T-CSI

This parameter is used to suppress the invocation of terminating CAMEL services.

7.6.3.34 GMSC CAMEL Subscription Info

This parameter contains CAMEL subscription information, i.e. O-CSI and/or D-CSI and/or T-CSI, which indicates to the GMSC that originating and/or terminating CAMEL services shall be invoked for the incoming call.

7.6.3.35 VLR CAMEL Subscription Info

This parameter identifies the subscriber as having CAMEL services that are invoked in the MSC or VLR.

7.6.3.36 Supported CAMEL Phases in the VLR

This parameter indicates which phases of CAMEL are supported in the VLR.

7.6.3.36A Supported CAMEL Phases in the SGSN

This parameter indicates which phases of CAMEL are supported in the SGSN.

7.6.3.36B Offered CAMEL4 CSIs in the VLR

This parameter indicates which CSIs of CAMEL phase 4 are offered in the VLR as defined in 3GPP TS 23.078.

7.6.3.36C Offered CAMEL4 CSIs in the SGSN

This parameter indicates which CSIs of CAMEL phase 4 are offered in the SGSN as defined in 3GPP TS 23.078.

7.6.3.36D Offered CAMEL4 CSIs

This parameter indicates which CSIs of CAMEL phase 4 are offered as defined in 3GPP TS 23.078.

7.6.3.36E Offered CAMEL4 CSIs in interrogating node

This parameter indicates which CSIs of CAMEL phase 4 are offered in the GMSC or in the gsmSCF as defined in 3GPP TS 23.078.

7.6.3.36F Offered CAMEL4 CSIs in VMSC

This parameter indicates which CSIs of CAMEL phase 4 are offered in the VMSC as defined in 3GPP TS 23.078.

7.6.3.36G Offered CAMEL4 Functionalities

7.6.3.36H Supported CAMEL Phases

This parameter indicates which phases of CAMEL are supported as defined in 3GPP TS 23.078.

7.6.3.361 Supported CAMEL Phases in interrogating node

This parameter indicates which phases of CAMEL are supported as defined in 3GPP TS 23.078. The interrogating node may be a GMSC or a gsmSCF.

This parameter indicates which functionalities of CAMEL phase 4 are offered as defined in 3GPP TS 23.078.

7.6.3.37 CUG Subscription Flag

This parameter indicates that a subscriber with a T-CSI also has a CUG subscription. It is defined in 3GPP TS 23.078.

7.6.3.38 CAMEL Subscription Info Withdraw

This parameter indicates that CAMEL Subscription Info shall be deleted from the VLR or SGSN.

7.6.3.39 Voice Group Call Service (VGCS) Data

This parameter refers to one or more groups a subscriber may be a member of for voice group calls.

7.6.3.40 Voice Broadcast Service (VBS) Data

This parameter refers to one or more groups a subscriber may be a member of for the voice broadcast service. Per group it is further indicated whether the subscriber is only allowed to listen to respective group calls or whether he is in addition entitled to initiate respective voice broadcast calls.

7.6.3.41 ISDN bearer capability

This parameter refers to the ISDN bearer capability information element defined in 3GPP TS 29.007 [56].

7.6.3.42 Lower layer Compatibility

This parameter refers to the lower layer compatibility information element defined in 3GPP TS 24.008 [35].

7.6.3.43 High Layer Compatibility

This parameter refers to the high layer compatibility information element defined in 3GPP TS 24.008 [35].

7.6.3.44 Alerting Pattern

This parameter is an indication that can be used by the MS to alert the user in a specific manner in case of mobile terminating traffic (switched call or USSD). That indication can be an alerting level or an alerting category.

7.6.3.45 GPRS Subscription Data Withdraw

This parameter indicates that GPRS Subscription Data shall be deleted from the SGSN.

7.6.3.46 GPRS Subscription Data

This parameter refers to the list of PDP-Contexts that subscriber has subscribed to.

7.6.3.47 QoS-Subscribed

This parameter indicates the quality of service subscribed for a certain service. It is defined in 3GPP TS 23.060 [104].

7.6.3.48 VPLMN address allowed

This parameter specifies whether the MS is allowed to use a dynamic address allocated in the VPLMN. It is defined in 3GPP TS 23.060 [104].

7.6.3.49 Roaming Restricted In SGSN Due To Unsupported Feature

This parameter defines that a subscriber is not allowed to roam in the current SGSN area. It may be used by the HLR if a feature or service is indicated as unsupported by the SGSN.

7.6.3.50 Network Access Mode

This parameter is defined in 3GPP TS 23.108.

7.6.3.51 Mobile Not Reachable Reason

This parameter stores the reason for the MS being absent when an attempt to deliver a short message to an MS fails at the MSC, SGSN or both. It is defined in 3GPP TS 23.040.

7.6.3.52 Cancellation Type

This parameter indicates the reason of location cancellation. It is defined in 3GPP TS 23.060 [104].

7.6.3.53 All GPRS Data

This parameter indicates to the SGSN that all GPRS Subscription Data shall be deleted for the subscriber.

7.6.3.54 Complete Data List Included

This parameter indicates to the SGSN that the complete GPRS Subscription Data stored for the Subscriber shall be replaced with the GPRS Subscription Data received.

7.6.3.55 PDP Context Identifier

This parameter is used to identify a PDP context for the subscriber.

7.6.3.56 LSA Information

This parameter refers to one or more localised service areas a subscriber may be a member of, together with the priority, the preferential access indicator, the active mode support indicator and active mode indication of each localised service area. The access right outside these localised service areas is also indicated.

7.6.3.57 SoLSA support indicator

This parameter indicates that the VLR or the SGSN supports SoLSA subscription.

7.6.3.58 LSA Information Withdraw

This parameter indicates that LSA information shall be deleted from the VLR or the SGSN.

7.6.3.59 LMU Indicator

This parameter indicates the presence of an LMU.

7.6.3.60 LCS Information

This parameter defines the LCS related information for an MS subscriber and contains the following components:

GMLC List (see clause 7.6.3.61).
 LCS Privacy Exception List (see clause 7.6.3.62).

- MO-LR List (see clause 7.6.3.65A).

- Additional LCS Privacy Exception List (see clause 7.6.3.62A).

7.6.3.61 GMLC List

This parameter contains the addresses of all GMLCs that are permitted to issue a call/session unrelated or call/session related MT-LR location request for this MS. Usage of this parameter is defined in 3GPP TS 23.271.

7.6.3.62 LCS Privacy Exception List

This parameter defines the classes of LCS Client that are allowed to locate any target MS. For each class, the following information is provided:

- SS-Code (see clause 7.6.4.1);
- a list of LCS privacy exception parameters (see clause 7.6.3.63).

7.6.3.62A Additional LCS Privacy Exception List

This parameter defines the classes of LCS Client that are allowed to locate any target MS. For each class, the following information is provided:

SS-Code (see clause 7.6.4.1);
 a list of LCS privacy exception parameters (see clause 7.6.3.63).

The Additional LCS Privacy Exception List shall be present only if the LCS Privacy Exception List is present and contains LCS privacy exception parameters for 4 privacy exception classes.

7.6.3.63 LCS Privacy Exception Parameters

This parameter gives the status of each LCS privacy exception class and any additional parameters relevant to this class. The parameter contains the following information:

provisioned SS-Status (see clause 7.6.3.17);
privacy notification to MS user (see clause 7.6.3.65B);
external client List (see clause 7.6.3.64);
internal client List (see clause 7.6.3.65).
service type List (see clause 7.6.3.65D);

7.6.3.64 External Client List

This parameter is only applicable to the call/session unrelated privacy class and call/session related privacy class, and gives the identities of the external clients that are allowed to locate a target MS for a MT-LR. Each identity is an international (e.g.E.164) address. For each identified external client, GMLC restrictions may be defined. It may also be indicated if the MS shall be notified of a non-restricted MT-LR from each identified LCS client and, if so, whether notification only or notification with privacy verification shall apply. Usage of this parameter is defined in 3GPP TS 23.271.

7.6.3.65 Internal Client List

This parameter is only applicable to the PLMN operator privacy class and gives the identities of the internal PLMN operator clients that are allowed to locate a target MS for an NI-LR or MT-LR. Usage of this parameter is defined in 3GPP TS 23.271.

7.6.3.65A MO-LR List

This parameter defines the classes of MO-LR for which a subscription exists for a particular MS. For each class, the following information is provided:

- SS-Code (see clause 7.6.4.1).

7.6.3.65B Privacy Notification to MS User

This parameter is applicable to the call/session unrelated privacy class and call/session related privacy class. For non-call/call related privacy class it indicates whether the MS user shall be notified for that class MT-LR from any value added LCS client when the MT-LR is restricted and be enabled to accept or override the restriction. Usage of this parameter is defined in 3GPP TS 23.271.

7.6.3.65C GMLC List Withdraw

This parameter indicates whether the subscriber"s LCS GMLC list shall be deleted from the VLR or SGSN.

7.6.3.65D Service Type List

This parameter is only applicable to the Service type privacy class and gives the identities of the service type of the clients that are allowed to locate a target MS for an MT-LR. Usage of this parameter is defined in 3GPP TS 23.271.

7.6.3.66 IST Alert Timer

This parameter indicates the IST Alert Timer value that must be used in the MSC to inform the HLR about the call activities that the subscriber performs. Units are minutes.

7.6.3.67 Call Termination Indicator

This parameter indicates whether the MSC shall terminate a specific ongoing call, or all the call activities related to a specified subscriber.

7.6.3.68 IST Information Withdraw

This parameter indicates that IST information shall be deleted from the VMSC.

7.6.3.69 IST Support Indicator

This parameter indicates the degree of IST functionality supported by the MSC (Visited MSC or Gateway MSC). It can take one of the following values:

- Basic IST functionality;
- IST command service (in addition to the basic IST functionality and including the ability to terminate all calls being carried for the identified subscriber).

7.6.3.70 Super-Charger Supported In HLR

This parameter is used by the HLR to indicate support of the Super-Charger functionality and an indication of the age of the subscription data stored in the HLR.

7.6.3.71 Super-Charger Supported In Serving Network Entity

This parameter is used to indicate support of the Super-Charger functionality by the originating entity and to indicate either that subscription data is required or the date and time of the last know subscriber data modification.

7.6.3.72 Age Indicator

This parameter is used by the HLR to determine the validity of the subscription data retained by the serving network entity in a Super-Charged network.

7.6.3.73 GPRS enhancements support indicator

This parameter indicates to the HLR that the SGSN supports GPRS enhancements.

7.6.3.74 Extension QoS-Subscribed

This parameter indicates the enhanced QoS subscribed for a certain service. It is defined in 3GPP TS 23.060. This parameter is an extension to QoS-Subscribed.

7.6.3.75 SGSN CAMEL Subscription Info

This parameter identifies the subscriber as having CAMEL services that are invoked in the SGSN.

7.6.3.75A Extension-2 QoS-Subscribed

This parameter indicates the additional QoS information to the Extension QoS-subscribed parameter. It is a further extension to Extension QoS-Subscribed. This parameter shall be used when the maximum bit rate exceeds 8640 kbps. For more details, refer to 3GPP TS 24.008 [35].

7.6.3.76 MO-SMS-CSI

This parameter identifies the subscriber as having mobile originating SMS CAMEL services as defined in 3GPP TS 23.078. For the CAMEL phase 3 the MO-SMS-CSI is the same as the SMS-CSI.

7.6.3.76a MT-SMS-CSI

This parameter identifies the subscriber as having mobile terminating SMS CAMEL services as defined in 3GPP TS 23.078.

7.6.3.77 GPRS-CSI

This parameter identifies the subscriber as having GPRS CAMEL services as defined in 3GPP TS 23.078.

7.6.3.78 CAMEL subscription info

This parameter indicates the CSI that can be controlled by CSE.

7.6.3.79 Extensible Call barring information for CSE

This parameter contains for each call barring service for CSE:

- SS-Code:
- a list of extensible call barring feature parameters.

The list may contain one item per Basic Service Group.

- password;
- wrong password attempt counter;
- notification-to-CSE flag.

7.6.3.80 Extensible Forwarding information for CSE

This parameter represents the information for CSE related to each call forwarding service:

- the SS-Code of the relevant call forwarding service;
- if required, a list of extensible forwarding feature parameters;
- the list may contain one item per Basic Service Group;
- notification-to-CSE flag.

7.6.3.81 Modification Request for CSI

This parameter indicates the CAMEL subscription information to be modified by CSE.

7.6.3.81a Modification Request for ODB data

This parameter indicates the operator determined barring data to be modified by CSE.

7.6.3.82 Modification Request for SS Information

This parameter indicates the call forwarding and call barring supplementary service data to be modified by CSE.

7.6.3.83 Call Barring Data

This parameter contains the extensible call barring feature list (see clause 7.6.3.21) and Notification to CSE flag.

7.6.3.84 Call Forwarding Data

This parameter contains the extensible call forwarding feature list (see clause 7.6.3.16) and Notification to CSE flag.

7.6.3.85 ODB Data

This parameter contains the ODB general data, ODB HPLMN specific data.

7.6.3.86 Requested Subscription Info

This parameter indicates the subscription information being requested.

7.6.3.87 CS Allocation/Retention priority

This parameter indicates the allocation/retention priority for Circuit Switched (CS). It corresponds to the allocation/retention priority that is defined in 3GPP TS 23.107.

7.6.3.88 ODB Info

This parameter contains the ODB data and Notification to CSE flag.

7.6.3.89 Suppress VT-CSI

This parameter is used to suppress the invocation of terminating CAMEL services at the VMSC.

7.6.3.90 Suppress Incoming Call Barring

This parameter is used to suppress the invocation of Incoming Call Barrings.

7.6.3.91 gsmSCF Initiated Call

This parameter is used to indicate that the call was initiated by the gsmSCF.

7.6.3.92 Call barring support indicator

This parameter is used to indicate that the SGSN supports the call barring services for SMS.

7.6.3.93 MNP Info Result

This parameter refers to the Mobile Number Portability (MNP) information result (see 3GPP TS 23.078 [98] and 3GPP TS 23.066 [108]). This parameter may contain the following information:

- Routeing Number (see clause 7.6.2.63).

- IMSI (see 3GPP TS 23.078[98], see also clause 7.6.2.1).

- MSISDN (see clause 7.6.2.17).

- Number Portability Status (see clause 7.6.5.14).

7.6.3.94 Allowed Services

This parameter is used by the HLR to indicate which service is available for a call when two services have been requested, for the SCUDIF feature described in 3GPP TS 23.172 [126].

7.6.3.95 Unavailability Cause

This parameter is used to indicate the reason for the unavailability of one of the services as indicated by the Allowed Services IE (see 7.6.3.94) when two services have been requested, for the SCUDIF feature described in 3GPP TS 23.172 [126].

7.6.3.96 MNP Requested Info

This parameter indicates by its presence that Mobile Number Portability (MNP) information is requested for the subscriber, as defined in 3GPP TS 23.078 [98].

7.6.3.97 Access Restriction Data

This parameter refers to the radio access technologies that are possibly restricted to a subscriber via subscription data. For the use of the parameter, see 3GPP TS 23.012[23] for CS domain and 3GPP TS 23.060[104] for PS domain.

7.6.4 Supplementary services parameters

7.6.4.1 SS-Code

This parameter may refer to one supplementary service or a set of supplementary services as defined in 3GPP TS 22.004. For MAP this includes:

- Calling Line Identification Presentation service (CLIP);
- Calling Line Identification Restriction service (CLIR);
- Connected Line Identification Presentation service (COLP);
- Connected Line Identification Restriction service (COLR);
- Calling Name Presentation (CNAP);
- All Call Forwarding services, including Call Deflection;
- Call Waiting (CW);
- Call Hold (HOLD);
- Multi-Party service (MPTY);

- Closed User Group (CUG);
- All Charging services;
- All Call Restriction services;
- Explicit Call Transfer service (ECT);
- enhanced Multi-Level Precedence and Pre-emption service (eMLPP);
- Completion of Calls to Busy Subscriber, originating side (CCBS-A);
- Completion of Calls to Busy Subscriber, destination side (CCBS-B);
- All LCS privacy exceptions (see clause 7.6.4.44);
- Mobile Originating Location Request (MO-LR) (see clause 7.6.4.45);
- Multicall (MC).

7.6.4.1A SS-Code 2

This parameter is used to refer to one or a set of supplementary services (as 7.6.4.1 "SS-Code") related to Network Signal Info 2 for SCUDIF calls (see 3GPP TS 23.172 [126]).

7.6.4.2 SS-Status

This parameter refers to the state information of individual supplementary services as defined in 3GPP TS 23.011.

7.6.4.3 SS-Data

This parameter refers to the necessary set of information required in order to characterise one supplementary service:

- SS-Code (see clause 7.6.4.1);
- SS-Status (if applicable) (see clause 7.6.4.2);
- Override subscription option (see clause 7.6.4.4);
- CLI Restriction (see clause 7.6.4.5);
- Basic Service Group Code (see clause 7.6.4.40).

7.6.4.4 Override Category

This parameter refers to the subscription option Override Category attached to a supplementary service. It can take the following two values:

- Enabled;
- Disabled.

7.6.4.5 CLI Restriction Option

This parameter refers to the subscription option Restriction mode attached to the CLIR supplementary service. It can take the following three values:

- Permanent;
- Temporary (Default Restricted);
- Temporary (Default Allowed).

7.6.4.6 Forwarding Options

This parameter refers to a forwarding option attached to a supplementary service. It can take one of the following values:

notification to forwarding party (see 3GPP TS 22.082 [10] for the meaning of this parameter);
 notification to calling party (see 3GPP TS 22.082 [10] for the meaning of this parameter);
 redirecting presentation (see 3GPP TS 22.082 [10] for the meaning of this parameter);
 Forwarding reason (see 3GPP TS 22.082 [10] for the meaning of this parameter).

7.6.4.7 No reply condition timer

This parameter refers to the no reply condition timer for call forwarding on no reply.

7.6.4.8 - 7.6.4.14 Void

7.6.4.15 Forwarding information

This parameter represents the information related to each call forwarding service:

the SS-Code of the relevant call forwarding service (see clause 7.6.4.1);
 if required, a list of forwarding feature parameters (see clause 7.6.4.16).
 the list may contain one item per Basic Service Group.

7.6.4.16 Forwarding feature

This parameter applies to each combination of call forwarding service and Basic Service Group and contains the following information, as required:

- Basic Service Group (see clause 7.6.4.40);
- SS-Status (see clause 7.6.4.2);
- forwarded-to number (see clause 7.6.2.22);
- forwarded-to subaddress (see clause 7.6.2.23);
- forwarding options (see clause 7.6.4.6);
- no reply condition timer (see clause 7.6.4.7);
- long forwarded-to number (see clause 7.6.2.22A).

If a number is required to define the forwarded-to destination then:

- If the VLR supports Long Forwarded-to Numbers then the long forwarded-to number shall be present and the forwarded-to number shall be absent.
- If the VLR does not support Long Forwarded-to Numbers then the forwarded-to number shall be present and the long forwarded-to number shall be absent.

7.6.4.17 Void

7.6.4.18 Call barring information

This parameter contains for each call barring service:

- SS-Code (see clause 7.6.4.1);

- a list of call barring feature parameters (see clause 7.6.4.19).

The list may contain one item per Basic Service Group.

7.6.4.19 Call barring feature

This parameter gives the status of call barring services as applicable to each Basic Service Group. The parameter contains the following information:

- Basic Service Group (see clause 7.6.4.40);

- SS-Status (see clause 7.6.4.2).

7.6.4.20 New password

This parameter refers to the password which the subscriber just registered in the network.

This parameter refers to a password used by the subscriber for supplementary service control.

7.6.4.21 Current password

This parameter refers to a password used by the subscriber for supplementary service control.

7.6.4.22 Guidance information

This parameter refers to guidance information given to a subscriber who is requested to provide a password. One of the following information may be given:

- "enter password";

this information is used for checking of the old password;

"enter new password";

this information is used during password registration for the request of the first new password;

"enter new password again";

this information is used during password registration for the request of the new password again for verification.

7.6.4.23 Void

7.6.4.24 SS-Info

This parameter refers to all the information related to a supplementary service and is a choice between:

- forwarding information (see clause 7.6.4.15);

- call barring information (see clause 7.6.4.18);

- CUG info (see clause 7.6.4.8);

- SS-Data (see clause 7.6.4.3).

- eMLPP information (see clause 7.6.4.41).

7.6.4.25 - 7.6.4.35 Void

7.6.4.36 USSD Data Coding Scheme

This parameter contains the information of the alphabet and the language used for the unstructured information in an Unstructured Supplementary Service Data operation. The coding of this parameter is according to the Cell Broadcast Data Coding Scheme as specified in 3GPP TS 23.038 [25].

7.6.4.37 USSD String

This parameter contains a string of unstructured information in an Unstructured Supplementary Service Data operation. The string is sent either by the mobile user or the network. The contents of a string sent by the MS are interpreted by the network as specified in 3GPP TS 22.090 [16].

7.6.4.38 Bearer service

This parameter may refer to a single bearer service, a set of bearer services or to all bearer services as defined in 3GPP TS 22.002 [3]. This parameter is used only for supplementary service management.

7,6,4.38A Bearer Service 2

This parameter is used to indicate the bearer service or set of bearer services (as 7.6.4.38 "Bearer service") related to Network Signal Info 2 for SCUDIF calls (see 3GPP TS 23.172 [126]).

7.6.4.39 Teleservice

This parameter may refer to a single teleservice, a set of teleservices or to all teleservices as defined in 3GPP TS 22.003 [4]. This parameter is used only for supplementary service management.

7.6.4.39A Teleservice 2

This parameter is used to indicate the teleservice or set of teleservices (as 7.6.4.39 "Teleservice") related to Network Signal Info 2 for SCUDIF calls (see 3GPP TS 23.172 [126]).

7.6.4.40 Basic Service Group

This parameter refers to the Basic Service Group either as a bearer service (see clause 7.6.4.38) or a teleservice (see clause 7.6.4.39). This parameter is used only for supplementary service management. The null value (i.e. neither bearer service nor teleservice) is used to denote the group containing all bearer services and all teleservices.

7.6.4.41 eMLPP information

This parameter contains two parameters which are associated with the eMLPP service. The following two parameters are included:

- maximum entitled priority:
 - indicates the highest priority level the subscriber is allowed to apply for an outgoing call set-up;
- default priority:
 - defines the priority level which shall be assigned to a call if no explicit priority is indicated during call set-up.

7.6.4.42 SS-event

This parameter indicates the Supplementary Service for which an invocation notification is sent towards the gsmSCF. It can indicate one of the following services:

- Explicit Call Transfer (ECT)
- Call Deflection (CD)
- Multi-Party call (MPTY)
- Completion of Calls to Busy Subscriber (CCBS)

7.6.4.43 SS-event data

This parameter contains additional information related to Supplementary Service invocation. Depending on the service invoked it can contain the following information:

- ECT A list with all Called Party Numbers involved.
- CD The called Party number involved.

7.6.4.44 LCS Privacy Exceptions

Distinct SS codes are assigned to the following classes of LCS client in a target MS subscriber"s privacy exception list.

- Universal Class;
- Call/session related value added class:
- Call/session unrelated value added class;
- PLMN operator class.
- Service type class.

7.6.4.45 Mobile Originating Location Request (MO-LR)

Distinct SS codes are assigned to the following classes of MO-LR:

- Basic Self Location;
- Autonomous Self Location;
- Transfer to Third Party.

7.6.4.46 NbrUser

This parameter indicates the maximum number of parallel bearers that may be used as defined by the user at registration of the MC SS.

7.6.4.47 MC Subscription Data

This parameter contains two parameters which are associated with the MC service. The following two parameters are included:

• NbrUser:

indicates the maximum number of parallel bearers that may be used as defined by the user at registration of the MC SS

• NbrSB:

indicates the maximum number of parallel bearers that may be used as defined by the user"s subscription.

7.6.4.48 MC Information

This parameter contains three parameters which are associated with the MC service. The following parameters are included:

- NbrSB;
- NbrUser;
- NbrSN.

Definitions of these parameters are provided in 3GPP TS 23.135.

7.6.4.49 CCBS Request State

This parameter indicates the current state of the CCBS request. It can take one of seven values:

- request;
- recall;
- active;
- completed;
- suspended;
- frozen;
- deleted.

7.6.4.50 Basic Service Group 2

This parameter refers to the Basic Service Group either as a bearer service (see clause 7.6.4.38) or a teleservice (see clause 7.6.4.39). This parameter is used only for supplementary service management.

7.6.5 Call parameters

7.6.5.1 Call reference number

This parameter refers to a call reference number allocated by a call control MSC.

7.6.5.2 Interrogation type

This parameter refers to the type of interrogation for routing information which is sent from a GMSC to an HLR. It can take either of two values:

- basic call (for information to route a call before the call has been extended to the VMSC of the called party);
- forwarding (for information to route the call to the forwarded-to destination after the VMSC of the forwarding party has requested the GMSC to resume handling of the call.

7.6.5.3 OR interrogation

This parameter indicates that the GMSC which interrogated the HLR for routeing information is not in the same PLMN as the HLR, and therefore that the call will potentially be optimally routed.

7.6.5.4 OR capability

This parameter indicates the phase of OR which the GMSC supports.

7.6.5.5 Forwarding reason

This parameter indicates the reason for which the call is to be forwarded. It can take one of three values:

- busy subscriber;
- mobile subscriber not reachable;
- no subscriber reply.

7.6.5.6 Forwarding interrogation required

This parameter indicates that if the VMSC of the forwarding subscriber requests the GMSC to resume handling of the call the GMSC shall interrogate the HLR for forwarding information.

7.6.5.7 O-CSI

This parameter identifies the subscriber as having originating CAMEL services as defined in 3GPP TS 23.078.

7.6.5.7A D-CSI

This parameter identifies the subscriber as having originating CAMEL dialled services as defined in 3GPP TS 23.078.

7.6.5.7B T-CSI

This parameter identifies the subscriber as having terminating CAMEL services in the GMSC, as defined in 3GPP TS 23.078.

7.6.5.7C VT-CSI

This parameter identifies the subscriber as having terminating CAMEL services in the VMSC, as defined in 3GPP TS 23.078.

7.6.5.7D O-IM-CSI

This parameter identifies the subscriber as having originating IP Multimedia Core Network CAMEL services as defined in 3GPP TS 23.278.

7.6.5.7E D-IM-CSI

This parameter identifies the subscriber as having originating IP Multimedia Core Network CAMEL dialled services as defined in 3GPP TS 23.278.

7.6.5.7F VT-IM-CSI

This parameter identifies the subscriber as having terminating IP Multimedia Core Network CAMEL services as defined in 3GPP TS 23.278.

7.6.5.8 Void

7.6.5.9 Void

7.6.5.10 Void

7.6.5.11 CCBS Feature

This parameter corresponds to the 'CCBS Description' parameter in 3GPP TS 23.093. It refers to the necessary set of information required in order to characterise a certain CCBS request. The parameter may contain the following information:

- CCBS Index (see 3GPP TS 23.093 for the use of this parameter);

- B-subscriber number (see clause 7.6.2.48);

- B-subscriber subaddress (see clause 7.6.2.49);

- Basic Service Group Code (see clause 7.6.4.40).

7.6.5.12 UU Data

This parameter includes User-To-User Data. It is defined in 3GPP TS 23.087.

7.6.5.13 UUS CF Interaction

This parameter indicates if the call forwarding or call deflection has been activated after UUS1 request has been accepted . It is defined in 3GPP TS 23.087.

7.6.5.14 Number Portability Status

This parameter indicates the number portability status of subscriber. See 3GPP TS 23.066 [108].

7.6.5.15 Pre-paging supported

This parameter indicates that the entity which sent it supports pre-paging.

7.6.6 Radio parameters

7.6.6.1 - 7.6.6.3 Void

7.6.6.4 GERAN Classmark

This information element is sent from one MSC to the other MSC in the signalling for inter MSC handover. It is used to convey information related to cell capabilities, as defined in 3GPP TS 48.008.

7.6.6.5 BSSMAP Service Handover

This parameter refers to the Service Handover information element defined in 3GPP TS 48.008

7.6.6.5A BSSMAP Service Handover List

This parameter refers to the list of Service Handover information elements defined in 3GPP TS 48.008. This parameter shall be used when there are multiple bearers and at least one of the bearers has an associated BSSMAP Service Handover parameter.

7.6.6.6 RANAP Service Handover

This parameter refers to the Service Handover information element defined in 3GPP TS 25.413.

7.6.6.7 HO-Number Not Required

This parameter indicates that no handover or relocation number allocation is necessary.

7.6.6.8 Integrity Protection Information

This parameter refers to the Integrity Protection Information element defined in 3GPP TS 25.413.

7.6.6.9 Encryption Information

This parameter refers to the Encryption Information element defined in 3GPP TS 25.413.

7.6.6.10 Radio Resource Information

This parameter refers to the Channel Type information element defined in 3GPP TS 48.008 [49].

7.6.6.10A Radio Resource List

This parameter refers to list of RAB-id's and their associated Channel Type information elements defined in 3GPP TS 48.008. This parameter shall be used when there are multiple bearers and at least one of the bearers has an associated Radio Resource Information parameter.

7.6.6.10B Chosen Radio Resource Information

This parameter refers to the Chosen Channel and Speech Version information elements defined in 3GPP TS 48.008.

7.6.6.11 Key Status

This parameter refers to the Key Status element defined in 3GPP TS 25.413.

7.6.6.12 Selected UMTS Algorithms

This parameters identifies the UMTS integrity and optionally encryption algorithms selected by MSC-B. Coding of this parameter is defined in 3GPP TS 25.413.

7.6.6.13 Allowed GSM Algorithms

This parameters identifies the allowed GSM algorithms in MSC-B. Coding of this parameter is defined in 3GPP TS 48.008.

7.6.6.14 Allowed UMTS Algorithms

This parameters identifies the allowed UMTS algorithms in MSC-B. Coding of this parameter is defined in 3GPP TS 25.413.

7.6.6.15 Selected GSM Algorithm

This parameter identifies the GSM algorithm selected by GSM BSC controlled by MSC-B. Coding of this parameter is defined in 3GPP TS 48.008.

7.6.6.16 Iu-Currently Used Codec

This parameter indicates the codec used at the Iu interface before handover.

7.6.6.17 Iu-Supported Codecs List

This parameter indicates the codecs supported by the UE and by MSC-A and the associated modes in priority order (the first entry being the highest priority codec). MSC-B uses this information to select the associated transcoder resources.

7.6.6.17A lu-Available Codecs List

This parameter indicates the codecs available at the Iu interface in MSC-B and the associated modes. MSC-A uses this information to decide whether a change to a different codec at the Iu interface is possible.

7.6.6.18 lu-Selected Codec

When sent by MSC-B, this parameter indicates the codec selected by MSC-B for the Iu interface. When sent by MSC-A, this parameter indicates the codec to be used by MSC-B at the Iu interface.

7.6.6.19 RAB Configuration Indicator

This parameter indicates by its presence that MSC-A (or MSC-B in case of subsequent handover) has generated the RAB parameters according to the preferred codec (first entry in the Available Codecs List).

7.6.6.20 UESBI-lu

This parameter refers to the UESBI-Iu (UE Specific Behaviour Information over the Iu interface) information element defined in 3GPP TS 25.413.

7.6.6.21 Alternative Channel Type

This parameter refers to the Channel Type information element defined in 3GPP TS 48.008 [49] for the alternative radio access bearer. This parameter is used for SCUDIF calls (see 3GPP TS 23.172 [126]).

7.6.7 Authentication parameters

7.6.7.1 Authentication set list

This parameter represents a list of sets of authentication parameters for a given subscriber.

The list either contains Authentication Triplets (Rand, Sres, Kc) or Authentication Quintuplets (Rand, Xres, Ck, Ik, Autn). If the list contains Authentication Quintuplets, the order of sequence in this list is chronological, the first quintuplet in the list is the oldest one.

7.6.7.2 Rand

This parameter represents a random number used for authentication.

7.6.7.3 Sres

This parameter represents the response to an authentication request.

7.6.7.4 Kc

This parameter refers to a key used for ciphering purposes.

7.6.7.5 Xres

This parameter represents the response to an UMTS authentication request.

7.6.7.5A Ck

This parameter refers to a key used for UMTS ciphering purposes.

7.6.7.5B lk

This parameter refers to the Integrity Key.

7.6.7.5C Autn

This parameter refers to the Authentication Token.

7.6.7.6 Cksn

This parameter refers to a ciphering key sequence number.

7.6.7.6A Ksi

This parameter refers to a key set identifier.

7.6.7.6B Auts

This parameter refers to the resynchronisation token.

7.6.7.7 Ciphering mode

This parameter refers to the ciphering mode which is associated with a radio channel. It may take values as follows:

- no encryption;
- identification of specific ciphering algorithm.

7.6.7.8 Current Security Context

This parameter represents a list of security context parameters for a given subscriber.

The list either contains GSM Security Context data (Kc, Cksn) or UMTS Security Context Data (Ck, Ik, Ksi).

7.6.7.9 Failure cause

This parameter refers to an authentication failure which has occurred. It may take values as follows:

- wrong user response;
- wrong network signature.

7.6.7.10 Re-attempt

It indicates whether the failure ocurred in a normal authentication attempt or in an authentication reattempt (there was a previous unsuccessful authentication).

7.6.7.11 Access Type

It indicates whether the authentication procedure was initiated due to a call, an emergency call, a location updating, a supplementary service procedure, a short message transfer, a GPRS attach procedure, a routing area updating, a service request, a MS initiated Detach in GPRS, a PDP context activation or a PDP context deactivation procedure.

7.6.8 Short message parameters

7.6.8.1 SM-RP-DA

This parameter represents the destination address used by the short message service relay sub-layer protocol. It can be either of the following:

IMSI (see clause 7.6.2.1);
LMSI (see clause 7.6.2.16);
MS-ISDN (see clause 7.6.2.17);
roaming number (see clause 7.6.2.19);
service centre address (see clause 7.6.2.27).

7.6.8.2 SM-RP-OA

This parameter refers to the originating address used by the short message service relay sub-layer protocol. It can be either of the following:

- MS-ISDN (see clause 7.6.2.17); - service centre address (see clause 7.6.2.27).

7.6.8.3 MWD status

This parameter indicates whether or not the address of the originator service centre is already contained in the Message Waiting Data file. In addition, it contains the status of the Memory Capacity Exceeded Flag (MCEF), the status of the Mobile subscriber Not Reachable Flag (MNRF) and the status of the Mobile station Not Reachable for GPRS flag (MNRG).

7.6.8.4 SM-RP-UI

This parameter represents the user data field carried by the short message service relay sub-layer protocol.

7.6.8.5 SM-RP-PRI

This parameter is used to indicate whether or not delivery of the short message shall be attempted when a service centre address is already contained in the Message Waiting Data file.

7.6.8.6 SM Delivery Outcome

This parameter indicates the cause for setting the message waiting data. It can take one of the following values:

- Absent subscriber:
- MS memory capacity exceeded;
- Successful transfer.

7.6.8.7 More Messages To Send

This parameter is used to indicate whether or not the service centre has more short messages to send.

7.6.8.8 Alert Reason

This parameter is used to indicate the reason why the service centre is alerted. It can take one of the following values:

- MS present;

- Memory Available.

7.6.8.9 Absent Subscriber Diagnostic SM

This parameter is used to indicate the reason why the subscriber is absent. For the values for this parameter see 3GPP TS 23.040.

7.6.8.10 Alert Reason Indicator

This parameter indicates that the alert reason is sent to the HLR due to GPRS activity.

7.6.8.11 Additional SM Delivery Outcome

This parameter is used to indicate the GPRS delivery outcome in case a combination between delivery outcome for GPRS and non-GPRS are sent to the HLR.

7.6.8.12 Additional Absent Subscriber Diagnostic SM

This parameter indicates the reason of the additional SM Delivery Outcome.

7.6.8.13 Delivery Outcome Indicator

This parameter indicates that the delivery outcome sent to the HLR is for GPRS.

7.6.8.14 GPRS Node Indicator

This parameter indicates that the Network Node Number sent by the HLR is the SGSN number.

7.6.8.15 GPRS Support Indicator

This parameter indicates that the SMS-GMSC supports GPRS specific procedure of combine delivery of Short Message via MSC and/or via the SGSN.

7.6.8.16 SM-RP-MTI

This parameter represents the RP-Message Type Indicator of the Short Message. It is used to distinguish a SM sent to the mobile station in order to acknowledge an MO-SM initiated by the mobile from a normal MT-SM. This parameter is formatted according to the formatting rules of address fields as described in 3GPP TS 23.040.

7.6.8.17 SM-RP-SMEA

This parameter represents the RP-Originating SME-address of the Short Message Entity that has originated the SM. This parameter is used by the short message service relay sub-layer protocol and is formatted according to the formatting rules of address fields as described in 3GPP TS 23.040.

7.6.9 Access and signalling system related parameters

7.6.9.1 AN-apdu

This parameter includes one or two concatenated complete 3GPP TS 25.413 or 3GPP TS 48.006 [48] messages, as described in 3GPP TS 23.009 and 3GPP TS 29.010. The access network protocol ID indicates that the message or messages are according to either 3GPP TS 48.006 [48] or 3GPP TS 25.413. For the coding of the messages see 3GPP TS 25.413, 3GPP TS 48.006 [48] and 3GPP TS 48.008 [49].

7.6.9.2 CM service type

This parameter identifies the service category being requested by the subscriber:

- mobile originating call;
- emergency call establishment;
- short message service;
- mobile originating call re-establishment;
- mobile terminating call;
- SS request;
- Voice group call set-up;
- Voice broadcast set-up.

7.6.9.3 Access connection status

This parameter represents the following access connection status information:

- RR-connection status (established/not established);
- ciphering mode (on/off);
- authentication status (authenticated/not authenticated).

7.6.9.4 External Signal Information

This parameter contains concatenated information elements (including tag and length) which are defined by a common protocol version, preceded by the associated protocol ID. It is used to transport information of the indicated protocol via MAP interfaces.

7.6.9.5 Access signalling information

This parameter refers to any set of information elements imported from 3GPP TS 24.008 [35].

7.6.9.6 Location update type

This parameter refers to the location update type (normal, periodic or IMSI attach) contained in the 3GPP TS 24.008 [35] LOCATION REGISTRATION REQUEST message.

7.6.9.7 Protocol ID

This parameter refers to the protocol to which the coding of the content of the associated External Signal Information conforms.

The following values are defined:

- 04.08;
- 08.06;
- ETS 300 102-1.

This value indicates the protocol defined by ETS 300 102-1 (EDSS1).

7.6.9.8 Network signal information

This parameter is transported as external signal information. The protocol ID shall be set to "ETS 300 102-1".

The network signal information may include the following information elements as defined in 3GPP TS 29.007 [56]:

- ISDN BC; the tag and length are defined by ETS 300 102-1.

For the content, see 3GPP TS 29.007 [56].

- HLC; the tag and length are defined by ETS 300 102-1.

For the content, see 3GPP TS 29.007 [56].

- LLC; the tag and length are defined by ETS 300 102-1.

For the content, see 3GPP TS 29.007 [56].

They are contained in the Signal Information parameter according to figure 7.6/1 (irrespective of the order):




Figure 7.6/1: Network signal information parameter

7.6.9.8A Network signal information 2

This parameter is transported as additional external signal information for SCUDIF calls, described in 3GPP TS 23.172 [126]. The protocol ID and possibly included information elements are identical to Network Signal Information, defined in 7.6.9.8, "Network signal information".

7.6.9.9 Call Info

This parameter is transported as external signal information. The protocol ID shall be set to "3GPP TS 24.008 [35]".

The Call Info includes the set of information elements from the original SETUP message and is imported from 3GPP TS 24.008 [35].

7.6.9.10 Additional signal info

This parameter is transported as external signal information. The protocol ID shall be set to "ETS 300 356".

The additional signal information may include the following information elements:

- Calling Party Number as defined by ETS 300 356.
- Generic Number as defined by ETS 300 356.

They are contained in the Signal Information parameter according to figure 7.6/2 (irrespective of the order):




Figure 7.6/2: Additional signal information parameter

7.6.10 System operations parameters

7.6.10.1 Network resources

This parameter refers to a class or type of network resource:

- PLMN;
- HLR:
- VLR (current or previous);
- MSC (controlling or current);
- EIR;
- radio sub-system.

7.6.10.2 Trace reference

This parameter represents a reference associated with a GSM only tracing request as defined in 3GPP TS 52.008 [61]. The parameter is managed by OMC/EM.

7.6.10.2A Trace reference 2

This parameter represents a reference associated with a tracing request as defined in 3GPP TS 32.421 [131] and 3GPP TS 32.422 [132]. The parameter is managed by EM.

7.6.10.3 Trace type

This parameter identifies the type of trace for GSM only tracing request. Trace types are fully defined in 3GPP TS 52.008 [61]. If the activation of the tracing is requested only for UMTS, then this parameter shall contain value "No MSC Trace" for MSC Record Type and value "No BSS Trace" for BSS Record Type.

7.6.10.4 Additional network resources

This parameter refers to a class or type of network resource:

- SGSN;
- GGSN;
- GMLC;
- gsmSCF;
- NPLR;

AuC.

7.6.10.5 Trace depth list

This parameter identifies the list of depths of trace per network element. See 3GPP TS 32.422 [132].

7.6.10.6 Trace NE type list

This parameter identifies the list of network elements to be traced. See 3GPP TS 32.422 [132].

7.6.10.7 Trace interface list

This parameter identifies the list of interfaces or protocols per network element to be traced. See 3GPP TS 32.422 [132].

7.6.10.8 Trace event list

This parameter identifies the list of events per network element, which trigger a Trace Recording Session. See 3GPP TS 32.422 [132].

7.6.10.9 Trace support indicator

This parameter indicates that UMTS trace parameters are supported in the VLR or in the SGSN.

7.6.10.10 Trace Propagation List

This parameter indicates UMTS trace propagation parameters sent from one MSC to the other MSC in the signalling for inter MSC handover/relocation. See 3GPP TS 32.422 [132].

7.6.11 Location Service Parameters

7.6.11.1 Age of Location Estimate

This parameter indicates how long ago the location estimate was obtained.

7.6.11.2 Deferred MT-LR Response Indicator

This parameter shows that this is a response to a deferred mt-lr request.

7.6.11.3 Deferred MT-LR Data

This parameter is used to report the deferred location event type, the location information and reason why the serving node aborted monitoring the event to the GMLC. The termination cause mt-lrRestart shall be used to trigger the GMLC to restart the location procedure in all the cases where the sending node detects that the location procedure cannot be successfully performed anymore by the sending node and that it could be successfully performed by another node (as for example when. Cancel Location or Send Identification has been received). The location information shall be included only if the termination cause is mt-lrRestart. The network node number contained in the location information refers to the node where the MS/UE has moved to and shall be included if available, like in case Send Identification has been received.

7.6.11.4 LCS Client ID

This parameter provides information related to the identity of an LCS client.

7.6.11.5 LCS Event

This parameter identifies an event associated with the triggering of a location estimate.

7.6.11.6 Void

7.6.11.7 LCS Priority

This parameter gives the priority of the location request.

7.6.11.8 LCS QoS

This parameter defines the Quality of Service (QoS) for any location request. It is composed of the following elements.

1) Response Time

Indicates the category of response time – 'low delay' or 'delay tolerant'.

2) Horizontal Accuracy

Indicates the required horizontal accuracy of the location estimate.

3) Vertical Coordinate

Indicates if a vertical coordinate is required (in addition to horizontal coordinates).

4) Vertical Accuracy

Indicates the required vertical accuracy of the location estimate (inclusion is optional).

7.6.11.9 CS LCS Not Supported by UE

This parameter is used by the VLR to indicate to the HLR that the UE does not support neither UE Based nor UE Assisted positioning methods for Circuit Switched Location Services. VLR defines the presence of this parameter on the basis of the Classmark 3 information.

7.6.11.10 PS LCS Not Supported by UE

This parameter is used by the SGSN to indicate to the HLR that the UE does not support neither UE Based nor UE Assisted positioning methods for Packet Switched Location Services. SGSN defines the presence of this parameter on the basis of the UE capability information and the access technology supported by the SGSN.

7.6.11.11 Location Estimate

This parameter gives an estimate of the location of an MS in universal coordinates and the accuracy of the estimate. The estimate is expressed in terms of the geographical shapes defined by 3GPP TS 23.032. and is composed of the type of shape plus the encoding of the shape itself. Any type of shape defined in 3GPP TS 23.032 can be filled in in the Location Estimate parameter, but only the encoding of the following shapes shall be carried by Location Estimate:

- Ellipsoid point with uncertainty circle
- Ellipsoid point with uncertainty ellipse
- Ellipsoid point with altitude and uncertainty ellipsoid
- Ellipsoid arc
- Ellipsoid point

The encoding for the remaining types of shape, defined in the 3GPP TS 23.032, shall be filled in in the Additional Location Estimate parameter.

7.6.11.11A GERAN Positioning Data

This parameter provides positioning data associated with a successful or unsuccessful location attempt for a target MS described in 3GPP TS 49.031 [59a].

7.6.11.11B UTRAN Positioning Data

This parameter provides positioning data associated with a successful location attempt for a target MS as described in 3GPP TS 25.413 [120]. It contains the positioningDataDiscriminator and positioningDataSet parts of the RANAP PositionData element only.

7.6.11.12 Location Type

This parameter indicates the type of location estimate required by the LCS client. Possible location estimate types include:

- current location;
- current or last known location;
- initial location for an emergency services call;
- deferred location event type.

7.6.11.13 NA-ESRD

This parameter only applies to location for an emergency services call in North America and gives the North American Emergency Services Routing Digits.

7.6.11.14 NA-ESRK

This parameter only applies to location for an emergency services call in North America and gives the North American Emergency Services Routing Key.

7.6.11.15 LCS Service Type Id

This parameter defines the LCS Service Type of the current positioning request. The possible values are defined in 3GPP TS 22.071 [123]

7.6.11.16 Privacy Override

This parameter indicates if MS privacy is overridden by the LCS client when the GMLC and VMSC/SGSN for an MT-LR are in the same country.

7.6.11.17 Supported LCS Capability Sets

This parameter indicates which capability sets of LCS are supported in the VLR or SGSN.

7.6.11.18 LCS Codeword

This parameter contains the codeword associated to current positioning request as described in 3GPP TS 23.271 [26a].

7.6.11.19 NA-ESRK Request

This parameter allows the MSC to indicate that it requires the GMLC to allocate a NA-ESRK based on the target MS location estimate. This parameter only applies to emergency services calls in North America.

7.6.11.20 Supported GAD Shapes

This parameter indicates which of the shapes defined in 3GPP TS 23.032 are supported. If the parameter is not provided then the receiving node shall assume that the sending entity supports the following shapes:

- Ellipsoid point with uncertainty circle
- Ellipsoid point with uncertainty ellipse
- Ellipsoid point with altitude and uncertainty ellipsoid
- Ellipsoid arc
- Ellipsoid point

7.6.11.21 Additional Location Estimate

This parameter gives an estimate of the location of an MS/UE in universal coordinates and the accuracy of the estimate. This parameter allows the location estimate to be expressed in any of the geographical shapes defined in 3GPP TS 23.032

7.6.11.22 Cell ld Or SAI

For GERAN access, this parameter contains the Global Cell Identifier for the cell that the subscriber is currently attached to. For UTRAN access, this parameter contains the Service Area Identifier for the cell that the subscriber is currently attached to.

7.6.11.23 LCS-Reference Number

This parameter represents a reference between a request and a responce of a deferred mt-lr procedure as described in 3GPP TS 23.271 [26a].

7.6.11.24 LCS Privacy Check

This parameter refers to the requested privacy check related actions (call/session unrelated and/or call/session related) from MSC or SGSN provided by H-GMLC. Possible requested actions are:

- positioning allowed without notifying the UE user;
- positioning allowed with notification to the UE user;
- positioning requires notification and verification by the UE user; positioning is allowed only if granted by the UE user or if there is no response to the notification;
- positioning requires notification and verification by the UE user; positioning is allowed only if granted by the UE user;
- positioning not allowed.

7.6.11.25 Additional LCS Capability Sets

This parameter indicates which capability sets of LCS are supported in the VLR or SGSN.

7.6.11.26 Area Event Info

This parameter defines the requested deferred MT-LR area event information. The parameter consists of area definition, type of area event, occurrence info and minimum interval time.

7.6.11.27 Accuracy Fulfilment Indicator

This parameter indicates the fulfilled accuracy of the positioning procedure. For details see 3GPP TS 23.271 [26a].

7.6.12 void

7.7 Representation of a list of a basic parameter in serviceprimitives

In some service-primitives several instances of a basic parameter of clause 7.6 are required. In the service descriptions such cases will be represented as

ParameterNameLIST

in the tables where ParameterName refers to one of the parameters defined in clause 7.6. This corresponds to the following construction rule:



Figure 7.7/1: Construction of Lists

8 Mobility services

8.1 Location management services

8.1.1 Void

8.1.1.1 Void

8.1.1.2 Void

8.1.1.3 Void

8.1.2 MAP_UPDATE_LOCATION service

8.1.2.1 Definition

This service is used by the VLR to update the location information stored in the HLR.

The MAP_UPDATE_LOCATION service is a confirmed service using the service primitives given in table 8.1/2.

8.1.2.2 Service primitives

Table 8.1/2: MAP_UPDATE_LOCATION

Parameter name	Request	Indication	Response	Confirm
Invoke Id	M	M(=)	M(=)	M(=)
IMSI	M	M(=)		
MSC Address	M	M(=)		
VLR number	M	M(=)		
LMSI	U	C(=)		
Supported CAMEL Phases	С	C(=)		
SoLSA Support Indicator	С	C(=)		
IST Support Indicator	С	C(=)		
Super-Charger Supported in Serving Network Entity	С	C(=)		

Long FTN Supported	С	C(=)		
Supported LCS Capability Sets	С	C(=)		
Offered CAMEL 4 CSIs	С	C(=)		
Inform Previous Network Entity	С	C(=)		
CS LCS Not Supported by UE	С	C(=)		
V-GMLC Address	U	C(=)		
IMEISV	С	C(=)		
Skip Subscriber Data Update	U	C(=)		
ADD Capability			U	C(=)
HLR number			С	C(=)
User error			С	C(=)
Provider error				0

8.1.2.3 Parameter definitions and use

Invoke Id

See definition in clause 7.6.1.

IMSI

See definition in clause 7.6.2.

MSC Address

See definition for MSC number in clause 7.6.2. The MSC address is used for short message delivery only and for each incoming call set-up attempt the MSRN will be requested from the VLR.

VLR number

See definition in clause 7.6.2.

LMSI

See definition in clause 7.6.2. It is an operator option to provide the LMSI from the VLR; it is mandatory for the HLR to support the LMSI handling procedures.

Supported CAMEL Phases

This parameter indicates which phases of CAMEL are supported. Must be present if a CAMEL phase different from phase 1 is supported. Otherwise may be absent.

HLR number

See definition in clause 7.6.2. The presence of this parameter is mandatory in case of successful HLR updating.

SoLSA Support Indicator

This parameter is used by the VLR to indicate to the HLR in the Update Location indication that SoLSA is supported. If this parameter is not included in the Update Location indication and the Subscriber is marked as only allowed to roam in Subscribed LSAs, then the HLR shall reject the roaming and indicate to the VLR that roaming is not allowed to that Subscriber in the VLR.

This SoLSA Support Indicator shall be stored by the HLR per VLR where there are Subscribers roaming. If a Subscriber is marked as only allowed to roam in Subscribed LSAs while roaming in a VLR and no SoLSA Support indicator is stored for that VLR, the location status of that Subscriber shall be set to Restricted.

IST Support Indicator

This parameter is used to indicate to the HLR that the VMSC supports basic IST functionality, that is, the VMSC is able to terminate the Subscriber Call Activity that originated the IST Alert when it receives the IST alert response indicating that the call(s) shall be terminated. If this parameter is not included in the Update Location indication and the Subscriber is marked as an IST Subscriber, then the HLR may limit the service for the subscriber (by inducing an Operator Determined barring of Roaming, Incoming or Outgoing calls), or allow service assuming the associated risk of not having the basic IST mechanism available.

This parameter can also indicate that the VMSC supports the IST Command service, including the ability to terminate all calls being carried for the identified subscriber by using the IMSI as a key. If this additional capability is not included in the Update Location indication and the HLR supports the IST Command capability, then the HLR may limit the service for the subscriber (by inducing an Operator Determined barring of Roaming, Incoming or Outgoing calls), or allow service assuming the associated risk of not having the IST Command mechanism available.

Long FTN Supported

This parameter indicates that the VLR supports Long Forwarded-to Numbers.

Super-Charger Supported in Serving Network Entity

This parameter is used by the VLR to indicate to the HLR that the VLR supports the Super-Charger functionality and whether subscription data has been retained by the VLR. If subscription data has been retained by the VLR the age indicator shall be included. Otherwise the VLR shall indicate that subscriber data is required.

If this parameter is absent then the VLR does not support the Super-Charger functionality.

Supported LCS Capability Sets

This parameter indicates, if present, the capability sets of LCS which are supported. If the parameter is sent but no capability set is marked as supported then the VLR does not support LCS at all.

If this parameter is absent then the VLR may support at most LCS capability set 1, that is LCS Release98 or Release99 version.

Offered CAMEL 4 CSIs

This parameter indicates the CAMEL phase 4 CSIs offered in the VMSC/VLR (see clause 7.6.3.36D).

Inform Previous Network Entity

This parameter is used by the VLR to ask the HLR to inform the previous network entity about the update by sending the previous network entity a Cancel Location message. It is used in case Super-Charger is supported in the network and the serving network entity has not been able to inform the previous network entity that MS has moved, that is if it has not sent Send Identification to the previous serving entity.

CS LCS Not Supported by UE

See definition in clause 7.6.11.

V-GMLC address

See definition in clause 7.6.2.

IMEISV

For definition of the parameter see clause 7.6.2. For the use of this parameter see 3GPP TS 23.012. IMEISV shall be present if ADD function is supported and a new IMEISV is to be notified to the HLR (The functional requirements for the presence of IMEISV due to ADD are described in 3GPP TS 22.101 clause 7.4).

Skip Subscriber Data Update

The presence of the parameter is optional and if present it indicates that the service is solely used to inform the HLR about change of IMEISV. The parameter is used to optimise signalling load during Location Update procedure.

ADD Capability

This parameter indicates, if present, the support of ADD function by the HLR.

<u>User error</u>

In case of unsuccessful updating, an error cause shall be returned by the HLR. The following error causes defined in clause 7.6.1 may be used, depending on the nature of the fault:

- unknown subscriber;

roaming not allowed;

This cause will be sent if the MS is not allowed to roam into the PLMN indicated by the VLR number. The cause is qualified by the roaming restriction reason "PLMN Not Allowed" or "Operator Determined Barring". If no qualification is received (HLR with MAP Version 1), "PLMN Not Allowed" is taken as default.

- system failure;
- unexpected data value.

Provider error

For definition of provider errors see clause 7.6.1.

8.1.3 MAP CANCEL LOCATION service

8.1.3.1 Definition

This service is used between HLR and VLR to delete a subscriber record from the VLR. It may be invoked automatically when an MS moves from one VLR area to another, to remove the subscriber record from the old VLR, or by the HLR operator to enforce a location updating from the VLR to the HLR, e.g. on withdrawal of a subscription.

Also this service is used between HLR and SGSN to delete a subscriber record from the SGSN. It may be invoked automatically when an MS moves from one SGSN area to another, to remove the subscriber record from the old SGSN, or by the HLR operator to enforce a location updating from the SGSN to the HLR.

The MAP_CANCEL_LOCATION service is a confirmed service using the primitives defined in table 8.1/3.

8.1.3.2 Service primitives

Table 8.1/3: MAP CANCEL LOCATION

Parameter name	Request	Indication	Response	Confirm
Invoke Id	М	M(=)	M(=)	M(=)
IMSI	М	M(=)		
LMSI	С	C(=)		
Cancellation Type	С	C(=)		
User error			С	C(=)
Provider error				0

8.1.3.3 Parameter definitions and use

Invoke Id

See definition in clause 7.6.1.

IMSI

See definition in clause 7.6.2.

LMSI

See definition in clause 7.6.2. The LMSI shall be included if it has been received from VLR. LMSI is not applicable between SGSN and HLR.

Value 0000 0000 can be used to indicate that the LMSI is not in use.

Cancellation Type

See definition in clause 7.6.3. The presence of this parameter is mandatory when the Cancel Location is sent to the SGSN. If the VLR receives this parameter and do not understand it the VLR shall ignore it.

User error

If the cancellation fails, an error cause is to be returned by the VLR or by the SGSN. One of the following error causes defined in clause 7.6.1 shall be used:

- unexpected data value;
- data missing.

Provider error

For definition of provider errors see clause 7.6.1.

8.1.4 MAP_SEND_IDENTIFICATION service

8.1.4.1 Definition

The MAP_SEND_IDENTIFICATION service is used between a VLR and a previous VLR to retrieve IMSI and authentication data for a subscriber registering afresh in that VLR.

It may also be used to send the MSC number from a VLR to a previous VLR.

The MAP_SEND_IDENTIFICATION service is a confirmed service using the service primitives defined in table 8.1/4.

8.1.4.2 Service primitives

Table 8.1/4: MAP_SEND_IDENTIFICATION

Parameter name	Request	Indication	Response	Confirm
Invoke Id	M	M(=)	M(=)	M(=)
TMSI	M	M(=)		
Number of requested vectors	M	M(=)		
Segmentation prohibited indicator	С	C(=)		
MSC Number	U	C(=)		
Previous Location Area Id	U	C(=)		
Hop Counter	U	C (=)		
IMSI			С	C(=)
Authentication set			U	C(=)
Current Security Context			U	C(=)
User error			С	C(=)
Provider error				0

8.1.4.3 Parameter definitions and use

Invoke Id

See definition in clause 7.6.1.

TMSI

See definition in clause 7.6.2.

If multiple service requests are present in a dialogue then this parameter shall be present in every service request.

Number of requested vectors

A number indicating how many authentication vectors the new VLR is prepared to receive. The previous VLR shall not return more vectors than indicated by this parameter.

This parameter shall be present in the first (or only) request of the dialogue. If multiple service requests are present in a dialogue then this parameter shall not be present in any service request other than the first one

Segmentation prohibited indicator

This parameter indicates if the new VLR or SGSN allows segmentation of the response at MAP user level.

This parameter may be present only in the first request of the dialogue.

IMSI

See definition in clause 7.6.2. The IMSI is to be returned if the service succeeds.

If multiple service requests are present in a dialogue and the service succeeds then this parameter shall not be present in any service response other than the first one

MSC Number

This is the ISDN number assigned to the MSC currently serving the MS.

Previous Location Area Id

See definition in clause 7.6.2. Together with the TMSI the Previous Location Area Id can be used to derive the IMSI.

Authentication set

See definition in clause 7.6.7. If the service succeeds a list of up to five authentication sets is returned, if there are any available.

Current Security Context

See definition in clause 7.6.7. If the service succeeds, a list of either GSM or UMTS Security Context parameters can be returned.

Hop Counter

For the use of this parameter see 3GPP TS 23.012 [23].

User error

This parameter is mandatory if the service fails. The following error cause defined in clause 7.6.1 may be used, depending on the nature of the fault:

- unidentified subscriber.

Provider error

For definition of provider errors see clause 7.6.1.

8.1.5 Void

0	1	5	4		١	/c	:	ᆈ	
×	Ή	'	1		١.	ľ	١I	П	

8.1.5.2 Void

8.1.5.3 Void

8.1.6 MAP_PURGE_MS service

8.1.6.1 Definition

This service is used between the VLR and the HLR to cause the HLR to mark its data for an MS so that any request for routing information for a mobile terminated call or a mobile terminated short message will be treated as if the MS is not reachable. It is invoked when the subscriber record for the MS is to be deleted in the VLR, either by MMI interaction or automatically, e.g. because the MS has been inactive for several days. This service shall not be used if both the VLR and HLR support the Super-Charger functionality.

Also this service is used between the SGSN and the HLR to cause the HLR to mark its data for an MS so that any request for routing information for a mobile terminated short message or a network requested PDP-context activation will be treated as if the MS is not reachable. It is invoked when the subscriber record for the MS is to be deleted in the SGSN, either by MMI interaction or automatically, e.g. because the MS has been inactive for several days. This service shall not be used if both the SGSN and HLR support the Super-Charger functionality.

The MAP_PURGE_MS service is a confirmed service using the primitives defined in table 8.1/6.

8.1.6.2 Service primitives

Table 8.1/6: MAP_PURGE_MS

Parameter name	Request	Indication	Response	Confirm
Invoke Id	М	M(=)	M(=)	M(=)
IMSI	М	M(=)		
VLR number	С	C(=)		
Freeze TMSI			С	C(=)
Freeze P-TMSI			С	C(=)
SGSN number	С	C(=)		
User error			С	C(=)
Provider error				0

8.1.6.3 Parameter definitions and use

Invoke ID

See definition in clause 7.6.1.

IMSI

See definition in clause 7.6.2.

VLR number

Shall be present if the sender is VLR. See definition in clause 7.6.2.

SGSN number

Shall be present if the sender is SGSN. See definition in clause 7.6.2.

Freeze TMSI

This parameter is sent to the VLR to indicate that the TMSI has to be frozen. It shall be present if the received VLR number matches the stored VLR number.

Freeze P-TMSI

This parameter is sent to the SGSN to indicate that the P-TMSI has to be frozen. It shall be present if the received SGSN number matches the stored SGSN number.

User error

This parameter is sent by the responder when an error is detected and if present, takes one of the following values:

- Data Missing;
- Unexpected Data Value;
- Unknown Subscriber.

Provider error

See definition of provider errors in clause 7.6.1.

8.1.7 MAP_UPDATE_GPRS_LOCATION service

8.1.7.1 Definition

This service is used by the SGSN to update the location information stored in the HLR.

The MAP_UPDATE_GPRS_LOCATION service is a confirmed service using the service primitives given in table 8.1/7.

8.1.7.2 Service primitives

Table 8.1/7: MAP_UPDATE_GPRS_LOCATION

Parameter name	Request	Indication	Response	Confirm
Invoke Id	M	M(=)	M(=)	M(=)
IMSI	М	M(=)		
SGSN number	M	M(=)		
SGSN address	M	M(=)		
Supported CAMEL Phases	С	C(=)		
SoLSA Support Indicator	С	C(=)		
Super-Charger Supported in Serving Network Entity	С	C(=)		
GPRS enhancements support indicator	С	C(=)		
Supported LCS Capability Sets	С	C(=)		
Offered CAMEL 4 CSIs	С	C(=)		
Inform Previous Network Entity	С	C(=)		
PS LCS Not Supported by UE	С	C(=)		
V-GMLC Address	U	C(=)		
Call barring support indicator	С	C(=)		
IMEISV	С	C(=)		
Skip Subscriber Data Update	U	C(=)		
ADD Capability			U	C(=)
HLR number			С	C(=)
User error			С	C(=)
Provider error				Ö

8.1.7.3 Parameter definitions and use

Invoke Id

See definition in clause 7.6.1.

IMSI

See definition in clause 7.6.2.

SGSN number

See definition in clause 7.6.2.

SGSN address

See definition in clause 7.6.2.

Supported CAMEL Phases

This parameter indicates which phases of CAMEL are supported. <u>The SGSN can only support CAMEL phase 3 or greater.</u>

SoLSA Support Indicator

This parameter is used by the SGSN to indicate to the HLR in the Update GPRS Location indication that SoLSA is supported. If this parameter is not included in the Update GPRS Location indication and the Subscriber is marked as

only allowed to roam in Subscribed LSAs, then the HLR shall reject the roaming and indicate to the SGSN that roaming is not allowed to that Subscriber in the SGSN.

This SoLSA Support Indicator shall be stored by the HLR per SGSN where there are Subscribers roaming. If a Subscriber is marked as only allowed to roam in Subscribed LSAs while roaming in a SGSN and no SoLSA Support indicator is stored for that SGSN, the location status of that Subscriber has to be set to Restricted.

Super-Charger Supported in Serving Network Entity

This parameter is used by the SGSN to indicate to the HLR that the SGSN supports the Super-Charger functionality and whether subscription data has been retained by the SGSN. If subscription data has been retained by the SGSN the age indicator shall be included. Otherwise the SGSN shall indicate that subscriber data is required.

If this parameter is absent then the SGSN does not support the Super-Charger functionality.

GPRS enhancements support indicator

This parameter is used by the SGSN to indicate to the HLR in the Update GPRS Location indication that GPRS enhancements are supported. If this parameter is included in the Update GPRS Location indication the HLR may send the extension QoS parameter in the PDP contexts to the SGSN. The HLR may send the extension-2 QoS parameter with the extension QoS parameter.

HLR number

See definition in clause 7.6.2. The presence of this parameter is mandatory in case of successful HLR updating.

Supported LCS Capability Sets

This parameter indicates, if present, the capability sets of LCS which are supported. If the parameter is sent but no capability set is marked as supported then the SGSN does not support LCS at all.

The SGSN is not allowed to indicate support for LCS capability set 1.

If this parameter is absent then the SGSN does not support LCS at all.

Offered CAMEL 4 CSIs

This parameter indicates the CAMEL phase 4 CSIs offered in the SGSN (see clause 7.6.3.36D).

Inform Previous Network Entity

This parameter is used by the SGSN to ask the HLR to inform the previous network entity about the update by sending the previous network entity a Cancel Location message. It is used in case Super-Charger is supported in the network and the serving network entity has not been able to inform the previous network entity that MS has moved, that is if it has not sent SGSN Context Request to the previous serving entity.

PS LCS Not Supported by UE

See definition in clause 7.6.11.

V-GMLC address

See definition in clause 7.6.2.

Call Barring support indicator

See definition in clause 7.6.3.92.

IMEISV

For definition of the parameter see clause 7.6.2. For the use of this parameter see 3GPP TS 23.060. IMEISV shall be present if ADD function is supported and the IMEISV is new in SGSN (The functional requirements for the presence of IMEISV due to ADD are described in 3GPP TS 22.101 clause 7.4).

Skip Subscriber Data Update

The presence of the parameter is optional and if present it indicates that the service is solely used to inform the HLR about change of IMEISV. The parameter is used to optimise signalling load during Location Update procedure.

ADD Capability

This parameter indicates, if present, the support of ADD function by the HLR.

User error

In case of unsuccessful updating, an error cause shall be returned by the HLR. The following error causes defined in clause 7.6.1 may be used, depending on the nature of the fault:

- unknown subscriber;
- roaming not allowed.

This cause will be sent if the MS is not allowed to roam into the PLMN indicated by the SGSN number. The cause is qualified by the roaming restriction reason "PLMN Not Allowed" or "Operator Determined Barring".

- system failure;
- unexpected data value.

The diagnostic in the Unknown Subscriber may indicate 'Imsi Unknown' or 'Gprs Subscription Unknown'.

Provider error

For definition of provider errors see clause 7.6.1.

8.1.8 MAP-NOTE-MM-EVENT

8.1.8.1 Definition

This service is used between the VLR and the gsmSCF or between the SGSN and the gsmSCF when a mobility management event for a subscriber has been processed successfully, that subscriber is provisioned with M-CSI or MG-CSI and the relevant mobility management event is marked for reporting.

This service is also used between the VLR and the Presence Network Agent or between the SGSN and the Presence Network Agent to notify the Presence Network Agent when a mobility management event for a subscriber has been processed successfully, that subscriber is provisioned with M-CSI or MG-CSI and the relevant mobility management event is marked for reporting (see 3GPP TS 23.141 [128]).

8.1.8.2 Service primitives

The service primitives are shown in table 8.1/8.

Table 8.1/8: MAP_NOTE_MM_EVENT parameters

Parameter name	Request	Indication	Response	Confirm
Invoke id	М	M(=)	M(=)	M(=)
Event Met	М	M(=)		
Service Key	М	M(=)		
IMSI	М	M(=)		
Basic MSISDN	М	M(=)		
Location Information for GPRS	С	C(=)		
Location Information	С	C(=)		
LSA Identity	С	C(=)		
Supported CAMEL Phases	М	M(=)		
Offered CAMEL 4	С	C(=)		
Functionalities				
User error			С	C(=)
Provider error				0

8.1.8.3 Parameter use

Event Met

This parameter indicates the mobility management event that has lead to the notification. It shall have one of the following values for a mobility management event reported by the VLR:

- Location update in the same VLR service area;
- Location update to another VLR service area;
- IMSI attach;
- MS initiated IMSI detach (explicit detach);
- Network initiated IMSI detach (implicit detach).

It shall have one of the following values for a mobility management event reported by the SGSN:

- Routeing area update in the same SGSN service area;
- Routeing area update to another SGSN service area;
- GPRS attach;
- MS initiated GPRS detach;
- Network initiated GPRS detach;
- Network initiated transfer to the "not reachable for paging" state.

Service Key

See clause 7.6.x.

<u>IMSI</u>

See clause 7.6.x.

Basic MSISDN

See clause 7.6.x.

Location Information

See clause 7.6.2.30. This information shall be sent when the event is reported by a VLR, if available.

Location Information for GPRS

See clause 7.6.2.30a. This information shall be sent when the event is reported by an SGSN, if available.

LSA Identity

See clause 7.6.x. This information shall be sent, if available.

Supported CAMEL Phases

See clause 7.6.x. This information shall always be sent.

Offered CAMEL 4 Functionalities

This parameter indicates the CAMEL phase 4 functionalities offered by the sending entity, VMSC/VLR or SGSN (see clause 7.6.3.36G).

User error

This parameter is sent by the receiving entity when an error is detected. It shall have one of the following values:

- Data Missing;

- Unexpected Data Value;
- Unknown Subscriber;
- MM-EventNotSupported.

Provider error

This is defined in clause 7.6.1.

8.2 Paging and search

8.2.1 MAP_PAGE service

8.2.1.1 Definition

This service is used between VLR and MSC to initiate paging of an MS for mobile terminated short message or unstructured SS notification.

The MAP_PAGE service is a confirmed service using the primitives from table 8.2/1.

8.2.1.2 Service primitives

Table 8.2/1: MAP_PAGE

Parameter name	Request	Indication	Response	Confirm
Invoke Id	M	M(=)	M(=)	M(=)
IMSI	M	M(=)		
Stored location area Id	M	M(=)		
TMSI	U	C(=)		
User error			С	C(=)
Provider error				0

8.2.1.3 Parameter definitions and use

Invoke Id

See definition in clause 7.6.1.

IMSI

See definition in clause 7.6.2. The IMSI is used to define the paging subgroup. If the TMSI is not supplied, paging on the radio path uses the IMSI as an identifier.

Stored location area Id

See definition in clause 7.6.2.

TMSI

See definition in clause 7.6.2. The TMSI is included if paging on the radio channel is to use the TMSI as an identifier.

User error

The following error causes defined in clause 7.6.1 may be sent by the user in case of a paging error, depending on the failure reason:

- absent subscriber;
- unknown location area;
- busy subscriber;

- system failure;
- this corresponds to the case where there is no call associated with the MAP_PAGE service, i.e. if the call has been released but the dialogue to the VLR has not been aborted;
- unexpected data value.

Provider error

See definition in clause 7.6.1.

8.2.2 MAP_SEARCH_FOR_MS service

8.2.2.1 Definition

This service is used between VLR and MSC to initiate paging of an MS in all location areas of that VLR. It is used if the VLR does not hold location area information confirmed by radio contact.

The MAP_SEARCH_FOR_MS service is a confirmed service using the primitives from table 8.2/2.

8.2.2.2 Service primitives

Table 8.2/2: MAP_SEARCH_FOR_MS

Parameter name	Request	Indication	Response	Confirm
Invoke Id	М	M(=)	M(=)	M(=)
IMSI	М	M(=)		
Current location area Id			С	C(=)
User error			С	C(=)
Provider error				0

8.2.2.3 Parameter definitions and use

Invoke Id

See definition in clause 7.6.1.

IMSI

See definition in clause 7.6.2. The IMSI is used to identify the subscriber when paging on the radio path.

Current location area Id

See definition in clause 7.6.2. In case of successful outcome of the service, i.e. if the MS responds to paging, the Location Area Id of the area in which the MS responded is given in the response.

User error

The following error causes defined in clause 7.6.1 shall be sent by the user if the search procedure fails, depending on the failure reason:

- absent subscriber;

this error cause is returned by the MSC if the MS does not respond to the paging request;

- system failure;
- this corresponds to the case where there is no call associated with the MAP_SEARCH_FOR_MS service, i.e. if the call has been released but the dialogue to the VLR has not been aborted;
- busy subscriber;
- unexpected data value.

Provider error

See definition in clause 7.6.1.

8.3 Access management services

8.3.1 MAP_PROCESS_ACCESS_REQUEST service

8.3.1.1 Definition

This service is used between MSC and VLR to initiate processing of an MS access to the network, e.g. for mobile originated short message submission or after being paged by the network.

The MAP_PROCESS_ACCESS_REQUEST service is a confirmed service using the primitives from table 8.3/1.

8.3.1.2 Service primitives

Table 8.3/1: MAP_PROCESS_ACCESS_REQUEST

Parameter name	Request	Indication	Response	Confirm
Invoke Id	M	M(=)	M(=)	M(=)
CM service type	M	M(=)		
Access connection status	M	M(=)		
Current Location Area Id	M	M(=)		
Serving cell Id	M	M(=)		
TMSI	С	C(=)		
Cksn	С	C(=)		
IMSI	С	C(=)	С	C(=)
IMEI	С	C(=)	С	C(=)
MSISDN			U	C(=)
User error			С	C(=)
Provider error				Ö

8.3.1.3 Parameter definitions and use

Invoke Id

See definition in clause 7.6.1.

CM service type

See definition in clause 7.6.9.

Access connection status

See definition in clause 7.6.9.

Current Location Area Id

See definition in clause 7.6.2. This parameter is used to update the VLR in case of previous VLR failure.

Serving cell Id

See definition in clause 7.6.2.

TMSI

See definition in clause 7.6.2. Either TMSI or IMSI as received from the MS are included in the Request/Indication, but one shall be present. In case of CM Service Type "Emergency Call Establishment", the IMEI may replace IMSI/TMSI.

Cksn

See definition in clause 7.6.7. In case of access with TMSI, the Cksn shall be present.

IMSI

See definition in clause 7.6.2. Either TMSI or IMSI as received from the MS are included in the Request/Indication, but one shall be present. In case of CM Service Type "Emergency Call Establishment", the IMEI may replace IMSI/TMSI.

In the Response/Confirmation, the IMSI is to be sent in case of successful outcome of the service. In case of CM Service Type "Emergency Call Establishment", IMEI may replace IMSI.

IMEI

See definition in clause 7.6.2. The IMEI may replace IMSI/TMSI in the Request/Indication and IMSI in the Response/Confirmation only in case the CM Service Type indicates "Emergency Call Establishment".

MSISDN

See definition in clause 7.6.2. The MSISDN is included in case of successful outcome of the service as an operator option, e.g. if it is needed at the MSC for charging purposes in case of call forwarding.

User error

One of the following error causes defined in clause 7.6.1 shall be sent by the user if the access request fails, depending on the failure reason:

- unidentified subscriber;
- illegal subscriber;

this error is sent if a correlated authentication procedure has not authenticated the subscriber;

- illegal equipment;

this error is sent if an IMEI check failed, i.e. the IMEI is blacklisted or not white-listed;

- roaming not allowed;
- this cause is used after VLR restart if the subscriber has no subscription for the current location area, e.g. due to regional subscription. The cause will be qualified by "location area not allowed" or "national roaming not allowed", respectively;
- unknown location area;
- system failure;
- unexpected data value.

Provider error

For definition of provider errors see clause 7.6.1.

8.4 Handover services

It should be noted that the handover services used on the B-interface have not been updated for Release 99. The B-interface is not fully operational specified. It is strongly recommended not to implement the B-interface as an external interface.

8.4.1 MAP_PREPARE_HANDOVER service

8.4.1.1 Definition

This service is used between MSC-A and MSC-B (E-interface) when a call is to be handed over or relocated from MSC-A to MSC-B.

The MAP_PREPARE_HANDOVER service is a confirmed service using the primitives from table 8.4/1.

8.4.1.2 Service primitives

Table 8.4/1: MAP_PREPARE_HANDOVER

Parameter name	Request	Indication	Response	Confirm
Invoke Id	M	M(=)	M(=)	M(=)
Target Cell Id	С	C(=)		
Target RNC Id	С	C(=)		
HO-NumberNotRequired	С	C(=)		
IMSI	С	C(=)		
Integrity Protection Information	С	C(=)		
Encryption Information	С	C(=)		
Radio Resource Information	С	C(=)		
AN-APDU	С	C(=)	С	C(=)
Allowed GSM Algorithms	С	C(=)		
Allowed UMTS Algorithms	С	C(=)		
Radio Resource List	С	C(=)		
RAB ID	С	C(=)		
GERAN Classmark	С	C(=)		
BSSMAP Service Handover	С	C(=)		
BSSMAP Service Handover	С	C(=)		
List				
RANAP Service Handover	С	C(=)		
Iu-Currently Used Codec	С	C(=)		
Iu-Supported Codecs List	С	C(=)		
RAB Configuration Indicator	С	C(=)		
ASCI Call Reference	С	C(=)		
UESBI-lu	С	C(=)		
IMEISV	С	C(=)		
Alternative Channel Type	С	C(=)		
Trace_Propagation_List	С	C(=)		
Handover Number			С	C(=)
Relocation Number List			С	C(=)
Multicall Bearer Information			С	C(=)
Multiple Bearer Requested	С	C(=)		
Multiple Bearer Not Supported			С	C(=)
Selected UMTS Algorithms			С	C(=)
Chosen Radio Resource			С	C(=)
Information				
lu-Selected Codec			С	C(=)
lu-Available Codecs List			С	C(=)
User error			С	C(=)
Provider error				0

8.4.1.3 Parameter use

Invoke Id

For definition of this parameter see clause 7.6.1.

Target Cell Id

For definition of this parameter see clause 7.6.2. This parameter is only included if the service is not in an ongoing transaction. This parameter shall also be excluded if the service is a part of the Inter-MSC SRNS Relocation procedure or the inter-system handover GSM to UMTS procedure described in 3GPP TS 23.009.

Target RNC Id

For definition of this parameter see clause 7.6.2. This parameter shall be included if the service is a part of the Inter-MSC SRNS Relocation procedure or the inter-system handover GSM to UMTS procedure described in 3GPP TS 23.009.

HO-Number Not Required

For definition of this parameter see clause 7.6.6.

IMSI

For definition of this parameter see clause 7.6.2. This UMTS parameter shall be included if:

- available and
- if the access network protocol is BSSAP and
- there is an indication that the MS also supports UMTS.

<u>Integrity Protection Information</u>

For definition of this parameter see clause 7.6.6. This UMTS parameter shall be included if available and if the access network protocol is BSSAP.

Encryption Information

For definition of this parameter see clause 7.6.6. This UMTS parameter shall be included if available and if the access network protocol is BSSAP.

Radio Resource Information

For definition of this parameter see clause 7.6.6. This GSM parameter shall be included if the access network protocol is RANAP and there is an indication that the UE also supports GSM. If the parameter Radio Resource List is sent , the parameter Radio Resource Information shall not be sent.

AN-APDU

For definition of this parameter see clause 7.6.9.

Allowed GSM Algorithms

For definition of this parameter see clause 7.6.6. This parameters includes allowed GSM algorithms. This GSM parameter shall be included if:

- the service is a part of the Inter-MSC SRNS Relocation procedure and
- Ciphering or Security Mode Setting procedure has been performed.and
- there is an indication that the UE also supports GSM.

Allowed UMTS Algorithms

For definition of this parameter see clause 7.6.6. This UMTS parameter shall be included if all of the following conditions apply:

- access network protocol is BSSAP and
- Integrity Protection Information and Encryption Information are not available and

Ciphering or Security Mode Setting procedure has been performed.

Radio Resource List

For definition of this parameter see clause 7.6.6. This parameter shall be included if the access network protocol is RANAP and there is an indication that the UE also supports GSM. This parameter shall be sent when MSC-A requests multiple bearers to MSC-B. If the parameter Radio Resource Information is sent , the parameter Radio Resource List shall not be sent.

RAB ID

For definition of this parameter see subclause 7.6.2. This parameter shall be included when MSC-A supports multiple bearers and access network protocol is BSSAP and the RAB ID has a value other than 1.

GERAN Classmark

For definition of this parameter see subclause 7.6.6 This parameter shall be included if available.

BSSMAP Service Handover

For definition of this parameter see clause 7.6.6. It shall be present if it is available and the access network protocol is RANAP. If the parameter BSSMAP Service Handover List is sent, the parameter BSSMAP Service Handover shall not be sent.

BSSMAP Service Handover List

For definition of this parameter see clause 7.6.6. It shall be present if it is available and the access network protocol is RANAP. This parameter shall be sent when MSC-A requests multiple bearers to MSC-B. If the parameter BSSMAP Service Handover is sent, the parameter BSSMAP Service Handover List shall not be sent.

RANAP Service Handover

For definition of this parameter see clause 7.6.6. It shall be present if it is available and the access network protocol is BSSAP.

Iu-Currently Used Codec

For definition of this parameter see subclause 7.6.6. This parameter shall be included if the handover is requested for a speech bearer and the MS is in UMTS or GERAN Iu-mode access. This parameter shall not be included if the Iu-Supported Codecs List is not included.

Iu-Supported Codecs List

For definition of this parameter see subclause 7.6.6. This parameter shall be included by MSC-A, if the handover is requested for a speech bearer.

RAB Configuration Indicator

For definition of this parameter see subclause 7.6.6. This parameter may be included if the handover is requested for a speech bearer and MSC-A knows by means of configuration information that MSC-B supports the use of the Iu-Supported Codecs List parameter. This parameter shall not be included if the Iu-Supported Codecs List is not included.

ASCI Call Reference

This parameter contains either the broadcast call reference or group call reference. It shall be included if a subscriber is undergoing handover during a VGCS or VBS call, where MSC-B already has a Bearer established, so that MSC-B can determine the Group or Broadcast Call to which it shall attach the subscriber, see 3GPP TS 48.008 [49].

UESBI-Iu

For definition of this parameter see clause 7.6.6. It shall be present if it is available and the access network protocol is BSSAP.

IMEISV

For definition of the parameter see clause 7.6.2. This parameter is used for Management based Trace Activation (see 3GPP TS 32.422) and shall be present, if available.

Alternative Channel Type

For definition of this parameter see clause 7.6.6 It shall be present for a SCUDIF call if the access network protocol is BSSAP.

Trace Propagation List

See definition in clause 7.6.10. This parameter shall be included when MSC-A requests trace invocation.

Handover Number

For definition of this parameter see clause 7.6.2. This parameter shall be returned at handover, unless the parameter HO-NumberNotRequired is sent. If the parameter Handover Number is returned, the parameter Relocation Number List shall not be returned.

Relocation Number List

For definition of this parameter see clause 7.6.2. This parameter shall be returned at relocation, unless the parameter HO-NumberNotRequired is sent. If the parameter Relocation Number List is returned, the parameter Handover Number shall not be returned.

Multicall Bearer Information

For a definition of this parameter see clause 7.6.2. This parameter shall be returned at relocation in the case that MSC-B supports multiple bearers.

Multiple Bearer Requested

For a definition of this parameter see clause 7.6.2. This parameter shall be sent when MSC-A requests multiple bearers to MSC-B.

Multiple Bearer Not Supported

For a definition of this parameter see clause 7.6.2. This parameter shall be returned at relocation when MSC-B receives Multiple Bearer Requested parameter and MSC-B does not support multiple bearers.

Selected UMTS Algorithms

For definition of this parameter see clause 7.6.6. This parameters includes the UMTS integrity and optionally encryption algorithms selected by RNC under the control of MSC-B. This UMTS parameter shall be included if the service is a part of the inter MSC inter system handover from GSM to UMTS.

Chosen Radio Resource Information

For definition of this parameter see clause 7.6.6. This parameter shall be returned at relocation if the encapsulated PDU is RANAP RAB Assignment Response and MS is in GSM access.

Iu-Selected Codec

For definition of this parameter see subclause 7.6.6. This parameter shall be included if an Iu-Supported Codecs List was received in the service request and MSC-B supports the selection of codec based on the Iu-Supported Codecs List, even if the Iu-Selected Codec is equal to the Iu-Currently Used Codec received in the service request. This parameter shall not be included if the Iu-Supported Codecs List was not received in the service request.

Iu-Available Codecs List

For definition of this parameter see subclause 7.6.6. This parameter shall be included by an MSC-B supporting TrFO, if the Iu-Supported Codecs List was included by MSC-A and the target radio access is UMTS or GERAN Iu-mode.

User error

For definition of this parameter see clause 7.6.1. The following errors defined in clause 7.6.1 may be used, depending on the nature of the fault:

- No handover number available.
- Target cell outside group call area;
- System failure.
- Unexpected data value.
- Data Missing.

Provider error

See definition of provider errors in clause 7.6.1.

8.4.2 MAP_SEND_END_SIGNAL service

8.4.2.1 Definition

This service is used between MSC-B and MSC-A (E-interface) indicating that the radio path has been established by MSC-B to the MS. MSC-A retains then the main control of the call until it clears.

The response is used by MSC-A to inform MSC-B that all resources for the call can be released in MSC-B, either because the call has been released in MSC-A or because the call has been successfully handed over or relocated from MSC-B to another MSC.

The MAP_SEND_END_SIGNAL service is a confirmed service using the primitives from table 8.4/2.

8.4.2.2 Service primitives

Table 8.4/2: MAP_SEND_END_SIGNAL

Parameter name	Request	Indication	Response	Confirm
Invoke Id	М	M(=)	M(=)	M(=)
AN-APDU	М	M(=)		
Provider error				0

8.4.2.3 Parameter use

Invoke Id

For definition of this parameter see clause 7.6.1.

AN-APDU

For definition of this parameter see clause 7.6.9.

Provider error

For definition of this parameter see clause 7.6.1.

8.4.3 MAP_PROCESS_ACCESS_SIGNALLING service

8.4.3.1 Definition

This service is used between MSC-B and MSC-A (E-interface) to pass information received on the A-interface or Iu-interface in MSC-B to MSC-A.

The MAP_PROCESS_ACCESS_SIGNALLING service is a non-confirmed service using the primitives from table 8.4/3.

8.4.3.2 Service primitives

Table 8.4/3: MAP_PROCESS_ACCESS_SIGNALLING

Parameter name	Request	Indication
Invoke Id	M	M(=)
AN-APDU	M	M(=)
Selected GSM Algorithm	С	C(=)
Selected UMTS Algorithms	С	C(=)
Chosen Radio Resource	С	C(=)
Information		
Selected RAB id	С	C(=)

Iu-Selected Codec	С	C(=)
Iu-Available Codecs List	С	C(=)

8.4.3.3 Parameter use

Invoke Id

For definition of this parameter see clause 7.6.1.

AN-APDU

For definition of this parameter see clause 7.6.9.

Selected GSM algorithm

For definition of this parameter see clause 7.6.6. This parameter shall be present if the encapsulated PDU is Security Mode Complete and MS is in GSM access.

Selected UMTS Algorithms

For definition of this parameter see clause 7.6.6. This parameters includes the UMTS integrity and optionally encryption algorithms selected by RNC under the control of MSC-B. This UMTS parameter shall be included if the encapsulated PDU is BSSMAP Cipher Mode Complete and the MS is in UMTS, or an interystem handover to UMTS is performed in MSC-B, or in the case of intra MSC-B intra UMTS relocation.

Chosen Radio Resource Information

For definition of this parameter see clause 7.6.6. This parameter shall be sent if the encapsulated PDU is RANAP RAB Assignment Response and MS is in GSM access.

Selected RAB ID

The selected radio access bearer that was kept at subsequent intra-MSC handover from UMTS to GSM after multiple bearers were used.

Iu-Selected Codec

For definition of this parameter see subclause 7.6.6. This parameter shall be included

- if MSC-B changes the selected codec;
- if intersystem handover to UMTS or GERAN Iu-mode is performed in MSC-B; or
- if MSC-B received a Forward Access Signalling service request including an Iu-Supported Codecs List and the MS is in UMTS or GERAN Iu-mode access.

This parameter shall not be included if the Iu-Supported Codecs List was not received either in the Prepare Handover service request or in the Forward Access Signalling service request.

Iu-Available Codecs List

For definition of this parameter see subclause 7.6.6. This parameter shall be included by an MSC-B supporting TrFO

- if the Iu-Available Codecs List has changed in MSC-B;
- if intersystem handover to UMTS or GERAN Iu-mode is performed in MSC-B; or
- if MSC-B received a Forward Access Signalling service request including an Iu-Supported Codecs List and the MS is in UMTS or GERAN Iu-mode access.

8.4.4 MAP_FORWARD_ACCESS_SIGNALLING service

8.4.4.1 Definition

This service is used between MSC-A and MSC-B (E-interface) to pass information to be forwarded to the A-interface or Iu-interface of MSC-B.

The MAP_FORWARD_ACCESS_SIGNALLING service is a non-confirmed service using the primitives from table 8.4/4.

8.4.4.2 Service primitives

Table 8.4/4: MAP_FORWARD_ACCESS_SIGNALLING

Parameter name	Request	Indication
Invoke Id	М	M(=)
Integrity Protection Information	С	C(=)
Encryption Information	С	C(=)
Key Status	С	C(=)
AN-APDU	M	M(=)
Allowed GSM Algorithms	С	C(=)
Allowed UMTS Algorithms	С	C(=)
Radio Resource Information	С	C(=)
Radio Resource List	С	C(=)
BSSMAP Service Handover	С	C(=)
BSSMAP Service Handover List	С	C(=)
RANAP Service Handover	С	C(=)
lu-Currently Used Codec	С	C(=)
Iu-Supported Codecs List	С	C(=)
RAB Configuration Indicator	С	C(=)
lu-Selected Codec	С	C(=)
Alternative Channel Type	С	C(=)
Trace Propagation List	С	C(=)

8.4.4.3 Parameter use

For the definition and use of all parameters and errors, see clause 7.6.1.

Invoke Id

For definition of this parameter see clause 7.6.1.

Integrity Protection Information

For definition of this parameter see clause 7.6.6. This UMTS parameter shall be included if available and if the encapsulated PDU is BSSMAP Cipher Mode Command.

Encryption Information

For definition of this parameter see clause 7.6.6. This UMTS parameter shall be included if available and if the encapsulated PDU is BSSMAP Cipher Mode Command.

Key Status

For definition of this parameter see clause 7.6.6. This UMTS parameter shall be included if available and if the encapsulated PDU is BSSMAP Cipher Mode Command.

AN-APDU

For definition of this parameter see clause 7.6.9.

Allowed GSM Algorithms

This parameters includes allowed GSM algorithms. This GSM parameter shall be included if the encapsulated PDU is RANAP Security Mode Command and there is an indication that the UE also supports GSM.

Allowed UMTS Algorithms

For definition of this parameter see clause 7.6.6. This UMTS parameter shall be included if Integrity Protection Information and <u>Encryption Information</u> are not available and the encapsulated PDU is BSSMAP Cipher Mode Command.

Radio Resource Information

For definition of this parameter see clause 7.6.6. This parameter shall be sent if the encapsulated PDU is RANAP RAB Assignment Request. If the parameter Radio Resource List is sent, the parameter Radio Resource Information shall not be sent.

Radio Resource List

For definition of this parameter see clause 7.6.6. This parameter shall be sent if the encapsulated PDU is RANAP RAB Assignment Request and MSC-A requests modification of multiple bearers. If the parameter Radio Resource Information is sent, the parameter Radio Resource List shall not be sent.

BSSMAP Service Handover

For definition of this parameter see clause 7.6.6. It shall be present if it is available and the encapsulated PDU is RANAP RAB Assignment Request. If the parameter BSSMAP Service Handover List is sent, the parameter BSSMAP Service Handover shall not be sent.

BSSMAP Service Handover List

For definition of this parameter see clause 7.6.6. It shall be present if it is available and the encapsulated PDU is RANAP RAB Assignment Request and MSC-A requests modification of multiple bearers. If the parameter BSSMAP Service Handover is sent, the parameter BSSMAP Service Handover List shall not be sent.

RANAP Service Handover

For definition of this parameter see clause 7.6.6.. It shall be present if it is available and the encapsulated PDU is BSSMAP Assignment Request.

Iu-Currently Used Codec

For definition of this parameter see subclause 7.6.6. This parameter shall be included if the encapsulated PDU is a RANAP RAB Assignment Request or BSSMAP Assignment Request for a speech bearer and the MS is in UMTS or GERAN Iu-mode access. This parameter shall not be included if the Iu-Supported Codecs List is not included.

Iu-Supported Codecs List

For definition of this parameter see subclause 7.6.6. This parameter shall be included if the encapsulated PDU is a RANAP RAB Assignment Request or BSSMAP Assignment Request and

- a new bearer is allocated for speech;
- an existing bearer is modified from data to speech; or
- for an existing speech bearer the order of priority in the Iu-Supported Codecs List needs to be modified.

This parameter shall not be included if the Iu-Selected Codec is included.

RAB Configuration Indicator

For definition of this parameter see subclause 7.6.6. This parameter may be included if the encapsulated PDU is a RANAP RAB Assignment Request for a speech bearer, and MSC-A knows by means of configuration information that MSC-B supports the use of the Iu-Supported Codecs List parameter. This parameter shall not be included if the Iu-Supported Codecs List is not included.

Iu-Selected Codec

For definition of this parameter see subclause 7.6.6. This parameter shall be included if

- the encapsulated PDU is a RANAP RAB Assignment Request or BSSMAP Assignment Request for an existing speech bearer;
- the MS is in UMTS or GERAN Iu-mode access; and
- an Iu-Available Codecs List was received by MSC-A for this speech bearer before, either in the Prepare Handover service response or in the Process Access Signalling service request.

This parameter shall not be included if the Iu-Supported Codecs List is included.

Alternative Channel Type

For definition of this parameter see clause 7.6.6. This parameter shall be present for a SCUDIF call if the encapsulated PDU is BSSMAP Assignment Request.

Trace Propagation List

See definition in clause 7.6.10. This parameter shall be included when MSC-A requests trace invocation.

8.4.5 MAP_PREPARE_SUBSEQUENT_HANDOVER service

8.4.5.1 Definition

This service is used between MSC-B and MSC-A (E-interface) to inform MSC-A that it has been decided that a handover or relocation to either MSC-A or a third MSC (MSC-B') is required.

The MAP_PREPARE_SUBSEQUENT_HANDOVER service is a confirmed service using the primitives from table 8.4/5.

8.4.5.2 Service primitives

Table 8.4/5: MAP_PREPARE_SUBSEQUENT_HANDOVER

Parameter name	Request	Indication	Response	Confirm
Invoke Id	M	M(=)	M(=)	M(=)
Target Cell Id	С	C(=)		
Target RNC Id	С	C(=)		
Target MSC Number	M	M(=)		
Selected RAB ID	С	C(=)		
GERAN Classmark	С	C(=)		
RAB Configuration Indicator	С	C(=)		
AN-APDU	M	M(=)	С	C(=)
User error			С	C(=)
Provider error				0

8.4.5.3 Parameter use

Invoke Id

For definition of this parameter see clause 7.6.1.

Target Cell Id

For definition of this parameter see clause 7.6.2. This parameter shall be excluded if the service is a part of the Inter-MSC SRNS Relocation procedure or the inter-system handover GSM to UMTS procedure described in 3GPP TS 23.009.

Target RNC Id

For definition of this parameter see clause 7.6.2. This parameter shall be included if the service is a part of the Inter-MSC SRNS Relocation procedure or the inter-system handover GSM to UMTS procedure described in 3GPP TS 23.009.

Target MSC Number

For definition of this parameter see clause 7.6.2.

Selected RAB ID

For definition of this parameter see clause 7.6.2.

GERAN Classmark

For definition of this parameter see subclause 7.6.6 This parameter shall be included if available.

RAB Configuration Indicator

For definition of this parameter see subclause 7.6.6. This parameter may be included if the call is a speech call and MSC-B knows by means of configuration information that MSC-B' (and MSC-A) supports the use of Available Codecs List parameter.

AN-APDU

For definition of this parameter see clause 7.6.9.

User error

For definition of this parameter see clause 7.6.1. The following error causes defined in clause 7.6.1 may be used, depending on the nature of the fault:

- Unknown MSC;
- Subsequent handover failure;
- Unexpected data value;
- Data Missing.

Provider error

For definition of this parameter see clause 7.6.1.

8.4.6 MAP_ALLOCATE_HANDOVER_NUMBER service

8.4.6.1 Definition

This service is used between MSC and VLR (B-interface) to request a handover number.

The MAP_ALLOCATE_HANDOVER_NUMBER service is a confirmed service using the primitives from table 8.4/6.

8.4.6.2 Service primitives

Table 8.4/6: MAP_ALLOCATE_HANDOVER_NUMBER

Parameter name	Request	Indication	Response	Confirm
Invoke Id	M	M(=)	M(=)	M(=)
User error			С	C(=)
Provider error				0

8.4.6.3 Parameter use

Invoke Id

For definition of this parameter see clause 7.6.1.

User error

For definition of this parameter see clause 7.6.1. The following errors defined in clause 7.6.1 may be used, depending on the nature of the fault:

- No handover number available.

Provider error

For definition of this parameter see clause 7.6.1.

8.4.7 MAP_SEND_HANDOVER_REPORT service

8.4.7.1 Definition

This service is used between VLR and MSC-B (B-interface) to transfer the handover number to be forwarded to and used by MSC-A.

The MAP_SEND_HANDOVER_REPORT service is a confirmed service using the primitives from table 8.4/7.

8.4.7.2 Service primitives

Table 8.4/7: MAP_SEND_HANDOVER_REPORT

Parameter name	Request	Indication	Response	Confirm
Invoke Id	M	M(=)	M(=)	M(=)
Handover Number	M	M(=)		
Linked Id	M	M(=)		
Provider error				0

8.4.7.3 Parameter use

Invoke Id

For definition of this parameter see clause 7.6.1.

Handover Number

For definition of this parameter see clause 7.6.2.

Linked Id

For definition of this parameter see clause 7.6.1. This service is linked with MAP_ALLOCATE_HANDOVER_NUMBER.

Provider error

For definition of this parameter see clause 7.6.1.

8.5 Authentication management services

8.5.1 MAP AUTHENTICATE service

The MAP_AUTHENTICATE service is used on the MAP B interface. This interface is not fully operational specified. It is strongly recommended not to implement the B-interface as an external interface.

8.5.1.1 Definition

This service is used between the VLR and the MSC when the VLR receives a MAP service indication from the MSC concerning a location registration, call set-up, operation on a supplementary service or a request from the MSC to initiate authentication.

The service is a confirmed service and consists of four service primitives.

8.5.1.2 Service primitives

The service primitives are shown in table 8.5/1.

Table 8.5/1: MAP AUTHENTICATE parameters

Parameter name	Request	Indication	Response	Confirm
Invoke id	M	M(=)	M(=)	M(=)
RAND	M	M(=)		
CKSN	M	M(=)		
SRES			М	M(=)
Provider error				0

8.5.1.3 Parameter use

Invoke id

See clause 7.6.1 for the use of this parameter.

RAND

See clause 7.6.7 for the use of this parameter.

CKSN

See clause 7.6.7 for the use of this parameter.

SRES

See clause 7.6.7 for the use of this parameter.

Provider error

See clause 7.6.1 for the use of this parameter.

8.5.2 MAP SEND AUTHENTICATION INFO service

8.5.2.1 Definition

This service is used between the VLR and the HLR for the VLR to retrieve authentication information from the HLR. The VLR requests up to five authentication vectors.

Also this service is used between the SGSN and the HLR for the SGSN to retrieve authentication information from the HLR. The SGSN requests up to five authentication vectors.

If the user is a UMTS subscriber, the HLR shall return authentication quintuplets. If the user is a GSM subscriber, the HLR shall return authentication triplets.

If the HLR cannot provide the VLR or the SGSN with triplets, an empty response is returned. The VLR or the SGSN may then re-use old authentication triplets, except where this is forbidden under the conditions specified in 3GPP TS 43.020 [24].

If the HLR cannot provide the VLR or the SGSN with quintuplets, an empty response is returned. The VLR or the SGSN shall not re-use old authentication quintuplets.

If the VLR or SGSN receives a MAP_SEND_AUTHENTICATION_INFO response containing a User Error parameter as part of the handling of an authentication procedure, the authentication procedure in the VLR or SGSN shall fail.

Security related network functions are further described in 3GPP TS 43.020 [24] and 3GPP TS 33.200.

The service is a confirmed service and consists of four service primitives.

8.5.2.2 Service primitives

The service primitives are shown in table 8.5/2.

Table 8.5/2: MAP_SEND_AUTHENTICATION_INFO parameters

Parameter name	Request	Indication	Response	Confirm
Invoke id	М	M(=)	M(=)	M(=)
IMSI	С	C(=)		
Number of requested vectors	С	C(=)		
Requesting node type	С	C(=)		
Re-synchronisation Info	С	C(=)		
Segmentation prohibited indicator	С	C (=)		
Immediate response preferred indicator	U	C (=)		
Requesting PLMN ID	С	C(=)		
AuthenticationSetList			С	C(=)
User error			С	C(=)
Provider error				0

8.5.2.3 Parameter use

Invoke id

See clause 7.6.1 for the use of this parameter.

IMSI

See clause 7.6.2 for the use of this parameter.

This parameter shall be present in the first (or only) request of the dialogue. If multiple service requests are present in a dialogue then this parameter shall not be present in any service request other than the first one.

Number of requested vectors

A number indicating how many authentication vectors the VLR or SGSN is prepared to receive. The HLR shall not return more vectors than indicated by this parameter.

This parameter shall be present in the first (or only) request of the dialogue. If multiple service requests are present in a dialogue then this parameter shall not be present in any service request other than the first one.

Requesting node type

The type of the requesting node (SGSN or VLR).

This parameter shall be present in the first (or only) request of the dialogue. If multiple service requests are present in a dialogue then this parameter shall not be present in any service request other than the first one.

Re-synchronisation Info

For definition and use of this parameter see 3GPP TS 33.200.

If multiple service requests are present in a dialogue then this parameter shall not be present in any service request other than the first one..

Segmentation prohibited indicator

This parameter indicates if the VLR or SGSN allows segmentation of the response at MAP user level.

This parameter may be present only in the first request of the dialogue.

<u>Immediate response preferred indicator</u>

This parameter indicates that one of the requested authentication vectors is requested for immediate use in the VLR or SGSN. It may be used by the HLR together with the number of requested vectors and the number of vectors stored in the HLR to determine the number of vectors to be obtained from the AuC. It shall be ignored if the number of available vectors is greater than the number of requested vectors.

If multiple service requests are present in a dialogue then this parameter shall not be present in any service request other than the first one.

Requesting PLMN ID

The PLMN-ID of the requesting node. See3GPP TS 23.003.

This parameter shall be present in the first (or only) request of the dialogue. If multiple service requests are present in a dialogue then this parameter shall not be present in any service request other than the first one.

AuthenticationSetList

A set of one to five authentication vectors are transferred from the HLR to the VLR or from the HLR to the SGSN, if the outcome of the service was successful.

User error

One of the following error causes defined in clause 7.6.1 shall be sent by the user in case of unsuccessful outcome of the service, depending on the respective failure reason:

- unknown subscriber;
- unexpected data value;
- system failure;
- data missing.

Provider error

See clause 7.6.1 for the use of this parameter.

8.5.3 MAP_AUTHENTICATION_FAILURE_REPORT service

8.5.3.1 Definition

This service is used between the VLR and the HLR or between the SGSN or HLR for reporting of authentication failures.

8.5.3.2 Service primitives

The service primitives are shown in table 8.5/3.

Table 8.5/3: MAP_AUTHENTICATION_FAILURE_REPORT parameters

Parameter name	Request	Indication	Response	Confirm
Invoke id	M	M(=)	M(=)	M(=)
IMSI	M	M(=)		
Failure cause	M	M(=)		
Re-attempt	M	M(=)		
Access Type	M	M(=)		
Rand	M	M(=)		
VLR number	С	C(=)		
SGSN number	С	C(=)		
User error			С	C(=)
Provider error				0

8.5.3.3 Parameter use

Invoke id

See clause 7.6.1 for the use of this parameter.

IMSI

See clause 7.6.2 for the use of this parameter.

Failure Cause

See clause 7.6.7 for use of this parameter.

Re-attempt

See clause 7.6.7 for use of this parameter.

Access Type

See clause 7.6.7 for use of this parameter.

Rand

This parameter identifies the specific AV that failed authentication.

See clause 7.6.7 for use of this parameter.

VLR number

Shall be present if the sender is VLR. See definition in clause 7.6.2.

SGSN number

Shall be present if the sender is SGSN. See definition in clause 7.6.2.

<u>User error</u>

This parameter is sent by the responder upon unsuccessful outcome of the service, and then takes one of the following values defined in clause 7.6.1:

- Unknown Subscriber;
- System Failure;
- Unexpected Data Value.

Provider error

These are defined in clause 7.6.

8.6 Security management services

8.6.1 MAP_SET_CIPHERING_MODE service

8.6.1.1 Definitions

This service is used between the VLR and the MSC to set the ciphering mode and to start ciphering if applicable. It is called when another service requires that information is to be sent on the radio path in encrypted form.

The service is a non-confirmed service and consists of two service primitives.

8.6.1.2 Service primitives

The service primitives are shown in table 8.6/1.

Table 8.6/1: MAP_SET_CIPHERING_MODE parameters

Parameter name	Request	Indication
Invoke id	M	M(=)
Ciphering mode	M	M(=)
Kc	С	C(=)

8.6.1.3 Parameter use

Invoke id

See clause 7.6.1 for the use of this parameter.

Ciphering mode

See clause 7.6.7 for the use of this parameter.

<u>Kc</u>

The Kc parameter should be included when the ciphering mode parameter indicates that ciphering must be performed.

8.7 International mobile equipment identities management services

8.7.1 MAP_CHECK_IMEI service

8.7.1.1 Definition

This service is used between the VLR and the MSC and between the MSC and the EIR and between the SGSN and EIR to request check of IMEI. If the IMEI is not available in the MSC or in the SGSN, it is requested from the MS and transferred to the EIR in the service request.

This service may also be used to request the BMUEF from the EIR.

The service is a confirmed service and consists of four service primitives.

8.7.1.2 Service primitives

The service primitives are shown in table 8.7/1.

Table 8.7/1: MAP_CHECK_IMEI parameters

Parameter name	Request	Indication	Response	Confirm
Invoke id	M	M(=)	M(=)	M(=)
IMEI	С	C(=)	С	C(=)
IMEISV	С	C(=)	C(=)	C(=)
Requested	M	M(=)		
Equipment Info				
Equipment status			С	C(=)
BMUEF			С	C(=)
User error			С	C(=)
Provider error				0

8.7.1.3 Parameter use

Invoke id

See clause 7.6.1 for the use of this parameter.

Requested Equipment Info

This parameter indicates whether Equipment Status or BMUEF or both is requested.

IMEI

See clause 7.6.2 for the use of this parameter. The parameter shall not be included in the service request between the VLR and the MSC, but one of IMEI and IMEISV is mandatory in the service request from the MSC to the EIR and from the SGSN to the EIR. It is not included in the service response from the EIR to the MSC or to the SGSN, but one of IMEI and IMEISV is mandatory in the service response from the MSC to the VLR on successful outcome.

IMEISV

See clause 7.6.2 for the use of this parameter. IMEISV shall be present if BMUEF is requested.

Equipment status

See clause 7.6.3 for the use of this parameter. This parameter is sent by the responder in case of successful outcome of the service if Equipment status was requested.

BMUEF

See clause 7.6.4 for the use of this parameter. This parameter is sent by the responder in case of successful outcome of the service if BMUEF was requested.

User error

One of the following error causes defined in clause 7.6.1 shall be sent by the user in case of unsuccessful outcome of the service, depending on the respective failure reason:

- unknown equipment;
 - this error is returned by the responder when the IMEI is not known in the EIR;
- system failure;
- unexpected data value.

Provider error

See clause 7.6.1 for the use of this parameter.

8.7.2 MAP OBTAIN IMEI service

8.7.2.1 Definition

This service is used between the VLR and the MSC to request the IMEI. If the IMEI is not available in the MSC, it is requested from the MS.

The service is a confirmed service and consists of four service primitives.

8.7.2.2 Service primitives

The service primitives are shown in table 8.7/2.

Table 8.7/2: MAP_OBTAIN_IMEI parameters

Parameter name	Request	Indication	Response	Confirm
Invoke id	M	M(=)	M(=)	M(=)

IMEI		С	C(=)
User error		С	C(=)
Provider error			0

8.7.2.3 Parameter use

Invoke id

See clause 7.6.1 for the use of this parameter.

<u>IMEI</u>

See clause 7.6.2 for the use of this parameter. The parameter is included in the service response from the MSC to the VLR on successful outcome of the service.

User error

If the service fails, the VLR sends the user error System Failure (see clause 7.6.1) to the MSC.

Provider error

See clause 7.6.1 for the use of this parameter.

8.8 Subscriber management services

8.8.1 MAP-INSERT-SUBSCRIBER-DATA service

8.8.1.1 Definition

This service is used by an HLR to update a VLR with certain subscriber data in the following occasions:

- the operator has changed the subscription of one or more supplementary services, basic services or data of a subscriber. Note that in case of withdrawal of a Basic or Supplementary service this primitive shall not be used;
- the operator has applied, changed or removed Operator Determined Barring;
- the subscriber has changed data concerning one or more supplementary services by using a subscriber procedure;
- the HLR provides the VLR with subscriber parameters at location updating of a subscriber or at restoration. In this case, this service is used to indicate explicitly that a supplementary service is not provisioned, if the supplementary service specification requires it. The only supplementary services which have this requirement are the CLIR and COLR services. Network access mode is provided only in restoration. If the Super-Charger functionality is supported the HLR may not need to provide the VLR with subscriber parameters at location updating of a subscriber. See TS 23.116.

Also this service is used by an HLR to update an SGSN with certain subscriber data in the following occasions:

- if the GPRS subscription has changed;
- if the network access mode is changed;
- the operator has applied, changed or removed Operator Determined Barring;
- the subscriber has changed data concerning one or more supplementary services by using a subscriber procedure;
- the HLR provides the SGSN with subscriber parameters at GPRS location updating of a subscriber. If the Super-Charger functionality is supported the HLR may not need to provide the SGSN with subscriber parameters. See 3GPP TS 23.116.

It is a confirmed service and consists of the primitives shown in table 8.8/1.

8.8.1.2 Service primitives

Table 8.8/1: MAP-INSERT-SUBSCRIBER-DATA

Parameter name	Request	Indication	Response	Confirm
Invoke Id	M	M(=)	M(=)	M(=)
IMSI	С	C(=)		
MSISDN	С	C(=)		
Category	С	C(=)		
Subscriber Status	С	C(=)		
Bearer service List	С	C(=)	C	C(=)
Teleservice List	000000000000	C(=)	С	C(=)
Forwarding information List	С	C(=)		
Call barring information List	С	C(=)		
CUG information List	С	C(=)		
SS-Data List	С	C(=)		
eMLPP Subscription Data	С	C(=)		
MC-Subscription Data	С	C(=)		
Operator Determined Barring General data	С	C(=)	С	C(=)
Operator Determined Barring HPLMN data	С	C(=)		
Roaming Restriction Due To Unsupported	С	C(=)		
Feature				
Regional Subscription Data	C C C C	C(=)		
VLR CAMEL Subscription Info	С	C(=)		
Voice Broadcast Data	С	C(=)		
Voice Group Call Data	С	C(=)		
Network access mode	С	C(=)		
GPRS Subscription Data	С	C(=)		
Roaming Restricted In SGSN Due To	С	C(=)		
Unsupported Feature		()		
North American Equal Access preferred Carrier	U	C(=)		
Id List		` ,		
SGSN CAMEL Subscription Info	С	C(=)		
LSA Information	C	C(=)		
IST Alert Timer	C	C(=)		
SS-Code List			С	C(=)
LMU Identifier	С	C(=)		
LCS Information	С	C(=)		
CS Allocation/Retention priority	С	C(=)		
Super-Charger Supported In HLR	C C C C	C(=)		
Subscribed Charging Characteristics	С	C(=)		
Access Restriction Data	С	C(=)		
Regional Subscription Response			С	C(=)
Supported CAMEL Phases			C	C (=)
Offered CAMEL 4 CSIs			С	C (=)
User error			U	C(=)
Provider error				0

8.8.1.3 Parameter use

All parameters are described in clause 7.6. The following clarifications are applicable:

Network access mode

This parameter defines if the subscriber has access to MSC/VLR and/or to SGSN. This parameter is used by SGSN and MSC/VLR. In VLR, the parameter is used only as part of Restore Data Procedure and the parameter is not stored in the VLR. This parameter shall always be sent to the SGSN as part of the GPRS subscriber data at GPRS location updating. It shall be sent to the SGSN if it is changed as a result of administrative action.

IMSI

It is only included if the service is not used in an ongoing transaction (e.g. location updating). This parameter is used by the VLR and the SGSN.

MSISDN

It is included either at location updating or when it is changed. The MSISDN sent shall be the basic MSISDN. This parameter is used by the VLR and the SGSN.

Category

It is included either at location updating or when it is changed. This parameter is used only by the VLR and if the SGSN receives this parameter it shall ignore it.

Subscriber Status

It is included either at location updating or when it is changed.

To apply, remove or update Operator Determined Barring Categories the Subscriber Status is set to Operator Determined Barring. In this case ODB General Data shall also be present. If the Operator Determined Barring applies and the subscriber is registered in the HPLMN and HPLMN specific Operator Determined Barring applies then ODB HPLMN Specific Data shall also be present.

To remove all Operator Determined Barring Categories the Subscriber Status shall be set to "Service Granted". This parameter is used by the VLR and the SGSN.

Bearer service List

A list of Extensible Bearer service parameters (Extensible Bearer service is defined in clause 7.6). An Extensible Bearer service parameter must be the code for an individual Bearer service, except in the cases described below.

The codes for the Bearer service groups "allAlternateSpeech-DataCDA" and "allAlternateSpeech-DataCDS" shall, if applicable, be sent from the HLR to the VLR as a pair. The codes for the Bearer service groups "allSpeechFollowedByDataCDA" and "allSpeechFollowedByDataCDS" shall, if applicable, be sent from the HLR to the VLR as a pair.

If it is included in the Request/Indication, it includes either all Extensible Bearer services subscribed (at location updating or at restoration) or only the ones added (at subscriber data modification).

If the VLR receives an Indication containing any Extensible Bearer service parameters which it does not support/allocate it returns them in the response to the HLR and discards the unsupported Extensible Bearer services (no error is sent back), except in the cases described below.

If the VLR receives the codes for the Bearer service groups "allSpeechFollowedByDataCDA" and "allSpeechFollowedByDataCDS" and supports one or more of the circuit-switched synchronous or asynchronous data rates specified for simple data bearer services, it shall accept the bearer service codes, and not return them in the response to the HLR. If the VLR does not support any of the circuit-switched synchronous or asynchronous data rates specified for simple data bearer services, and receives the pair of codes for "allAlternateSpeech-DataCDA" and "allAlternateSpeech-DataCDS" or the pair of codes for "allSpeechFollowedByDataCDA" and "allSpeechFollowedByDataCDS", it shall reject the pair of codes by returning them in the response to the HLR. This parameter is used only by the VLR and if the SGSN receives this parameter it shall ignore it.

Teleservice List

A list of Extensible Teleservice parameters (Extensible Teleservice is defined in clause 7.6). An Extensible Teleservice parameter must be the code for an individual Teleservice.

If it is included in the Request/Indication, it contains either all Extensible Teleservices subscribed (at location updating or at restoration) or the ones added (at subscriber data modification). Only the Extensible Teleservices that are relevant to the node at which the message is received should be included in the Teleservice List.

If the VLR or the SGSN receives an Indication containing any Extensible Teleservice parameters which it does not support/allocate it returns them in the response to the HLR and discards the unsupported Extensible Teleservices (no error is sent back). This parameter is used by the VLR and the SGSN.

Forwarding information List

A list of Extensible Forwarding information parameters (Extensible Forwarding information is defined in clause 7.6). It includes Call Forwarding services either at location updating or at restoration or when they are changed. Each Extensible Forwarding information parameter shall be treated independently of all other parameters in the primitive.

The Extensible Forwarding information shall include the SS-Code for an individual call forwarding supplementary service. The Extensible Forwarding information shall contain one or more Extensible Forwarding Features (Extensible Forwarding Feature is defined in clause 7.6).

The Extensible Forwarding Feature may include an Extensible Basic Service Group. This shall be interpreted according to the rules in clause 8.8.1.4.

The Extensible Forwarding Feature shall contain an Extensible SS-Status parameter.

If the Extensible SS-Status indicates that call forwarding is registered then (except for call forwarding unconditional) the Extensible Forwarding Feature shall contain a number to define the forwarded-to destination and, if available, the forwarded-to subaddress. In other states the forwarded-to number and, if applicable, the forwarded-to subaddress shall not be included. For call forwarding unconditional the forwarded-to number and, if applicable, the forwarded-to subaddress shall not be included. If the VLR does not receive a forwarded-to subaddress then it shall assume that a forwarded-to subaddress has not been registered.

The Extensible Forwarding Feature shall contain the extensible forwarding options (except for call forwarding unconditional where the extensible forwarding options shall not be included). Bits 3 and 4 of the extensible forwarding options shall be ignored by the VLR, and may be set to any value by the HLR.

For call forwarding on no reply: If the extensible SS-Status indicates that call forwarding is registered then the Extensible Forwarding Feature shall contain an extensible no reply condition timer. In other states the no reply condition timer shall not be included.

For call forwarding services other than call forwarding on no reply: The Extensible Forwarding Feature shall not contain a no reply condition timer.

If the VLR receives an Indication containing any Call Forwarding service codes which it does not support/allocate it returns them to the HLR in the parameter SS-Code List and discards the unsupported Call Forwarding service codes (no error is sent back). This parameter is used only by the VLR and if the SGSN receives this parameter it shall ignore it

Call barring information List

A list of Extensible Call barring information parameters (Extensible Call barring information is defined in clause 7.6). It includes Call Barring services either at location updating or at restoration or when they are changed. Each Extensible Call barring information parameter shall be treated independently of all other parameters in the primitive.

The Extensible Call barring information shall include the SS-Code for an individual call barring supplementary service. The Extensible Call barring information shall contain one or more Extensible Call Barring Features (Extensible Call Barring Feature is defined in clause 7.6).

The Extensible Call Barring Feature may include an Extensible Basic Service Group. This shall be interpreted according to the rules in clause 8.8.1.4.

The Extensible Call Barring Feature shall contain an extensible SS-Status parameter.

If the VLR or the SGSN receives an Indication containing any Extensible Call Barring service codes which it does not support/allocate it returns them to the HLR in the parameter SS-Code List and discards the unsupported Extensible Call Barring service codes (no error is sent back).

CUG information List

A list of CUG information list parameters (CUG information is defined in clause 7.6). It includes CUG information either at location updating or at restoration or when it is changed.

At location updating, restoration or when there is a change in CUG data, the HLR shall include the complete CUG-SubscriptionList and, if there are options per basic group, it shall also include the complete CUG-FeatureList. If there are not options per extensible basic service group the CUG-FeatureList shall not be included.

In any dialogue, the first insertSubscriberData message which contains CUG information shall include a non-empty CUG-SubscriptionList.

When the VLR receives CUG data it shall replace the stored CUG data with the received data set.

If CUG-FeatureList is omitted in the Insert Subscriber Data operation VLR shall interpret that no options per extensible basic service group exist, and then it shall apply the default values i.e. no outgoing access, no incoming access, no preferential CUG exists.

If CUG-Feature is received without preferential CUG, the VLR shall interpret that no preferential CUG applies.

If the VLR detects that there is overlapping in the information received within a dialogue, it shall send the error Unexpected Data Value.

Note that data consistency between CUG subscription data and CUG feature data is the responsibility of the HLR.

If the VLR does not support the CUG service it returns its code to the HLR in the parameter SS-Code List and discards the received information (no error is sent back). This parameter is used only by the VLR and if the SGSN receives this parameter it shall ignore it.

SS-Data List

A list of Extensible SS-Data parameters (Extensible SS-Data is defined in clause 7.6). It is sent for any other supplementary service than Call Forwarding, Call Barring, CUG and eMLPP either at location updating or at restoration or when they are changed. Each SS-Data parameter shall be treated independently of all other parameters in the primitive.

The Extensible SS-Data shall include the SS-Code for an individual supplementary service.

The Extensible SS-Data shall contain an Extensible SS-Status parameter and any subscription options that are applicable to the service defined by the SS-Code.

The SS-Data may include a Basic Service Group List. This shall be interpreted according to the rules in clause 8.8.1.4.

If the VLR receives an Indication containing any supplementary service codes which it does not support/allocate it returns them to the HLR in the parameter SS-Code List and therefore discards the unsupported service codes received (no error is sent back).

This parameter is used by the SGSN only for LCS. If the SGSN receives an Indication containing any LCS related supplementary service codes which it does not support/allocate it returns them to the HLR in the parameter SS-Code List and therefore discards the unsupported service codes received (no error is sent back). SS-codes not related to the supported LCS capability set shall be discarded.

Operator Determined Barring General data

If it is included in a Request/Indication, it includes all the Operator Determined Barring categories that may be applied to a subscriber registered in any PLMN. This parameter is only included in a Request/Indication when the parameter Subscriber Status is set to the value Operator Determined Barring. Note that all General Operator Determined Barring Categories shall be set to their actual status.

If the VLR or the SGSN receives an Indication containing Operator Determined Barring General Data which shows that the subscriber is subject to barring not supported / not allocated by the VLR or by the SGSN, it returns Operator Determined Barring General Data in the response to the HLR to show the barring categories which are not supported / not allocated by the VLR or by the SGSN. This parameter is used by the VLR and the SGSN.

Operator Determined Barring HPLMN data

It includes all the Operator Determined Barring categories that may be applied only to a subscriber registered in the HPLMN. Therefore, it shall only be transferred to the VLR or to the SGSN when the subscriber is roaming into the HPLMN and when the parameter Subscriber Status is set to the value Operator Determined Barring. Note that all HPLMN Operator Determined Barring Categories shall be set to their actual status.

If Subscriber Status is set to the value Operator Determined Barring and no Operator Determined Barring HPLMN data is present then the VLR or the SGSN shall not apply any HPLMN specific ODB services to the subscriber. This parameter is used by the VLR and the SGSN.

eMLPP Subscription Data

If included in the Insert Subscriber Data request this parameter defines the priorities the subscriber might apply for a call (as defined in clause 7.6). It contains both subparameters of eMLPP.

If the VLR does not support the eMLPP service it returns its code to the HLR in the parameter SS-Code List and therefore discards the received information (no error is sent back).

eMLPP subscription data that have been stored previously in a subscriber data record in the VLR are completely replaced by the new eMLPP subscription data received in a MAP_INSERT_SUBSCRIBER_DATA during either an Update Location or Restore Data procedure or a stand alone Insert Subscriber data procedure. This parameter is used only by the VLR and if the SGSN receives this parameter it shall ignore it.

MC Subscription Data

If included in the Insert Subscriber Data request, this parameter provides the MC Subscription Data as defined in clause 7.6.

If the VLR does not support the MC service, it returns its code to the HLR in the parameter SS-Code List and therefore discards the received information (no error is sent back).

MC subscription data that have been stored previously in a subscriber data record in the VLR are completely replaced by the new MC subscription data received in a MAP_INSERT_SUBSCRIBER_DATA during either an Update Location or Restore Data procedure or a stand alone Insert Subscriber data procedure. This parameter is used only by the VLR and if the SGSN receives this parameter it shall ignore it.

Roaming Restriction Due To Unsupported Feature

The HLR may decide to include this parameter in the request if certain services or features are indicated as not supported by the MSC/VLR (e.g. Advice of Charge Charging Level).

If this parameter is sent to the VLR the MSC area is restricted by the HLR and the VLR. This parameter is used only by the VLR and if the SGSN receives this parameter it shall ignore it.

Regional Subscription Data

If included in the Insert Subscriber Data request this parameter defines the subscriber's subscription area for the addressed VLR or for the addressed SGSN (as defined in clause 7.6). It contains the complete list of up to 10 Zone Codes that apply to a subscriber in the currently visited PLMN. The HLR shall send only those Zone Codes which are stored against the CC and NDC of the VLR or the CC and NDC of the SGSN to be updated.

NOTE: Support of this parameter is a network operator option and it will not be sent to networks which do not support Regional Subscription.

Regional subscription data that have been stored previously in a subscriber data record in the VLR or in the SGSN are completely replaced by the regional subscription data received in an Insert Subscriber Data indication during either an Update Location or Restore Data procedure or a stand alone Insert Subscriber data procedure.

After the regional subscription data are inserted the VLR or the SGSN shall derive whether its location areas are allowed or not. If the whole MSC or SGSN area is restricted it will be reported to HLR by returning the Regional Subscription Response.

The VLR or the SGSN returns a Regional Subscription Response indicating that a problem with the Zone Code has been detected in one of the following cases:

- Too Many Zone Codes: more than 10 Zone Codes are to be stored in the VLR or in the SGSN.
- Regional Subscription Not Supported by the VLR or the SGSN.
- Zone Codes Conflict: the VLR or the SGSN detects that the zone codes indicate conflicting service permission for a location area.

Zone codes which have no mapping to location areas shall be ignored.

If a sequence of MAP_INSERT_SUBSCRIBER_DATA services is used during a dialogue, Regional Subscription Data shall be accepted only in one service. Regional Subscription Data received in a subsequent service shall be rejected with the error Unexpected Data Value.

If Regional Subscription Data are not included in any MAP_INSERT_SUBSCRIBER_DATA service, there is no restriction of roaming due to Regional Subscription. This parameter is used by the VLR and the SGSN.

Voice Broadcast Data

This parameter contains a list of group id's a user might have subscribed to; (VBS-Data is defined in clause 7.6). It includes VBS information either at location updating or at restoration or when it is changed.

At location updating, restoration or when there is a change in VBS data, the HLR shall include the complete VBS-Data.

When the VLR receives VBS-Data within a dialogue it shall replace the stored VBS-data with the received data set. All subsequent VBS-data received within this dialogue shall be interpreted as add-on data.

If VBS-data is omitted in the Insert Subscriber Data operation the VLR shall keep the previously stored VBS data.

If the VLR detects that there is overlapping in the information received within a dialogue, it shall send the error Unexpected Data Value. This parameter is used only by the VLR and if the SGSN receives this parameter it shall ignore it

Voice Group Call Data

This parameter contains a list of group id's a user might have subscribed to; see clause 7.6.

At location updating, restoration or when there is a change in VGCS data, the HLR shall include the complete VGCS-Data.

When the VLR receives VGCS-Data within a dialogue it shall replace the stored VGCS-Data with the received data set. All VGCS-Data received within this dialogue shall be interpreted as add-on data.

If VBCS-Data is omitted in the Insert Subscriber Data operation the VLR shall keep the previously stored VGCS-Data.

If the VLR detects that there is overlapping in the information received within a dialogue, it shall send the error Unexpected Data Value. This parameter is used only by the VLR and if the SGSN receives this parameter it shall ignore it

North American Equal Access preferred Carrier Id List

A list of the preferred carrier identity codes that are subscribed to.

When the VLR receives this parameter from the HLR, it shall replace the previously stored preferred carrier identity codes with the received ones. It is not possible to delete all the preferred carrier identity codes from the VLR using this service. To delete all the preferred carrier identity codes from the VLR, the HLR shall use the MAP_CANCEL_LOCATION service.

LSA Information

If included in the ISD request, this parameter contains a list of localised service area identities a user might have subscribed to together with the priority, the preferential access indicator, the active mode support indicator and active mode indication of each localised service area; see clause 7.6. The access right outside these localised service areas is also indicated. In all cases mentioned below, the LSA information shall only include LSA Data applicable to the VPLMN where the Subscriber is located. The VLR number, received in the MAP-UPDATE_LOCATION primitive, or the SGSN number, received in the MAP_UPDATE_GPRS_LOCATION primitive, can be used, alongside data stored in the HLR, to determine the LSA Data applicable to the VPLMN.

At restoration, location updating or GPRS location updating the HLR shall include the complete set of applicable LSA Information.

When there is a change in LSA data the HLR shall include at least the new and/or modified LSA data.

When there is a change in the access right outside the localised service areas the HLR shall include the LSA only access indicator.

When the SGSN or the VLR receives LSA information within a dialogue it shall check if the received data has to be considered as the entire LSA information. If so, it shall replace the stored LSA information with the received data set, otherwise it shall replace the data only for the modified LSA data (if any) and/or access right, and add the new LSA data (if any) to the stored LSA Information.

If the entire LSA information is received, it shall always include the LSA only access indicator value together with the LSA data applicable for the PLMN (if any).

If LSA Information is omitted in the Insert Subscriber Data operation the SGSN or the VLR shall keep the previously stored LSA Information.

If the SGSN or the VLR detects that there is overlapping in the information received within a dialogue, it shall send the error Unexpected Data Value. This parameter is used by the VLR and the SGSN.

IST Alert Timer

This parameter contains the IST Alert timer value that must be used to inform the HLR about the call activities that the subscriber performs.

At Location Updating, restoration, or when there is a change in the IST data defined for the Subscriber, the HLR shall include the IST Alert timer.

LMU Identifier

This parameter indicates the presence of an LMU. This parameter is used only by the VLR and shall be ignored if received by an SGSN.

LCS Information

This parameter provides the following LCS related information for an MS subscriber:

- list of GMLCs in the HPLMN;
- privacy exception list;
- MO-LR list.

At restoration and location updating, the HLR shall include the complete LCS data of the subscriber.

When there is a change in LCS subscriber data the HLR shall include at least the new and/or modified LCS data. LCS data that is not modified need not be included.

The VLR/SGSN shall keep any previously stored LCS Information that is not included in an Insert Subscriber Data operation.

If the VLR/SGSN detects that there is overlapping in the LCS information received within a dialogue, it shall send the error Unexpected Data Value. However, if the VLR receives the LCS code in both the LCS Information and the SS-Data List, then the VLR shall not interpret this as overlapping data.

Super-Charger Supported In HLR

This parameter is used by the HLR to indicate support for the Super-Charger functionality. If this parameter is present it shall include an indication of the age of the subscription data stored in the HLR.

If this parameter is absent then the HLR does not support the Super-Charger functionality.

SS-Code List

The list of SS-Code parameters for the services that are provided to a subscriber but are not supported/allocated by the VLR/SGSN (SS-Code is defined in clause 7.6). The list can only include individual SS-Codes that were sent in the service request. For the VLR, this list can also include SS-Codes for the eMLPP and/or CUG services if the above mentioned conditions, as described in eMLPP Subscription Data and/or CUG information List, are met (that is, eMLPP Subscription Data and/or CUG information List are received).

Regional Subscription Response

If included in the response this parameter indicates one of:

- MSC Area Restricted entirely because of regional subscription;
- SGSN Area Restricted entirely because of regional subscription;
- Too Many Zone Codes to be inserted;
- Zone Codes Conflict;

- Regional Subscription not Supported by the VLR or by the SGSN.

If the VLR determines after insertion of Regional Subscription Data that the entire MSC area is restricted, the VLR shall respond with a Regional Subscription Response indicating MSC Area Restricted. Otherwise MSC Area Restricted is not sent. The HLR shall check whether the current MSC area is no longer restricted.

If the SGSN determines after insertion of Regional Subscription Data that the entire SGSN area is restricted, the SGSN shall respond with a Regional Subscription Response indicating SGSN Area Restricted. Otherwise SGSN Area Restricted is not sent. The HLR shall check whether the current SGSN area is no longer restricted. This parameter is used by the VLR and by the SGSN.

VLR CAMEL Subscription Info

This parameter is sent for subscribers who have CAMEL services which are invoked in the MSC.

- In CAMEL phase 1, this parameter contains only the O-CSI.
- In CAMEL Phase 2, this parameter may contain O-CSI, SS-CSI and TIF-CSI. In CAMEL Phase 2 and onwards, TDP-Criteria for O-CSI may be associated with O-CSI.
- In CAMEL Phase 3, this parameter may contain O-CSI, D-CSI, SS-CSI, VT-CSI, MO-SMS-CSI, M-CSI and TIF-CSI. In CAMEL Phase 3 and onwards, TDP-Criteria for VT-CSI may be associated with VT-CSI.
 - In CAMEL Phase 4, this parameter may contain O-CSI, D-CSI, SS-CSI, VT-CSI, MO-SMS-CSI, MT-SMS-CSI, M-CSI and TIF-CSI. In CAMEL Phase 4, TDP-Criteria for MT-SMS-CSI may be associated with MT-SMS-CSI.

The VLR CAMEL Subscription Info is sent at location updating or when any information in the applicable CAMEL Subscription Info in the HLR has been changed.

At location updating, the complete set of VLR CAMEL Subscription Info is sent in one dialogue.

When CAMEL Subscription Information is changed in the HLR and changed data have to be sent to the VLR, then:

- for CAMEL Phase 1 and CAMEL Phase 2, the complete set of VLR CAMEL Subscription Info is sent in one dialogue;
- for CAMEL Phase 3 or higher, one or more specific elements of VLR CAMEL Subscription Info are sent in one dialogue.

When the VLR receives a specific element of VLR CAMEL Subscription Info, it shall overwrite the corresponding specific element of VLR CAMEL Subscription Info (if any) which it has stored for that subscriber.

For CAMEL Phase 1 and CAMEL Phase 2, the VLR CAMEL Subscription Info consists of any one or more of:

O-CSI (irrespective of the value of the 'CAMEL Capability Handling' inside O-CSI), TDP-Criteria for O-CSI, SS-CSI and TIF-CSI.

(The complete set of above shall be sent even if only one CSI has changed in case of stand alone ISD. The omitted elements of above list will be withdrawn in the VLR.)

From CAMEL phase 3 onwards, the specific elements of VLR CAMEL Subscription Info which may be sent are:

- O-CSI (irrespective of the value of the 'CAMEL Capability Handling' inside O-CSI), TDP criteria for O-CSI, SS-CSI and TIF-CSI;

(The complete set of above shall be sent even if only one CSI has changed in case of stand alone ISD. The omitted elements of above list will be withdrawn in the VLR.)

- D-CSI;
- VT-CSI;
- TDP-Criteria for VT-CSI;
- MO-SMS-CSI;

- MT-SMS-CSI;
- TDP-Criteria for MT-SMS-CSI;
- M-CSI.

If the VLR CAMEL Subscription Info is omitted in the Insert Subscriber Data operation the VLR shall keep the previously stored VLR CAMEL Subscription Info. Within one dialogue subsequent received data are interpreted as add-on data. If the VLR detects that there is overlapping in the information received within a dialogue, it shall send the error Unexpected Data Value. This parameter is used only by the VLR and if the SGSN receives this parameter it shall ignore it.

The VLR CAMEL Subscription Info may contain the TIF-CSI (Translation Information Flag) for CAMEL Phase 2 and higher. See 3GPP TS 23.072 for the use of this parameter and the conditions for its presence.

Supported CAMEL Phases

The use of this parameter and the requirements for its presence are specified in 3GPP TS 23.078. This parameter is used by the VLR and SGSN.

A VLR or SGSN not supporting any CAMEL Phase may omit this parameter.

GPRS Subscription Data

This parameter contains a list of PDP-contexts a user has subscribed to; see clause 7.6.

At GPRS location updating the HLR shall include the complete GPRS Subscription Data.

When there is a change in GPRS subscriber data the HLR shall include only the new and/or modified PDP contexts.

When the SGSN receives GPRS Subscription Data within a dialogue it shall check if the received data has to be considered as the entire GPRS subscription data. If so, it shall replace the stored GPRS Subscription Data with the received data set, otherwise it shall replace the data only for the modified PDP contexts (if any) and add the new PDP contexts (if any) to the stored GPRS Subscription Data.

If GPRS Subscription Data is omitted in the Insert Subscriber Data operation the SGSN shall keep the previously stored GPRS Subscription Data.

If the SGSN detects that there is overlapping in the information received within a dialogue, it shall send the error Unexpected Data Value. This parameter is used only by the SGSN and if the VLR receives this parameter it shall ignore it.

SGSN CAMEL Subscription Info

The SGSN CAMEL Subscription Info is sent at GPRS location updating or when any information in the applicable SGSN CAMEL Subscription Info in the HLR has been changed.

- In CAMEL Phase 3, this parameter may contain one or both of GPRS-CSI and MO-SMS-CSI.
- In CAMEL Phase 4, this parameter may contain GPRS-CSI, MO-SMS-CSI and MT-SMS-CSI and TDP-Criteria for MT-SMS-CSI.

At GPRS location updating the complete set of SGSN CAMEL Subscription Info is sent.

When CAMEL Subscription Information is changed in the HLR and changed data have to be sent to the SGSN, then one or more specific elements of SGSN CAMEL Subscription Info are sent in one dialogue.

When the SGSN receives a specific element of SGSN CAMEL Subscription Info, it shall overwrite the corresponding specific element of SGSN CAMEL Subscription Info (if any) which it has stored for that subscriber.

The specific elements of SGSN CAMEL Subscription Info which may be sent are:

- MO-SMS-CSI;
- MT-SMS-CSI:
- TDP-Criteria for MT-SMS-CSI;

- GPRS-CSI;
- MC-CSI.

This parameter is used only by the SGSN and if the VLR receives this parameter it shall ignore it.

Roaming Restricted In SGSN Due To Unsupported Feature

The HLR may decide to include this parameter in the request if certain services or features are indicated as not supported by the SGSN. This parameter is used only by the SGSN and if the VLR receives this parameter it shall ignore it.

CS Allocation/Retention priority

The CS Allocation/Retention priority is used only for Circuit Switched (CS). This parameter specifies relative importance to compare with other bearers about allocation and retention of bearer. This parameter is used only by the VLR and if the SGSN receives this parameter it shall ignore it.

Offered CAMEL 4 CSIs

This parameter indicates the CAMEL phase 4 CSIs offered in the VMSC/VLR or SGSN (see clause 7.6.3.36D).

Subscribed Charging Characteristics

This parameter refers to the Subscribed Charging Characteristics as defined in 3GPP TS 32.251.

For a detailed description of the use of the parameter, see 3GPP TS 32.251.

This parameter is used only by the SGSN and if the VLR receives this parameter it shall ignore it.

Access Restriction Data

This parameter indicates the allowed RAT according to subscription data. (see clause 7.6.3.96)

If the VLR/SGSN supports the Access Restriction feature but does not receive the Access Restriction Data parameter from the HLR at location updating or restoration, the VLR/SGSN shall assume that the subscriber's profile does not have any restrictions enabled.

For a detailed description of the use of the parameter, see 3GPP TS 23.012[23] for CS domain and 3GPP TS 23.060[104] for PS domain.

User error

Only one of the following values is applicable:

- Unidentified subscriber:
- Data missing;
- Unexpected data value.

8.8.1.4 Basic service information related to supplementary services

A number of parameters that relate to supplementary services can be qualified by a Basic Service Group (or a Basic Service Group List). This clause explains how this information is to be interpreted. Supplementary service parameters to which this clause is applicable only apply to the basic service groups described in this clause, and only those basic service groups shall be overwritten at the VLR or the SGSN.

The Basic Service Group (or Basic Service Group List) is optional.

If present the Basic Service Group (or each element of the Basic Service Group List) shall be one of:

- an Elementary Basic Service Group for which the supplementary service is applicable to at least one basic service in the group and for which the subscriber has a subscription to at least one basic service in the group;
- the group "All Teleservices" provided that the service is applicable to at least one teleservice and that the subscriber has a subscription to at least one teleservice which is in the same Elementary Basic Service Group as a teleservice to which the service is applicable;
- the group "All Bearer Services" provided that the service is applicable to at least one bearer service and that the subscriber has a subscription to at least one bearer service which is in the same Elementary Basic Service Group as a basic service to which the service is applicable.

If the Basic Service Group (or Basic Service Group List) is not present then the parameter shall apply to all Basic Service Groups.

If the basic service information is not a single Elementary Basic Service Group then the parameter shall be taken as applying individually to all the Elementary Basic Service Groups for which:

- the supplementary service is applicable to at least one basic service in the Basic Service Group; and
- the subscriber has a subscription to at least one basic service in the Basic Service Group.

The VLR and the SGSN are not required to store supplementary services data for Basic Service Groups which are not supported at the VLR or the SGSN respectively.

8.8.2 MAP-DELETE-SUBSCRIBER-DATA service

8.8.2.1 Definition

This service is used by an HLR to remove certain subscriber data from a VLR or SGSN if the subscription of one or more supplementary services or basic services is withdrawn. Note that this service is not used in case of erasure or deactivation of supplementary services.

This service is also used by an HLR to remove GPRS subscription data from an SGSN.

It is a confirmed service and consists of the primitives shown in table 8.8/2.

8.8.2.2 Service primitives

Table 8.8/2: MAP-DELETE-SUBSCRIBER-DATA

Parameter name	Request	Indication	Response	Confirm
Invoke Id	M	M(=)	M(=)	M(=)
IMSI	M	M(=)		
Basic service List	С	C(=)		
SS-Code List	С	C(=)		
Roaming Restriction Due To				
Unsupported Feature	С	C(=)		
Camel Subscription Info Withdraw	С	C(=)		
Specific CSI Withdraw	С	C(=)		
Regional Subscription Data	С	C(=)		
VBS Group Indication	С	C(=)		
VGCS Group Indication	С	C(=)		
GPRS Subscription Data Withdraw	С	C(=)		
Roaming Restricted In SGSN Due To	С	C(=)		
Unsupported Feature				
LSA Information Withdraw	С	C(=)		
IST Information Withdraw	С	C(=)		
Regional Subscription Response			С	C(=)
GMLC List Withdraw	С	C(=)		
Subscribed Charging Characteristics	С	C(=)	_	
Withdraw				
User error			С	C(=)

Provider error		0

8.8.2.3 Parameter use

All parameters are described in clause 7.6. The following clarifications are applicable:

Basic service List

A list of Extensible Basic service parameters (Extensible Basic service is defined in clause 7.6). It is used when one, several or all basic services are to be withdrawn from the subscriber. If the VLR or the SGSN receives a value for an Extensible Basic Service which it does not support, it shall ignore that value. This parameter is used by the VLR and by the SGSN.

SS-Code List

A list of SS-Code parameters (SS-Code is defined in clause 7.6). It is used when several or all supplementary services are to be withdrawn from the subscriber.

There are three possible options:

deletion of basic service(s);

The parameter Basic service List is only included.

deletion of supplementary service(s);

The parameter SS-Code List is only included.

- deletion of basic and supplementary services;

Both Basic service List and SS-Code List are included.

This parameter is used by the VLR and SGSN for Call Barring and LCS. Otherwise, this parameter is used only by the VLR and if the SGSN receives this parameter it shall ignore it.

Roaming Restriction Due To Unsupported Feature

This parameter is used if Roaming Restriction Due To Unsupported Feature is deleted from the subscriber data. This may occur if unsupported features or services are removed from the subscriber data in the HLR.

If this parameter is sent the VLR shall check if the current Location Area is possibly allowed now. This parameter is used only by the VLR and if the SGSN receives this parameter it shall ignore it.

CAMEL Subscription Info Withdraw

This parameter is used to indicate that CAMEL Subscription Info shall be deleted from the VLR or from the SGSN. All CAMEL Subscription Info for the subscriber shall be deleted. This parameter is used by the VLR and by the SGSN. This parameter should not be sent in the same message as the Specific CSI Withdraw parameter.

Specific CSI Withdraw

This parameter is used to indicate that one or more specific elements of CAMEL Subscription Info shall be deleted from the VLR or from the SGSN.

The specific elements of CAMEL Subscription Info which may be withdrawn are:

- O-CSI with TDP criteria for O-CSI;
- SS-CSI;
- TIF-CSI;
- D-CSI:
- VT-CSI with TDP criteria for VT-CSI;

- MO-SMS-CSI;
- MT-SMS-CSI with TDP-Criteria for MT-SMS-CSI;
- M-CSI;
- MG-CSI:
- GPRS-CSI.

This parameter is used by the VLR and by the SGSN. It shall not be sent to VLRs that do not support CAMEL phase 3 or higher. This parameter should not be sent in the same message as the CAMEL Subscription Info Withdraw parameter.

Regional Subscription Identifier

Contains one single Zone Code (as defined in clause 7.6) and is used if all Zone Codes shall be deleted from the subscriber data. When all the Zone Codes are deleted, the VLR or the SGSN shall check for its location areas whether they are allowed or not. If the whole MSC area is restricted, VLR will report it to HLR by returning the Regional Subscription Response "MSC Area Restricted". If the whole SGSN area is restricted, SGSN will report it to HLR by returning the Regional Subscription Response "SGSN Area Restricted".

The binary coding of the Zone Code value received in a Delete Subscriber Data request shall not be checked by the VLR or by the SGSN.

Note that support of this parameter is a network operator option and it shall not be sent to networks which do not support Regional Subscription.

If Regional Subscription is not supported by the VLR or by the SGSN, the request for deletion of Zone Codes is refused by sending the Regional Subscription Response "Regional Subscription Not Supported" to the HLR.

If no Zone Codes are stored in the respective subscriber data record, the request for deleting all Zone Code information shall be ignored and no Regional Subscription Response shall be returned. This parameter is used by the VLR and by the SGSN.

VBS Group Indication

Contains an indication (flag) which is used if all Group Ids shall be deleted from the subscriber data for the Voice Broadcast teleservice.

If VBS is not supported in the VLR or no Group Ids are stored for VBS in the respective subscriber record, the request for deletion of all Group Ids shall be ignored. This parameter is used only by the VLR and if the SGSN receives this parameter it shall ignore it.

VGCS Group Indication

Contains an indication (flag) which is used if all Group Id's shall be deleted from the subscriber data for the Voice Group Call teleservice. This parameter is used only by the VLR and if the SGSN receives this parameter it shall ignore it.

If VGCS is not supported in the VLR or no Group Ids are stored for VGCS in the respective subscriber record, the request for deletion of all Group Ids shall be ignored.

GPRS Subscription Data Withdraw

This parameter is used to indicate whether all GPRS Subscription Data for the subscriber shall be deleted or if only a subset of the stored GPRS Subscription Data for the subscriber shall be deleted. In the latter case only those PDP contexts whose identifiers are included in the subsequent identifier list will be deleted. This parameter is used only by the SGSN and if the VLR receives this parameter it shall ignore it.

Roaming Restricted In SGSN Due To Unsupported Feature

This parameter is used if Roaming Restricted In SGSN Due To Unsupported Feature is deleted from the GPRS subscriber data. This may occur if unsupported features or services are removed from the GPRS subscriber data in the HLR.

If this parameter is sent the SGSN shall check if the current Location Area is possibly allowed now. This parameter is used only by the SGSN and if the VLR receives this parameter it shall ignore it.

LSA Information Withdraw

This parameter is used to indicate whether all LSA Information for the subscriber shall be deleted or if only a subset of the stored LSA Information for the subscriber shall be deleted. In the latter case only the LSA data whose LSA identities are included in the subsequent LSA data list will be deleted. This parameter is used by the VLR and the SGSN.

IST Information Withdraw

This parameter is used to indicate that the IST condition has been removed for the subscriber. See 3GPP TS 43.035 for the use of this parameter.

Regional Subscription Response

If included in the Delete Subscriber Data response this parameter indicates one of:

- MSC Area Restricted;
- SGSN Area Restricted:
- Regional Subscription Not Supported.

This parameter is used by the VLR and by the SGSN.

GMLC List Withdraw

This parameter indicates that the subscriber's LCS GMLC List shall be deleted from the VLR or SGSN.

Subscribed Charging Characteristics Withdraw

This parameter indicates that the Subscribed Charging Characteristics shall be replaced with a local default value in the SGSN (see 3GPP TS 32.251).

This parameter is used only by the SGSN and if the VLR receives this parameter it shall ignore it.

User error

Only one of the following values is applicable:

- Unidentified subscriber;
- Data missing;
- Unexpected data value.

8.9 Identity management services

8.9.1 MAP-PROVIDE-IMSI service

8.9.1.1 Definition

This service is used by a VLR in order to get, via the MSC, the IMSI of a subscriber (e.g. when a subscriber has identified itself with a TMSI not allocated to any subscriber in the VLR).

It is a confirmed service and consists of the primitives shown in table 8.9/1.

8.9.1.2 Service primitives

Table 8.9/1: MAP-PROVIDE-IMSI

Parameter name	Request	Indication	Response	Confirm
Invoke Id	M	M(=)	M(=)	M(=)

IMSI		С	C(=)
User error		С	C(=)
Provider error			0

8.9.1.3 Parameter use

All parameters are described in clause 7.6. The following clarifications are applicable:

IMSI

This parameter is received when the request is successfully carried out. It contains the requested IMSI.

User error

Only one of the following values is applicable:

- Absent subscriber.

8.9.2 MAP-FORWARD-NEW-TMSI service

8.9.2.1 Definition

This service is used by a VLR to allocate, via MSC, a new TMSI to a subscriber during an ongoing transaction (e.g. call set-up, location updating or supplementary services operation).

It is a confirmed service and consists of the primitives shown in table 8.9/2.

8.9.2.2 Service primitives

Table 8.9/2: MAP-FORWARD-NEW-TMSI

Parameter name	Request	Indication	Response	Confirm
Invoke Id	M	M(=)	M(=)	M(=)
TMSI	M	M(=)		
Provider error				0

8.9.2.3 Parameter use

The parameter TMSI is described in clause 7.6.

8.10 Fault recovery services

8.10.1 MAP_RESET service

8.10.1.1 Definition

This service is used by the HLR, after a restart, to indicate to a list of VLRs or SGSNs that a failure occurred.

The MAP_RESET service is a non-confirmed service using the service primitives defined in table 8.10/1.

8.10.1.2 Service primitives

Table 8.10/1: MAP_RESET

Parameter name	Request	Indication
Invoke Id	M	M(=)
HLR number	M	M(=)

LI D I4 I ICT		0()
HLR Id LIST	l U	C(=)

8.10.1.3 Parameter definition and use

Invoke Id

See definition in clause 7.6.1.

HLR number

See definition in clause 7.6.2.

HLR Id LIST

The HLR Id List is a list of HLR Ids. If the parameter is present in the indication, the VLR or SGSN may base the retrieval of subscribers to be restored on their IMSI: the subscribers affected by the reset are those whose IMSI leading digits are equal to one of these numbers. If the parameter is absent, subscribers to be restored are those for which the OriginatingEntityNumber received at location updating time matches the equivalent parameter of the Reset Indication.

8.10.2 MAP_FORWARD_CHECK_SS_INDICATION service

8.10.2.1 Definition

This service may be used by an HLR as an implementation option, to indicate to a mobile subscriber that supplementary services parameters may have been altered, e.g. due to a restart. If received from the HLR, the VLR shall forward this indication to the MSC, which in turn forwards it to the MS. The HLR only sends this indication after successful completion of the subscriber data retrieval from HLR to VLR that ran embedded in a MAP_UPDATE_LOCATION procedure.

The MAP_FORWARD_CHECK_SS_INDICATION service is a non-confirmed service using the service primitives defined in table 8.10/2.

8.10.2.2 Service primitives

Table 8.10/2: MAP_FORWARD_CHECK_SS_INDICATION

Parameter name	Request	Indication
Invoke Id	M	M(=)

8.10.2.3 Parameter definition and use

Invoke Id

See definition in clause 7.6.1.

8.10.3 MAP_RESTORE_DATA service

8.10.3.1 Definition

This service is invoked by the VLR on receipt of a MAP_PROVIDE_ROAMING_NUMBER indication for an unknown IMSI, or for a known IMSI with the indicator "Confirmed by HLR" set to "Not confirmed". The service is used to update the LMSI in the HLR, if provided, and to request the HLR to send all data to the VLR that are to be stored in the subscriber's IMSI record.

The MAP_RESTORE_DATA service is a confirmed service using the service primitives defined in table 8.10/3.

8.10.3.2 Service primitives

Table 8.10/3: MAP_RESTORE_DATA

Parameter name	Request	Indication	Response	Confirm
Invoke Id	M	M(=)	M(=)	M(=)
IMSI	M	M(=)		
LMSI	U	C(=)		
Supported CAMEL phases	С	C(=)		
SoLSA Support Indicator	C	C(=)		
IST Support Indicator	C	C(=)		
Super-Charger Supported in	С	C(=)		
Serving Network Entity				
Long FTN Supported	С	C(=)		
Supported LCS Capability	С	C(=)		
Sets				
Offered CAMEL 4 CSIs	С	C(=)		
HLR number			С	C(=)
MS Not Reachable Flag			С	C(=)
User error			С	C(=)
Provider error				0

8.10.3.3 Parameter definitions and use

Invoke Id

See definition in clause 7.6.1.

IMSI

See definition in clause 7.6.2.

LMSI

See definition in clause 7.6.2. It is an operator option to provide the LMSI from the VLR; it is mandatory for the HLR to support the LMSI handling procedures.

Supported CAMEL Phases

This parameter indicates which phases of CAMEL are supported. Must be present if a CAMEL phase different from phase 1 is supported. Otherwise may be absent.

SoLSA Support Indicator

This parameter is used by the VLR to indicate to the HLR in the Restore Data indication that SoLSA is supported. If this parameter is not included in the Restore Data indication then the HLR shall not perform any specific error handling.

This SoLSA Support Indicator shall be stored by the HLR per VLR where there are Subscribers roaming. If a Subscriber is marked as only allowed to roam in Subscribed LSAs while roaming in a VLR and no SoLSA Support indicator is stored for that VLR, the location status of that Subscriber shall be set to Restricted.

IST Support Indicator

This parameter is used to indicate to the HLR that the VMSC supports basic IST functionality, that is, the VMSC is able to terminate the Subscriber Call Activity that originated the IST Alert when it receives the IST alert response indicating that the call(s) shall be terminated. If this parameter is not included in the Restore Data indication and the Subscriber is marked as an IST Subscriber, then the HLR may limit the service for the subscriber (by inducing an Operator Determined barring of Outgoing calls), or allow service assuming the associated risk of not having the basic IST mechanism available.

This parameter can also indicate that the VMSC supports the IST Command service, including the ability to terminate all calls being carried for the identified subscriber by using the IMSI as a key. If this additional capability is not included in the Restore Data indication and the HLR supports the IST Command capability, then the HLR may limit the service for the subscriber (by inducing an Operator Determined barring of Outgoing calls), or allow service assuming the associated risk of not having the IST Command mechanism available.

Long FTN Supported

This parameter indicates that the VLR supports Long Forwarded-to Numbers.

Super-Charger Supported in Serving Network Entity

This parameter is used by the VLR to indicate to the HLR that the VLR supports the Super-Charger functionality and that subscriber data is required.

If this parameter is absent then the VLR does not support the Super-Charger functionality.

Supported LCS Capability Sets

This parameter indicates, if present, the capability sets of LCS which are supported. If the parameter is sent but no capability set is marked as supported then the VLR does not support LCS at all.

If this parameter is absent then the VLR may support at most LCS capability set 1, that is LCS Release98 or Release99 version.

Offered CAMEL 4 CSIs

This parameter indicates the CAMEL phase 4 CSIs offered in the VMSC/VLR (see clause 7.6.3.36D).

HLR number

See definition in clause 7.6.2. The presence of this parameter is mandatory in case of successful outcome of the service.

MS Not Reachable Flag

See definition in clause 7.6.8. This parameter shall be present in case of successful outcome of the service, if the "MS Not Reachable flag" was set in the HLR.

User error

In case of unsuccessful outcome of the service, an error cause shall be returned by the HLR. The following error causes defined in clause 7.6.1 may be used, depending on the nature of the fault:

- unknown subscriber;
- system failure;
- unexpected data value;
- data missing.

Provider error

For definition of provider errors see clause 7.6.1.

8.11 Subscriber Information services

8.11.1 MAP-ANY-TIME-INTERROGATION service

8.11.1.1 Definition

This service is used by the gsmSCF, to request information (e.g. subscriber state and location) from the HLR or the GMLC at any time. This service may also be used by the gsmSCF to request the Mobile Number Portability (MNP) information from the NPLR.

This service is also used by the Presence Network Agent to request information, (e.g. subscriber state and location) about the subscriber (associated with a presentity) from the HLR at any time (see 3GPP TS 23.141 [128]).

When this service is used to the HLR, the subscriber state or location may be requested.

When this service is used to the GMLC, only the location may be requested.

When this service is used to the NPLR, only the MNP information may be requested.

The MAP-ANY-TIME-INTERROGATION service is a confirmed service using the service primitives defined in table 8.11/1.

8.11.1.2 Service primitives

Table 8.11/1: Any_Time_Interrogation

Parameter name	Request	Indication	Response	Confirm
Invoke id	M	M(=)	M(=)	M(=)
Requested Info	M	M(=)		
Requested domain	С	C(=)		
MNP Requested Info	С	C(=)		
gsmSCF-Address	M	M(=)		
IMSI	С	C(=)		
MSISDN	С	C(=)		
Location Information			С	C(=)
Location Information for			С	C(=)
GPRS				
Subscriber State			С	C(=)
PS Subscriber State			С	C(=)
IMEI			С	C(=)
MS Classmark 2			С	C(=)
GPRS MS Class			С	C(=)
MNP info Result			С	C(=)
User error			С	C(=)
Provider error				0

8.11.1.3 Parameter definition and use

All parameters are described in clause 7.6. The use of these parameters and the requirements for their presence are specified in 3GPP TS 23.018 [97] and 3GPP TS 23.078 [98].

The HLR or GMLC may be able to use the value of the parameter gsmSCF-address to screen a MAP_Any_Time_Interrogation indication.

The use of the parameters and the requirements for their presence are specified in 3GPP TS 23.078.

User error

This parameter is sent by the responder when an error is detected and if present, takes one of the following values:

- System Failure;
- Any Time Interrogation Not Allowed;
- Data Missing;
- Unexpected Data Value;
- Unknown Subscriber.

Provider error

These are defined in clause 7.6.1.

8.11.2 MAP-PROVIDE-SUBSCRIBER-INFO service

8.11.2.1 Definition

This service is used to request information (e.g. subscriber state and location) from the VLR or SGSN at any time.

The MAP-PROVIDE-SUBSCRIBER-INFO service is a confirmed service using the primitives defined in table 8.11/2.

8.11.2.2 Service primitives

Table 8.11/2: Provide_Subscriber_Information

Parameter name	Request	Indication	Response	Confirm
Invoke id	M	M(=)	M(=)	M(=)
Requested Info	M	M(=)		
IMSI	M	M(=)		
LMSI	U	0		
Location Information			С	C(=)
Location Information for			С	C(=)
GPRS				
Subscriber State			С	C(=)
PS Subscriber State			О	C(=)
IMEI			С	C(=)
MS Classmark 2			С	C(=)
GPRS MS Class			С	C(=)
User error			С	C(=)
Provider error				0

8.11.2.3 Parameter definition and use

All parameters are defined in clause 7.6. The use of these parameters and the requirements for their presence are specified in 3GPP TS 23.018 [97] and 3GPP TS 23.078 [98].

User error

This parameter is sent by the responder when an error is detected and if present, takes one of the following values:

- Data Missing;
- Unexpected Data Value.

Provider error

These are defined in clause 7.6.1.

8.11.3 MAP-ANY-TIME-SUBSCRIPTION-INTERROGATION service

8.11.3.1 Definition

This service is used by the gsmSCF, to request subscription information (e.g. call forwarding supplementary service data or CSI) from the HLR at any time. In an IP Multimedia Core Network, an IM-SSF can take on the role of a gsmSCF for this service.

8.11.3.2 Service primitives

Table 8.11/3: Any_Time_Subscription_Interrogation

Parameter name	Request	Indication	Response	Confirm
Invoke id	М	M(=)	M(=)	M(=)
Requested Subscription Info	М	M(=)		
GsmSCF-Address	М	M(=)		
IMSI	С	C(=)		
MSISDN	С	C(=)		
Long FTN Supported	С	C(=)		
Call Forwarding Data			С	C(=)
Call Barring Data			С	C(=)
ODB Info			С	C(=)
CAMEL Subscription Info			С	C(=)

Supported CAMEL phases in VLR	С	C(=)
Supported CAMEL phases in SGSN	С	C(=)
Offered CAMEL 4 CSIs in VLR	С	C(=)
Offered CAMEL 4 CSIs in SGSN	С	C(=)
User error	С	C(=)
Provider error		0

8.11.3.3 Parameter definition and use

All parameters are described in clause 7.6.

The HLR may be able to use the value of the parameter gsmSCF-address to screen a MAP_Any_Time_Subscription_Interrogation indication. The gsmSCF-address shall contain the IM-SSF address when the IM-SSF takes the role of the gsmSCF.

The use of the parameters and the requirements for their presence are specified in 3GPP TS 23.078 and 3GPP TS 23.278.

User error

This parameter is sent by the responder when an error is detected and if present, takes one of the following values:

- Unexpected Data Value;
- Unknown Subscriber;
- BearerServiceNotProvisioned;
- TeleserviceNotProvisioned;
- CallBarred;
- IllegalSS-Operation;
- SS-NotAvailable;
- InformationNotAvailable;
- Any Time Subscription Interrogation Not Allowed;
- Data Missing.

Provider error

These are defined in clause 7.6.1.

8.11.4 MAP-ANY-TIME-MODIFICATION service

8.11.4.1 Definition

This service is used by the gsmSCF, to modify information of the HLR at any time.

This service is also used by the Presence Network Agent to activate or deactivate reporting of mobility management events (associated with a presentity) from the VLR or SGSN (see 3GPP TS 23.141 [128]).

8.11.4.2 Service primitives

Table 8.11/4: Any_Time_Modification

Parameter name	Request	Indication	Response	Confirm
Invoke id	M	M(=)	M(=)	M(=)

gsmSCF-Address	M	M(=)		
IMSI	С	C(=)		
MSISDN	С	C(=)		
Modification request for ODB data	С	C(=)		
Modification request for SS information	С	C(=)		
Modification request for CSI	С	C(=)		
Long FTN Supported	С	C(=)		
Ext Forwarding information-for-CSE			C	C(=)
Ext Call barring information-for-CSE			C	C(=)
ODB Info			C	C(=)
CAMEL subscription info			C	C(=)
User error			С	C(=)
Provider error				0

8.11.4.3 Parameter definition and use

All parameters are described in clause 7.6.

The HLR may be able to use the value of the parameter gsmSCF-address to screen a MAP_Any_Time_Modification indication.

The use of these parameters and the requirements for their presence are specified in 3GPP TS 23.078 and 3GPP TS 23.278.

User error

This parameter is sent by the responder when an error is detected and if present, takes one of the following values:

- Any Time Modification Not Allowed;
- Data Missing;
- Unexpected Data Value;
- Unknown Subscriber;
- Bearer service not provisioned;

This error is returned only if not even a subset of the requested bearer service group has been subscribed to;

- Teleservice not provisioned;

This error is returned only if not even a subset of the requested teleservice group has been subscribed to;

- Call Barred;
- Illegal SS operation;
- SS error status;
- SS incompatibility;
- SS subscription violation;
- Information Not Available.

Provider error

These are defined in clause 7.6.1.

8.11.5 MAP-NOTE-SUBSCRIBER-DATA-MODIFIED service

8.11.5.1 Definition

This service is used by the HLR to inform the gsmSCF that subscriber data have been modified. In an IP Multimedia Core Network, an IM-SSF can take on the role of a gsmSCF for this service.

8.11.5.2 Service primitives

Table 8.11/5: Note_Subscriber_Data_Modified

Parameter name	Request	Indication	Response	Confirm
Invoke id	М	M(=)	M(=)	M(=)
IMSI	M	M(=)		
MSISDN	M	M(=)		
Ext Forwarding information-for-CSE	С	C(=)		
Ext Call barring information-for-CSE	С	C(=)		
ODB Info	С	C(=)		
CAMEL subscription info	С	C(=)		
All Information Sent	С	C(=)		
User error			С	C(=)
Provider error				0

8.11.5.3 Parameter definition and use

Invoke id

See clause 7.6.1 for the use of this parameter.

IMSI

See clause 7.6.2 for the use of this parameter.

MSISDN

See clause 7.6.2 for the use of this parameter. In an IP Multimedia Core Network, if no MSISDN is available, the HLR shall populate this parameter with a dummy MSISDN.

Ext Forwarding information-for-CSE

See clause 7.6.3 for the use of this parameter. The use of this parameter and the requirements for their presence are specified in 3GPP TS 23.078.

Ext Call barring information-for-CSE

See clause 7.6.3 for the use of this parameter. The use of this parameter and the requirements for their presence are specified in 3GPP TS 23.078.

ODB Info

See clause 7.6.3 for the use of this parameter. The use of this parameter and the requirements for their presence are specified in 3GPP TS 23.078.

CAMEL subscription info

See clause 7.6.3 for the use of this parameter. The use of this parameter and the requirements for their presence are specified in 3GPP TS 23.078 and 3GPP TS 23.278.

All Information Sent

This parameter is set when the HLR has sent all information to gsmSCF.

User error

This parameter is sent by the responder when an error is detected and if present, takes one of the following values:

- Data Missing;
- Unexpected Data Value;
- Unknown Subscriber.

Provider error

These are defined in clause 7.6.1.

The use of the parameters and the requirements for their presence are specified in 3GPP TS 23.078 and 3GPP TS 23.278.

9 Operation and maintenance services

9.1 Subscriber tracing services

9.1.1 MAP-ACTIVATE-TRACE-MODE service

9.1.1.1 Definition

This service is used between the HLR and the VLR to activate subscriber tracing in the VLR.

Also this service is used between the HLR and the SGSN to activate subscriber tracing in the SGSN.

The MAP-ACTIVATE-TRACE-MODE service is a confirmed service using the primitives from table 9.1/1.

9.1.1.2 Service primitives

Table 9.1/1: MAP-ACTIVATE-TRACE-MODE

Parameter name	Request	Indication	Response	Confirm
Invoke id	M	M(=)	M(=)	M(=)
IMSI	С	C(=)		
Trace reference	M	M(=)		
Trace type	M	M(=)		
Trace reference 2	С	C(=)		
Trace depth list	С	C(=)		
Trace NE type list	С	C(=)		
Trace interface list	С	C(=)		
Trace event list	С	C(=)		
Trace support			С	C(=)
indicator				
OMC Id	U	C(=)		
User error			С	C(=)
Provider error				0

9.1.1.3 Parameter use

Invoke id

See definition in clause 7.6.1.

IMSI

See definition in clause 7.6.2. The IMSI is a mandatory parameter in a stand-alone operation.

Trace reference

See definition in clause 7.6.10. This parameter contains trace reference for GSM only tracing request.

Trace type

See definition in clause 7.6.10. This parameter contains trace type for GSM only tracing request.

OMC Id

See definition in clause 7.6.2. The use of this parameter is an operator option.

Trace reference 2

See definition in clause 7.6.10. This parameter shall be used for UMTS trace activation.

Trace depth list

See definition in clause 7.6.10. This parameter shall be used for UMTS trace activation.

Trace NE type list

See definition in clause 7.6.10. This parameter shall be used for UMTS trace activation.

Trace interface list

See definition in clause 7.6.10. This parameter shall be used for UMTS trace activation.

Trace event list

See definition in clause 7.6.10. This parameter shall be used for UMTS trace activation.

Trace support indicator

See definition in clause 7.6.10. This parameter shall be used for UMTS trace activation.

User error

The following errors defined in clause 7.6.1 may be used, depending on the nature of the fault:

- Unidentified Subscriber;
- Facility Not Supported;
- Tracing Buffer Full;
- System Failure;
- Unexpected Data Value;
- Data missing.

Provider error

For definition of provider errors see clause 7.6.1.

9.1.2 MAP-DEACTIVATE-TRACE-MODE service

9.1.2.1 Definition

This service is used between the VLR and the HLR for deactivating subscriber tracing in the VLR.

Also this service is used between the SGSN and the HLR for deactivating subscriber tracing in the SGSN.

The MAP-DEACTIVATE-TRACE-MODE service is a confirmed service using the primitives from table 9.1/2.

9.1.2.2 Service primitives

Table 9.1/2: MAP-DEACTIVATE-TRACE-MODE

Parameter name	Request	Indication	Response	Confirm
Invoke id	M	M(=)	M(=)	M(=)
IMSI	С	C(=)		
Trace reference	M	M(=)		
Trace reference 2	С	C(=)		
User error			С	C(=)
Provider error				0

9.1.2.3 Parameter use

Invoke id

See definition in clause 7.6.1.

IMSI

See definition in clause 7.6.2. The IMSI is a mandatory parameter in a stand-alone operation.

Trace reference

See definition in clause 7.6.10.

Trace reference 2

See definition in clause 7.6.10. This parameter shall be used for UMTS trace activation.

User error

The following errors defined in clause 7.6.1 may be used, depending on the nature of the fault:

- Unidentified Subscriber;
- Facility Not Supported;
- System Failure;
- Unexpected Data Value;
- Data missing.

Provider error

For definition of provider errors see clause 7.6.1.

9.1.3 MAP-TRACE-SUBSCRIBER-ACTIVITY service

9.1.3.1 Definition

This service is used between the VLR and the MSC to activate the subscriber tracing in the MSC.

The MAP-TRACE-SUBSCRIBER-ACTIVITY service is a non-confirmed service using the primitives from table 9.1/3.

9.1.3.2 Service primitives

Table 9.1/3: MAP-TRACE-SUBSCRIBER-ACTIVITY

Invoke id	M	M(=)
IMSI	С	C(=)
Trace reference	M	M(=)
Trace type	M	M(=)
OMC Id	U	C(=)

9.1.3.3 Parameter use

Invoke id

See definition in clause 7.6.1.

IMSI

See definition in clause 7.6.2. The controlling MSC shall provide either the IMSI or the IMEI to the servicing MSC.

Trace reference

See definition in clause 7.6.10.

Trace type

See definition in clause 7.6.10.

OMC Id

See definition in clause 7.6.2. The use of this parameter is an operator option.

9.2 Other operation and maintenance services

9.2.1 MAP-SEND-IMSI service

9.2.1.1 Definition

This service is used by a VLR in order to fetch the IMSI of a subscriber in case of some Operation & Maintenance procedure where subscriber data are needed in the Visited PLMN and MSISDN is the only subscriber's identity known.

It is a confirmed service and consists of the primitives shown in table 9.2/1.

9.2.1.2 Service primitives

Table 9.2/1: MAP-SEND-IMSI

Parameter name	Request	Indication	Response	Confirm
Invoke Id	M	M(=)	M(=)	M(=)
MSISDN	M	M(=)		
IMSI			С	C(=)
User error			С	C(=)
Provider error				Ö Ö

9.2.1.3 Parameter use

All parameters are described in clause 7.6. The following clarifications are applicable.

User error

Only one of the following values is applicable:

- Unknown subscriber;

- Unexpected data value;
- Data missing.

10 Call handling services

10.1 MAP_SEND_ROUTING_INFORMATION service

10.1.1 Definition

This service is used between the Gateway MSC and the HLR. The service is invoked by the Gateway MSC to perform the interrogation of the HLR in order to route a call towards the called MS.

This is a confirmed service using the primitives listed in table 10.1/1.

This service is also used between the GMSC and the NPLR and between the gsmSCF and the HLR.

10.1.2 Service primitives

Table 10.1/1: MAP_SEND_ROUTING_INFORMATION parameters

Parameter name	Request	Indication	Response	Confirm
Invoke Id	M	M(=)	M(=)	M(=)
Interrogation Type	M	M(=)		
GMSC or gsmSCF Address	M	M(=)		
MSISDN	M	M(=)	С	C(=)
OR Interrogation	С	C(=)		
OR Capability	000000000000000000000000000000000000000	C(=)		
CUG Interlock	С	C(=)	C	C(=)
CUG Outgoing Access	С	C(=)	С	C(=)
Number of Forwarding	С	C(=)		
Network Signal Info	С	C(=)		
Supported CAMEL Phases	С	C(=)	С	C(=)
Suppress T-CSI	С	C(=)		
Offered CAMEL 4 CSIs	С	C(=)		
Suppression of Announcement	С	C(=)		
Call Reference Number	С	C(=)		
Forwarding Reason	С	C(=)		
Basic Service Group	С	C(=)		
Basic Service Group 2	С	C(=)		
Alerting Pattern	С	C(=)		
CCBS Call	С	C(=)		
Supported CCBS Phase	С	C(=)		
Additional Signal Info	С	C(=)		
IST Support Indicator	С	C(=)		
Pre-paging supported	С	C(=)		
Call Diversion Treatment Indicator	С	C(=)		
Long FTN Supported	С	C(=)		
Suppress VT-CSI	С	C(=)		
Suppress Incoming Call Barring	С	C(=)		
gsmSCF Initiated Call	С	C(=)		
Network Signal Info 2	С	C(=)		
IMSI		,	С	C(=)
MSRN			С	C(=)
Forwarding Data			С	C(=)
Forwarding Interrogation Required			000000000	C(=)
VMSC address			С	C(=)
ReleaseResourcesSupported			С	C(=)
GMSC Camel Subscription Info			С	C(=)
Location Information			С	C(=)
Subscriber State			С	C(=)
Basic Service Code			С	C(=)

Parameter name	Request	Indication	Response	Confirm
CUG Subscription Flag			С	C(=)
North American Equal Access preferred			U	C(=)
Carrier Id				
User error			С	C(=)
SS-List			U	C(=)
CCBS Target			С	C(=)
Keep CCBS Call Indicator			С	C(=)
IST Alert Timer			С	C(=)
Number Portability Status			U	C(=)
Supported CAMEL Phases in VMSC			С	
Offered CAMEL 4 CSIs in VMSC			С	C(=)
MSRN 2			С	C(=)
Forwarding Data 2			С	C(=)
SS-List 2			С	C(=)
Basic Service Code 2			С	C(=)
Allowed Services			С	C(=)
Unavailability Cause			С	C(=)
Provider error				0

10.1.3 Parameter use

See clause 7.6 for a definition of the parameters used in addition to the following. Note that:

- a conditional parameter whose use is defined only in 3GPP TS 23.078 shall be absent if the sending entity does not support CAMEL;
- a conditional parameter whose use is defined only in 3GPP TS 23.079 [99] shall be absent if the sending entity does not support optimal routeing;
- a conditional parameter whose use is defined only in 3GPP TS 23.078 & 3GPP TS 23.079 [99] shall be absent if the sending entity supports neither CAMEL nor optimal routeing.

Interrogation Type

See 3GPP TS 23.079 [99] for the use of this parameter.

GMSC or gsmSCF address

The E.164 address of the GMSC or the gsmSCF. This parameter contains the gsmSCF address if the gsmSCF iniated call parameter is present, otherwise it is the GMSC address.

MSISDN

This is the Mobile Subscriber ISDN number assigned to the called subscriber. In the Request & Indication it is the number received by the GMSC in the ISUP IAM. If the call is to be forwarded and the HLR supports determination of the redirecting number, the HLR inserts the basic MSISDN in the Response.

See 3GPP TS 23.066 [108] for the use of this parameter and the conditions for its presence in the response.

OR Interrogation

See 3GPP TS 23.079 [99] for the use of this parameter and the conditions for its presence.

OR Capability

See 3GPP TS 23.079 [99] for the use of this parameter and the conditions for its presence.

CUG Interlock

See 3GPP TS 23.018 [97] for the use of this parameter and the conditions for its presence.

CUG Outgoing Access

See 3GPP TS 23.018 [97] for the use of this parameter and the conditions for its presence.

Number of Forwarding

See 3GPP TS 23.018 [97] for the use of this parameter and the conditions for its presence.

Network Signal Info

See 3GPP TS 23.018 [97] for the conditions for the presence of the components of this parameter.

Supported CAMEL Phases

The use of this parameter and the requirements for its presence are specified in 3GPP TS 23.078.

T-CSI Suppression

The use of this parameter and the requirements for its presence are specified in 3GPP TS 23.078.

Offered CAMEL 4 CSIs

This parameter indicates the CAMEL phase 4 CSIs offered in the GMSC/VLR (see clause 7.6.3.36D).

Suppression Of Announcement

The use of this parameter and the requirements for its presence are specified in 3GPP TS 23.078.

Call Reference Number

The use of this parameter and the conditions for its presence are specified in 3GPP TS 23.078 [98] and 3GPP TS 23.079 [99].

Forwarding Reason

See 3GPP TS 23.079 [99] for the use of this parameter and the conditions for its presence.

Basic Service Group

See 3GPP TS 23.079 [99] for the use of this parameter and the conditions for its presence.

Basic Service Group 2

See 3GPP TS 23.079[99] for the use of this parameter and the conditions for its presence.

Alerting Pattern

See 3GPP TS 23.018 [97] and 3GPP TS 23.078 [98] for the use of this parameter and the conditions for its presence.

CCBS Call

See 3GPP TS 23.093 [107] for the use of this parameter and the conditions for its presence.

Supported CCBS Phase

This parameter indicates by its presence that CCBS is supported and the phase of CCBS which is supported.

Additional Signal Info

See 3GPP TS 23.081 [27] for the conditions for the presence of the components of this parameter.

IST Support Indicator

This parameter is used to indicate to the HLR that the GMSC supports basic IST functionality, that is, the GMSC is able to terminate the subscriber call activity that originated the IST Alert when it receives the IST Alert response indicating that the call(s) shall be terminated. If this parameter is not included in the Send Routing Information indication and the subscriber is marked as an IST subscriber, then the HLR may limit the service for the call (by barring the incoming call if it is not subject to forwarding, or suppressing Call Forwarding from the GMSC), or allow the call assuming the associated risk of not having the basic IST mechanism available.

This parameter can also indicate that the GMSC supports the IST Command, including the ability to terminate all calls being carried for the identified subscriber by using the IMSI as a key. If this additional capability is not included in the Send Routing Information indication and the subscriber is marked as an IST subscriber, then the HLR may limit the service for the subscriber (by barring the incoming calls if they are not subject to forwarding, or suppressing Call Forwarding from the GMSC), or allow the incoming calls assuming the associated risk of not having the IST Command mechanism available.

Pre-paging supported

See 3GPP TS 23.018 for the use of this parameter and the conditions for its presence.

Call Diversion Treatment Indicator

This parameter indicates whether or not call diversion is allowed.

Network Signal Info 2

See 3GPP TS 23.172 [126] for the conditions for the presence of the components of this parameter.

IMSI

See 3GPP TS 23.018 [97] and 3GPP TS 23.066 [108] for the use of this parameter and the conditions for its presence.

MSRN

See 3GPP TS 23.018 [97], 3GPP TS 23.066 [108] and 3GPP TS 23.079 [99] for the use of this parameter and the conditions for its presence. If the NPLR returns only the MSISDN-number without Routeing Number to the GMSC, the MSISDN-number shall be returned as MSRN.

Forwarding Data

This parameter includes a number to define the forwarded-to destination, the forwarding reason and the forwarding options Notification to calling party and Redirecting presentation, and can include the forwarded-to subaddress. See 3GPP TS 23.018 [97] and 3GPP TS 23.079 [99] for the conditions for the presence of its components.

Forwarding Interrogation Required

See 3GPP TS 23.079 [99] for the use of this parameter and the conditions for its presence.

Long FTN Supported

This parameter indicates that the GMSC supports Long Forwarded-to Numbers.

Suppress VT-CSI

The use of this parameter and the requirements for its presence are specified in 3GPP TS 23.078.

Suppress Incoming Call Barring

The use of this parameter and the requirements for its presence are specified in 3GPP TS 23.078.

gsmSCF Initiated Call

The use of this parameter and the requirements for its presence are specified in 3GPP TS 23.078.

VMSC address

See 3GPP TS 23.079 [99] and 3GPP TS 23.078 [98] for the use of this parameter and the conditions for its presence. In addition this parameter shall be present if the ReleaseResourcesSupported parameter is present.

Release Resources Supported

This parameter indicates by its presence that the MAP_RELEASE_RESOURCES service is supported at the VMSC. It shall be present if so indicated by the VMSC with MAP_PROVIDE_ROAMING_NUMBER confirm.

GMSC CAMEL Subscription Info

The use of this parameter and the requirements for its presence are specified in 3GPP TS 23.078.

Location Information

The use of this parameter and the requirements for its presence are specified in 3GPP TS 23.078.

Subscriber State

The use of this parameter and the requirements for its presence are specified in 3GPP TS 23.078.

CUG Subscription Flag

The use of this parameter and the requirements for its presence are specified in 3GPP TS 23.078.

North American Equal Access preferred Carrier Id

This parameter is returned to indicate the preferred carrier identity to be used to set-up the call (i.e. forwarding the call or establishing the roaming leg).

SS-List

This parameter includes SS-codes and will be returned as an operator option. The HLR shall not send PLMN-specific SS-codes across PLMN boundaries. However if the GMSC receives PLMN-specific SS-codes from a foreign PLMN's HLR the GMSC may ignore it. If the GMSC attempts to process the PLMN- specific SS- codes, this may lead to unpredictable behaviour but the GMSC shall continue call processing.

Basic Service Code

The use of this parameter and the requirements for its presence are specified in 3GPP TS 23.078.

If the CAMEL service is not involved, this parameter includes the basic service code and will be returned as an operator option. The HLR shall not send a PLMN-specific Basic Service Code across PLMN boundaries. However if the GMSC receives a PLMN-specific Basic Service Code from a foreign PLMN's HLR the GMSC may ignore it. If the GMSC attempts to process the PLMN specific Basic Service codes, this may lead to unpredictable behaviour but the GMSC shall continue call processing.

CCBS Target

See 3GPP TS 23.093 [107] for the use of this parameter and the conditions for its presence.

Keep CCBS Call Indicator

See 3GPP TS 23.093 [107] for the use of this parameter and the conditions for its presence.

IST Alert Timer

It includes the IST Alert timer value that must be used to inform the HLR about the call activities that the subscriber performs. This parameter is only sent to the GMSC in response to a Send Routing Information request which indicates the the GMSC supports IST.

Number Portability Status

This parameter indicates the number portability status of the subscriber. This parameter may be present if the sender of SRIack is NPLR.

Supported CAMEL Phases in VMSC

The use of this parameter and the requirements for its presence are specified in 3GPP TS 23.078.

Offered CAMEL 4 CSIs in VMSC

This parameter is defined in clause 7.6.3.36F.

MSRN 2

The use of this parameter and the requirements for its presence are specified in 3GPP TS 23.172 [126].

Forwarding Data 2

The use of this parameter and the requirements for its presence are specified in 3GPP TS 23.172 [126].

SS-List 2

The use of this parameter and the requirements for its presence are specified in 3GPP TS 23.172 [126].

Basic Service Code 2

The use of this parameter and the requirements for its presence are specified in 3GPP TS 23.172 [126].

Allowed Services

The use of this parameter and the requirements for its presence are specified in 3GPP TS 23.172 [126].

Unavailability Cause

The use of this parameter and the requirements for its presence are specified in 3GPP TS 23.172 [126].

User error

This parameter is sent by the responder when an error is detected and if present, takes one of the following values:

- Unknown Subscriber:

The diagnostic for the Unknown Subscriber error may indicate 'NPDB Mismatch'.

- Number changed;
- Call Barred:

This error will indicate that either incoming calls are barred for this MS or that calls are barred due to Operator Determined Barring (see 3GPP TS 22.041 [8] for a definition of this network feature);

CUG Reject;

The value of this error cause will indicate the reason for CUG Reject;

- Bearer Service Not Provisioned;
- Teleservice Not Provisioned:

A subscription check has been performed and the call has not passed the check due to incompatibility with regard to the requested service. Depending on the nature of the incompatibility, either of these messages will be returned:

- Facility Not Supported;
- Absent Subscriber;

This indicates that the location of the MS is not known (either the station is not registered and there is no location information available or the Provide Roaming Number procedure fails due to IMSI detached flag being set), or the GMSC requested forwarding information with a forwarding reason of not reachable, and the call forwarding on MS not reachable service is not active;

- Busy Subscriber;

This indicates that Call Forwarding on Busy was not active for the specified basic service group when the GMSC requested forwarding information with a forwarding reason of busy;

The error may also indicate that the subscriber is busy due to an outstanding CCBS recall. In the error data it may then be specified that CCBS is possible for the busy encountered call;

No Subscriber Reply;

This indicates that Call Forwarding on No Reply was not active for the specified basic service group when the GMSC requested forwarding information with a forwarding reason of no reply;

- OR Not Allowed;

This indicates that the HLR is not prepared to accept an OR interrogation from the GMSC, or that calls to the specified subscriber are not allowed to be optimally routed;

- Forwarding Violation;
- System Failure;
- Data Missing;
- Unexpected Data Value.

See clause 7.6 for a definition of these errors.

Provider error

These are defined in clause 7.6.

10.2 MAP_PROVIDE_ROAMING_NUMBER service

10.2.1 Definition

This service is used between the HLR and VLR. The service is invoked by the HLR to request a VLR to send back a roaming number to enable the HLR to instruct the GMSC to route an incoming call to the called MS.

This is a confirmed service which uses the primitives described in table 10.2/1.

10.2.2 Service primitives

Table 10.2/1: MAP_PROVIDE_ROAMING_NUMBER parameters

Parameter name	Request	Indication	Response	Confirm
Invoke Id	М	M(=)	M(=)	M(=)
IMSI	М	M(=)		
MSC Number	М	M(=)		
MSISDN	U	C(=)		
LMSI	С	C(=)		
GSM Bearer Capability	C	C(=)		
Network Signal Info	С	C(=)		
Suppression Of Announcement	С	C(=)		
Call Reference Number	С	C(=)		
GMSC Address	C	C(=)		
OR Interrogation	С	C(=)		
OR Not Supported in GMSC	С	C(=)		
Alerting Pattern	С	C(=)		
CCBS Call	С	C(=)		
Supported CAMEL Phases in	С	C(=)		
interrogating node				
Additional Signal Info	С	C(=)		
Pre-paging supported	С	C(=)		
Long FTN Supported	С	C(=)		
Suppress VT-CSI	С	C(=)		
Offered CAMEL 4 CSIs in	С	C(=)		
interrogating node				
Roaming Number	_		С	C(=)
ReleaseResourcesSupported			U	C(=)
User error			С	C(=)
Provider error				0

10.2.3 Parameter use

See clause 7.6 for a definition of the parameters used, in addition to the following. Note that:

- a conditional parameter whose use is defined only in 3GPP TS 23.078 [98] shall be absent if the sending entity does not support CAMEL;
- a conditional parameter whose use is defined only in 3GPP TS 23.079 [99] shall be absent if the sending entity does not support optimal routeing;
- a conditional parameter whose use is defined only in 3GPP TS 23.078 [98] & 3GPP TS 23.079 [99] shall be absent if the sending entity supports neither CAMEL nor optimal routeing.

IMSI

This is the IMSI of the called Subscriber.

MSC Number

This is the ISDN number assigned to the MSC currently serving the MS. The MSC number will have been stored in the HLR as provided at location updating.

MSISDN

See 3GPP TS 23.018 [97] for the use of this parameter and the conditions for its presence.

LMSI

See 3GPP TS 23.018 [97] for the use of this parameter and the conditions for its presence.

GSM Bearer Capability

See 3GPP TS 23.018 [97] for the use of this parameter and the conditions for its presence.

This information is passed according to the rules specified in TS 3GPP TS 29.007 [56].

There may be two GSM Bearer Capabilities supplied.

Network Signal Info

See 3GPP TS 23.018 [97] for the conditions for the presence of the components of this parameter.

Suppression Of Announcement

The use of this parameter and the requirements for its presence are specified in 3GPP TS 23.078 [98].

Call Reference Number

The use of this parameter and the conditions for its presence are specified in 3GPP TS 23.078 [98] and 3GPP TS 23.079 [99].

GMSC Address

The use of this parameter and the conditions for its presence are specified in 3GPP TS 23.078 [98] and 3GPP TS 23.079 [99].

OR Interrogation

See 3GPP TS 23.079 [99] for the use of this parameter and the conditions for its presence.

OR Not Supported in GMSC

See 3GPP TS 23.079 [99] for the use of this parameter and the conditions for its presence.

Supported CAMEL Phases in interrogating node_

This parameter is defined in clause 7.6.3.36I. Alerting Pattern

See 3GPP TS 23.078 [98] for the use of this parameter and the conditions for its presence.

CCBS Call

See 3GPP TS 23.093 [107] for the use of this parameter and the conditions for its presence.

Additional Signal Info

See 3GPP TS 23.081 [27] for the conditions for the presence of the components of this parameter.

Pre-paging supported

See 3GPP TS 23.018 for the use of this parameter and the conditions for its presence.

Long FTN supported

See 3GPP TS 23.082 for the use of this parameter and the conditions for its presence.

Suppress VT-CSI

See 3GPP TS 23.078 for the use of this parameter and the conditions for its presence.

Offered CAMEL 4 CSIs in interrogating node

This parameter is defined in clause 7.6.3.36E.

Roaming Number

See 3GPP TS 23.018 [97] for the use of this parameter and the conditions for its presence.

ReleaseResourcesSupported

This parameter indicates by its presence that the MAP_RELEASE_RESOURCES service is supported at the VMSC.

User error

This parameter is sent by the responder when an error is detected and if present, takes one of the following values:

- Absent Subscriber;

This error will be returned if the IMSI detach flag is set.

- No Roaming Number Available;
- OR Not Allowed;

This indicates that the MAP_PROVIDE_ROAMING_NUMBER indication included the OR interrogation indicator, but the VLR does not support optimal routeing.

- Facility Not Supported;
- System Failure;
- Data Missing;
- Unexpected Data Value.

See clause 7.6 for a definition of these reasons.

Provider error

These are defined in clause 7.6.

10.3 MAP_RESUME_CALL_HANDLING service

10.3.1 Definition

This service is used between the terminating VMSC and the GMSC. The service is invoked by the terminating VMSC to request the GMSC to resume handling the call and forward it to the specified destination.

This is a confirmed service which uses the Primitives listed in table 10.3/1.

10.3.2 Service primitives

Table 10.3/1: MAP_RESUME_CALL_HANDLING parameters

Parameter name	Request	Indication	Response	Confirm
Invoke Id	М	M(=)	M(=)	M(=)
Call Reference Number	С	C(=)		
Basic Service Group	С	C(=)		
Basic Service Group 2	С	C(=)		
IMSI	С	C(=)		
Forwarding Data	С	C(=)		
CUG Interlock	С	C(=)		
CUG Outgoing Access	С	C(=)		
O-CSI	С	C(=)		
D-CSI	С	C(=)		
CCBS Target	С	C(=)		
UU Data	С	C(=)		
UUS CF Interaction	С	C(=)		
All Information Sent	С	C(=)		
MSISDN	С	C(=)		
User error			С	C(=)
Provider error				0

10.3.3 Parameter use

Information received in subsequent segment of a segmented dialogue shall not overwrite information received in an earlier segment.

See clause 7.6 for a definition of the parameters used, in addition to the following.

Call Reference Number

See 3GPP TS 23.079 [99] for the use of this parameter. This parameter shall be present in the first segment of the dialogue.

Basic Service Group

See 3GPP TS 23.079 [99] for the use of this parameter. This parameter shall be present in the first segment of the dialogue.

Basic Service Group 2

See 3GPP TS 23.079[99] for the use of this parameter. If this parameter is present, it shall be in the first segment of the dialogue.

IMSI

This is the IMSI of the forwarding Subscriber. This parameter shall be present in the first segment of the dialogue.

Forwarding Data

This parameter includes a number to define the forwarded-to destination, the forwarding reason and the forwarding options Notification to calling party and Redirecting presentation, and can include the forwarded-to subaddress. See 3GPP TS 23.079 [99] for the conditions for the presence of its components. This parameter shall be present in a first segment of the dialogue.

CUG Interlock

See 3GPP TS 23.079 [99] for the use of this parameter and the conditions for its presence.

CUG Outgoing Access

See 3GPP TS 23.079 [99] for the use of this parameter and the conditions for its presence.

O-CSI

See 3GPP TS 23.078 for the use of this parameter and the conditions for its presence.

For CAMEL phases 1 & 2, the O-CSI shall contain only one set of O-BCSM TDP data.

D-CSI

The Dialled Services-CSI.

See 3GPP TS 23.078 for the use of this parameter and the conditions for its presence.

CCBS Target

See 3GPP TS 23.093 [107] for the use of this parameter and the conditions for its presence.

UU Data

See 3GPP TS 23.087 for the use of this parameter and the conditions for its presence.

UUS CF Interaction

See 3GPP TS 23.087 for the use of this parameter and the conditions for its presence.

All Information Sent

This parameter is set when the VMSC has sent all information to GMSC.

MSISDN

This parameter is the basic MSISDN of the forwarding subscriber. It shall be present if the VMSC supports determination of the redirecting number.

User error

This parameter is sent by the responder when an error is detected and if present, takes one of the following values:

- Optimal Routeing not allowed;
- Forwarding failed;
- Unexpected Data Value;
- Data Missing.

Provider error

These are defined in clause 7.6.

10.4 MAP PREPARE GROUP CALL service

10.4.1 Definition

This service is used by the Anchor_MSC to inform the Relay_MSC about a group call set-up.

The MAP_PREPARE_GROUP_CALL service is a confirmed service using the service primitives given in table 10.4/1.

10.4.2 Service primitives

Table 10.4/1: MAP_PREPARE_GROUP_CALL service

Parameter name	Request	Indication	Response	Confirm
Invoke Id	M	M(=)	M(=)	M(=)
Teleservice	М	M(=)		
ASCI Call Reference	М	M(=)		
Ciphering Algorithm	М	M(=)		
Group Key Number VK-Id	С	C(=)		
VSTK Key	С	C(=)		
VSTK-RAND	С	C(=)		
Priority	С	C(=)		
CODEC-Information	М	M(=)		
Uplink Free Indicator	М	M(=)		
Group Call Number			М	M(=)
User Error			С	C(=)
Provider Error				0

10.4.3 Parameter definitions and use

Invoke Id

See definition in clause 7.6.1.

Teleservice

Voice Broadcast Service or Voice Group Call Service.

ASCI Call Reference

Broadcast call reference or group call reference. This item is used to access the VBS-GCR or VGCS-GCR within the Relay_MSC.

Ciphering Algorithm

The ciphering algorithm to be used for the group call.

Group Key Number VK-Id

This Group Key Number has to be broadcast and is used by the mobile station to derive the key for ciphering on the radio interface (see 3GPP TS 43.020 [24]). Values 2 to 15 are reserved for future use.

Shall be present if the ciphering applies.

VSTK

The VGCS/VBS Short Term Key is used to derive the key for ciphering on the radio interface (see 3GPP TS 43.020 [24]).

Shall be present if the ciphering applies.

VSTK-RAND

This random number has to be broadcast and is used by the mobile station to derive the group key for ciphering on the radio interface (see 3GPP TS 43.020 [24]).

Shall be present if the ciphering applies.

Priority

Default priority level related to the call if eMLPP applies.

CODEC-Information

Information on the codecs allowed for this call.

Uplink Free Indicator

A flag indicating whether the call is initiated from a dispatcher.

Group Call Number

This temporary allocated E.164 number is used for routing the call from the Anchor MSC to the Relay MSC.

User Error

For definition of this parameter see clause 7.6.1 The following errors defined in clause 7.6.1 may be used, depending on the nature of the fault:

- No Group Call Number available;
- System Failure;
- Unexpected Data Value.

Provider Error

See definition of provider error in clause 7.6.1.

10.5 MAP PROCESS GROUP CALL SIGNALLING service

10.5.1 Definitions

This service is used between Relay MSC and Anchor MSC for transmission of Group Call notifications.

The MAP_PROCESS_GROUP_CALL_SIGNALLING service is a non-confirmed service using the service primitives given in table 10.5/1.

10.5.2 Service primitives

Table 10.5/1: MAP PROCESS GROUP CALL SIGNALLING service

Parameter name	Request	Indication
Invoke Id	M	M(=)
Uplink Request	С	C(=)
Uplink Release Indication	С	C(=)
Release Group Call	С	C(=)

10.5.3 Parameter definitions and use

Invoke Id

See definition in clause 7.6.1

<u>Uplink Request</u>

This information element indicates to the anchor MSC that a service subscriber roaming in the relay MSC area requests access to the uplink.

<u>Uplink Release Indication</u>

This information element if included by the Relay MSC indicates to the Anchor MSC that the uplink has become free.

Release Group Call

This information element if included by the Relay MSC indicates to the Anchor MSC that the service subscriber who has initiated the call and who currently has access to the uplink terminates the call.

10.6 MAP_FORWARD_GROUP_CALL_SIGNALLING service

10.6.1 Definitions

This service is used between Anchor MSC and Relay MSC for transmission of Group Call notifications.

The MAP_FORWARD_GROUP_CALL_SIGNALLING service is a non-confirmed service using the service primitives given in table 10.6/1.

10.6.2 Service primitives

Table 10.6/1: MAP_FORWARD_GROUP_CALL_SIGNALLING service

Parameter name	Request	Indication
Invoke Id	М	M(=)
IMSI	С	C(=)
Uplink Request	С	C(=)
Acknowledgement		
Uplink Release Indication	С	C(=)
Uplink Reject Command	С	C(=)
Uplink Seized Command	С	C(=)
Uplink Release Command	С	C(=)
State Attributes	С	C(=)

10.6.3 Parameter definitions and use

IMSI

Identity of the service subscriber who has established the call and who is allowed to terminate the call.

Invoke Id

See definition in clause 7.6.1.

Uplink Request Acknowledgement

This information element is used for positive acknowledgement of an uplink request.

Uplink Release Indication

This information element if included by the Anchor MSC indicates to the Relay MSC that the uplink has become free.

Uplink Reject Command

This information element is used for negative acknowledgement of an uplink request.

Uplink Seized Command

This information element if included by the Anchor MSC indicates to the Relay MSC that the uplink is no longer free.

Uplink Release Command

This information element if included by the Anchor MSC indicates to the Relay MSC that the uplink which is granted to a MS in the relay MSC area shall be released.

State Attributes

This information element is used to allow service logic running in an Anchor MSC to mute a VGCS talker even when the talker is served on a Relay MSC. The IE is used to build a GCC message that provides a mechanism to induce the VGCS talker terminal to mute/unmute the downlink at the Anchor MSC, as defined in 3GPP TS 44.068.

10.7 MAP SEND GROUP CALL END SIGNAL service

10.7.1 Definitions

This service is used between the Relay MSC and the Anchor MSC indicating that VGCS / VBS channels have been established in the Relay MSC area. The response is used by the Anchor MSC to inform the Relay MSC that all resources for the call can be released in the Relay MSC because the call has been released in the Anchor MSC.

The MAP_SEND_GROUP_CALL_END_SIGNAL service is a confirmed service using the service primitives given in table 10.7/1.

10.7.2 Service primitives

Table 10.7/1: MAP SEND GROUP CALL END SIGNAL service

Parameter name	Request	Indication	Response	Confirm
Invoke Id	M	M(=)	M(=)	M(=)
IMSI	С	C(=)		
Provider Error				0

10.7.3 Parameter definitions and use

IMSI

Identity of the service subscriber who has established the call and who is allowed to terminate the call.

Shall be present if the call was established by a service subscriber roaming in the relay MSC area.

Invoke Id

See definition in clause 7.6.1

Provider Error

See definition of provider error in clause 7.6.1.

10.8 Void

10.9 Void

10.10 MAP_SET_REPORTING_STATE service

10.10.1 Definition

This service is used between the HLR and the VLR to set the reporting state for a requested service. It is a confirmed service using the service primitives shown in table 10.10/1.

10.10.2 Service primitives

Table 10.10/1: MAP_SET_REPORTING_STATE parameters

Parameter name	Request	Indication	Response	Confirm
Invoke id	M	M(=)	M(=)	M(=)
IMSI	С	C(=)		
LMSI	С	C(=)		
CCBS Monitoring	С	C(=)		
CCBS Subscriber Status			С	C(=)
User error			С	C(=)
Provider error	_			0

10.10.3 Parameter use

See clause 7.6 for a definition of the parameters used, in addition to the following.

IMSI

The IMSI is a mandatory parameter if the service is used as the only one in a dialogue.

CCBS Monitoring

This parameter indicates whether monitoring for CCBS shall be started or stopped. If it indicates that monitoring shall be started this service corresponds to the message 'Start Reporting' in 3GPP TS 23.093 [107]; if it indicates that monitoring shall be stopped this service corresponds to the message 'Stop Reporting' in 3GPP TS 23.093 [107].

CCBS Subscriber Status

See 3GPP TS 23.093 [107] for the use of this parameter and the conditions for its presence.

User error

This parameter is sent by the responder upon unsuccessful outcome of the service, and then takes one of the following values defined in clause 7.6.1:

- System Failure;
- Unidentified Subscriber;
- Unexpected Data Value;
- Data Missing;
- Resource Limitation;
- Facility Not Supported.

NOTE: This error is reserved for future use.

Provider error

These are defined in clause 7.6.

10.11 MAP_STATUS_REPORT service

10.11.1 Definition

This service is used by the VLR to report an event or call outcome to the HLR. It is a confirmed service using the service primitives shown in table 10.11/1.

10.11.2 Service primitives

Table 10.11/1: MAP_STATUS_REPORT parameters

Parameter name Request Indication Response Confirm	n
--	---

Invoke id	M	M(=)	M(=)	M(=)
IMSI	M	M(=)		
CCBS Subscriber Status	С	C(=)		
Monitoring Mode	С	C(=)		
Call Outcome	С	C(=)		
User error			С	C(=)
Provider error				0

10.11.3 Parameter use

See clause 7.6 for a definition of the parameters used, in addition to the following.

CCBS Subscriber Status

If this parameter is present without Monitoring Mode and Call Outcome this service corresponds to the message 'Event Report' in 3GPP TS 23.093 [107]. See 3GPP TS 23.093 [107] for the use of this parameter and the conditions for its presence.

Monitoring Mode

If this parameter is present with CCBS Call Outcome this service corresponds to the message 'CCBS Call Report' in 3GPP TS 23.093 [107]. See 3GPP TS 23.093 [107] for the use of this parameter and the conditions for its presence.

Call Outcome

See 3GPP TS 23.093 [107] for the use of this parameter and the conditions for its presence.

User error

This parameter is sent by the responder upon unsuccessful outcome of the service, and then takes one of the following values defined in clause 7.6.1:

- Unknown Subscriber;
- System Failure;
- Unexpected Data Value;
- Data Missing.

Provider error

These are defined in clause 7.6.

10.12 MAP REMOTE USER FREE service

10.12.1 Definition

This service is used between the HLR and the VLR to report that the B subscriber is now idle and that the A subscriber can be notified. It is a confirmed service using the service primitives shown in table 10.12/1.

10.12.2 Service primitives

Table 10.12/1: MAP_REMOTE_USER_FREE parameters

Parameter name	Request	Indication	Response	Confirm
Invoke id	M	M(=)	M(=)	M(=)
IMSI	M	M(=)		
Call Info	M	M(=)		
CCBS Feature	M	M(=)		
Translated B Number	M	M(=)		
Replace B Number	С	C(=)		

Alerting Pattern	С	C(=)		
RUF Outcome			С	C(=)
User error			С	C(=)
Provider error				0

10.12.3 Parameter use

See clause 7.6 for a definition of the parameters used, in addition to the following.

Call Info

See 3GPP TS 23.093 [107] for the use of this parameter.

CCBS Feature

See 3GPP TS 23.093 [107] for the conditions for the presence of the parameters included in the CCBS feature.

Translated B Number

See 3GPP TS 23.093 [107] for the use of this parameter.

Replace B Number

See 3GPP TS 23.093 [107] for the use of this parameter and the conditions for its presence.

Alerting Pattern

See 3GPP TS 23.093 [107] for the use of this parameter and the conditions for its presence.

RUF Outcome

See 3GPP TS 23.093 [107] for the use of this parameter and the conditions for its presence.

User error

This parameter is sent by the responder upon unsuccessful outcome of the service, and then takes one of the following values defined in clause 7.6.1:

- Unexpected Data Value;
- Data Missing;
- Incompatible Terminal;
- This error is returned by the responder when the terminal used for CCBS activation is not compatible with the terminal used for the CCBS recall. For details refer to 3GPP TS 24.008 [35];
- Absent Subscriber (IMSI Detach; Restricted Area; No Page Response);
- System Failure;
- Busy Subscriber (CCBS Busy).

Provider error

These are defined in clause 7.6.

10.13 MAP_IST_ALERT service

10.13.1 Definition

This service is used between the MSC (Visited MSC or Gateway MSC) and the HLR, to report that the IST timer running for a call for the Subscriber has expired. It is a confirmed service using the service primitives shown in table 10.13/1.

10.13.2 Service primitives

Table 10.13/1: MAP_IST_ALERT parameters

Parameter name	Request	Indication	Response	Confirm
Invoke Id	M	M(=)	M(=)	M(=)
IMSI	M	M(=)		
IST Alert Timer			С	C(=)
IST Information Withdraw			С	C(=)
Call termination Indicator			С	C(=)
User error			С	C(=)
Provider error				0

10.13.3 Parameter use

All parameters are described in clause 7.6. The following clarifications are applicable:

IST Alert Timer

If included in the IST Alert response, it includes the new IST Alert timer value that must be used to inform the HLR about the call activities that the subscriber performs.

IST Information Withdraw

If included in the IST Alert response, this parameter is used to indicate that the IST condition has been removed for the subscriber. When the MSC receives this parameter, IST control for that call shall be terminated.

Call termination Indicator

If included in the IST Alert response, this parameter is used to indicate whether the MSC shall terminate the call activity that had previously triggered the IST Alert procedure, or it shall also release all other call activities for the specified subscriber (outgoing call activities if the IST Alert is initiated by the VMSC, or incoming call activities if the IST Alert is initiated by the GMSC). Release of all other call activities is possible only if the MSC has the capability to link the call activities for the Subscriber by using the IMSI as key.

User error

This parameter is sent by the responder when an error is detected and if present, takes one of the following values:

- System Failure;
- Unexpected Data Value;
- Resource Limitation;
- Facility Not Supported;
- Unknown Subscriber.

10.14 MAP_IST_COMMAND service

10.14.1 Definition

This service is used by the HLR to instruct the MSC (Visited MSC or Gateway MSC) to terminate ongoing call activities for a specific subscriber. It is a confirmed service using the service primitives shown in table 10.14/1.

10.14.2 Service primitives

Table 10.14/1: MAP IST COMMAND parameters

Parameter name	Request	Indication	Response	Confirm
----------------	---------	------------	----------	---------

Invoke Id	M	M(=)	M(=)	M(=)
IMSI	M	M(=)		
User error			С	C(=)
Provider error				0

10.14.3 Parameter use

All parameters are described in clause 7.6. The following clarifications are applicable:

User error

This parameter is sent by the responder when an error is detected and if present, takes one of the following values:

- System Failure;
- Unexpected Data Value;
- Resource Limitation;
- Facility Not Supported;
- Unknown Subscriber.

10.15 MAP RELEASE RESOURCES service

10.15.1 Definition

This service is used between the GMSC and the terminating VMSC. The service is invoked by the GMSC to request the VMSC to release the resources associated with the specified MSRN.

This is a confirmed service which uses the Primitives listed in table 10.15/1.

10.15.2 Service primitives

Table 10.15/1: MAP_RELEASE_RESOURCES parameters

Parameter name	Request	Indication	Response	Confirm
Invoke Id	M	M(=)	M(=)	M(=)
MSRN	M	M(=)		
User error			С	C(=)
Provider error				0

10.15.3 Parameter use

MSRN

See 3GPP TS 23.018 [97] for the use of this parameter.

User error

This parameter is sent by the responder when an error is detected and if present, takes one of the following values:

- System Failure;
- Unexpected Data Value;

Provider error

These are defined in clause 7.6.

11 Supplementary services related services

11.1 MAP_REGISTER_SS service

11.1.1 Definition

This service is used between the MSC and the VLR and between the VLR and the HLR to register data related to a supplementary service. The VLR will relay the message to the HLR.

The service is a confirmed service and uses the service primitives shown in table 11.1./1.

11.1.2 Service primitives

Table 11.1/1: MAP_REGISTER_SS parameters

Parameter name	Request	Indication	Response	Confirm
Invoke id	M	M(=)	M(=)	M(=)
SS-Code	M	M(=)		
Basic service	С	C(=)		
Forwarded-to number with subaddress	С	C(=)		
No reply condition time	С	C(=)		
EMLPP default priority	С	C(=)	С	C(=)
Long FTN Supported	С	C(=)		
NbrUser	С	C(=)	С	C(=)
Forwarding information			С	C(=)
User error			С	C(=)
Provider error				0

11.1.3 Parameter use

Invoke id

See clause 7.6.1 for the use of this parameter.

SS-Code

This parameter indicates the supplementary service which the mobile subscriber wants to register.

Basic service

This parameter indicates for which basic service group the supplementary service is to be registered. If it is not included, the registration request applies to all basic services.

Forwarded-to number with subaddress

This parameter is obligatory if the registration applies to one or more call forwarding supplementary services. It can optionally include a sub-address.

No reply condition time

This parameter is included if the registration applies to the Call Forwarding on No Reply supplementary service (or a superset of this service) and the mobile subscriber supplies a value for this time.

EMLPP default priority

This parameter is sent by the initiator to register the eMLPP default priority level and is returned by the responder at successful outcome of the service.

Long FTN Supported

This parameter indicates that the mobile station supports Long Forwarded-to Numbers.

NbrUser

This parameter is sent by the initiator to register the MC maximum number of user defined circuit switched bearers to be used.

Forwarding information

This parameter is returned by the responder at successful outcome of the service, if the registration request concerned one or a group of Call Forwarding supplementary services.

User error

This parameter is sent by the responder upon unsuccessful outcome of the service, and then takes one of the following values defined in clause 7.6.1:

- System failure;
- Data missing;
- Unexpected data value;
- Call Barred;
- Bearer service not provisioned;
- This error is returned only if not even a subset of the requested bearer service group has been subscribed to;
- Teleservice not provisioned;

This error is returned only if not even a subset of the requested teleservice group has been subscribed to;

- Illegal SS operation;
- SS error status;
- SS incompatibility.

Provider error

See clause 7.6.1 for the use of this parameter.

11.2 MAP_ERASE_SS service

11.2.1 Definition

This service is used between the MSC and the VLR and between the VLR and the HLR to erase data related to a supplementary service. The VLR will relay the message to the HLR.

The service is a confirmed service and uses the service primitives shown in table 11.2/1.

11.2.2 Service primitives

Table 11.2/1: MAP_ERASE_SS parameters

Parameter name	Request	Indication	Response	Confirm
Invoke id	M	M(=)	M(=)	M(=)
SS-Code	M	M(=)		
Basic service	С	C(=)		
Forwarding information			С	C(=)
User error			С	C(=)
Provider error				0

11.2.3 Parameter use

Invoke id

See clause 7.6.1 for the use of this parameter.

SS-Code

This parameter indicates the supplementary service which the mobile subscriber wants to erase.

Basic service

This parameter indicates for which basic service group the supplementary service should be erased. If it is not included, the erasure request applies to all basic services.

Forwarding information

This parameter is returned by the responder at successful outcome of the service, if the erasure request concerned one or a group of Call Forwarding supplementary services.

User error

This parameter is sent by the responder upon unsuccessful outcome of the service, and then takes one of the following values, defined in clause 7.6.1:

- System failure;
- Data Missing;
- Unexpected data value;
- Bearer service not provisioned;

This error is returned only if not even a subset of the requested bearer service group has been subscribed to;

- Teleservice not provisioned;

This error is returned only if not even a subset of the requested teleservice group has been subscribed to;

- Call Barred;
- Illegal SS operation;
- SS error status.

Provider error

See clause 7.6.1 for the use of this parameter.

11.3 MAP ACTIVATE SS service

11.3.1 Definition

This service is used between the MSC and the VLR and between the VLR and the HLR to activate a supplementary service. The VLR will relay the message to the HLR.

The service is a confirmed service and uses the service primitives shown in table 11.3/1.

11.3.2 Service primitives

Table 11.3/1: MAP ACTIVATE SS parameters

Parameter name	Request	Indication	Response	Confirm
Invoke id	М	M(=)	M(=)	M(=)

SS-Code	М	M(=)		
Long FTN Supported	С	C(=)		
Basic service	С	C(=)		
Forwarding information			С	C(=)
Call barring information			С	C(=)
SS-Data			С	C(=)
User error			С	C(=)
Provider error				0

11.3.3 Parameter use

Invoke id

See clause 7.6.1 for the use of this parameter.

SS-Code

This parameter indicates the supplementary service which the mobile subscriber wants to activate.

Basic service

This parameter indicates for which basic service groups the requested supplementary service(s) should be activated. If it is not included, the activation request applies to all basic services.

Forwarding information

This parameter is returned by the responder at successful outcome of the service, if the activation request concerned Call Forwarding.

Long FTN Supported

This parameter indicates that the mobile station supports Long Forwarded-to Numbers.

Call barring information

This parameter is returned by the responder at successful outcome of the service, if the activation request concerned Call Barring.

SS-Data

This parameter is returned by the responder at successful outcome of the service, if the activation request concerned for example Call Waiting.

User error

This parameter is sent by the responder upon unsuccessful outcome of the service, and then takes one of the following values, defined in clause 7.6.1:

- System failure;
- Data Missing;
- Unexpected data value;
- Bearer service not provisioned;
- This error is returned only if not even a subset of the requested bearer service group has been subscribed to.
- Teleservice not provisioned;
- This error is returned only if not even a subset of the requested teleservice group has been subscribed to.
- Call Barred;
- Illegal SS operation;

- SS error status;
- SS subscription violation;
- SS incompatibility;
- Negative PW check;
- Number Of PW Attempts Violation.

Provider error

See clause 7.6.1 for the use of this parameter.

11.4 MAP_DEACTIVATE_SS service

11.4.1 Definitions

This service is used between the MSC and the VLR and between the VLR and the HLR to deactivate a supplementary service. The VLR will relay the message to the HLR.

The service is a confirmed service and uses the service primitives shown in table 11.4/1.

11.4.2 Service primitives

Table 11.4/1: MAP_DEACTIVATE_SS parameters

Parameter name	Request	Indication	Response	Confirm
Invoke id	M	M(=)	M(=)	M(=)
SS-Code	M	M(=)		
Basic service	С	C(=)		
Forwarding information			С	C(=)
Call barring information			С	C(=)
SS-Data			С	C(=)
User error			С	C(=)
Provider error				0

11.4.3 Parameter use

Invoke id

See clause 7.6.1 for the use of this parameter.

SS-Code

This parameter indicates the supplementary service which the mobile subscriber wants to deactivate.

Basic service

This parameter indicates for which basic service group the requested supplementary service(s) should be deactivated. If it is not included the deactivation request applies to all basic services.

Forwarding information

This parameter is returned by the responder at successful outcome of the service, if the deactivation request concerned one or a group of Call Forwarding supplementary services.

Call barring information

This parameter is returned by the responder at successful outcome of the service, if the activation request concerned one or a group of Call Barring supplementary services.

SS-Data

This parameter is returned by the responder at successful outcome of the service, for example if the deactivation request concerned the Call Waiting supplementary service.

User error

This parameter is sent by the responder upon unsuccessful outcome of the service, and then takes one of the following values, defined in clause 7.6.1:

- System failure;
- Data Missing;
- Unexpected data value;
- Bearer service not provisioned;

This error is returned only if not even a subset of the requested bearer service group has been subscribed to;

Teleservice not provisioned;

This error is returned only if not even a subset of the requested teleservice group has been subscribed to;

- Call Barred;
- Illegal SS operation;
- SS error status;
- SS subscription violation;
- Negative PW check;
- Number Of PW Attempts Violation.

Provider error

See clause 7.6.1 for the use of this parameter.

11.5 MAP INTERROGATE SS service

11.5.1 Definitions

This service is used between the MSC and the VLR and between the VLR and the HLR to retrieve information related to a supplementary service. The VLR will relay the message to the HLR if necessary.

The service is a confirmed service and consists of four service primitives.

11.5.2 Service primitives

The service primitives are shown in table 11.5/1.

Table 11.5/1: MAP_INTERROGATE_SS parameters

Parameter name	Request	Indication	Response	Confirm
Invoke id	M	M(=)	M(=)	M(=)
SS-Code	М	M(=)		
Basic service	С	C(=)		
Long FTN Supported	С	C(=)		
SS-Status			С	C(=)
Basic service Group LIST			С	C(=)
Forwarding feature LIST			С	C(=)
CLI restriction Info			С	C(=)

EMLPP Info	С	C(=)
MC Information	С	C(=)
CCBS Feature LIST	С	C(=)
User error	С	C(=)
Provider error		0

11.5.3 Parameter use

For additional information on parameter use refer to the GSM 04.8x and 04.9x-series of technical specifications.

Invoke id

See clause 7.6.1 for the use of this parameter.

SS-Code

The mobile subscriber can only interrogate a single supplementary service per service request.

Basic service

This parameter indicates for which basic service group the given supplementary service is interrogated. If it is not included, the interrogation request applies to all basic services.

SS-Status

This parameter is included by the responder if:

- the interrogated supplementary service can only be subscribed for all applicable basic services simultaneously; or
- the interrogated supplementary service is not active for any of the interrogated basic services, or
- the interrogation was for the CCBS supplementary service and no CCBS request is active or the service is not provisioned.

Basic service group LIST

This parameter LIST is used to include one or a series of basic service groups for which the interrogated supplementary service is active. If the interrogated supplementary service is not active for any of the interrogated (and provisioned) basic service groups, the SS-Status parameter is returned.

Long FTN Supported

This parameter indicates that the mobile station supports Long Forwarded-to Numbers.

Forwarding feature LIST

The forwarding feature parameter is described in clause 7.6.4. A list of one or more forwarding features is returned by the responder when the interrogation request applied to Call Forwarding supplementary service.

If no basic service code parameter is provided within this sequence, the forwarding feature parameter applies to all provisioned basic services.

CLI restriction Info

The CLI-RestrictionInfo parameter is returned by the responder when the interrogation request applies to the CLIR supplementary service.

EMLPP Info

The eMLPP info (maximum entitled priority and default priority) is returned by the responder if the interrogation request applies to the eMLPP supplementary service.

MC Information

The MC information (NbrSB, NbrUser and NbrSN) is returned by the responder if the interrogation request applies to the MC supplementary service. For a definition of these 3 components, refer to 3GPP TS 23.135 and 3GPP TS 24.135.

CCBS Feature LIST

The CCBS feature parameter is described in clause 7.6. A list of one or more CCBS features is returned by the responder when the interrogation request applied to the CCBS supplementary service. See 3GPP TS 23.093 [107] for the conditions for the presence of the parameters included in the CCBS feature.

User error

This error is sent by the responder upon unsuccessful outcome of the interrogation service, and then takes one of the following values, defined in clause 7.6.1:

- System failure;
- Data Missing;
- Unexpected data value;
- Bearer Service not provisioned;

This error is returned only if not even a subset of the interrogated bearer services are provided;

Teleservice not provisioned;

This error is returned only if not even a subset of the interrogated teleservices are provided;

- Call Barred:
- Illegal SS operation;
- SS not available.

Provider error

See clause 7.6.1 for the use of this parameter.

11.6 Void

11.7 MAP_REGISTER_PASSWORD service

11.7.1 Definitions

This service is used between the MSC and the VLR and between the VLR and the HLR if the mobile subscriber requests to register a new password. The VLR will relay the message to the HLR.

The service is a confirmed service and consists of four service primitives.

11.7.2 Service primitives

The service primitives are shown in table 11.7/1.

Table 11.7/1: MAP_REGISTER_PASSWORD parameters

Parameter name	Request	Indication	Response	Confirm
Invoke id	M	M(=)	M(=)	M(=)
SS-Code	M	M(=)		
New password			С	C(=)
User error			С	C(=)
Provider error				0

11.7.3 Parameter use

Invoke id

See clause 7.6.1 for the use of this parameter.

SS-Code

This parameter indicates for which supplementary service(s) the password should be registered.

New Password

See clause 7.6.4 for the use of this parameter.

User error

This parameter is sent by the responder upon unsuccessful outcome of the service, and then takes one of the following values, defined in clause 7.6.1:

- System failure;
- Data Missing;
- Unexpected data value;
- Call Barred;
- SS subscription violation;
- Password registration failure;
- Negative PW check;
- Number Of PW Attempts Violation.

Provider error

See clause 7.6.1 for the use of this parameter.

11.8 MAP_GET_PASSWORD service

11.8.1 Definitions

This service is used between the HLR and the VLR and between the VLR and the MSC when the HLR receives a request from the mobile subscriber for an operation on a supplementary service which requires a password from the subscriber. The VLR will relay the message to the MSC.

The service is a confirmed service and uses the service primitives shown in table 11.8/1.

11.8.2 Service primitives

Table 11.8/1: MAP_GET_PASSWORD parameters

Parameter name	Request	Indication	Response	Confirm
Invoke id	M	M(=)	M(=)	M(=)
Linked id	С	C(=)		
Guidance info	M	M(=)		
Current password			M	M(=)
Provider error				0

11.8.3 Parameter use

Invoke id

See clause 7.6.1 for the use of this parameter.

Linked Id

See clause 7.6.1 for the use of this parameter. If the MAP_GET_PASSWORD service is used in conjunction with the MAP_REGISTER_PASSWORD service, this parameter must be present; otherwise it must be absent.

Guidance info

See clause 7.6.4 for the use of this parameter.

Current password

See clause 7.6.4 for the use of this parameter.

Provider error

See clause 7.6.1 for the use of this parameter.

11.9 MAP_PROCESS_UNSTRUCTURED_SS_REQUEST service

11.9.1 Definitions

This service is used between the MSC and the VLR, between the VLR and the HLR, between the HLR and gsmSCF and between the HLR and HLR to relay information in order to allow unstructured supplementary service operation.

The MAP_PROCESS_UNSTRUCTURED_SS_REQUEST service is a confirmed service using the primitives from table 11.9/1.

11.9.2 Service primitives

Table 11.9/1: MAP_PROCESS_UNSTRUCTURED_SS_REQUEST parameters

Parameter name	Request	Indication	Response	Confirm
Invoke id	M	M(=)	M(=)	M(=)
USSD Data Coding Scheme	M	M(=)	С	C(=)
USSD String	M	M(=)	С	C(=)
MSISDN	С	C(=)		
User error			С	C(=)
Provider error				0

11.9.3 Parameter use

Invoke id

See clause 7.6.1 for the use of this parameter.

USSD Data Coding Scheme

See clause 7.6.4 for the use of this parameter. The presence of the parameter in the response is dependent on the unstructured supplementary service application. If this parameter is present, then the USSD String parameter has to be present.

USSD String

See clause 7.6.1 for the use of this parameter. The presence of the parameter in the response is dependent on the unstructured supplementary service application. If this parameter is present, then the USSD Data Coding Scheme parameter has to be present.

MSISDN

The subscriber"s basic MSISDN.

See definition in clause 7.6.2. For Follow Me when the service request is sent from the HLR of the A subscriber, the parameter shall contain the MSISDN of the A subscriber, see 3GPP TS 23.094 [129]. For other purposes the MSISDN may be included as an operator option, e.g. to allow addressing the subscriber"s data in the gsmSCF with the MSISDN.

User error

This parameter is sent by the responder upon unsuccessful outcome of the service, and then takes one of the following values defined in clause 7.6.1:

- System failure;
- Data missing;
- Unexpected data value;

This error is returned by the responder if it is not able to deal with the contents of the USSD string.

- Call Barred:
- Unknown Alphabet.

Provider error

See clause 7.6.1 for the use of this parameter.

11.10 MAP_UNSTRUCTURED_SS_REQUEST service

11.10.1 Definitions

This service is used between the gsmSCF and the HLR, the HLR and the VLR and between the VLR and the MSC when the invoking entity requires information from the mobile user, in connection with unstructured supplementary service handling.

The MAP_UNSTRUCTURED_SS_REQUEST service is a confirmed service using the primitives from table 11.10/1.

11.10.2 Service primitives

Table 11.10/1: MAP_UNSTRUCTURED_SS_REQUEST parameters

Parameter name	Request	Indication	Response	Confirm
Invoke id	M	M(=)	M(=)	M(=)
USSD Data Coding Scheme	M	M(=)	С	C(=)
USSD String	М	M(=)	С	C(=)
Alerting Pattern	С	C(=)		
User error			С	C(=)
Provider error				Ö

11.10.3 Parameter use

Invoke id

See clause 7.6.1 for the use of this parameter.

USSD Data Coding Scheme

See clause 7.6.4 for the use of this parameter. The presence of the parameter in the response is dependent on the mobile user's MMI input. If this parameter is present, then the USSD String parameter has to be present.

USSD String

See clause 7.6.1 for the use of this parameter. The presence of the parameter in the response is dependent on the mobile user's MMI input. If this parameter is present, then the USSD Data Coding Scheme parameter has to be present.

Alerting Pattern

See clause 7.6.3 for the use of this parameter.

User error

This parameter is sent by the responder upon unsuccessful outcome of the service, and then takes one of the following values defined in clause 7.6.1:

- System failure;
- Data missing;
- Unexpected data value;

This error is returned by the responder if it is not able to deal with the contents of the USSD string;

- Absent Subscriber;
- Illegal Subscriber;

This error indicates that delivery of the unstructured supplementary service data failed because the MS failed authentication;

- Illegal Equipment;
- USSD Busy;
- Unknown Alphabet.

Provider error

See clause 7.6.1 for the use of this parameter.

11.11 MAP_UNSTRUCTURED_SS_NOTIFY service

11.11.1 Definitions

This service is used between the gsmSCF and the HLR, the HLR and the VLR and between the VLR and the MSC when the invoking entity requires a notification to be sent to the mobile user, in connection with unstructured supplementary services handling.

The MAP_UNSTRUCTURED_SS_NOTIFY service is a confirmed service using the primitives from table 11.11/1.

11.11.2 Service primitives

Table 11.11/1: MAP_UNSTRUCTURED_SS_NOTIFY parameters

Parameter name	Request	Indication	Response	Confirm
Invoke id	M	M(=)	M(=)	M(=)
USSD Data Coding Scheme	M	M(=)		
USSD String	M	M(=)		
Alerting Pattern	С	C(=)		
User error			С	C(=)
Provider error				O

11.11.3 Parameter use

Invoke id

See clause 7.6.1 for the use of this parameter.

USSD Data Coding Scheme:

See clause 7.6.4 for the use of this parameter.

USSD String:

See clause 7.6.1 for the use of this parameter.

Alerting Pattern

See clause 7.6.3 for the use of this parameter.

User error

This parameter is sent by the responder upon unsuccessful outcome of the service, and then takes one of the following values defined in clause 7.6.1:

- System failure;
- Data missing;
- Unexpected data value;

This error is returned by the responder if it is not able to deal with the contents of the USSD string.

- Absent Subscriber;
- Illegal Subscriber;

This error indicates that delivery of the unstructured supplementary service data failed because the MS failed authentication.

- Illegal Equipment;
- USSD Busy;
- Unknown Alphabet.

Provider error

See clause 7.6.1 for the use of this parameter.

11.12 MAP_SS_INVOCATION_NOTIFY

11.12.1 Definition

This service is used between the MSC and the gsmSCF when the subscriber invokes one of the following supplementary services; Call Deflection (CD), Explicit Call Transfer (ECT) or Multi Party (MPTY).

This service is used between the HLR and the gsmSCF when the subscriber invokes the CCBS supplementary service.

11.12.2 Service primitives

The service primitives are shown in table 11.12/1.

Table 11.12/1: SS_INVOCATION_NOTIFY parameters

Parameter name	Request	Indication	Response	Confirm
Invoke id	M	M(=)	M(=)	M(=)
MSISDN	М	M(=)		
IMSI	М	M(=)		
SS- event	М	M(=)		
SS- event data	С	C(=)		
B-subscriber Number	С	C(=)		
CCBS Request State	С	C(=)		
User error			С	C(=)
Provider error				0

11.12.3 Parameter use

All parameters are described in clause 7.6. The use of these parameters and the requirements for their presence are specified in 3GPP TS 23.078.

User error

This parameter is sent by the responder when an error is detected and if present, takes one of the following values:

- Data Missing;
- Unexpected Data Value;
- Unknown Subscriber.

Provider error

This is defined in clause 7.6.1.

11.13 MAP_REGISTER_CC_ENTRY service

11.13.1 Definition

This service is used between the MSC and the VLR and between the VLR and the HLR to register data for a requested call completion supplementary service. The VLR will relay the message to the HLR.

The service is a confirmed service and uses the service primitives shown in table 11.13/1.

11.13.2 Service primitives

Table 11.13/1: MAP_REGISTER_CC_ENTRY parameters

Parameter name	Request	Indication	Response	Confirm
Invoke id	M	M(=)	M(=)	M(=)
SS Code	M	M(=)		
CCBS Feature	С	C(=)	С	C(=)
Translated B number	С	C(=)		
Service Indicator	С	C(=)		
Call Info	С	C(=)		
Network Signal Info	С	C(=)		
User error			C	C(=)
Provider error				0

11.13.3 Parameter use

See clause 7.6 for a definition of the parameters used, in addition to the following.

SS-Code

This parameter indicates the call completion supplementary service for which the mobile subscriber wants to register an entry.

CCBS Feature

See 3GPP TS 23.093 [107] for the conditions for the presence of the parameters included in the CCBS feature.

Translated B Number

See 3GPP TS 23.093 [107] for the use of this parameter and the conditions for its presence.

Service Indicator

This parameter corresponds to the parameters 'Presentation Indicator' and 'CAMEL Invoked' in 3GPP TS 23.093 [107]. It indicates which services have been invoked for the original call (e.g. CLIR, CAMEL). See 3GPP TS 23.093 [107] for the use of this parameter and the conditions for its presence.

Call Info

See 3GPP TS 23.093 [107] for the use of this parameter and the conditions for its presence.

Network Signal Info

See 3GPP TS 23.093 [107] for the use of this parameter and the conditions for its presence.

User error

This parameter is sent by the responder upon unsuccessful outcome of the service, and then takes one of the following values, defined in clause 7.6.1:

- System failure;
- Data missing;
- Unexpected data value;
- Call Barred;
- Illegal SS operation;
- SS error status;
- SS incompatibility.

- Short Term Denial;
- Long Term Denial;
- Facility Not Supported;

NOTE: This error is reserved for future use.

Private Extensions shall not be sent with these user errors for this operation.

Provider error

See clause 7.6.1 for the use of this parameter.

11.14 MAP ERASE CC ENTRY service

11.14.1 Definition

This service is used between the MSC and the VLR and between the VLR and the HLR to erase data related to a call completion supplementary service. The VLR will relay the message to the HLR.

The service is a confirmed service and uses the service primitives shown in table 11.14/1.

11.14.2 Service primitives

Table 11.14/1: MAP_ERASE_CC_ENTRY parameters

Parameter name	Request	Indication	Response	Confirm
Invoke id	M	M(=)	M(=)	M(=)
SS-Code	M	M(=)	C(=)	C(=)
CCBS Index	С	C(=)		
SS-Status			С	C(=)
User error			С	C(=)
Provider error				0

11.14.3 Parameter use

See clause 7.6 for a definition of the parameters used, in addition to the following.

SS-Code

This parameter indicates the call completion supplementary service for which the mobile subscriber wants to erase an entry/entries.

CCBS Index

See 3GPP TS 23.093 [107] for the use of this parameter and the condition for its presence.

SS-Status

Depending on the outcome of the service request this parameter may indicate either provisioned and active or not provisioned.

<u>User error</u>

This parameter is sent by the responder upon unsuccessful outcome of the service, and then takes one of the following values, defined in clause 7.6.1:

- System failure;
- Data Missing;

- Unexpected data value;
- Call Barred;
- Illegal SS operation;
- SS error status.

Private Extensions shall not be sent with these user errors for this operation.

Provider error

See clause 7.6.1 for the use of this parameter.

12 Short message service management services

12.1 MAP-SEND-ROUTING-INFO-FOR-SM service

12.1.1 Definition

This service is used between the gateway MSC and the HLR to retrieve the routing information needed for routing the short message to the servicing MSC.

The MAP-SEND-ROUTING-INFO-FOR-SM is a confirmed service using the primitives from table 12.1/1.

12.1.2 Service primitives

Table 12.1/1: MAP-SEND-ROUTING-INFO-FOR-SM

Parameter name	Request	Indication	Response	Confirm
Invoke Id	M	M(=)	M(=)	M(=)
MSISDN	M	M(=)		
SM-RP-PRI	М	M(=)		
Service Centre Address	M	M(=)		
SM-RP-MTI	С	C(=)		
SM-RP-SMEA	С	C(=)		
GPRS Support Indicator	С	C(=)		
IMSI			С	C(=)
Network Node Number			С	C(=)
LMSI			С	C(=)
GPRS Node Indicator			С	C(=)
Additional Number			С	C(=)
User error			С	C(=)
Provider error				0

12.1.3 Parameter use

Invoke id

See definition in clause 7.6.1.

MSISDN

See definition in clause 7.6.2.

SM-RP-PRI

See definition in clause 7.6.8.

Service Centre Address

See definition in clause 7.6.2.

SM-RP-MTI

See definition in clause 7.6.8. This parameter shall be present when the feature « SM filtering by the HPLMN » is supported by the SMS-GMSC and when the equivalent parameter is received from the short message service relay sublayer protocol.

SM-RP-SMEA

See definition in clause 7.6.8. This parameter shall be present when the feature « SM filtering by the HPLMN » is supported by the SMS-GMSC and when the equivalent parameter is received from the short message service relay sublayer protocol.

GPRS Support Indicator

See definition in clause 7.6.8. The presence of this parameter is mandatory if the SMS-GMSC supports receiving of the two numbers from the HLR.

IMSI

See definition in clause 7.6.2. The presence of this parameter is mandatory in a successful case.

Network Node Number

See definition in clause 7.6.2. This parameter is provided in a successful response.

LMSI

See definition in clause 7.6.2. It is an operator option to provide this parameter from the VLR; it is mandatory for the HLR to include the LMSI in a successful response, if the VLR has used the LMSI.

GPRS Node Indicator

See definition in clause 7.6.8. The presence of this parameter is mandatory if only the SGSN number is sent in the Network Node Number.

Additional Number

See definition in clause 7.6.2. This parameter is provided in a successful response.

User error

The following errors defined in clause 7.6.1 may be used, depending on the nature of the fault:

- Unknown subscriber:
- Call Barred:
- Teleservice Not Provisioned;
- Absent Subscriber_SM;
- Facility Not Supported;
- System failure;
- Unexpected Data Value;
- Data missing.

Provider error

For definition of provider errors see clause 7.6.1.

12.2 MAP-MO-FORWARD-SHORT-MESSAGE service

12.2.1 Definition

This service is used between the serving MSC or the SGSN and the SMS Interworking MSC to forward mobile originated short messages.

The MAP-MO-FORWARD-SHORT-MESSAGE service is a confirmed service using the service primitives given in table 12.2/1.

12.2.2 Service primitives

Table 12.2/1: MAP-MO-FORWARD-SHORT-MESSAGE

Parameter name	Request	Indication	Response	Confirm
Invoke Id	M	M(=)	M(=)	M(=)
SM RP DA	M	M(=)		
SM RP OA	M	M(=)		
SM RP UI	M	M(=)	С	C(=)
IMSI	С	C(=)		
User error			С	C(=)
Provider error				0

12.2.3 Parameter use

Invoke id

See definition in clause 7.6.1.

SM RP DA

See definition in clause 7.6.8.

In the mobile originated SM transfer this parameter contains the Service Centre address received from the mobile station.

SM RP OA

See definition in clause 7.6.8.

The MSISDN received from the VLR or from the SGSN is inserted in this parameter in the mobile originated SM transfer.

SM RP UI

See definition in clause 7.6.8. The short message transfer protocol data unit received from the Service Centre is inserted in this parameter.

IMSI

See definition in clause 7.6.2.1. The IMSI of the originating subscriber is inserted in this parameter in the mobile originated SM transfer.

This parameter shall be included if the sending entity, whether MSC or SGSN, supports mobile number portability.

User error

The following errors defined in clause 7.6.1 may be used, depending on the nature of the fault:

- Facility Not Supported;
- System Failure;

- SM Delivery Failure;
 - The reason of the SM Delivery Failure can be one of the following in the mobile originated SM:
 - unknown Service Centre address;
 - Service Centre congestion;
 - invalid Short Message Entity address;
 - subscriber not Service Centre subscriber;
 - protocol error.
- Unexpected Data Value

Provider error

For definition of provider errors see clause 7.6.1.

12.3 MAP-REPORT-SM-DELIVERY-STATUS service

12.3.1 Definition

This service is used between the gateway MSC and the HLR. The MAP-REPORT-SM-DELIVERY-STATUS service is used to set the Message Waiting Data into the HLR or to inform the HLR of successful SM transfer after polling. This service is invoked by the gateway MSC.

The MAP-REPORT-SM-DELIVERY-STATUS service is a confirmed service using the service primitives given in table 12.3/1.

12.3.2 Service primitives

Table 12.3/1: MAP-REPORT-SM-DELIVERY-STATUS

Parameter name	Request	Indication	Response	Confirm
Invoke Id	M	M(=)	M(=)	M(=)
MSISDN	M	M(=)		
Service Centre Address	M	M(=)		
SM Delivery Outcome	M	M(=)		
Absent Subscriber Diagnostic SM	С	C(=)		
GPRS Support Indicator	С	C(=)		
Delivery Outcome Indicator	С	C(=)		
Additional SM Delivery Outcome	С	C(=)		
Additional Absent Subscriber Diagnostic SM	С	C(=)		
MSIsdn-Alert			С	C(=)
User error			С	C(=)
Provider error				Ö

12.3.3 Parameter use

Invoke id

See definition in clause 7.6.1.

MSISDN

See definition in clause 7.6.2.

Service Centre Address

See definition in clause 7.6.2.

SM Delivery Outcome

See definition in clause 7.6.8. This parameter indicates the status of the mobile terminated SM delivery.

Absent Subscriber Diagnostic SM

See definition in clause 7.6.8.

GPRS Support Indicator

See definition in clause 7.6.8. The presence of this parameter is mandatory if the SMS-GMSC supports handling of two delivery outcomes.

Delivery Outcome Indicator

See definition in clause 7.6.8.

Additional SM Delivery Outcome

See definition in clause 7.6.8.

Additional Absent Subscriber Diagnostic SM

See definition in clause 7.6.8.

MSIsdn-Alert

See definition in clause 7.6.2. This parameter shall be present in case of unsuccessful delivery, when the MSISDN received in the operation is different from the stored MSIsdn-Alert; the stored MSIsdn-Alert is the value that is returned to the gateway MSC.

User error

The following errors defined in clause 7.6.1 may be used, depending on the nature of the fault:

- Unknown Subscriber;
- Message Waiting List Full;
- Unexpected Data Value;
- Data missing.

Provider error

For definition of provider errors see clause 7.6.1.

12.4 MAP-READY-FOR-SM service

12.4.1 Definition

This service is used between the MSC and VLR as well as between the VLR and the HLR. The MSC initiates this service if a subscriber indicates memory available situation. The VLR uses the service to indicate this to the HLR.

The VLR initiates this service if a subscriber, whose message waiting flag is active in the VLR, has radio contact in the MSC.

Also this service is used between the SGSN and the HLR. The SGSN initiates this service if a subscriber indicates memory available situation. The SGSN uses the service to indicate this to the HLR.

The SGSN initiates this service if a subscriber, whose message waiting flag is active in the SGSN, has radio contact in the GPRS.

The MAP-READY-FOR-SM service is a confirmed service using the primitives from table 12.4/1.

12.4.2 Service primitives

Table 12.4/1: MAP-READY-FOR-SM

Parameter name	Request	Indication	Response	Confirm
Invoke Id	M	M(=)	M(=)	M(=)
IMSI	С	C(=)		
TMSI	С	C(=)		
Alert Reason	М	M(=)		
Alert Reason Indicator	С	C(=)		
User error			С	C(=)
Provider error				0

12.4.3 Parameter use

Invoke id

See definition in clause 7.6.1.

IMSI

See definition in clause 7.6.2. The IMSI is used always between the VLR and the HLR and between the SGSN and the HLR. Between the MSC and the VLR the identification can be either IMSI or TMSI.

TMSI

See definition in clause 7.6.2. The identification can be either IMSI or TMSI between MSC and VLR.

Alert Reason

See definition in clause 7.6.8. This parameter indicates if the mobile subscriber is present or the MS has memory available.

Alert Reason Indicator

See definition in clause 7.6.8.

User error

The following errors defined in clause 7.6.1 may be used, depending on the nature of the fault:

- Unknown Subscriber;
- Facility Not Supported;
- System Failure;
- Unexpected Data Value;
- Data missing.

Provider error

For definition of provider errors see clause 7.6.1.

12.5 MAP-ALERT-SERVICE-CENTRE service

12.5.1 Definition

This service is used between the HLR and the interworking MSC. The HLR initiates this service, if the HLR detects that a subscriber, whose MSISDN is in the Message Waiting Data file, is active or the MS has memory available.

The MAP-ALERT-SERVICE-CENTRE service is a confirmed service using the primitives from table 12.5/1.

12.5.2 Service primitives

Table 12.5/1: MAP-ALERT-SERVICE-CENTRE

Parameter name	Request	Indication	Response	Confirm
Invoke Id	M	M(=)	M(=)	M(=)
MSIsdn-Alert	M	M(=)		
Service Centre Address	M	M(=)		
User error			С	C(=)
Provider error				0

12.5.3 Parameter use

Invoke id

See definition in clause 7.6.1.

MSIsdn-Alert

See definition in clause 7.6.2. The provided MSISDN shall be the one which is stored in the Message Waiting Data file.

Service Centre Address

See definition in clause 7.6.2.

User error

The following errors defined in clause 7.6.1 may be used, depending on the nature of the fault:

- System Failure;
- Unexpected Data Value;
- Data missing.

Provider error

For definition of provider errors see clause 7.6.1.

12.6 MAP-INFORM-SERVICE-CENTRE service

12.6.1 Definition

This service is used between the HLR and the gateway MSC to inform the Service Centre which MSISDN number is stored in the Message Waiting Data file. If the stored MSISDN number is not the same as the one received from the gateway MSC in the MAP-SEND-ROUTING-INFO-FOR-SM service primitive the stored MSISDN number is included in the message.

Additionally the status of MCEF, MNRF and MNRG flags and the inclusion of the particular Service Centre address in the Message Waiting Data list is informed to the gateway MSC when appropriate.

If the HLR has stored a single MNRR, the value is included in the Absent Subscriber Diagnostic SM parameter.

If the HLR has stored a second MNRR, the value of the MNRR for the MSC is included in the Absent Subscriber Diagnostic SM parameter and the value of the MNRR for the SGSN is included in the Additional Absent Subscriber Diagnostic SM parameter.

The MAP-INFORM-SERVICE-CENTRE service is a non-confirmed service using the primitives from table 12.6/1.

12.6.2 Service primitives

Table 12.6/1: MAP-INFORM-SERVICE-CENTRE

Parameter name	Request	Indication
Invoke Id	M	M(=)
MSIsdn-Alert	С	C(=)
MWD Status	С	C(=)
Absent Subscriber Diagnostic SM	С	C(=)
Additional Absent Subscriber Diagnostic SM	С	C(=)

12.6.3 Parameter use

Invoke id

See definition in clause 7.6.1.

MSIsdn-Alert

See definition in clause 7.6.2. This parameter refers to the MSISDN stored in a Message Waiting Data file in the HLR.

MWD Status

See definition in clause 7.6.8. This parameter indicates the status of the MCEF, MNRF and MNRG flags and the status of the particular SC address presence in the Message Waiting Data list.

Absent Subscriber Diagnostic SM

See definition in clause 7.6.8.

Additional Absent Subscriber Diagnostic SM

See definition in clause 7.6.8.

12.7 MAP-SEND-INFO-FOR-MT-SMS service

12.7.1 Definition

This service is used between the MSC and the VLR. The service is invoked by the MSC receiving a mobile terminated short message to request subscriber related information from the VLR.

The MAP-SEND-INFO-FOR-MT-SMS service is a confirmed service using the primitives from table 12.7/1.

12.7.2 Service primitives

Table 12.7/1: MAP-SEND-INFO-FOR-MT-SMS

Parameter name	Request	Indication	Response	Confirm
Invoke Id	M	M(=)	M(=)	M(=)
SM RP DA	М	M(=)		
IMSI	С	C(=)		
MSISDN			С	C(=)
User error			С	C(=)
Provider error				0

12.7.3 Parameter use

Invoke id

See definition in clause 7.6.1.

SM RP DA

See definition in clause 7.6.8. This parameter shall contain either an IMSI or an LMSI.

IMSI

See definition in clause 7.6.2. This parameter shall be present if the SM RP DA parameter contains an LMSI; otherwise it shall be absent.

MSISDN

See definition in clause 7.6.2.

User error

The following errors defined in clause 7.6.1 may be used, depending on the nature of the fault:

- Unknown subscriber;
- Unidentified Subscriber;
- Absent subscriber;
- Unexpected Data Value;
- Data Missing;
- Illegal subscriber;
- Illegal equipment;
- Subscriber busy for MT SMS;
- System Failure.

Provider error

For definition of provider errors see clause 7.6.1.

12.8 MAP-SEND-INFO-FOR-MO-SMS service

12.8.1 Definition

This service is used between the MSC and the VLR. The service is invoked by the MSC which has to handle a mobile originated short message request to request the subscriber related information from the VLR.

The MAP-SEND-INFO-FOR-MO-SMS service is a confirmed service using the primitives from table 12.8/1.

12.8.2 Service primitives

Table 12.8/1: MAP-SEND-INFO-FOR-MO-SMS

Parameter name	Request	Indication	Response	Confirm
Invoke Id	M	M(=)	M(=)	M(=)
Service Centre Address	M	M(=)		
MSISDN			С	C(=)
User error			С	C(=)
Provider error				Ö

12.8.3 Parameter use

Invoke id

See definition in clause 7.6.1.

Service Centre Address

See definition in clause 7.6.2.

MSISDN

See definition in clause 7.6.2.

User error

The following errors defined in clause 7.6.1 may be used, depending on the nature of the fault:

- Teleservice Not Provisioned:
- Call Barred;
- Unexpected Data Value;
- Data Missing.

Provider error

For definition of provider errors see clause 7.6.1.

12.9 MAP-MT-FORWARD-SHORT-MESSAGE service

12.9.1 Definition

This service is used between the gateway MSC and the servicing MSC or the SGSN to forward mobile terminated short messages.

The MAP-MT-FORWARD-SHORT-MESSAGE service is a confirmed service using the service primitives given in table 12.9/1.

12.9.2 Service primitives

Table 12.9/1: MAP-MT-FORWARD-SHORT-MESSAGE

Parameter name	Request	Indication	Response	Confirm
Invoke Id	M	M(=)	M(=)	M(=)
SM RP DA	M	M(=)		
SM RP OA	M	M(=)		
SM RP UI	M	M(=)	С	C(=)
More Messages To Send	С	C(=)		
User error			С	C(=)
Provider error				Ö

12.9.3 Parameter use

Invoke id

See definition in clause 7.6.1.

SM RP DA

See definition in clause 7.6.8. This parameter can contain either an IMSI or a LMSI. The use of the LMSI is an operator option. The LMSI can be provided if it is received from the HLR. The IMSI is used if the use of the LMSI is not available.

This parameter is omitted in the mobile terminated subsequent SM transfers.

SM RP OA

See definition in clause 7.6.8. The Service Centre address received from the originating Service Centre is inserted in this parameter.

This parameter is omitted in the mobile terminated subsequent SM transfers.

SM RP UI

See definition in clause 7.6.8. The short message transfer protocol data unit received from the Service Centre is inserted in this parameter. A short message transfer protocol data unit may also be inserted in this parameter in the message delivery acknowledgement from the MSC or from the SGSN to the Service Centre.

More Messages To Send

See definition in clause 7.6.8. The information from the MMS indication received from the Service Centre is inserted in this parameter.

User error

The following errors defined in clause 7.6.1 may be used, depending on the nature of the fault:

- Unidentified subscriber;
- Absent Subscriber SM;
- Subscriber busy for MT SMS;
- Facility Not Supported;
- Illegal Subscriber indicates that delivery of the mobile terminated short message failed because the mobile station failed authentication;
- Illegal equipment indicates that delivery of the mobile terminated short message failed because an IMEI check failed, i.e. the IMEI was blacklisted or not white-listed;
- System Failure;
- SM Delivery Failure:
 - The reason of the SM Delivery Failure can be one of the following in the mobile terminated SM:
 - memory capacity exceeded in the mobile equipment;
 - protocol error;
 - mobile equipment does not support the mobile terminated short message service.
- Unexpected Data Value;
- Data Missing.

Provider error

For definition of provider errors see clause 7.6.1.

13 Network-Requested PDP Context Activation services

13.1 MAP_SEND_ROUTING_INFO_FOR_GPRS service

13.1.1 Definition

This service is used by the GGSN to request GPRS routing information from the HLR.

13.1.2 Service primitives

Table 13.1/1: MAP_SEND_ROUTING_INFO_FOR_GPRS

Parameter name	Request	Indication	Response	Confirm
Invoke id	М	M(=)	M(=)	M(=)
IMSI	M	M(=)		
GGSN address	С	C(=)	С	C(=)
GGSN number	M	M(=)		
SGSN address			С	C(=)
Mobile Not Reachable Reason			С	C(=)
User error			С	C(=)
Provider error				0

13.1.3 Parameter definition and use

Invoke Id

See definition in clause 7.6.1.

IMSI

See definition in clause 7.6.2.

GGSN address

This parameter shall be present if the protocol-converting GSN is used between the GGSN and the HLR.

GGSN number

See definition in clause 7.6.2.

SGSN address

This parameter shall be present if the outcome of the Send Routing Info For GPRS request to the GPRS application process in the HLR is positive.

Mobile Not Reachable Reason

This parameter shall be present if the outcome of the Send Routing Info For GPRS request to the GPRS application process in the HLR is positive and the MNRG flag in the HLR is set. See definition in clause 7.6.3.51.

User error

This parameter is sent by the responder when an error is detected and if present, takes one of the following values:

- Absent Subscriber;
- System Failure;
- Data Missing;
- Unexpected Data Value;

- Unknown Subscriber.

The diagnostic in the Unknown Subscriber may indicate 'Imsi Unknown' or 'Gprs Subscription Unknown'.

- Call Barred;

This error will indicate that the received PDP PDUs in the GGSN shall be barred for this MS due to Operator Determined Barring. (The CallBarringCause must be the operatorBarring.)

Provider error

These are defined in clause 7.6.1.

13.2 MAP_FAILURE_REPORT service

13.2.1 Definition

This service is used by the GGSN to inform the HLR that network requested PDP-context activation has failed.

13.2.2 Service primitives

Table 13.2/1: MAP_FAILURE_REPORT

Parameter name	Request	Indication	Response	Confirm
Invoke id	M	M(=)	M(=)	M(=)
IMSI	M	M(=)		
GGSN address	С	C(=)	С	C(=)
GGSN number	М	M(=)		
User error			С	C(=)
Provider error				0

13.2.3 Parameter definition and use

Invoke Id

See definition in clause 7.6.1.

<u>IMSI</u>

See definition in clause 7.6.2.

GGSN address

This parameter shall be present if the protocol-converting GSN is used between the GGSN and the HLR.

GGSN number

See definition in clause 7.6.2.

User error

This parameter is sent by the responder when an error is detected and if present, takes one of the following values:

- System Failure;
- Data Missing;
- Unexpected Data Value;
- Unknown Subscriber.

Provider error

These are defined in clause 7.6.1.

13.3 MAP_NOTE_MS_PRESENT_FOR_GPRS service

13.3.1 Definition

This service is used by the HLR to inform the GGSN that the MS is present for GPRS again.

13.3.2 Service primitives

Table 13.3/1: MAP_NOTE_MS_PRESENT_FOR_GPRS

Parameter name	Request	Indication	Response	Confirm
Invoke id	M	M(=)	M(=)	M(=)
IMSI	M	M(=)		
GGSN address	С	C(=)		
SGSN address	M	M(=)		
User error			С	C(=)
Provider error				0

13.3.3 Parameter definition and use

Invoke Id

See definition in clause 7.6.1.

IMSI

See definition in clause 7.6.2.

GGSN address

This parameter shall be present if the protocol-converting GSN is used between the GGSN and the HLR.

SGSN address

See definition in clause 7.6.2.

User error

This parameter is sent by the responder when an error is detected and if present, takes one of the following values:

- System Failure;
- Data Missing;
- Unexpected Data Value;
- Unknown Subscriber.

Provider error

These are defined in clause 7.6.1.

13A Location Service Management Services

13A.1 MAP-SEND-ROUTING-INFO-FOR-LCS Service

13A.1.1 Definition

This service is used between the GMLC and the HLR to retrieve the routing information needed for routing a location service request to the servicing VMSC or SGSN. The MAP-SEND-ROUTING-INFO-FOR-LCS is a confirmed service using the primitives from table 13A.1/1.

13A.1.2 Service Primitives

Table 13A.1/1: MAP-SEND-ROUTING-INFO-FOR-LCS

Parameter name	Request	Indication	Response	Confirm
Invoke Id	М	M(=)	M(=)	M(=)
MLC Number	М	M(=)		
MSISDN	С	C(=)	С	C(=)
IMSI	С	C(=)	С	C(=)
LMSI			С	C(=)
Network Node Number			С	C(=)
GPRS Node Indicator			С	C(=)
Additional Number			С	C(=)
Supported LCS Capability			С	C(=)
Sets				
Additional LCS Capability			С	C(=)
Sets				
V-GMLC Address			U	C(=)
Additional V-GMLC Address			U	C(=)
H-GMLC Address			С	C(=)
PPR Address			U	C(=)
User error			С	C(=)
Provider error	·			0

13A.1.3 Parameter Use

Invoke id

See definition in clause 7.6.1.

MLC Number

See definition in clause 7.6.2.

MSISDN

See definition in clause 7.6.2. The request shall carry either the IMSI or MSISDN. The response shall carry whichever of these was not included in the request (see 3GPP TS 23.271 for details).

IMSI

See definition in clause 7.6.2.

LMSI

See definition in clause 7.6.2. It is an operator option to provide this parameter from the VLR; it is mandatory for the HLR to include the LMSI in a successful response, if the VLR has used the LMSI.

Network Node Number

See definition in clause 7.6.2. This parameter is provided in a successful response. If the Network Node Number and Additional Number are received in the GMLC, the Network Node Number is used in preference to the Additional Number.

GPRS Node Indicator

See definition in clause 7.6.8. The presence of this parameter is mandatory only if the SGSN number is sent in the Network Node Number.

Additional Number

See definition in clause 7.6.2. This parameter is provided in a successful response. If the Network Node Number and Additional Number are received in the GMLC, the Network Node Number is used in preference to the Additional Number.

Supported LCS Capability Sets

See definition in clause 7.6.11. This parameter indicates the LCS capability of the serving node that is indicated by the Network Node Number. This parameter is provided only if LCS capability sets are available in HLR and Network Node Number is present in this message.

Additional LCS Capability Sets

See definition in clause 7.6.11. This parameter indicates the LCS capability of the serving node that is indicated by the Additional Number. This parameter is provided only if LCS capability sets are available in HLR and Additional Number is present in this message.

V-GMLC address

See definition in clause 7.6.2. This parameter indicates the V-GMLC address of the serving node that is indicated by the Network Node Number.

Additional V-GMLC address

See definition in clause 7.6.2. This parameter indicates the V-GMLC address of the serving node that is indicated by the Additional Number. This parameter is provided only if additional LCS capability sets are available in HLR and Additional Number is present in this message.

H-GMLC address

See definition in clause 7.6.2. The requirements for its presence are specified in 3GPP TS 23.271 [26a].

PPR address

See definition in clause 7.6.2.

User error

The following errors defined in clause 7.6.1 may be used, depending on the nature of the fault:

- Unknown subscriber;
- Absent Subscriber;
- Facility Not Supported;
- System failure;
- Unexpected Data Value;
- Data missing;
- Unauthorised requesting network.

Provider error

For definition of provider errors see clause 7.6.1.

13A.2 MAP-PROVIDE-SUBSCRIBER-LOCATION Service

13A.2.1 Definition

This service is used by a GMLC to request the location of a target MS from the visited MSC or SGSN at any time. This is a confirmed service using the primitives from table 13A.2/1.

13A.2.2 Service Primitives

Table 13A.2/1: Provide_Subscriber_Location

Parameter name	Request	Indication	Response	Confirm
Invoke id	М	M(=)	M(=)	M(=)
Location Type	М	M(=)		
MLC Number	М	M(=)		
LCS Client ID	М	M(=)		
Privacy Override	U	C(=)		
IMSI	С	C(=)		
MSISDN	С	C(=)		
LMSI	С	C(=)		
LCS Priority	С	C(=)		
LCS QoS	С	C(=)		
IMEI	U	C(=)		
Supported GAD Shapes	С	C(=)		
LCS-Reference Number	С	C(=)		
LCS Codeword	С	C(=)		
LCS Service Type Id	С	C(=)		
LCS Privacy Check	С	C(=)		
Area Event Info	С	C(=)		
H-GMLC Address	С	C(=)		
Location Estimate			M	M(=)
GERAN Positioning Data			С	C(=)
UTRAN Positioning Data			С	C(=)
Age of Location Estimate			С	C(=)
Additional Location			С	C(=)
Estimate				
Deferred MT-LR			С	C(=)
Response Indicator				
Cell Id Or SAI			C	C(=)
Accuracy Fulfilment			С	C(=)
Indicator				
User error			С	C(=)
Provider error				0

13A.2.3 Parameter Definition and Use

All parameters are defined in clause 7.6. The use of these parameters and the requirements for their presence are specified in 3GPP TS 23.271 [26a].

Location Type

This parameter identifies the type of location information requested.

MLC Number

This is the E.164 number of the requesting GMLC.

LCS Client ID

This parameter provides information related to the identity of an LCS client.

Privacy Override

This parameter indicates if MS privacy is overridden by the LCS client when the GMLC and VMSC or SGSN for an MT-LR are in the same country.

IMSI

The IMSI is provided to identify the target MS. At least one of the IMSI or MSISDN is mandatory.

MSISDN

The MSISDN is provided to identify the target MS. At least one of the IMSI or MSISDN is mandatory.

LMSI

The LMSI shall be provided if previously supplied by the HLR. This parameter is only used in the case of the MT-LR for CS domain.

LCS Priority

This parameter indicates the priority of the location request.

LCS QoS

This parameter indicates the required quality of service in terms of response time and accuracy.

IMEI

The requirements for its presence are specified in 3GPP TS 23.271 [26a].

Supported GAD Shapes

This parameter indicates which of the shapes defined in 3GPP TS 23.032 [122] are supported.

LCS-Reference Number

This parameter shall be included if a deferred MT-LR procedure is performed for a UE available event or an area event.

LCS Codeword

See definition in clause 7.6.11.18. The requirements for its presence are specified in 3GPP TS 23.271 [26a].

LCS Service Type Id

See definition in clause 7.6.11.15. The requirements for its presence are specified in 3GPP TS 23.271 [26a].

LCS Privacy Check

See definition in clause 7.6.11. The requirements for its and its components presence are specified in 3GPP TS 23.271 [26a].

Area Event Info

See definition in clause 7.6.11. The parameter shall be included if a deferred MT-LR procedure is performed for an area event.

H-GMLC address

See definition in clause 7.6.2. The parameter shall be included if a deferred MT-LR procedure is performed for a UE available event or an area event.

Location Estimate

This parameter provides the location estimate if this is encoded in one of the supported geographical shapes. Otherwise this parameter shall consist of one octet, which shall be discarded by the receiving node.

GERAN Positioning Data

This parameter indicates the usage of each positioning method that was attempted to determine the location estimate either successfully or unsuccessfully. If Positioning Data received from the RAN contains no Positioning Methods, Positioning Data is excluded from the MAP message. It may be included in the message only if the access network is GERAN, see 3GPP TS 23.271 [26a].

UTRAN Positioning Data

This parameter indicates the usage of each positioning method that was successfully attempted to determine the location estimate. If Position Data received from the RAN contains no Positioning Methods, UTRAN Positioning Data is excluded from the MAP message. It may be included in the message only if the access network is UTRAN, see 3GPP TS 23.271 [26a].

Age of Location Estimate

This parameter indicates how long ago the location estimate was obtained.

Additional Location Estimate

This parameter provides the location estimate when not provided by the Location Estimate parameter. It may be sent only if the parameter Supported GAD Shapes has been received in the Provide Subscriber Location indication and the shape to be included is supported by the GMLC.

Deferred MT-LR Response Indicator

See definition in clause 7.6.11.2.

Cell Id Or SAI

For GERAN access, this parameter indicates Global Cell Identifier of the cell that the served subscriber is currently attached to. For UTRAN access, this parameter contains the Service Area Identifier for the cell that the subscriber is currently attached to. This parameter is included only for North American Emergency Calls as described in 3GPP TS 23.271 [26a].

Accuracy Fulfilment Indicator

See definition in clause 7.6.11.27.

User error

This parameter is sent by the responder when the location request has failed or cannot proceed and if present, takes one of the following values defined in clause 7.6.1.

- System Failure;
- Data Missing;
- Unexpected Data Value;
- Facility Not Supported;
- Unidentified Subscriber;
- Illegal Subscriber;
- Illegal Equipment;
- Absent Subscriber (diagnostic information may also be provided);
- Unauthorised requesting network;
- Unauthorised LCS Client with detailed reason;
- Position method failure with detailed reason.

Provider error

These are defined in clause 7.6.1.

13A.3 MAP-SUBSCRIBER-LOCATION-REPORT Service

13A.3.1 Definition

This service is used by a VMSC or SGSN to provide the location of a target MS to a GMLC when a request for location is either implicitly administered or made at some earlier time. This is a confirmed service using the primitives from table 13A.3/1.

13A.3.2 Service Primitives

Table 13A.3/1: Subscriber_Location_Report

Parameter name	Request	Indication	Response	Confirm
Invoke id	М	M(=)	M(=)	M(=)
LCS Event	М	M(=)		
LCS Client ID	M	M(=)		
Network Node Number	М	M(=)		
IMSI	С	C(=)		
MSISDN	С	C(=)		
NA-ESRD	С	C(=)	С	C(=)
NA-ESRK	С	C(=)	С	C(=)
IMEI	U	C(=)		
Location Estimate	С	C(=)		
GERAN Positioning Data	С	C(=)		
UTRAN Positioning Data	С	C(=)		
Age of Location Estimate	С	C(=)		
LMSI	U	C(=)		
GPRS Node Indicator	С	C(=)		
Additional Location Estimate	С	C(=)		
Deferred MT-LR Data	С	C(=)		
LCS-Reference Number	С	C(=)		
NA-ESRK Request	С	C(=)		
Cell Id Or SAI	С	C(=)		
H-GMLC Address	С	C(=)		
LCS Service Type Id	С	C(=)		
Pseudonym Indicator	С	C(=)		
Accuracy Fulfilment	С	C(=)		
Indicator				
User error			С	C(=)
Provider error				0

13A.3.3 Parameter Definition and Use

All parameters are defined in clause 7.6. The use of these parameters and the requirements for their presence are specified in. 3GPP TS 23.271 [26a].

LCS Event

This parameter indicates the event that triggered the Subscriber Location Report.

LCS Client ID

This parameter provides information related to the identity of the recipient LCS client.

Network Node Number

See definition in clause 7.6.2. This parameter provides the address of the sending node.

IMSI

The IMSI shall be provided if available to the VMSC or SGSN.

MSISDN

The MSISDN shall be provided if available to the VMSC or SGSN.

NA-ESRD

If the target MS has originated an emergency service call in North America, the NA-ESRD shall be provided by the VMSC if available.

If the target MS has originated an emergency service call in North America and NA-ESRK Request is included in Subscriber_Location_Report-Arg, an NA-ESRK or NA-ESRD, but not both, may also be included in the response to the MSC, see 3GPP TS 23.271 [26a].

NA-ESRK

If the target MS has originated an emergency service call in North America, the NA-ESRK shall be provided by the VMSC if assigned.

If the target MS has originated an emergency service call in North America and NA-ESRK Request is included in Subscriber_Location_Report-Arg, an NA-ESRK or NA-ESRD, but not both, may also be included in the response to the MSC, see 3GPP TS 23.271 [26a].

IMEI

The requirements for its presence are specified in 3GPP TS 23.271 [26a].

Location Estimate

This parameter provides the location estimate. The absence of this parameter implies that a location estimate was not available or could not be successfully obtained. If the obtained location estimate is not encoded in one of the supported geographical shapes then this parameter shall consist of one octet, which shall be discarded by the receiving node.

GERAN Positioning Data

This parameter indicates the usage of each positioning method that was attempted to determine the location estimate either successfully or unsuccessfully. If Positioning Data received from the RAN contains no Positioning Methods, Positioning Data is excluded from the MAP message. It may be included in the message only if the access network is GERAN, see 3GPP TS 23.271 [26a].

UTRAN Positioning Data

This parameter indicates the usage of each positioning method that was successfullyattempted to determine the location estimate. If Position Data received from the RAN contains no Positioning Methods, UTRAN Positioning Data is excluded from the MAP message. It may be included in the message only if the access network is UTRAN, see 3GPP TS 23.271 [26a].

Age of Location Estimate

This parameter indicates how long ago the location estimate was obtained.

LMSI

The LMSI may be provided if assigned by the VLR.

GPRS Node Indicator

See definition in clause 7.6.8. This presence of this parameter is mandatory only if the SGSN number is sent in the Network Node Number.

Additional Location Estimate

This parameter provides the location estimate when not provided by the Location Estimate parameter..

Deferred MT-LR Data

See definition in clause 7.6.11.3.

LCS-Reference Number

This parameter shall be included if the Subscriber Location Report is the response to a deferred MT location request.

NA-ESRK Request

If the target MS has originated an emergency service call in North America, NA-ESRK Request may be included to indicate that the MSC is able to accept NA-ESRK in the Response message, see section 7.6.11.19.

Cell Id Or SAI

For GERAN access, this parameter indicates Global Cell Identifier of the cell that the served subscriber is currently attached to. For UTRAN access, this parameter contains the Service Area Identifier for the cell that the subscriber is currently attached to. This parameter is included only for North American Emergency Calls as described in 3GPP TS 23.271 [26a].

H-GMLC address

See definition in clause 7.6.2. The parameter shall be included if the Subscriber Location Report is the response to a deferred MT location request for a UE available event or an area event.

LCS Service Type Id

See definition in clause 7.6.11.15. The requirements for its presence are specified in 3GPP TS 23.271 [26a].

Pseudonym Indicator

This parameter indicates by its presence that the pseudonym is required. Refer to 3GPP TS 23.271 [26a].

Accuracy Fulfilment Indicator

For a mobile terminated periodic LDR, this parameter indicates whether the obtained location estimate satisfies the requested accuracy or not, provided that this indication is obtained from RAN or the UE with the location estimate.

User error

This parameter is sent by the responder when the received message contains an error, cannot be forwarded or stored for an LCS client or cannot be accepted for some other reason and if present, takes one of the following values defined in clause 7.6.1.

- System Failure;
- Data Missing;
- Unexpected Data Value;
- Resource Limitation;
- Unknown Subscriber;
- Unauthorised requesting network;
- Unknown or unreachable LCS Client.

Provider error

These are defined in clause 7.6.1.

- 13A.4 Void
- 13A.4.1 Void
- 13A.4.2 Void
- 13A.4.3 Void
- 13A.5 Void
- 13A.5.1 Void
- 13A.5.2 Void
- 13A.5.3 Void
- 13A.6 Void
- 13A.6.1 Void
- 13A.6.2 Void
- 13A.6.3 Void
- 13A.7 Void
- 13A.7.1 Void
- 13A.7.2 Void
- 13A.7.3 Void
- 13A.8 Void
- 13A.8.1 Void
- 13A.8.2 Void
- 13A.8.3 Void
- 13A.9 Void
- 13A.9.1 Void

13A.9.2 Void

13A.9.3 Void

14 General

14.1 Overview

Clauses 14 to 17 specify the protocol elements to be used to provide the MAP services described in clause 7.

Clause 15 specifies the elements of procedures for the MAP protocol. Clause 16 specifies the mapping onto TC service primitives. Clause 17 specifies the application contexts, operation packages and abstract syntaxes for the MAP protocol as well as the encoding rules to be applied.

14.2 Underlying services

The MAP protocol relies on the services provided by the Transaction Capabilities (TC) of Signalling System Number No. 7, as referenced in clause 6.

14.3 Model

The MAP Protocol Machine (MAP PM) can be modelled as a collection of service state machines (SSMs) - one per MAP specific service invoked - coordinated by a MAP dialogue control function with its one state machine: MAP dialogue state machine (DSM). There are two types of Service State Machines: Requesting Service State Machines (RSM) and Performing Service State Machines (PSM).

A new invocation of a MAP PM is employed on the receipt of a MAP-OPEN request primitive or a TC-BEGIN indication primitive. Each invocation controls exactly one MAP dialogue. For each MAP specific service invoked during a dialogue, a MAP RSM is created at the requestor's side and a MAP PSM is created at the performer's side.

This modelling is used only to facilitate understanding and the MAP behaviour descriptions and is not intended to suggest any implementation. SDL descriptions are organised according to this model.

How the MAP-service-user and the MAP refer to a MAP dialogue (i.e. a MAP PM invocation) is a local implementation matter.

How TC dialogue identifiers are assigned to a MAP PM invocation is also a local implementation matter.

14.4 Conventions

The behaviour of the MAP PM depends on the application-context-name associated with the dialogue. One major difference is that the MAP requests the transfer of the application-context-name by TC only for those contexts which do not belong to the so-called "version one context set".

The "version one context set" is a set of application-contexts which model the behaviour of a MAP V1 implementation according to the latest phase 1 version of GSM 09.02. This set is defined in clause 15.

The procedures described in clause 15 are used when the application-context-name does not refer to a dialogue between an MSC and its VLR. When the application-context-name refers to a dialogue between an MSC and its VLR the MAP PM procedures are a local implementation matter.

15 Elements of procedure

15.1 Handling of unknown operations

Unknown operations (i.e. a standard operation introduced in a later version of the MAP specification, or a private operation) can be introduced into MAP in a backwards compatible way. This means that the receiver of an unknown operation shall, if the dialogue state allows it, send a TC-REJECT component to the sender of the operation indicating 'unrecognised operation' and continue with the processing of further components or messages exchanged within the dialogue as if the unknown operation had not been received.

The standardised structure of a MAP dialogue shall not be affected by the invocation of unknown operations, i.e. if a dialogue uses only a TC-BEGIN message which is acknowledged by a TC-END message, a TC-CONTINUE message shall not be used to invoke an unknown operation. However the standardised structure of a MAP dialogue may be affected by the rejection of unknown operations, i.e. if a dialogue uses only a TC-BEGIN message which is acknowledged by a TC-END message, a TC-CONTINUE message followed by a TC-END message may be used to carry the rejection of an unknown operation and the response to the standardised operation. The entity which initiated a dialogue whose standardised structure is a TC-BEGIN message which is acknowledged by a TC-END message shall not send any messages in that dialogue after the TC-BEGIN. Note that if the dialogue structure is affected as described in this paragraph the TC-CONTINUE shall include the dialogue portion required to confirm the acceptance of the dialogue.

Unknown operations may be invoked in the following types of message (there is no restriction as to how many unknown operations can be invoked in a message):

- TC-BEGIN: the component to invoke the unknown operation shall follow the component of the standard operation which is included in this message.
- TC-CONTINUE: the component to invoke the unknown operation may be transported as the only component in a stand-alone message or may be grouped with existing operations. In the latter case a specific sequencing of components is not required.
- TC-END: if the component to invoke the unknown operation is grouped with an existing operation a specific sequencing of components is not required

The TC-REJECT component may be sent in the following messages:

- TC-CONTINUE or TC-END: either as the only component of the message or grouped with an existing component. The choice is up to the MAP-Service User.

If the received message contains only unknown operations the MAP-Service User shall send the TC-REJECT components in a TC-CONTINUE message to the peer entity, if the dialogue state allows it.

If the received message contains unknown operations and standard operations and the standardised structure of the dialogue requires the response to the standard operation to be sent within a TC-END message, then the MAP-Service User may send the response to the standard operations and the TC-REJECT components for the unknown operations in a TC-CONTINUE message followed by a TC-END message. Neither a specific distribution of the components to the TC messages nor a specific sequencing of components is required.

Note that the SDL diagrams of clauses 19 - 25 do not show the report to the MAP-Service User about the reception of the unknown operation. This has been done for simplicity of description; the MAP PM may inform the MAP-Service User.

The sender of the unknown operation shall ensure that there is enough room in the used message for the unknown operation.

15.2 Dialogue establishment

The establishment of a MAP dialogue involves two MAP-service-users: the dialogue-initiator and the dialogue-responder.

This procedure is driven by the following signals:

- a MAP-OPEN request primitive from the dialogue-initiator;
- a TC-BEGIN indication primitive occurring at the responding side;
- a MAP-OPEN response primitive from the dialogue-responder;
- the first TC-CONTINUE indication primitive occurring at the initiating side;

and under specific conditions:

- a TC-END indication primitive occurring at the initiating side;
- a TC-U-ABORT indication primitive occurring at the initiating side;
- a TC-P-ABORT indication primitive occurring at the initiating side.

One instance of the MAP dialogue state machine runs at the initiating side, and one at the responding side.

15.2.1 Behaviour at the initiating side

The behaviour of the MAP dialogue state machine at the initiating side is defined in sheets 1 - 8 of the process MAP_DSM (figure 15.6/3).

Sheet 3: When the MAP dialogue state machine at the initiating side is waiting for a response from the responding side, a TC-END indication which echoes the AC name which was sent in the TC-BEGIN indicates acceptance of the dialogue.

Sheet 3: If the dialogue opening is accepted, any components included in the TC-END are processed and passed to the MAP-Service User. The dialogue is closed by sending a MAP-CLOSE to the MAP-Service User.

Sheet 3, sheet 4, sheet 5, sheet 6, sheet 7, sheet 8: when a dialogue is terminated, the MAP dialogue state machine terminates all instances of the Requesting_MAP_SSM which are active for this dialogue.

Sheet 4: A TC-P-ABORT with an abort parameter Incorrect_Transaction_Portion indicates that the responding side does not support a MAP version higher than 1. This triggers a MAP-OPEN confirm indicating that the dialogue is refused, with a refuse reason potential version incompatibility. The MAP-Service User may then decide to retry the dialogue at MAP version 1.

Sheet 8: When the MAP dialogue state machine at the initiating side is waiting for a response from the responding side, a TC-CONTINUE indication which echoes the AC name which was sent in the TC-BEGIN indicates acceptance of the dialogue.

Sheet 8: If the dialogue opening is accepted, any components included in the TC-CONTINUE are processed and passed to the MAP-Service User. The dialogue has then reached the established state.

15.2.2 Behaviour at the responding side

The behaviour of the MAP dialogue state machine at the responding side is defined in sheets 9 - 14 of the process MAP_DSM (figure 15.6/3).

Sheet 9: If no application context information is included in the TC-BEGIN indication, this implies a MAP version 1 dialogue. An explicit application context indicating version 1 is treated as abnormal behaviour.

Sheet 11: The v1 application context name which corresponds to a v1 operation is derived using the information in table 15.2/1.

Table 15.2/1: Mapping of V1 operation codes on to application-context-names

Operation	Application-context-name (note 1)
updateLocation	networkLocUpContext-v1
cancelLocation	locationCancellationContext-v1
provideRoamingNumber	roamingNumberEnquiryContext-v1
insertSubscriberData	subscriberDataMngtContext-v1
deleteSubscriberData	subscriberDataMngtContext-v1
sendParameters	infoRetrievalContext-v1
	networkLocUpContext-v1 (note 2)
beginSubscriberActivity	networkFunctionalSsContext-v1
sendRoutingInfo	locationInfoRetrievalContext-v1
performHandover	handoverControlContext-v1
reset	resetContext-v1
activateTraceMode	tracingContext-v1
deactivateTraceMode	tracingContext-v1
sendRoutingInfoForSM	shortMsgGatewayContext-v1
forwardSM	shortMsgRelayContext-v1
reportSM-deliveryStatus	shortMsgGatewayContext-v1
noteSubscriberPresent	mwdMngtContext-v1
alertServiceCentreWithoutResult	shortMsgAlertContext-v1
checkIMEI	EquipmentMngtContext-v1

NOTE 1: These symbolic names refer to the object identifier value defined in clause 17 and allocated to each application-context used for the MAP.

NOTE 2: The choice between the application contexts is based on the parameters received in the operation.

Sheet 12: If the dialogue is accepted, each component present in the TC-BEGIN is forwarded to an instance of a Performing MAP SSM, by executing the procedure Process Components.

Sheet 13: If the MAP dialogue state machine receives a MAP-OPEN response with a result accepted, it waits for any MAP specific service request or response primitives or a MAP-DELIMITER request.

Sheet 13, sheet 14: When a dialogue is terminated, the MAP dialogue state machine terminates all instances of the Requesting_MAP_SSM or Performing_MAP_SSM which are active for this dialogue.

Sheet 14: A MAP-DELIMITER request triggers a TC-CONTINUE request to accept the dialogue. The dialogue has then reached the established state.

15.3 Dialogue continuation

Once established the dialogue is said to be in a continuation phase. The behaviour of the MAP dialogue state machine in this phase is defined in sheets 15 - 17 of the process MAP_DSM (figure 15.6/3).

Both MAP users can request the transfer of MAP APDUs until one of them requests the termination of the dialogue.

Normal closure of an established dialogue is shown on sheet 16; abnormal termination is shown on sheet 17.

15.4 Load control

If an entity which should respond to a MAP dialogue opening request is overloaded, it uses the AC of the request to determine whether to discard the request.

The priority level allocated to each application-context is described in clause 5, tables 5.1/1, 5.1/2 and 5.1/3.

15.5 Procedures for MAP specific services

This clause describes the MAP procedures for MAP specific services. These procedures are driven by the following types of event:

- a MAP specific request or a MAP specific response primitive;

- a component handling primitive from TC.

A Service State Machine is activated when of one of the following signals is received:

- a MAP request primitive, which activates a requesting SSM;
- a TC-INVOKE indication primitive without a linked identifier, which activates a performing SSM.

For component handling primitives there are two types of event:

- events which activate a Service State Machine or which can be related to an existing one;
- events which cannot be related to a Service State Machine.

15.5.1 Service invocation

The behaviour of the requesting SSM which handles a service is defined by the SDL for the process Requesting_MAP_SSM. The requesting SSM receives a MAP service request from the MAP-Service User via the MAP dialogue state machine and sends a TC-INVOKE request to TCAP. When a confirm is received from TCAP via the MAP dialogue state machine, the requesting SSM forwards a MAP service confirm to the MAP-Service User.

The response to a MAP service invocation may come in the form of a linked request. If the linked request corresponds to a class 4 operation, this is handled by the requesting SSM. If the linked request corresponds to a class 1, 2 or 3 operation, the MAP dialogue state machine sends a notification to the requesting SSM and creates an instance of a performing SSM to handle the linked request. The test "Linked_Operation_Allowed" on sheet 3 of the process Requesting_MAP_SSM takes the (TRUE) exit if the definition of the parent operation includes the received linked operation as a permitted linked operation; otherwise the test takes the (FALSE) exit.

The mapping of MAP specific services on to remote operations is given in table 16.2/1.

15.5.2 void

15.5.3 Service invocation receipt

The behaviour of the performing SSM which handles a service is defined by the SDL for the process Performing_MAP_SSM. The performing SSM receives a TC-INVOKE component from TCAP via the MAP dialogue state machine and sends a MAP service indication to the MAP-Service User. When a MAP service response is received from the MAP-Service User via the MAP dialogue state machine, the performing SSM forwards a TC-RESULT or TC-U-ERROR component to TCAP.

15.5.4 void

15.5.5 Handling of components received from TC

The procedure Process_Components shows the handling of components received in a TC-BEGIN, TC-CONTINUE or TC-END message.

Sheet 2: If a linked invoke component corresponds to a class 4 operation, the MAP dialogue state machine sends it to the requesting SSM instance identified by the linked invoke ID. If a linked invoke component corresponds to any other class of operation, the MAP dialogue state machine sends a notification to the requesting SSM instance identified by the linked invoke ID, creates an instance of a performing SSM and sends the invoke component to it.

15.6 SDL descriptions

The following SDL specification describes a system which includes three blocks: MAP-user, MAP-provider and TC.

Such a system resides in each network component supporting MAP and communicates with its peers via the lower layers of the signalling network which are part of the environment.

Only the MAP-provider is fully described in this clause. The various types of processes which form the MAP-User block and the TC block are described respectively in clauses 18 to 25 of the present document and in CCITT Recommendation Q.774.

The MAP-Provider block communicates with the MAP_USER via two channels U1 and U2. Via U1 the MAP-provider receives the MAP request and response primitives. Via U2 it sends the MAP indication and confirm primitives.

The MAP-Provider block communicates with TC via two channels P1 and P2. Via P1 the MAP-Provider sends all the TC request primitives. Via P2 it receives all the TC indication primitives.

The MAP-Provider block is composed of the four following types of process:

- a) MAP_DSM: This type of process handles a dialogue for transport of MAP messages. There exists one process instance per MAP dialogue.
- b) Load_Ctrl: This type of process is in charge of load control. There is only one instance of this process in each system.
- c) Requesting_MAP_SSM: This type of process handles a MAP service requested during a dialogue. An instance of this process is created by the instance of the Secure_MAP_DSM process for each requested MAP service.
- d) Performing_MAP_SSM: This type of process handles a MAP service performed during a dialogue. An instance of this process is created by the instance of the Secure_MAP_DSM process for each MAP service to be performed.

A process MAP_DSM exchanges external signals with other blocks as well as internal signals with the other processes of the MAP-Provider block. The external signals are either MAP service primitives or TC service primitives.

The signal routes used by the various processes are organised as follows:

- a) A process MAP_DSM receives and sends events from/to the MAP_user via signal route User1/User2. These routes use channels U1 and U2 respectively.
- b) A process MAP_DSM receives and sends events from/to the TCAP via signal route TC1/TC2. These routes use channels P1 and P2 respectively.
- c) A process MAP_DSM receives and sends events from/to the LOAD_CTRL process via signal route Load1/Load2. These routes are internal.
- d) A process MAP_DSM sends events to the Performing_MAP_SSM processes via signal route Intern1. This route is internal.
- e) A process MAP_DSM sends events to the Requesting_MAP_SSM processes via signal route Intern2. This route is internal.
- f) A process Performing_MAP_SSM sends events to the MAP_USER via signal route User3. This route uses channel U2.
- g) A process Performing_MAP_SSM sends events to the TCAP via signal route TC3. This route uses channel P1.
- h) A process Requesting_MAP_SSM sends events to the MAP_USER via signal route User4. This route uses channel U2.
- i) A process Requesting_MAP_SSM sends events to the TCAP via signal route TC4. This route uses channel P1.




Figure 15.6/1: System MAP_Stack




Figure 15.6/2: Block MAP_Provider




Figure 15.6/3a: Process MAP_DSM (sheet 1)




Figure 15.6/3b: Process MAP_DSM (sheet 2)




Figure 15.6/3c: Process MAP_DSM (sheet 3)




Figure 15.6/3d: Process MAP_DSM (sheet 4)




Figure 15.6/3e: Process MAP_DSM (sheet 5)




Figure 15.6/3f: Process MAP_DSM (sheet 6)




Figure 15.6/3g: Process MAP_DSM (sheet 7)




Figure 15.6/3h: Process MAP_DSM (sheet 8)




Figure 15.6/3i: Process MAP_DSM (sheet 9)




Figure 15.6/3j: Process MAP_DSM (sheet 10)




Figure 15.6/3k: Process MAP_DSM (sheet 11)




Figure 15.6/3I: Process MAP_DSM (sheet 12)




Figure 15.6/3m: Process MAP_DSM (sheet 13)




Figure 15.6/3n: Process MAP_DSM (sheet 14)




Figure 15.6/30: Process MAP_DSM (sheet 15)




Figure 15.6/3p: Process MAP_DSM (sheet 16)




Figure 15.6/3q: Process MAP_DSM (sheet 17)




Figure 15.6/4a: Procedure Process_Components (sheet 1)




Figure 15.6/4b: Procedure Process_Components (sheet 2)




Figure 15.6/4c: Procedure Process_Components (sheet 3)




Figure 15.6/4d: Procedure Process_Components (sheet 4)




Figure 15.6/4e: Procedure Process_Components (sheet 5)




Figure 15.6/5: Process Load_Ctrl




Figure 15.6/6a: Process Requesting_MAP_SSM (sheet 1)




Figure 15.6/6b: Process Requesting_MAP_SSM (sheet 2)




Figure 15.6/6c: Process Requesting_MAP_SSM (sheet 3)




Figure 15.6/6d: Process Requesting_MAP_SSM (sheet 4)




Figure 15.6/8a: Process Performing_MAP_SSM (sheet 1)




Figure 15.6/8b: Process Performing_MAP_SSM (sheet 2)

16 Mapping on to TC services

16.1 Dialogue control

Dialogue control services are mapped to TC dialogue handling services. The TC-UNI service is not used by the MAP PM

16.1.1 Directly mapped parameters

The following parameters of the MAP-OPEN request and indication primitives are directly mapped on to the corresponding parameters of the TC-BEGIN primitives:

- destination address;
- originating address.

16.1.2 Use of other parameters of dialogue handling primitives

16.1.2.1 Dialogue Id

The value of this parameter is associated with the MAP PM invocation in an implementation dependent manner.

16.1.2.2 Application-context-name

The application-context-name parameter of a MAP primitive is mapped to the application-context-name parameter of TC dialogue handling primitives according to the rules described in clause 15.1.

16.1.2.3 User information

The user information parameter of TC dialogue primitives is used to carry the MAP dialogue APDUs.

16.1.2.4 Component present

This parameter is used by the MAP PM as described in CCITT Recommendation Q.771. It is not visible to the MAP user.

16.1.2.5 Termination

The value of this parameter of the TC-END request primitive is set by the MAP PM on the basis of the release method parameter of the MAP-CLOSE request primitive, except when the dialogue state machine is in the state DIALOGUE INITIATED, in which case the Termination parameter shall always indicate "pre-arranged end".

16.1.2.6 P-Abort-Cause

Values of the P-abort-cause parameter are mapped to the values of the provider-reason parameter of the MAP-P-ABORT indication primitive according to table 16.1/1, except in the dialogue initiated phase for the "incorrectTransactionPortion" and "noCommonDialoguePortion" values which are mapped to the "potential incompatibility problem" value of the refuse-reason parameter of the MAP-OPEN cnf primitive. The source parameter in the MAP-P-ABORT ind takes the value "TC problem".

16.1.2.7 Quality of service

The quality of service of TC request primitives is set by the MAP as shown below.

- Return option: "Return message on error" or "Discard message on error" as required by the network operator;

- Sequence control: "Sequence guaranteed" or "Sequence result not guaranteed" as required by the network operator;
- "Sequence guaranteed" shall be used when a segmented result is to be transferred (e.g. subscriber data in response to SendParameters). It may also be appropriate to use Sequence guaranteed when a series of InsertSubscriberData, ProcessAccessSignalling or ForwardAccessSignalling operations is used.

It is essential that the TC message which indicates acceptance of a dialogue opening request is received by the dialogue initiator before any subsequent message in that dialogue; otherwise the dialogue opening will fail. The dialogue responder shall ensure that this requirement is met by:

- Sending the dialogue acceptance message in a TC-END, if the dialogue structure requires it; or
- Using "Sequence guaranteed", if the dialogue acceptance message is sent in a TC-CONTINUE; or
- Waiting until the dialogue acceptance message has been acknowledged by the dialogue initiator before sending a subsequent message, if the dialogue acceptance message is sent in a TC-CONTINUE.

Table 16.1/1: Mapping of P-Abort cause in TC-P-ABORT indication on to provider-reason in MAP-P-ABORT indication

TC P-Abort cause	MAP provider-reason	
unrecognised message type	provider malfunction	
unrecognised transaction Id	supporting dialogue released	
badlyFormattedTransactionPortion	provider malfunction	
incorrectTransactionPortion	provider malfunction (note)	
resourceLimitation	resource limitation	
abnormalDialogue	provider malfunction	
noCommonDialoguePortion	version incompatibility	
NOTE: Or version incompatibility in the dialogue initiated phase.		

16.2 Service specific procedures

Specific services are mapped to TC component handling services.

16.2.1 Directly mapped parameters

The Invoke Id parameter of the MAP request and indication primitive is directly mapped on to the Invoke Id parameter of the component handling primitives.

16.2.2 Use of other parameters of component handling primitives

16.2.2.1 Dialogue Id

The value of this parameter is associated with the MAP PM invocation in an implementation dependent manner.

16.2.2.2 Class

The value of this parameter is set by the MAP PM according to the type of the operation to be invoked.

16.2.2.3 Linked Id

When a service response is mapped to a class 4 operation, the value of this parameter is set by the MAP PM and corresponds to the value assigned by the user to the initial service request (i.e. the value of the invoke ID parameter of the request primitive). Otherwise if such a parameter is included in MAP request/indication primitives it is directly mapped to the linked ID parameter of the associated TC-INVOKE request/indication primitives.

16.2.2.4 Operation

When mapping a request primitive on to a Remote Operations PDU (invoke), the MAP PM shall set the operation code according to the mapping described in table 16.2/1.

When mapping a response primitive on to a Remote Operations service, the MAP PM shall set the operation code of the TC-RESULT-L/NL primitive (if required) to the same value as the one received at invocation time.

Table 16.2/1: Mapping of MAP specific services on to MAP operations

MAP-SERVICE	operation
MAP-ACTIVATE-SS	activateSS
MAP-ACTIVATE-TRACE-MODE	activateGG
MAP-ALERT-SERVICE-CENTRE	alertServiceCentre
MAP-ANY-TIME-INTERROGATION	anyTimeInterrogaton
MAP_AUTHENTICATION_FAILURE_REPORT	authenticationFailureReport
MAP-ANY-TIME-MODIFICATION	anyTimeModification
MAP-ANY-TIME-SUBSCRIPTION-INTERROGATION	anyTimeSubscriptionInterrogation
MAP-CANCEL-LOCATION MAP-CANCEL-LOCATION	cancelLocation
MAP-CHECK-IMEI	checkIMEI
MAP-DEACTIVATE-SS	
MAP-DEACTIVATE-SS MAP-DEACTIVATE-TRACE-MODE	deactivateSS deactivateTraceMode
MAP-DELETE-SUBSCRIBER-DATA	deleteSubscriberData
MAP-ERASE-CC-ENTRY	eraseCC-Entry
MAP-ERASE-SS	eraseSS
MAP-FAILURE-REPORT	failureReport
MAP-FORWARD-ACCESS-SIGNALLING	forwardAccessSignalling
MAP-FORWARD-CHECK-SS-INDICATION	forwardCheckSsIndication
MAP-FORWARD-GROUP-CALL-SIGNALLING	forwardGroupCallSignalling
MAP-MT-FORWARD-SHORT-MESSAGE	mt-forwardSM
MAP-MO-FORWARD-SHORT-MESSAGE	mo-forwardSM
MAP-GET-PASSWORD	getPassword
MAP-INFORM-SERVICE-CENTRE	informServiceCentre
MAP-INSERT-SUBSCRIBER-DATA	insertSubscriberData
MAP-INTERROGATE-SS	interrogateSs
MAP-IST-ALERT	istAlert
MAP-IST-COMMAND	istCommand
MAP-NOTE-MS-PRESENT-FOR-GPRS	noteMsPresentForGprs
MAP-NOTE-SUBSCRIBER-DATA-MODIFIED	noteSubscriberDataModified
MAP-PREPARE-GROUP-CALL	prepareGroupCall
MAP-PREPARE-HANDOVER	prepareHandover
MAP-PREPARE-SUBSEQUENT-HANDOVER	prepareSubsequentHandover
MAP-PROCESS-ACCESS-SIGNALLING	processAccessSignalling
MAP-PROCESS-GROUP-CALL-SIGNALLING	processGroupCallSignalling
MAP-PROCESS-UNSTRUCTURED-SS-REQUEST	processUnstructuredSS-Request
MAP-PROVIDE-ROAMING-NUMBER	provideRoamingNumber
MAP-PROVIDE-SUBSCRIBER-LOCATION	provideSubscriberLocation
MAP-PROVIDE-SUBSCRIBER-INFO	provideSubscriberInfo
MAP-PURGE-MS	purgeMS
MAP-READY-FOR-SM	readyForSM
MAP-REGISTER-CC-ENTRY	registerCC-Entry
MAP-REGISTER-PASSWORD	registerPassword
MAP-REGISTER-SS	registerSS
MAP-REMOTE-USER-FREE	remoteUserFree
MAP-REPORT-SM-DELIVERY-STATUS	reportSmDeliveryStatus
MAP-RESET	reset
MAP-RESTORE-DATA	restoreData
MAP-SEND GROUP-CALL END SIGNAL	sendGroupCallEndSignal
MAP-SEND-END-SIGNAL	sendendSignal
MAP-SEND-AUTHENTICATION-INFO	sendEndSignal sendAuthenticationInfo
MAP-SEND-IMSI	
	sendIMSI
MAP-SEND-IDENTIFICATION	sendIdentification
MAP-SEND-ROUTING-INFO-FOR-SM	sendRoutingInfoForSM
MAP-SEND-ROUTING-INFO-FOR-GPRS	sendRoutingInfoForGprs

MAP-SEND-ROUTING-INFO-FOR-LCS	sendRoutingInfoForLCS
MAP-SEND-ROUTING-INFORMATION	sendRoutingInfo
MAP-SET-REPORTING-STATE	setReportingState
MAP-STATUS-REPORT	statusReport
MAP-SUBSCRIBER-LOCATION-REPORT	subscriberLocationReport
MAP-SUPPLEMENTARY-SERVICE-INVOCATION-NOTIFICATION	ss-Invocation-Notification
MAP-UNSTRUCTURED-SS-NOTIFY	unstructuredSS-Notify
MAP-UNSTRUCTURED-SS-REQUEST	unstructuredSS-Request
MAP-UPDATE-GPRS-LOCATION	updateGprsLocation
MAP-UPDATE-LOCATION	updateLocation
MAP-NOTE-MM-EVENT	NoteMM-Event

16.2.2.5 Error

The error parameter in a TC-U-ERROR indication primitive is mapped to the user error parameter in the MAP confirm primitive of the service associated with the operation to which the error is attached.

The user error parameter in MAP response primitives is mapped to the error parameter of the TC-U-ERROR request primitive, except for "initiating-release" and "resource-limitation" which are mapped to the problem code parameter of the TC-U-REJECT request primitive.

16.2.2.6 Parameters

The parameters of MAP specific request and indication primitives are mapped to the argument parameter of TC-INVOKE primitives.

The parameters of MAP specific response and confirm primitives are mapped to the result parameter of TC-RESULT-L primitives, the parameter of TC-U-ERROR primitives or the argument of TC-INVOKE primitives when mapping on linked class 4 operations is used.

16.2.2.7 Time out

The value of this parameter is set by the MAP PM according to the type of operation invoked.

16.2.2.8 Last component

This parameter is used by the MAP PM as described in CCITT Recommendation Q.711. It is not visible from the MAP user.

16.2.2.9 Problem code

16.2.2.9.1 Mapping to MAP User Error

The following values of the user error parameter are mapped as follows to values of the TC problem code parameter. These values are generated by the MAP user. This mapping is valid from the TC-U-REJECT indication primitive to the MAP confirm service primitive and from the MAP response service primitive to the TC-U-REJECT request primitive.

Table 16.2/2: Mapping of MAP User Error parameter on to TC problem code in TC-U-REJECT primitives

MAP User Error	TC problem code
resource limitation	resource limitation
initiating release	initiating release

16.2.2.9.2 Mapping to MAP Provider Error parameter

The following values of the TC problem code parameter of the TC-U-REJECT indication primitive are mapped as follows to values of the MAP Provider Error parameter of the MAP confirm primitive.

Table 16.2/3: Mapping of TC problem code in TC-U-REJECT on to MAP Provider Error parameter

TC problem code	MAP Provider Error
duplicated invoke Id	duplicated invoke id
unrecognised operation	service not supported
mistyped parameter	mistyped parameter

The following values of the problem code parameters of the TC-L-REJECT primitive are mapped to values of the provider error parameter of the MAP confirm primitive as follows.

Table 16.2/4: Mapping of TC problem code in TC-L-REJECT on to MAP Provider Error parameter

TC problem code	MAP Provider Error
return result unexpected	unexpected response from the peer
return error unexpected	unexpected response from the peer

16.2.2.9.3 Mapping to diagnostic parameter

The following values of the problem code parameter of the TC-R-REJECT and TC-U-REJECT primitive are mapped to values of the diagnostic parameter of the MAP-NOTICE indication primitive as follows:

Table 16.2/5: Mapping of TC problem code of TC-R-REJECT and TC-U-REJECT on to diagnostic parameter

TC problem code	MAP diagnostic
General problem	- abnormal event detected by the peer
Invoke problem	
- unrecognised linked ID	- abnormal event detected by the peer
- linked response unexpected	- response rejected by the peer
- unexpected linked operation	- response rejected by the peer
Return result problem	
- unrecognised invoke ID	- response rejected by the peer
- return result unexpected	- response rejected by the peer
- mistyped parameter	- response rejected by the peer
Return error problem	
- unrecognised invoke ID	- response rejected by the peer
- return error unexpected	- response rejected by the peer
- unrecognised error	- response rejected by the peer
- unexpected error	- response rejected by the peer
- mistyped parameter	- response rejected by the peer

The following values of the problem code parameter of the TC-L-REJECT primitive are mapped to values of the diagnostic parameter of the MAP-NOTICE indication primitive as follows.

Table 16.2/6: Mapping of TC problem code of TC-L-REJECT on to diagnostic parameter

TC problem code	MAP diagnostic
General problems	- abnormal event received from the peer
Invoke problem	
- unrecognised linked ID	- abnormal event received from the peer
Return result problem	
- unrecognised invoke ID	- abnormal event received from the peer
Return error problem	
- unrecognised invoke ID	- abnormal event received from the peer

17 Abstract syntax of the MAP protocol

17.1 General

This clause specifies the Abstract Syntaxes for the Mobile Application Part as well as the associated set of Operations and Errors, using the Abstract Syntax Notation One (ASN.1), defined in ITU-T Recommendations X.680 and X.681 with additions as defined in clause 17.1.4 on Compatibility Considerations and the OPERATION and ERROR external information object classes, defined in ITU-T Recommendation X.880.

The Abstract Syntax is defined for all interfaces specified in clause 4.4 except for the A- and B-interfaces.

The Mobile Application Part protocol is defined by two Abstract Syntaxes:

 one Abstract Syntax which encompass all Operations and Errors identified by the various MAP subsystem numbers.

This Abstract Syntax represents the set of values each of which is a value of the ASN.1 type TCAPMessages. TCMessage as defined in ITU-T Recommendation Q.773 with the component relationconstraint sections resolved by the operation and error codes included in the ASN.1 modules MAP-*Operations and MAP-Errors. However, only the subset of this abstract syntax which is required by the procedures defined for an entity needs to be supported.

- one Abstract Syntax identified by the OBJECT IDENTIFIER value MAP-DialogueInformation.map-DialogueAS.

This Abstract Syntax represents the set of values each of which is a value of the ASN.1 type MAP-DialogueInformation.MAP-DialoguePDU. Such a value of the ASN.1 single-ASN.1-type element is contained within the user-information element of the TCAPMessages.DialoguePortion ASN.1 type. This Abstract Syntax name is to be used as a direct reference.

17.1.1 Encoding rules

The encoding rules which are applicable to the defined Abstract Syntaxes are the Basic Encoding Rules for Abstract Syntax Notation One, defined in ITU-T Recommendation X.690 with the same exceptions as in ITU-T Recommendation Q.773, clause 4 Message Representation.

When the definite form is used for length encoding, a data value of length less than 128 octets must have the length encoded in the short form.

When the long form is employed to code a length, the minimum number of octets shall be used to code the length field.

OCTET STRING values and BIT STRING values must be encoded in a primitive form.

There is no restriction to the use of empty constructors (e.g. an empty SEQUENCE type). That is, the encoding of the content of any data value shall consist of zero, one or more octets.

17.1.2 Use of TC

The mapping of OPERATION and ERROR to TC components is defined in ETS 300 287 (version 2) which is based on ITU-T Recommendation Q.773.

NOTE 1: The class of an operation is not stated explicitly but is specified as well in the ASN.1 operation definition.

Class 1: RESULT and ERROR appear in ASN.1 operation definition.

Class 2: only ERROR appears in ASN.1 operation definition.

Class 3: only RESULT appears in ASN.1 operation definition.

Class 4: both RESULT and ERROR do not appear in ASN.1 operation definition.

The field "ARGUMENT", "PARAMETER" or "RESULT" (for information objects of class OPERATION and ERROR) is always optional from a syntactic point of view. However, except when specifically mentioned with the

ASN.1 comment "-- optional", the "parameter" part of a component has to be considered as mandatory from a semantic point of view.

When an optional element is missing in an invoke component or in an inner data structure while it is required by the context, an error component is returned if specified in the information object associated with the operation; the associated type of error is "DataMissing". This holds also when the entire parameter of an invoke component is missing while it is required by the context.

NOTE 2: When a mandatory element is missing in the parameter or inner data structure of any component, a reject component is returned (if the dialogue still exists). The problem code to be used is "Mistyped parameter".

The Timer Values used in the operation definitions are indicated as ASN.1 comments. The Timer Value Ranges are:

```
s = from 3 seconds to 10 seconds;
```

m = from 15 seconds to 30 seconds;

ml = from 1 minute to 10 minutes;

1 = from 28 hours to 38 hours.

17.1.2.1 Use of Global Operation and Error codes defined outside MAP

An entity supporting an application context greater than 2 shall be capable of receiving an operation or error code, within an application context defined in GSM 29.002, encoded as either an Object Identifier (as defined in ITU-T Recommendation X.690) or an integer value (as defined in clause 17.5). Related restrictions regarding the use of Object Identifiers are as follows:

- The length of the Object Identifier shall not exceed 16 octets and the number of components of the Object Identifier shall not exceed 16.
- Object Identifiers shall be used only for operations or errors defined outside of GSM 29.002.
- Global error codes may be sent only in response to a global operation. If a standard operation is received then a global error code shall not be sent in response.

Handling of an unknown operation codes by the receiving entity is defined in clause 15.1.1.

17.1.3 Use of information elements defined outside MAP

An information element or a set of information elements (messages) transparently carried in the Mobile Application Part but defined in other recommendations/technical specifications are handled in one of the following ways:

- i) The contents of each information element (without the octets encoding the identifier and the length in the recommendation/technical specification where it is defined unless explicitly stated otherwise) is carried as the value of an ASN.1 type derived from the OCTET STRING data type. Additionally, the internal structure may be explained by means of comments. In case of misalignment the referred to recommendation/technical specification takes precedence.
- ii) The complete information element (including the octets encoding the identifier and the length in the recommendation/technical specification where it is defined) or set of information elements and the identity of the associated protocol are carried as the value of the ExternalSignalInfo data type defined in the present document. Where more than one information element is carried, the information elements are sent contiguously with no filler octets between them.

17.1.4 Compatibility considerations

The following ASN.1 modules conform to ITU-T Recommendation X.680 and X.681. An extension marker ("...") is used wherever future protocol extensions are foreseen.

The "..." construct applies only to SEQUENCE and ENUMERATED data types. An entity supporting a version greater than 1 shall not reject an unsupported extension following "..." of that SEQUENCE or ENUMERATED data type. The

Encoding Rules from clause 17.1.1 apply to every element of the whole Transfer Syntax especially to the ASN.1 type EXTERNAL.

The extension container "privateExtensionList" is defined in this specification in order to carry extensions which are defined outside this specification. Private extensions can be defined by, for example, network operators, manufacturers, and regional standardisation bodies.

Private extensions shall:

1) if included in operations of an AC of V2, follow the extension marker and be tagged using PRIVATE tags up to and including 29.

NOTE: This type of extension is in most cases used only within a PLMN.

2) if included in operations of an AC of V3 or higher: be included only in the Private Extension Container that is defined in the specification.

NOTE: This type of extension can be used between PLMNs.

Private extensions shall not be included in v2 supplementary service operations.

Private extensions shall not be included within user error for RegisterCCEntry and EraseCCEntry operations.

PCS extensions shall be included in the PCS Extension Container that is defined in this specification.

In order to improve extensibility, a few error parameters have been defined as a CHOICE between the version 2 description and a SEQUENCE including the version 2 description and an extension container. Operations used in a v2-application-context must consider only the first alternative while operations used in a vn-application-context (n>2) must consider only the second alternative.

17.1.5 Structure of the Abstract Syntax of MAP

For each MAP parameter which has to be transferred by a MAP Protocol Data Unit (MAP message), there is a PDU field (an ASN.1 type) which has the same name as the corresponding parameter, except for the differences required by the ASN.1 notation (blanks between words are removed or replaced by hyphen, the first letter of the first word is capital and the first letter of each of the following words ise capitalised, e.g. "no reply condition time" is mapped to "NoReplyConditionTime"). Additionally some words may be abbreviated as follows:

```
bs basic service
ch call handling
      closed user group
cug
ho handover
ic incoming call
id identity
info
      information
mm
      mobility management
lcs location services
ms mobile service
oc outgoing call
om operation & maintenance
pw Password
sm short message service
ss supplementary service
```

The MAP protocol is composed of several ASN.1 modules dealing with either operations, errors, data types, and, if applicable, split into those dealing with mobile services, call handling services, supplementary services and short message services. For operations and errors the code values are given as parameters, in order to allow use of the defined information objects also by other protocols (e.g. 3GPP TS 24.080 [38]). The ASN.1 source lines are preceded by line-numbers at the left margin in order to enable the usage of the cross-reference in annex A.

The module containing the definition of the operation packages for MAP is:

1. MAP-OperationPackages.

The module containing the definition of the application contexts for MAP is:

2. MAP-ApplicationContexts.

The module containing the data types for the Abstract Syntax to be used for TCAPMessages. DialoguePortion for MAP is:

3. MAP-DialogueInformation.

The module containing the supported operations is:

4. MAP-Protocol.

The modules containing all operation definitions for MAP are:

- 5. MAP-MobileServiceOperations;
- 6. MAP-OperationAndMaintenanceOperations;
- 7. MAP-CallHandlingOperations;
- 8. MAP-SupplementaryServiceOperations;
- 9. MAP-ShortMessageServiceOperations;
- 10. MAP-Group-Call-Operations;
- 11. MAP-LocationServiceOperations.

The module containing all error definitions for MAP is:

12. MAP-Errors.

Modules containing all data type definitions for MAP are:

- 13. MAP-MS-DataTypes;
- 14. MAP-OM-DataTypes;
- 15. MAP-CH-DataTypes;
- 16. MAP-SS-DataTypes;
- 17. MAP-SS-Code:
- 18. MAP-SM-DataTypes;
- 19. MAP-ER-DataTypes;
- 20. MAP-CommonDataTypes;
- 21. MAP-TS-Code:
- 22. MAP-BS-Code;
- 23. MAP-ExtensionDataTypes;
- 24. MAP-GR-DataTypes;

25. MAP-LCS-DataTypes.

References are made also to modules defined outside of the present document. They are defined in the technical specification Mobile Services Domain, technical specification Transaction Capability and ITU-T Recommendation X.880 respectively:

MobileDomainDefinitions;

TCAPMessages, DialoguePDUs;

Remote-Operations-Information-Objects.

17.1.6 Application Contexts

The following informative table lists the latest versions of the Application Contexts used in this specification, with the operations used by them and, where applicable, whether or not the operation description is exactly the same as for previous versions. Information in 17.6 & 17.7 relates only to the ACs in this table.

AC Name	AC Version	Operations Used	Comments
IocationCancellationContext	v3	cancelLocation	
equipmentMngtContext	V3	checkIMEI	
imsiRetrievalContext	v2	sendIMSI	
infoRetrievalContext	v3	sendAuthenticationInfo	
interVIrInfoRetrievalContext	v3	sendIdentification	
handoverControlContext	v3	prepareHandover forwardAccessSignalling sendEndSignal processAccessSignalling prepareSubsequentHandover	the syntax of this operation has been extended in comparison with release 98 version
mwdMngtContext	v3	readyForSM	
msPurgingContext	v3	purgeMS	
shortMsgAlertContext	v2	alertServiceCentre	
resetContext	v2	reset	
networkUnstructuredSsContext	V2	processUnstructuredSS-Request unstructuredSS-Request unstructuredSS-Notify	
tracingContext	v3	activateTraceMode deactivateTraceMode	
networkFunctionalSsContext	v2	registerSS eraseSS activateSS deactivateSS registerPassword interrogateSS getPassword	
shortMsgMO-RelayContext	v3	mo-forwardSM	
shortMsgMT-RelayContext	v3	mt-forwardSM	
shortMsgGatewayContext	v3	sendRoutingInfoForSM reportSM-DeliveryStatus InformServiceCentre	the syntax of this operation has been extended in comparison with release 96 version
networkLocUpContext	v3	updateLocation forwardCheckSs-Indication restoreData insertSubscriberData activateTraceMode	the syntax is the same in v1 & v2
gprsLocationUpdateContext	v3	updateGprsLocation insertSubscriberData activateTraceMode	
subscriberDataMngtContext	v3	insertSubscriberData deleteSubscriberData	

AC Name	AC Version	Operations Used	Comments
roamingNumberEnquiryContext	v3	provideRoamingNumber	
locationInfoRetrievalContext	v3	sendRoutingInfo	
gprsNotifyContext	v3	noteMsPresentForGprs	
gprsLocationInfoRetrievalContext	v4	sendRoutingInfoForGprs	
failureReportContext	v3	failureReport	
callControlTransferContext	v4	resumeCallHandling	
subscriberInfoEnquiryContext	v3	provideSubscriberInfo	
anyTimeEnquiryContext	v3	anyTimeInterrogation	
anyTimeInfoHandlingContext	v3	anyTimeSubscriptionInterrogation anyTimeModification	
ss-InvocationNotificationContext	v3	ss-InvocationNotification	
groupCallControlContext	v3	prepareGroupCall processGroupCallSignalling forwardGroupCallSignalling sendGroupCallEndSignal	
reportingContext	v3	setReportingState statusReport remoteUserFree	
callCompletionContext	v3	registerCC-Entry eraseCC-Entry	
istAlertingContext	v3	istAlert	
ServiceTerminationContext	v3	istCommand	
IocationSvcEnquiryContext	v3	provideSubscriberLocation subscriberLocationReport	
IocationSvcGatewayContext	v3	sendRoutingInfoForLCS	
mm-EventReportingContext	v3	noteMM-Event	
subscriberDataModificationNotificati onContext	v3	noteSubscriberDataModified	
authenticationFailureReportContext	v3	authenticationFailureReport	
resourceManagementContext	v3	releaseResources	

NOTE (*): The syntax of the operations is not the same as in previous versions unless explicitly stated

17.2 Operation packages

17.2.1 General aspects

This clause describes the operation-packages which are used to build the application-contexts defined in clause 17.3.

Each operation-package is a specification of the roles of a pair of communicating objects (i.e. a pair of MAP-Providers), in terms of operations which they can invoke of each other.

The grouping of operations into one or several packages does not necessarily imply any grouping in terms of Application Service Elements.

The following ASN.1 information object class is used to describe operation-packages in this clause:

```
OPERATION-PACKAGE ::= CLASS {
              OPERATION
                                          OPTIONAL.
     &Both
     &Consumer OPERATION
                                          OPTIONAL,
     &Supplier OPERATION
                                          OPTIONAL,
     &id
              OBJECT IDENTIFIER
                                          UNIQUE OPTIONAL }
WITH SYNTAX {
     [ OPERATIONS
                        &Both 1
     [ CONSUMER INVOKES &Supplier ]
     [ SUPPLIER INVOKES &Consumer ]
                        &id ]
```

Since the application-context definitions provided in clause 17.3 use only an informal description technique, only the type notation is used in the following clauses to define operation-packages.

The following definitions are used throughout this clause (n>=2):

- v1-only operation: An operation which shall be used only in v1 application-contexts;
- vn-only operation: An operation which shall be used only in vn application-contexts;
- v(n-1)-operation: An operation whose specification has not been modified since the MAP v(n-1) specifications or if the modifications are considered as not affecting v(n-1) implementations;
- v(n-1)-equivalent operation: The version of an operation which excludes all the information elements and errors which have been added since the MAP v(n-1) specification;
- vn-only package: An operation package which contains only vn-only operations;
- v(n-1)-package: An operation package which contains only v(n-1)- operations.

The names of vn-packages are suffixed by "-vn" where n>=2.

For each operation package which is not vn-only (n>=2) and which does not include only v(n-1)-operations, there is a v(n-1)-equivalent package. Except when a definition is explicitly provided in the following clauses, the v(n-1)-equivalent package includes the v(n-1)-equivalent operations of the operations which belong to this package.

17.2.2 Packages specifications

17.2.2.1 Location updating

This operation package includes the operations required for location management procedures between HLR and VLR.

The v1-equivalent and v2-equivalent packages can be determined according to the rules described in clause 17.2.1.

17.2.2.2 Location cancellation

This operation package includes the operations required for location cancellation and MS purging procedures between HLR and VLR and between HLR and SGSN.

```
locationCancellationPackage-v3     OPERATION-PACKAGE ::= {
          -- Supplier is VLR or SGSN if Consumer is HLR
          CONSUMER INVOKES {
                cancelLocation}     }
```

The v1-equivalent and v2-equivalent packages can be determined according to the rules described in clause 17.2.1.

17.2.2.3 Roaming number enquiry

This operation package includes the operations required for roaming number enquiry procedures between HLR and VLR.

```
roamingNumberEnquiryPackage-v3 OPERATION-PACKAGE ::= {
    -- Supplier is VLR if Consumer is HLR
    CONSUMER INVOKES {
        provideRoamingNumber} }
```

The v1-equivalent and v2-equivalent packages can be determined according to the rules described in clause 17.2.1.

17.2.2.4 Information retrieval

This operation package includes the operation required for the authentication information retrieval procedure between HLR and VLR and between HLR and SGSN.

```
infoRetrievalPackage-v3     OPERATION-PACKAGE ::= {
         -- Supplier is HLR if Consumer is VLR
         -- Supplier is HLR if Consumer is SGSN
         CONSUMER INVOKES {
            sendAuthenticationInfo} }
```

The v2-equivalent package is defined as follows:

```
infoRetrievalPackage-v2     OPERATION-PACKAGE ::= {
         -- Supplier is HLR if Consumer is VLR
         -- Supplier is HLR if Consumer is SGSN
         CONSUMER INVOKES {
            sendAuthenticationInfo} }
```

The v1-equivalent package is defined as follows:

```
infoRetrievalPackage-v1    OPERATION-PACKAGE ::= {
      -- Supplier is HLR or VLR if Consumer is VLR
      -- Supplier is HLR if Consumer is SGSN
      CONSUMER INVOKES {
            sendParameters} }
```

17.2.2.5 Inter-VLR information retrieval

This operation package includes the operations required for inter VLR information retrieval procedures.

```
interVlrInfoRetrievalPackage-v3     OPERATION-PACKAGE ::= {
          -- Supplier is VLR if Consumer is VLR
          CONSUMER INVOKES {
                sendIdentification}     }
```

The v2-equivalent package is defined as follows:

```
interVlrInfoRetrievalPackage-v2 OPERATION-PACKAGE ::= {
    -- Supplier is VLR if Consumer is VLR
    CONSUMER INVOKES {
        sendIdentification} }
```

The v1-equivalent package is : infoRetrievalPackage-v1.

17.2.2.6 IMSI retrieval

This operation package includes the operation required for the IMSI retrieval procedure between HLR and VLR.

```
imsiRetrievalPackage-v2     OPERATION-PACKAGE ::= {
         -- Supplier is HLR if Consumer is VLR
          CONSUMER INVOKES {
                sendIMSI}     }
```

This package is v2 only.

17.2.2.7 Call control transfer

This operation package includes the operation required for the call control transfer procedure between VMSC and GMSC.

```
callControlTransferPackage-v4   OPERATION-PACKAGE ::= {
    -- Supplier is GMSC if Consumer is VMSC
    CONSUMER INVOKES {
        resumeCallHandling} }
```

The v3-equivalent package can be determined according to the rules described in clause 17.2.1.

17.2.2.8 void

17.2.2.9 Void

17.2.2.10 Interrogation

This operation package includes the operations required for interrogation procedures between MSC and HLR or NPLR or between HLR and gsmSCF.

```
interrogationPackage-v3     OPERATION-PACKAGE ::= {
         -- Supplier is HLR or NPLR if Consumer is MSC
         -- Supplier is HLR if Consumer is gsmSCF
         CONSUMER INVOKES {
            sendRoutingInfo} }
```

The v1-equivalent and v2-equivalent packages can be determined according to the rules described in clause 17.2.1.

17.2.2.11 Void

17.2.2.12 Handover Control

This operation package includes the operations required for handover procedures between MSCs.

```
handoverControlPackage-v3 OPERATION-PACKAGE ::= {
    -- Supplier is MSCB if Consumer is MSCA
    CONSUMER INVOKES {
        prepareHandover |
        forwardAccessSignalling}
    SUPPLIER INVOKES {
        sendEndSignal |
        processAccessSignalling |
        prepareSubsequentHandover} }
```

The v2-equivalent package can be determined according to the rules described in clause 17.2.1.

The v1-equivalent package is defined as follows.

```
handoverControlPackage-v1 OPERATION-PACKAGE ::= {
    -- Supplier is MSCB if Consumer is MSCA
    CONSUMER INVOKES {
        performHandover |
        forwardAccessSignalling |
        traceSubscriberActivity}
    SUPPLIER INVOKES {
        sendEndSignal |
        noteInternalHandover |
        processAccessSignalling |
        performSubsequentHandover} }
```

17.2.2.13 Subscriber Data management stand alone

This operation package includes the operations required for stand alone subscriber data management procedures between HLR and VLR or between HLR and SGSN.

The v1-equivalent and v2-equivalent packages can be determined according to the rules described in clause 17.2.1.

17.2.2.14 Equipment management

This operation package includes the operations required for equipment management procedures between EIR and MSC or between EIR and SGSN.

```
equipmentMngtPackage-v3     OPERATION-PACKAGE ::= {
         -- Supplier is EIR if Consumer is MSC
         -- Supplier is EIR if Consumer is SGSN
         CONSUMER INVOKES {
               checkIMEI} }
```

The v1-equivalent and v2-equivalent packages can be determined according to the rules described in clause 17.2.1.

17.2.2.15 Subscriber data management

This operation package includes the operations required for subscriber data management procedures between HLR and VLR or between HLR and SGSN.

The v1-equivalent and v2-equivalent packages can be determined according to the rules described in clause 17.2.1.

17.2.2.16 Location register restart

This operation package includes the operations required for location register restart procedures between HLR and VLR or between HLR and SGSN.

```
resetPackage-v2     OPERATION-PACKAGE ::= {
          -- Supplier is VLR or SGSN if Consumer is HLR
          CONSUMER INVOKES {
          reset} }
```

The v1-equivalent package can be determined according to the rules described in clause 17.2.1.

17.2.2.17 Tracing stand-alone

This operation package includes the operations required for stand alone tracing procedures between HLR and VLR or between HLR and SGSN.

The v1-equivalent and v2-equivalent packages can be determined according to the rules described in clause 17.2.1.

17.2.2.18 Functional SS handling

This operation package includes the operations required for functional supplementary services procedures between VLR and HLR.

The v1-equivalent package can be determined according to the rules described in clause 17.2.1.

17.2.2.19 Tracing

This operation package includes the operations required for tracing procedures between HLR and VLR or between HLR and SGSN.

The v1-equivalent and v2-equivalent packages can be determined according to the rules described in clause 17.2.1.

17.2.2.20 Binding

This operation package includes the operation required to initialise a supplementary service procedure between VLR and HLR or between gsmSCF and HLR.

```
bindingPackage-v1      OPERATION-PACKAGE ::= {
            -- Supplier is HLR if Consumer is VLR
            -- Supplier is gsmSCF if Consumer is HLR
            CONSUMER INVOKES {
                beginSubscriberActivity} }
```

This package is v1 only.

17.2.2.21 Unstructured SS handling

This operation package includes the operations required for unstructured supplementary services procedures between VLR and HLR, between the HLR and the gsmSCF, and between HLR and HLR.

The v1-equivalent package is defined as follows:

```
unstructuredSsPackage-v1 OPERATION-PACKAGE ::= {
    -- Supplier is HLR if Consumer is VLR
    -- Supplier is gsmSCF if Consumer is HLR
    CONSUMER INVOKES {
        processUnstructuredSS-Data} }
```

17.2.2.22 MO Short message relay services

This operation package includes the operations required for short message relay service procedures between IWMSC and VMSC or between GMSC and MSC or between SGSN and IWMSC.

```
The v2-equivalent package is defined as follows:

shortMsgRelayPackage-v2 OPERATION-PACKAGE ::= {

-- Supplier is IWMSC if Consumer is MSC

-- Supplier is MSC or SGSN if Consumer is GMSC

-- Supplier is IWMSC if Consumer is SGSN

CONSUMER INVOKES {

forwardSM} }
```

The v1-equivalent package can be determined according to the rules described in clause 17.2.1.

17.2.2.23 Short message gateway services

This operation package includes the operations required for short message service gateway procedures between MSC and HLR.

The v2-equivalent package can be determined according to the rules described in clause 17.2.1.

The v1-equivalent package is defined as follows:

17.2.2.24 MT Short message relay services

This operation package includes the operations required for short message relay service procedures between GMSC and MSC or between GMSC and SGSN.

The v2-equivalent package is: shortMsgRelayPackage-v2

17.2.2.25 Void

17.2.2.26 Message waiting data management

This operation package includes the operations required for short message waiting data procedures between HLR and VLR, between HLR and SGSN.

```
mwdMngtPackage-v3      OPERATION-PACKAGE ::= {
            -- Supplier is HLR if Consumer is SGSN
            -- Supplier is HLR if Consumer is VLR
            CONSUMER INVOKES {
                readyForSM}      }
```

The v2-equivalent package can be determined according to the rules described in clause 17.2.1.

The v1-equivalent package is defined as follows:

17.2.2.27 Alerting

This operation package includes the operations required for alerting between HLR and IWMSC.

```
alertingPackage-v2 OPERATION-PACKAGE ::= {
    -- Supplier is IWMSC if Consumer is HLR
    CONSUMER INVOKES {
        alertServiceCentre} }
```

The v1-equivalent package is defined as follows.

```
alertingPackage -v1 OPERATION-PACKAGE ::= {
    -- Supplier is IWMSC if Consumer is HLR
    CONSUMER INVOKES {
        alertServiceCentreWithoutResult} }
```

17.2.2.28 Data restoration

This operation package includes the operations required for VLR data restoration between HLR and VLR.

```
dataRestorationPackage-v3    OPERATION-PACKAGE ::= {
     -- Supplier is HLR if Consumer is VLR
     CONSUMER INVOKES {
        restoreData} }
```

The v2-equivalent package can be determined according to the rules described in clause 17.2.1.

The v1-equivalent package is: infoRetrievalPackage-v1

17.2.2.29 Purging

This operation package includes the operations required for purging between HLR and VLR or between HLR and SGSN.

```
purgingPackage-v3      OPERATION-PACKAGE ::= {
            -- Supplier is HLR if Consumer is VLR
            -- Supplier is HLR if Consumer is SGSN
            CONSUMER INVOKES {
                purgeMS}      }
```

The v2-equivalent package can be determined according to the rules described in clause 17.2.1.

17.2.2.30 Subscriber information enquiry

This operation package includes the operations required for subscriber information enquiry procedures between HLR and VLR or between HLR and SGSN.

```
subscriberInformationEnquiryPackage-v3     OPERATION-PACKAGE ::= {
          -- Supplier is VLR or SGSN if Consumer is HLR
          CONSUMER INVOKES {
                provideSubscriberInfo} }
```

This package is v3 only.

17.2.2.31 Any time information enquiry

This operation package includes the operations required for any time information enquiry procedures between gsmSCF and HLR or between gsmSCF and GMLC or between gsmSCF and NPLR.

This package is v3 only.

17.2.2.32 Group Call Control

This operation package includes the operations required for group call and broadcast call procedures between MSCs.

This package is v3 only.

17.2.2.33 Void

17.2.2.34 Void

17.2.2.35 Gprs location updating

This operation package includes the operations required for the gprs location management procedures between HLR and SGSN.

```
gprsLocationUpdatingPackage-v3 OPERATION-PACKAGE ::= {
    -- Supplier is HLR if Consumer is SGSN
    CONSUMER INVOKES {
        updateGprsLocation} }
```

This package is v3 only.

17.2.2.36 Gprs Interrogation

This operation package includes the operations required for interrogation procedures between HLR and GGSN.

```
gprsInterrogationPackage-v4    OPERATION-PACKAGE ::= {
     -- Supplier is HLR if Consumer is GGSN
     CONSUMER INVOKES {
        sendRoutingInfoForGprs} }
```

The v3-equivalent package is defined as follows.

```
gprsInterrogationPackage-v3     OPERATION-PACKAGE ::= {
          -- Supplier is HLR if Consumer is GGSN
          CONSUMER INVOKES {
                sendRoutingInfoForGprs} }
```

17.2.2.37 Failure reporting

This operation package includes the operations required for failure reporting between HLR and GGSN.

```
failureReportingPackage-v3      OPERATION-PACKAGE ::= {
          -- Supplier is HLR if Consumer is GGSN
          CONSUMER INVOKES {
                failureReport} }
```

This package is v3 only.

17.2.2.38 GPRS notifying

This operation package includes the operations required for notifying that GPRS subscriber is present between HLR and GGSN.

This package is v3 only.

17.2.2.39 Supplementary Service invocation notification

This operation package includes the operations required for Supplementary Service invocation notification procedures between the MSC and the gsmSCF and between the HLR and the gsmSCF.

This package is v3 only.

17.2.2.40 Set Reporting State

This operation package includes the operation required for procedures between HLR and VLR to set the reporting state.

This package is v3 only.

17.2.2.41 Status Report

This operation package includes the operation required for procedures between VLR and HLR to report call results and events.

```
statusReportPackage-v3    OPERATION-PACKAGE ::= {
         -- Supplier is HLR if Consumer is VLR
         CONSUMER INVOKES {
            statusReport} }
```

This package is v3 only.

17.2.2.42 Remote User Free

This operation package includes the operation required by the HLR to indicate to the VLR that the remote user is free.

```
remoteUserFreePackage-v3     OPERATION-PACKAGE ::= {
         -- Supplier is VLR if Consumer is HLR
          CONSUMER INVOKES {
            remoteUserFree}     }
```

This package is v3 only.

17.2.2.43 Call Completion

This operation package includes the operations required for procedures between VLR and HLR for subscriber control of call completion services.

```
callCompletionPackage-v3    OPERATION-PACKAGE ::= {
     -- Supplier is HLR if Consumer is VLR
     CONSUMER INVOKES {
        registerCC-Entry |
        eraseCC-Entry} }
```

This package is v3 only.

17.2.2.44 Location service gateway services

This operation package includes the operations required for location service gateway procedures between GMLC and HLR.

This package is v3 only.

17.2.2.45 Location service enquiry

This operation package includes the operations required for the location service enquiry procedures between GMLC and MSC and between GMLC and SGSN.

```
locationSvcEnquiryPackage-v3    OPERATION-PACKAGE ::= {
      -- Supplier is MSC or SGSN if Consumer is GMLC
      CONSUMER INVOKES {
          provideSubscriberLocation} }
```

This package is v3 only.

17.2.2.45A Location service reporting

This operation package includes the operations required for the location service enquiry procedures between MSC and GMLC and between SGSN and GMLC.

```
locationSvcReportingPackage-v3    OPERATION-PACKAGE ::= {
         -- Supplier is GMLC if Consumer is MSC
         -- Supplier is GMLC if Consumer is SGSN
         CONSUMER INVOKES {
            subscriberLocationReport} }
```

17.2.2.46 Void

17.2.2.47 Void

17.2.2.48 Void

17.2.2.49 IST Alerting

This operation package includes the operation required for alerting procedures between the MSC (Visited MSC or Gateway MSC) and HLR.

```
ist-AlertingPackage-v3     OPERATION-PACKAGE ::= {
         -- Supplier is HLR if Consumer is VMSC
         -- Supplier is HLR if Consumer is GMSC
         CONSUMER INVOKES {
            istAlert} }
```

This package is v3 only.

17.2.2.50 Service Termination

This operation package includes the operation required for immediate service termination procedures between the HLR and the Visited MSC or between the HLR and the Gateway MSC.

```
serviceTerminationPackage-v3    OPERATION-PACKAGE ::= {
          -- Supplier is VMSC or GMSC if Consumer is HLR
           CONSUMER INVOKES {
                istCommand}    }
```

This package is v3 only.

17.2.2.51 Mobility Management event notification

This operation package includes the operations required for Mobility Management event notification procedures between VLR and gsmSCF.

This package is v3 only.

17.2.2.52 Any time information handling

This operation package includes the operations required for any time information handling procedures between gsmSCF and HLR.

```
anyTimeInformationHandlingPackage-v3     OPERATION-PACKAGE ::= {
         -- Supplier is HLR if Consumer is gsmSCF
         CONSUMER INVOKES {
               anyTimeSubscriptionInterrogation |
                anyTimeModification} }
```

This package is v3 only.

17.2.2.53 Subscriber Data modification notification

This operation package includes the operations required for Subscriber Data modification notification procedures between HLR and gsmSCF.

This package is v3 only.

17.2.2.54 Authentication Failure Report

This operation package includes the operation required for procedures between VLR and HLR or the SGSN and the HLR for reporting of authentication failures.

```
authenticationFailureReportPackage-v3    OPERATION-PACKAGE ::= {
        -- Supplier is HLR if Consumer is VLR
        -- Supplier is HLR if Consumer is SGSN
        CONSUMER INVOKES {
            authenticationFailureReport} }
```

This package is v3 only.

17.2.2.55 Resource Management

This operation package includes the operation required for procedures between GMSC and VMSC for resource management purpose.

```
resourceManagementPackage-v3     OPERATION-PACKAGE ::= {
          -- Supplier is VMSC if Consumer is GMSC
          CONSUMER INVOKES {
            releaseResources}     }
```

This package is v3 only.

17.3 Application contexts

17.3.1 General aspects

An application-context is assigned for each dialogue established by a MAP-user. In the present document each application-context is assigned a name which is supplied in the MAP-OPEN Req primitive by the MAP-User and transmitted to the peer under certain circumstances.

The following ASN.1 information object class is used to describe the main aspects of application-contexts in the following clauses:

The following definitions are used throughout this clause:

- v1-application-context: An application-context which contains only v1-packages and uses only TC v1 facilities;
- v1 context set: the set of v1-application-contexts defined in the present document.
- vn-application-context (n>=2): An application-context which contains only vn-packages;

The names of v1-application-contexts are suffixed by "-v1" while other names are suffixed by "-vn" where n>=2.

Application-contexts which do not belong to the v1 context set use v2 TC facilities.

The last component of each application-context-name (i.e. the last component of the object identifier value) assigned to an application-context which belongs to the v1 context set indicates explicitly "version1".

For each application-context which does not belong to the "v1 context set" there is a v1-equivalent application context. This is a v1-application-context which includes the v1-equivalents of the packages included in the original context.

Each application-context uses the abstract-syntax associated with the operation-packages it includes and uses the transfer-syntax derived from it by applying the encoding rules defined in clause 17.1.1.

ACs which do not belong to the v1 context set require the support of the abstract-syntax identified by the object identifier value: MAP-DialogueInformation.map-Dialogue-AS defined in clause 17.4.

17.3.2 Application context definitions

17.3.2.1 Void

17.3.2.2 Location Updating

This application context is used between HLR and VLR for location updating procedures.

```
networkLocUpContext-v3 APPLICATION-CONTEXT ::= {
    -- Responder is HLR if Initiator is VLR
    INITIATOR CONSUMER OF {
        locationUpdatingPackage-v3 |
        dataRestorationPackage-v3}
    RESPONDER CONSUMER OF {
        subscriberDataMngtPackage-v3 |
        tracingPackage-v3}
    ID {map-ac networkLocUp(1) version3(3)}
}
```

The following application-context-name is assigned to the v2-equivalent application-context:

```
ID {map-ac networkLocUp(1) version2(2)}
```

The following application-context-name is assigned to the v1-equivalent application-context:

```
ID {map-ac networkLocUp(1) version1(1)}
```

17.3.2.3 Location Cancellation

This application context is used between HLR and VLR or between HLR and SGSN for location cancellation procedures. For the HLR - SGSN interface only version 3 of this application context is applicable.

The following application-context-name is assigned to the v2-equivalent application-context:

```
ID map-ac locationCancel(2) version2(2)
```

The following application-context-name is assigned to the v1-equivalent application-context:

```
ID map-ac locationCancel(2) version1(1)
```

17.3.2.4 Roaming number enquiry

This application context is used between HLR and VLR for roaming number enquiry procedures.

```
roamingNumberEnquiryContext-v3 APPLICATION-CONTEXT ::= {
    -- Responder is VLR if Initiator is HLR
    INITIATOR CONSUMER OF {
        roamingNumberEnquiryPackage-v3}
    ID {map-ac roamingNbEnquiry(3) version3(3)} }
```

The following application-context-name is assigned to the v2-equivalent application-context:

```
ID {map-ac roamingNbEnquiry(3) version2(2)}
```

The following application-context-name is assigned to the v1-equivalent application-context:

```
ID {map-ac roamingNbEnquiry(3) version1(1)}
```

17.3.2.5 Void

17.3.2.6 Location Information Retrieval

This application-context is used between GMSC and HLR or between GMSC and NPLR or between gsmSCF and HLR when retrieving location information. For the GMSC - NPLR interface version 1, version 2 and version 3 of this application context are applicable.

```
locationInfoRetrievalContext-v3 APPLICATION-CONTEXT ::= {
    -- Responder is HLR or NPLR if Initiator is GMSC
    -- Responder is HLR if Initiator is gsmSCF
    INITIATOR CONSUMER OF {
        interrogationPackage-v3}
    ID {map-ac locInfoRetrieval(5) version3(3)} }
```

The following application-context-name is assigned to the v2-equivalent application-context:

```
ID {map-ac locInfoRetrieval(5) version2(2)}
```

The following application-context-name is assigned to the v1-equivalent application-context:

```
ID {map-ac locInfoRetrieval(5) version1(1)}
```

17.3.2.7 Call control transfer

This application context is used for the call control transfer procedure between the VMSC and the GMSC.

```
callControlTransferContext-v4 APPLICATION-CONTEXT ::= {
    -- Responder is GMSC if Initiator is VMSC
    INITIATOR CONSUMER OF {
        callControlTransferPackage-v4}
    ID {map-ac callControlTransfer(6) version4(4)} }
```

The following application-context-name is assigned to the v3-equivalent application-context:

```
ID {map-ac callControlTransfer(6) version3(3)}
```

17.3.2.8 void

17.3.2.9 - 17.3.2.10 Void

17.3.2.11 Location registers restart

This application context is used between HLR and VLR or between HLR and SGSN for location register restart procedures. For the HLR - SGSN interface version 1 and version 2 of this application context are applicable.

```
resetContext-v2 APPLICATION-CONTEXT ::= {
    -- Responder is VLR or SGSN if Initiator is HLR
    INITIATOR CONSUMER OF {
        resetPackage-v2}
    ID {map-ac reset(10) version2(2)} }
```

The following application-context-name is assigned to the v1-equivalent application-context:

```
ID {map-ac reset(10) version1(1)}
```

17.3.2.12 Handover control

This application context is used for handover procedures between MSCs.

```
handoverControlContext-v3 APPLICATION-CONTEXT ::= {
    -- Responder is MSCB if Initiator is MSCA
    INITIATOR CONSUMER OF {
        handoverControlPackage-v3}
    ID {map-ac handoverControl(11) version3(3)} }
```

The following application-context-name is assigned to the v2-equivalent application-context:

```
ID {map-ac handoverControl(11) version2(2)}
```

The following application-context-name is assigned to the v1-equivalent application-context:

```
ID {map-ac handoverControl(11) version1(1)}
```

17.3.2.13 IMSI Retrieval

This application context is used for IMSI retrieval between HLR and VLR.

```
imsiRetrievalContext-v2 APPLICATION-CONTEXT ::= {
    -- Responder is HLR if Initiator is VLR
    INITIATOR CONSUMER OF {
        imsi-RetrievalPackage-v2}
    ID {map-ac imsiRetrieval(26) version2(2)} }
```

This application-context is v2 only.

17.3.2.14 Equipment Management

This application context is used for equipment checking between MSC and EIR or between SGSN and EIR. For the SGSN - EIR interface version 1 and version 2 and version 3 of this application context are applicable:

```
equipmentMngtContext-v3 APPLICATION-CONTEXT ::= {
     -- Responder is EIR if Initiator is MSC
     -- Responder is EIR if Initiator is SGSN
     INITIATOR CONSUMER OF {
          equipmentMngtPackage-v3}
     ID {map-ac equipmentMngt(13) version3(3)} }
```

The following application-context-name is assigned to the v2-equivalent application-context:

```
equipmentMngtContext-v2 APPLICATION-CONTEXT ::= {
    -- Responder is EIR if Initiator is MSC
    -- Responder is EIR if Initiator is SGSN
    INITIATOR CONSUMER OF {
        equipmentMngtPackage-v2}
    ID {map-ac equipmentMngt(13) version2(2)} }
```

The following application-context-name is assigned to the v1-equivalent application-context:

```
ID {map-ac equipmentMngt(13) version1(1)}
```

17.3.2.15 Information retrieval

This application context is used for authentication information retrieval between HLR and VLR or between HLR and SGSN. For the HLR - SGSN interface version 1 and version 2 and version 3 of this application context are applicable.

```
infoRetrievalContext-v3 APPLICATION-CONTEXT ::= {
    -- Responder is HLR if Initiator is VLR
    -- Responder is HLR if Initiator is SGSN
    INITIATOR CONSUMER OF {
        infoRetrievalPackage-v3}
    ID {map-ac infoRetrieval(14) version3(3)} }
```

The following application-context-name is assigned to the v2-equivalent application-context:

```
infoRetrievalContext-v2 APPLICATION-CONTEXT ::= {
    -- Responder is HLR if Initiator is VLR
    -- Responder is HLR if Initiator is SGSN
    INITIATOR CONSUMER OF {
        infoRetrievalPackage-v2}
    ID {map-ac infoRetrieval(14) version2(2)}
}
```

The following application-context-name is assigned to the v1-equivalent application-context:

```
ID {map-ac infoRetrieval(14) version1(1)}
```

17.3.2.16 Inter-VLR information retrieval

This application context is used for information retrieval between VLRs.

```
interVlrInfoRetrievalContext-v3 APPLICATION-CONTEXT ::= {
    -- Responder is VLR if Initiator is VLR
    INITIATOR CONSUMER OF {
        interVlrInfoRetrievalPackage-v3}
    ID {map-ac interVlrInfoRetrieval(15) version3(3)} }
```

The v2-equivalent application-context is:

```
interVlrInfoRetrievalContext-v2 APPLICATION-CONTEXT ::= {
    -- Responder is VLR if Initiator is VLR
    INITIATOR CONSUMER OF {
        interVlrInfoRetrievalPackage-v2}
    ID {map-ac interVlrInfoRetrieval(15) version2(2)} }
```

The v1-equivalent application-context is:

```
ID {map-ac infoRetrieval(14) version1(1)}
```

17.3.2.17 Stand Alone Subscriber Data Management

This application context is used for stand alone subscriber data management between HLR and VLR or between HLR and SGSN. For the HLR - SGSN interface only version 3 of this application context is applicable:

```
subscriberDataMngtContext-v3 APPLICATION-CONTEXT ::= {
    -- Responder is VLR or SGSN if Initiator is HLR
    INITIATOR CONSUMER OF {
        subscriberDataMngtStandAlonePackage-v3}
    ID {map-ac subscriberDataMngt(16) version3(3)} }
```

The following application-context-name is assigned to the v2-equivalent application-context:

```
ID {map-ac subscriberDataMngt(16) version2(2)}
```

The following application-context-name is assigned to the v1-equivalent application-context:

```
ID {map-ac subscriberDataMngt(16) version1(1)}
```

17.3.2.18 Tracing

This application context is used between HLR and VLR or between HLR and SGSN for stand alone tracing control procedures. For the HLR - SGSN interface version 1, version 2 and version 3 of this application context are applicable.

```
tracingContext-v3 APPLICATION-CONTEXT ::= {
    -- Responder is VLR or SGSN if Initiator is HLR
    INITIATOR CONSUMER OF {
        tracingStandAlonePackage-v3}
    ID {map-ac tracing(17) version3(3)} }
```

The following application-context-name is assigned to the v2-equivalent application-context:

```
ID {map-ac tracing(17) version2(2)}
```

The following application-context-name is assigned to the v1-equivalent application-context:

```
ID {map-ac tracing(17) version1(1)}
```

17.3.2.19 Network functional SS handling

This application context is used for functional-like SS handling procedures between VLR and HLR.

```
networkFunctionalSsContext-v2 APPLICATION-CONTEXT ::= {
     -- Responder is HLR, Initiator is VLR
     INITIATOR CONSUMER OF {
          functionalSsPackage-v2}
     ID {map-ac networkFunctionalSs(18) version2(2)} }
```

The v1-equivalent application-context is defined as follows:

17.3.2.20 Network unstructured SS handling

This application context is used for handling stimuli-like procedures between HLR and VLR, between the HLR and gsmSCF, and between HLR and HLR.

```
networkUnstructuredSsContext-v2 APPLICATION-CONTEXT ::= {
    -- Responder is HLR, Initiator is VLR
    -- Responder is VLR, Initiator is HLR
    -- Responder is gsmSCF, Initiator is HLR
    -- Responder is HLR, Initiator is gsmSCF
    -- Responder is HLR, Initiator is HLR
    OPERATIONS OF {
        unstructuredSsPackage-v2}
    ID {map-ac networkUnstructuredSs(19) version2(2)} }
```

The following application-context-name is assigned to the v1-equivalent application-context:

```
ID {map-ac networkFunctionalSs(18) version1(1)}
```

17.3.2.21 Short Message Gateway

This application context is used for short message gateway procedures.

```
shortMsgGatewayContext-v3 APPLICATION-CONTEXT ::= {
    -- Responder is HLR if Initiator is GMSC
    INITIATOR CONSUMER OF {
        shortMsgGatewayPackage-v3}
    ID {map-ac shortMsgGateway(20) version3(3)} }
```

The following application-context-name is assigned to the v2-equivalent application-context:

```
ID {map-ac shortMsgGateway(20) version2(2)}
```

The following application-context-name is assigned to the v1-equivalent application-context:

```
ID {map-ac shortMsgGateway(20) version1(1)}
```

17.3.2.22 Mobile originating Short Message Relay

This application context is used between MSC and IWMSC or between SGSN and IWMSC for mobile originating short message relay procedures. For the SGSN - IWMSC interface version 1, version 2 and version 3 of this application context are applicable.

```
shortMsgMO-RelayContext-v3 APPLICATION-CONTEXT ::= {
     -- Responder is IWMSC if Initiator is MSC
     -- Responder is IWMSC if Initiator is SGSN
     INITIATOR CONSUMER OF {
           mo-ShortMsgRelayPackage-v3}
     ID {map-ac shortMsgMO-Relay(21) version3(3)} }
```

The following application-context-name is assigned to the v2-equivalent application-context:

```
ID {map-ac shortMsgMO-Relay(21) version2(2)}
```

The following application-context-name is assigned to the v1-equivalent application-context:

```
ID {map-ac shortMsg-Relay(21) version1(1)}
```

17.3.2.23 Void

17.3.2.24 Short message alert

This application context is used for short message alerting procedures.

```
shortMsgAlertContext-v2 APPLICATION-CONTEXT ::= {
    -- Responder is IWMSC if Initiator is HLR
    INITIATOR CONSUMER OF {
        alertingPackage-v2}
    ID {map-ac shortMsgAlert(23) version2(2)} }
```

The following application-context-name is symbolically assigned to the v1-equivalent application-context:

```
ID {map-ac shortMsgAlert(23) version1(1)}
```

17.3.2.25 Short message waiting data management

This application context is used between VLR and HLR or between SGSN and HLR for short message waiting data management procedures. For the SGSN - HLR interface only version 3 of this application context is applicable.

```
mwdMngtContext-v3 APPLICATION-CONTEXT ::= {
    -- Responder is HLR if Initiator is SGSN
    -- Responder is HLR if Initiator is VLR
    INITIATOR CONSUMER OF {
        mwdMngtPackage-v3}
    ID {map-ac mwdMngt(24) version3(3)} }
```

The following application-context-name is assigned to the v2-equivalent application-context:

```
ID {map-ac mwdMngt(24) version2(2)}
```

The following application-context-name is assigned to the v1-equivalent application-context:

```
ID {map-ac mwdMngt(24) version1(1)}
```

17.3.2.26 Mobile terminating Short Message Relay

This application context is used between GMSC and MSC or between GMSC and SGSN for mobile terminating short message relay procedures. For the GMSC - SGSN interface version 2 and version 3 of this application context and the equivalent version 1 application context are applicable.

```
shortMsgMT-RelayContext-v3 APPLICATION-CONTEXT ::= {
    -- Responder is MSC or SGSN if Initiator is GMSC
     INITIATOR CONSUMER OF {
        mt-ShortMsgRelayPackage-v3}
     ID {map-ac shortMsgMT-Relay(25) version3(3)} }
```

The following application-context-name is assigned to the v2-equivalent application-context:

```
ID {map-ac shortMsgMT-Relay(25) version2(2)}
```

The following application-context-name is assigned to the v1-equivalent application-context:

```
ID {map-ac shortMsgMO-Relay(21) version1(1)}
```

17.3.2.27 MS purging

This application context is used between HLR and VLR or between HLR and SGSN for MS purging procedures. For the SGSN - HLR interface only version 3 of this application context is applicable.

```
msPurgingContext-v3 APPLICATION-CONTEXT ::= {
    -- Responder is HLR if Initiator is VLR
    -- Responder is HLR if Initiator is SGSN
    INITIATOR CONSUMER OF {
        purgingPackage-v3}
    ID {map-ac msPurging(27) version3(3)} }
```

The following application-context-name is assigned to the v2-equivalent application-context:

```
ID {map-ac msPurging(27) version2(2)}
```

17.3.2.28 Subscriber information enquiry

This application context is used between HLR and VLR or between HLR and SGSN for subscriber information enquiry procedures.

```
subscriberInfoEnquiryContext-v3 APPLICATION-CONTEXT ::= {
    -- Responder is VLR or SGSN if Initiator is HLR
    INITIATOR CONSUMER OF {
        subscriberInformationEnquiryPackage-v3}
    ID {map-ac subscriberInfoEnquiry(28) version3(3)} }
```

This application-context is v3 only.

17.3.2.29 Any time information enquiry

This application context is used between gsmSCF and HLR or between gsmSCF and GMLC or between gsmSCF and NPLR for any time information enquiry procedures.

```
anyTimeInfoEnquiryContext-v3 APPLICATION-CONTEXT ::= {
    -- Responder is HLR or GMLC or NPLR if Initiator is gsmSCF
    INITIATOR CONSUMER OF {
        anyTimeInformationEnquiryPackage-v3}
    ID {map-ac anyTimeInfoEnquiry(29) version3(3)} }
```

This application-context is v3 only.

17.3.2.30 Group Call Control

This application context is used between anchor MSC and relay MSC for group call and broadcast call procedures.

```
groupCallControlContext-v3 APPLICATION-CONTEXT ::= {
     -- Responder is relay MSC if Initiator is anchor MSC
     INITIATOR CONSUMER OF {
          groupCallControlPackage-v3}
     ID {map-ac groupCallControl(31) version3(3)} }
```

This application-context is v3 only.

17.3.2.31 Void

17.3.2.32 Gprs Location Updating

This application context is used between HLR and SGSN for gprs location updating procedures.

```
gprsLocationUpdateContext-v3 APPLICATION-CONTEXT ::= {
    -- Responder is HLR if Initiator is SGSN
    INITIATOR CONSUMER OF {
        gprsLocationUpdatingPackage-v3}
    RESPONDER CONSUMER OF {
        subscriberDataMngtPackage-v3 |
        tracingPackage-v3}
    ID {map-ac gprsLocationUpdate(32) version3(3)}
}
```

This application-context is v3 only.

17.3.2.33 Gprs Location Information Retreival

This application context is used between HLR and GGSN when retrieving gprs location information.

```
gprsLocationInfoRetrievalContext-v4 APPLICATION-CONTEXT ::= {
    -- Responder is HLR if Initiator is GGSN
    INITIATOR CONSUMER OF {
        gprsInterrogationPackage-v4}
    ID {map-ac gprsLocationInfoRetrieval(33) version4(4)} }
```

The following application-context-name is assigned to the v3-equivalent application-context:

```
ID {map-ac gprsLocationInfoRetrieval(33) version3(3)}
```

17.3.2.34 Failure Reporting

This application context is used between HLR and GGSN to inform that network requested PDP-context activation has failed.

```
failureReportContext-v3 APPLICATION-CONTEXT ::= {
    -- Responder is HLR if Initiator is GGSN
    INITIATOR CONSUMER OF {
        failureReportingPackage-v3}
    ID {map-ac failureReport(34) version3(3)} }
```

This application-context is v3 only.

17.3.2.35 GPRS Notifying

This application context is used between HLR and GGSN for notifying that GPRS subscriber is present again.

```
gprsNotifyContext-v3 APPLICATION-CONTEXT ::= {
    -- Responder is GGSN if Initiator is HLR
    INITIATOR CONSUMER OF {
        gprsNotifyingPackage-v3}
    ID {map-ac gprsNotify(35) version3(3)} }
```

This application-context is v3 only.

17.3.2.36 Supplementary Service invocation notification

This application context is used between the MSC and the gsmSCF and between the HLR and the gsmSCF for Supplementary Service invocation notification procedures.

```
ss-InvocationNotificationContext-v3 APPLICATION-CONTEXT ::= {
    -- Responder is gsmSCF, Initiator is MSC
    -- Responder is gsmSCF, Initiator is HLR
    INITIATOR CONSUMER OF {
        ss-InvocationNotificationPackage-v3}
    ID {map-ac ss-InvocationNotification(36) version3(3)} }
```

This application-context is v3 only.

17.3.2.37 Reporting

This application context is used between HLR and VLR for reporting procedures.

This application-context is v3 only.

17.3.2.38 Call Completion

This application context is used between VLR and the HLR for subscriber control of call completion services.

```
callCompletionContext-v3 APPLICATION-CONTEXT ::= {
    -- Responder is HLR if Initiator is VLR
    INITIATOR CONSUMER OF {
        callCompletionPackage-v3}
    ID {map-ac callCompletion(8) version3(3)} }
```

This application-context is v3 only.

17.3.2.39 Location Service Gateway

This application context is used for location service gateway procedures.

```
locationSvcGatewayContext-v3 APPLICATION-CONTEXT ::= {
    -- Responder is HLR if Initiator is GMLC
    INITIATOR CONSUMER OF {
        locationSvcGatewayPackage-v3}
    ID {map-ac locationSvcGateway(37) version3(3)} }
```

17.3.2.40 Location Service Enquiry

This application context is used for location service enquiry procedures.

```
locationSvcEnquiryContext-v3 APPLICATION-CONTEXT ::= {
    -- Responder is MSC or SGSN if Initiator is GMLC
    -- Responder is GMLC if Initiator is MSC
    -- Responder is GMLC if Initiator is SGSN
    INITIATOR CONSUMER OF {
        locationSvcEnquiryPackage-v3 |
        locationSvcEeportingPackage-v3}
    ID {map-ac locationSvcEnquiry(38) version3 (3)} }
```

- 17.3.2.41 Void
- 17.3.2.42 Void
- 17.3.2.43 Void

17.3.2.44 IST Alerting

This application context is used between MSC (Visited MSC or Gateway MSC) and HLR for alerting services within IST procedures.

```
istAlertingContext-v3 APPLICATION-CONTEXT ::= {
    -- Responder is HLR if Initiator is VMSC
    -- Responder is HLR if Initiator is GMSC
    INITIATOR CONSUMER OF {
        ist-AlertingPackage-v3}
    ID {map-ac alerting(4) version3(3)} }
```

This application-context is v3 only.

17.3.2.45 Service Termination

This application context is used between HLR and MSC (Visited MSC or Gateway MSC) for service termination services within IST procedures.

```
serviceTerminationContext-v3 APPLICATION-CONTEXT ::= {
    -- Responder is VMSC or GMSC if Initiator is HLR
    INITIATOR CONSUMER OF {
        serviceTerminationPackage-v3}
    ID {map-ac serviceTermination(9) version3(3)} }
```

This application-context is v3 only.

17.3.2.46 Mobility Management event notification

This application context is used between VLR and gsmSCF for Mobility Management event notification procedures.

```
mm-EventReportingContext-v3 APPLICATION-CONTEXT ::= {
    -- Responder is gsmSCF, Initiator is VLR
    INITIATOR CONSUMER OF {
        mm-EventReportingPackage-v3}
    ID {map-ac mm-EventReporting(42) version3(3)} }
```

This application-context is v3 only.

17.3.2.47 Any time information handling

This application context is used between gsmSCF and HLR for any time information handling procedures.

```
anyTimeInfohandlingContext-v3 APPLICATION-CONTEXT ::= {
    -- Responder is HLR if Initiator is gsmSCF
    INITIATOR CONSUMER OF {
        anyTimeInformationHandlingPackage-v3}
    ID {map-ac anyTimeInfoHandling(43) version3(3)} }
```

This application-context is v3 only.

17.3.2.48 Subscriber Data modification notification

This application context is used between HLR and gsmSCF for Subscriber Data modification notification procedures.

```
subscriberDataModificationNotificationContext-v3 APPLICATION-CONTEXT ::= {
    -- Responder is gsmSCF, Initiator is HLR
    INITIATOR CONSUMER OF {
        subscriberDataModificationNotificationPackage-v3}
    ID {map-ac subscriberDataModificationNotification(22) version3(3)} }
```

This application-context is v3 only.

17.3.2.49 Authentication Failure Report

This application context is used between VLR and HLR or SGSN and HLR for reporting of authentication failures.

```
authenticationFailureReportContext-v3 APPLICATION-CONTEXT ::= {
    -- Responder is HLR if Initiator is VLR
    -- Responder is HLR if Initiator is SGSN
    INITIATOR CONSUMER OF {
        authenticationFailureReportPackage-v3 }
    ID {map-ac authenticationFailureReport(39) version3(3)} }
```

This application-context is v3 only.

17.3.2.50 Resource Management

This application context is used between GMSC and VMSC for resource management purpose.

```
resourceManagementContext-v3 APPLICATION-CONTEXT ::= {
    -- Responder is VMSC if Initiator is GMSC
    INITIATOR CONSUMER OF {
        resourceManagementPackage-v3 }
    ID {map-ac resourceManagement(44) version3(3)} }
```

This application-context is v3 only.

17.3.3 ASN.1 Module for application-context-names

The following ASN.1 module summarises the application-context-name assigned to MAP application-contexts.

```
MAP-ApplicationContexts {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-ApplicationContexts (2) version9 (9) }

DEFINITIONS
::=

BEGIN
-- EXPORTS everything

IMPORTS
   gsm-NetworkId,
   ac-Id
FROM MobileDomainDefinitions {
   itu-t (0) identified-organization (4) etsi (0) mobileDomain (0) mobileDomainDefinitions (0) version1 (1) }

,
-- application-context-names
```

```
map-ac OBJECT IDENTIFIER ::= {gsm-NetworkId ac-Id}
```

```
networkLocUpContext-v3 OBJECT IDENTIFIER ::=
    {map-ac networkLocUp(1) version3(3)}
locationCancellationContext-v3 OBJECT IDENTIFIER ::=
    {map-ac locationCancel(2) version3(3)}
roamingNumberEnquiryContext-v3 OBJECT IDENTIFIER ::=
    {map-ac roamingNbEnquiry(3) version3(3)}
authenticationFailureReportContext-v3 OBJECT IDENTIFIER ::=
    {map-ac authenticationFailureReport(39) version3(3)}
{map-ac locInfoRetrieval(5) version3(3)}
resetContext-v2 OBJECT IDENTIFIER ::=
    {map-ac reset(10) version2(2)}
handoverControlContext-v3 OBJECT IDENTIFIER ::=
    {map-ac handoverControl(11) version3(3)}
equipmentMngtContext-v3 OBJECT IDENTIFIER ::=
    {map-ac equipmentMngt(13) version3(3)}
{map-ac infoRetrieval(14) version3(3)}
interVlrInfoRetrievalContext-v3      OBJECT IDENTIFIER ::=
    {map-ac interVlrInfoRetrieval(15) version3(3)}
subscriberDataMngtContext-v3 OBJECT IDENTIFIER ::=
    {map-ac subscriberDataMngt(16) version3(3)}
tracingContext-v3    OBJECT IDENTIFIER ::=
    {map-ac tracing(17) version3(3)}
networkFunctionalSsContext-v2 OBJECT IDENTIFIER ::=
    {map-ac networkFunctionalSs(18) version2(2)}
networkUnstructuredSsContext-v2 OBJECT IDENTIFIER ::=
    {map-ac networkUnstructuredSs(19) version2(2)}
shortMsgGatewayContext-v3 OBJECT IDENTIFIER ::=
    {map-ac shortMsgGateway(20) version3(3)}
shortMsgMO-RelayContext-v3 OBJECT IDENTIFIER ::=
    {map-ac shortMsgMO-Relay(21) version3(3)}
shortMsgAlertContext-v2 OBJECT IDENTIFIER ::=
    {map-ac shortMsgAlert(23) version2(2)}
mwdMngtContext-v3 OBJECT IDENTIFIER ::=
    {map-ac mwdMngt(24) version3(3)}
shortMsgMT-RelayContext-v3 OBJECT IDENTIFIER ::=
    {map-ac shortMsgMT-Relay(25) version3(3)}
imsiRetrievalContext-v2     OBJECT IDENTIFIER ::=
    {map-ac imsiRetrieval(26) version2(2)
msPurgingContext-v3 OBJECT IDENTIFIER ::=
    {map-ac msPurging(27) version3(3)}
subscriberInfoEnquiryContext-v3 OBJECT IDENTIFIER ::=
    {map-ac subscriberInfoEnquiry(28) version3(3)]
anyTimeInfoEnquiryContext-v3 OBJECT IDENTIFIER ::=
    {map-ac anyTimeInfoEnquiry(29) version3(3)
callControlTransferContext-v4 OBJECT IDENTIFIER ::=
    {map-ac callControlTransfer(6) version4(4)}
ss-InvocationNotificationContext-v3 OBJECT IDENTIFIER ::=
    {map-ac ss-InvocationNotification(36) version3(3)}
```

```
groupCallControlContext-v3 OBJECT IDENTIFIER ::=
    {map-ac groupCallControl(31) version3(3)}
gprsLocationUpdateContext-v3 OBJECT IDENTIFIER ::=
    {map-ac gprsLocationUpdate(32) version3(3)}
gprsLocationInfoRetrievalContext-v4 OBJECT IDENTIFIER ::=
    {map-ac gprsLocationInfoRetrieval(33) version4(4)}
failureReportContext-v3 OBJECT IDENTIFIER ::=
    {map-ac failureReport(34) version3(3)}
gprsNotifyContext-v3 OBJECT IDENTIFIER ::=
    {map-ac gprsNotify(35) version3(3)}
reportingContext-v3 OBJECT IDENTIFIER ::=
    {map-ac reporting(7) version3(3)}
callCompletionContext-v3 OBJECT IDENTIFIER ::=
    {map-ac callCompletion(8) version3(3)}
istAlertingContext-v3 OBJECT IDENTIFIER ::=
    {map_ac istAlerting(4) version3(3)}
serviceTerminationContext-v3 OBJECT IDENTIFIER ::=
    {map-ac immediateTermination(9) version3(3)
locationSvcGatewayContext-v3 OBJECT IDENTIFIER ::=
    {map-ac locationSvcGateway(37) version3(3)}
locationSvcEnquiryContext-v3 OBJECT IDENTIFIER ::=
    {map-ac locationSvcEnquiry(38) version3(3)}
mm-EventReportingContext-v3 OBJECT IDENTIFIER ::=
    {map-ac mm-EventReporting(42) version3(3)}
anyTimeInfoHandlingContext-v3 OBJECT IDENTIFIER ::=
    {map-ac anyTimeInfoHandling(43) version3(3)}
{map-ac subscriberDataModificationNotification(22) version3(3)}
resourceManagementContext-v3 OBJECT IDENTIFIER ::=
    {map-ac resourceManagement(44) version3(3)}
```

- -- The following Object Identifiers are reserved for application-contexts
- -- existing in previous versions of the protocol

AC Name & Version	Object Identifier	
	,	
networkLocUpContext-v1	map-ac networkLocUp (1)	version1 (1)
networkLocUpContext-v2	map-ac networkLocUp (1)	version2 (2)
locationCancellationContext-v1	map-ac locationCancellation (2)	version1 (1)
locationCancellationContext-v2	map-ac locationCancellation (2)	version2 (2)
roamingNumberEnquiryContext-v1	map-ac roamingNumberEnquiry (3)	version1 (1)
roamingNumberEnquiryContext-v2	map-ac roamingNumberEnquiry (3)	version2 (2)
locationInfoRetrievalContext-v1	map-ac locationInfoRetrieval (5)	version1 (1)
locationInfoRetrievalContext-v2	map-ac locationInfoRetrieval (5)	version2 (2)
resetContext-v1	map-ac reset (10)	version1 (1)
handoverControlContext-v1	map-ac handoverControl (11)	version1 (1)
handoverControlContext-v2	map-ac handoverControl (11)	version2 (2)
sIWFSAllocationContext-v3	map-ac sIWFSAllocation (12)	version3 (3)
equipmentMngtContext-v1	map-ac equipmentMngt (13)	version1 (1)
equipmentMngtContext-v2	map-ac equipmentMngt (13)	version2 (2)
infoRetrievalContext-v1	map-ac infoRetrieval (14)	version1 (1)
infoRetrievalContext-v2	map-ac infoRetrieval (14)	version2 (2)
interVIrInfoRetrievalContext-v2	map-ac interVIrInfoRetrieval (15)	version2 (2)
subscriberDataMngtContext-v1	map-ac subscriberDataMngt (16)	version1 (1)
subscriberDataMngtContext-v2	map-ac subscriberDataMngt (16)	version2 (2)
tracingContext-v1	map-ac tracing (17)	version1 (1)
tracingContext-v2	map-ac tracing (17)	version2 (2)
networkFunctionalSsContext-v1	map-ac networkFunctionalSs (18)	version1 (1)
shortMsgGatewayContext-v1	map-ac shortMsgGateway (20)	version1 (1)
shortMsgGatewayContext-v2	map-ac shortMsgGateway (20)	version2 (2)
shortMsgRelayContext-v1	map-ac shortMsgRelay (21)	version1 (1)
shortMsgAlertContext-v1	map-ac shortMsgAlert (23)	version1 (1)
mwdMngtContext-v1	map-ac mwdMngt (24)	version1 (1)
mwdMngtContext-v2	map-ac mwdMngt (24)	version2 (2)
shortMsgMT-RelayContext-v2	map-ac shortMsgMT-Relay (25)	version2 (2)
msPurgingContext-v2	map-ac msPurging (27)	version2 (2)
callControlTransferContext-v3	map-ac callControlTransferContext (6)	version3 (3)
gprsLocationInfoRetrievalContext-v3	map-ac gprsLocationInfoRetrievalContex	t (33) version3 (3)

17.4 MAP Dialogue Information

```
MAP-DialogueInformation {
  itu-t identified-organization (4) etsi (0) mobileDomain (0)
  gsm-Network (1) modules (3) map-DialogueInformation (3) version9 (9)}
DEFINITIONS
IMPLICIT TAGS
::=
BEGIN
EXPORTS
  map-DialogueAS,
  MAP-DialoguePDU
IMPORTS
  gsm-NetworkId,
FROM MobileDomainDefinitions {
  itu-t (0) identified-organization (4) etsi (0) mobileDomain (0)
  mobileDomainDefinitions (0) version1 (1) }
  AddressString
FROM MAP-CommonDataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
  gsm-Network(1) modules (3) map-CommonDataTypes (18) version9 (9) }
  ExtensionContainer
FROM MAP-ExtensionDataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
  gsm-Network (1) modules (3) map-ExtensionDataTypes (21) version9 (9) }
```

map-DialogueAS OBJECT IDENTIFIER ::=

```
-- abstract syntax name for MAP-DialoguePDU
```

```
{gsm-NetworkId as-Id map-DialoguePDU (1) version1 (1)}
MAP-DialoguePDU ::= CHOICE {
                                          [0] MAP-OpenInfo,
    map-open
    map-accept
                                          [1] MAP-AcceptInfo,
    map-close
                                          [2] MAP-CloseInfo,
                                          [3] MAP-RefuseInfo,
    map-refuse
    map-userAbort
                                          [4] MAP-UserAbortInfo,
    map-providerAbort
                                          [5] MAP-ProviderAbortInfo}
MAP-OpenInfo ::= SEQUENCE {
    destinationReference
                                          [0] AddressString
                                                                            OPTIONAL,
    originationReference
                                         [1] AddressString
                                                                            OPTIONAL,
     extensionContainer
                                         ExtensionContainer
                                                                            OPTIONAL
     -- extensionContainer must not be used in version 2
MAP-AcceptInfo ::= SEQUENCE {
     extensionContainer
                                                                            OPTIONAL
                                         ExtensionContainer
     -- extensionContainer must not be used in version 2
MAP-CloseInfo ::= SEQUENCE {
     extensionContainer
                                         ExtensionContainer
                                                                            OPTIONAL
      - extensionContainer must not be used in version 2
MAP-RefuseInfo ::= SEQUENCE {
    reason Reason,
    extensionContainer
                                         ExtensionContainer
                                                                            OPTIONAL,
     -- extensionContainer must not be used in version 2
     alternativeApplicationContext OBJECT IDENTIFIER
                                                                            OPTIONAL
     -- alternativeApplicationContext must not be used in version 2
Reason ::= ENUMERATED {
    noReasonGiven
                                          (0),
     invalidDestinationReference
                                          (1),
     {\tt invalidOriginatingReference}
                                          (2)
MAP-UserAbortInfo ::= SEQUENCE {
    map-UserAbortChoice
                                         MAP-UserAbortChoice,
     extensionContainer
                                         ExtensionContainer
                                                                            OPTIONAL
     -- extensionContainer must not be used in version 2
MAP-UserAbortChoice ::= CHOICE {
    userSpecificReason
                                          [0] NULL,
                                          [1] NULL.
    userResourceLimitation
     resourceUnavailable
                                         [2] ResourceUnavailableReason,
    applicationProcedureCancellation
                                         [3] ProcedureCancellationReason
ResourceUnavailableReason ::= ENUMERATED {
    shortTermResourceLimitation (0),
     longTermResourceLimitation (1) }
ProcedureCancellationReason ::= ENUMERATED {
    handoverCancellation (0),
     radioChannelRelease (1),
    networkPathRelease (2),
    callRelease (3),
    associatedProcedureFailure (4),
     tandemDialogueRelease (5),
     remoteOperationsFailure (6) }
```

```
MAP-ProviderAbortReason ::= ENUMERATED {
    abnormalDialogue (0),
    invalidPDU (1)}
```

 $_{
m END}$

17.5 MAP operation and error codes

```
MAP-Protocol {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   qsm-Network (1) modules (3) map-Protocol (4) version9 (9)}
DEFINITIONS
BEGIN
IMPORTS
FROM Remote-Operations-Information-Objects {
  joint-iso-itu-t remote-operations(4) informationObjects(5) version1(0) }
  updateLocation,
   cancelLocation,
  purgeMS.
   sendIdentification.
  updateGprsLocation,
  prepareHandover,
   sendEndSignal,
  processAccessSignalling,
   forwardAccessSignalling,
  prepareSubsequentHandover,
   sendAuthenticationInfo,
   authenticationFailureReport,
  checkIMEI,
   insertSubscriberData,
  deleteSubscriberData,
   forwardCheckSS-Indication,
  restoreData,
  provideSubscriberInfo,
   anyTimeInterrogation,
   anyTimeSubscriptionInterrogation,
   anyTimeModification,
   sendRoutingInfoForGprs,
   failureReport,
  noteMsPresentForGprs,
  noteMM-Event,
  noteSubscriberDataModified
FROM MAP-MobileServiceOperations {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-MobileServiceOperations (5)
   version9 (9)}
   activateTraceMode,
  deactivateTraceMode,
FROM MAP-OperationAndMaintenanceOperations {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-OperationAndMaintenanceOperations (6)
   version9 (9)}
   sendRoutingInfo,
   provideRoamingNumber,
   resumeCallHandling,
   setReportingState,
   statusReport,
```

```
remoteUserFree,
   ist-Alert,
  ist-Command.
  releaseResources
FROM MAP-CallHandlingOperations {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-CallHandlingOperations (7)
   version9 (9)}
   registerSS,
   eraseSS,
   activateSS
   deactivateSS.
   interrogateSS,
   processUnstructuredSS-Request,
   unstructuredSS-Request,
   unstructuredSS-Notify,
   registerPassword,
   getPassword,
   ss-InvocationNotification,
  registerCC-Entry,
   eraseCC-Entry
FROM MAP-SupplementaryServiceOperations {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-SupplementaryServiceOperations (8)
   version9 (9)}
   sendRoutingInfoForSM,
   mo-ForwardSM,
   mt-ForwardSM,
   reportSM-DeliveryStatus,
   alertServiceCentre,
   informServiceCentre,
   readyForSM
FROM MAP-ShortMessageServiceOperations {
  itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-ShortMessageServiceOperations (9)
   version9 (9)}
   prepareGroupCall,
   processGroupCallSignalling,
   forwardGroupCallSignalling,
   sendGroupCallEndSignal
FROM MAP-Group-Call-Operations {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-Group-Call-Operations (22)
   version9 (9)}
  provideSubscriberLocation,
   sendRoutingInfoForLCS,
   subscriberLocationReport
FROM MAP-LocationServiceOperations {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-LocationServiceOperations (24)
   version9 (9)}
Supported-MAP-Operations OPERATION ::= {updateLocation | cancelLocation | purgeMS |
   sendIdentification | updateGprsLocation | prepareHandover | sendEndSignal |
   processAccessSignalling | forwardAccessSignalling | prepareSubsequentHandover |
   \tt sendAuthenticationInfo \mid authenticationFailureReport \mid checkIMEI \mid insertSubscriberData \mid
   deleteSubscriberData | reset | forwardCheckSS-Indication | restoreData | provideSubscriberInfo | anyTimeInterrogation | anyTimeSubscriptionInterrogation | anyTimeModification |
   sendRoutingInfoForGprs | failureReport | noteMsPresentForGprs | noteMM-Event
   noteSubscriberDataModified | activateTraceMode | deactivateTraceMode | sendIMSI |
   sendRoutingInfo | provideRoamingNumber | resumeCallHandling | setReportingState | statusReport |
remoteUserFree | ist-Alert | ist-Command | registerSS | eraseSS | activateSS | deactivateSS | interrogateSS
   processUnstructuredSS-Request | unstructuredSS-Request | unstructuredSS-Notify |
   registerPassword | getPassword | ss-InvocationNotification | registerCC-Entry | eraseCC-Entry |
   \verb| sendRoutingInfoForSM | \verb| mo-ForwardSM | \verb| mt-ForwardSM | reportSM-DeliveryStatus |
  alertServiceCentre | informServiceCentre | readyForSM | prepareGroupCall | processGroupCallSignalling | forwardGroupCallSignalling | sendGroupCallEndSignal |
   provideSubscriberLocation | sendRoutingInfoForLCS | subscriberLocationReport |
   releaseResources }
```

- -- The following operation codes are reserved for operations
- -- existing in previous versions of the protocol

Operation Name	AC used	Oper. Code
sendParameters	map-ac infoRetrieval (14) version1 (1)	local:9
processUnstructuredSS-Data	map-ac networkFunctionalSs (18) version1 (1)	local:19
performHandover	map-ac handoverControl (11) version1 (1)	local:28
performSubsequentHandover	map-ac handoverControl (11) version1 (1)	local:30
provideSIWFSNumber	map-ac sIWFSAllocation (12) version3 (3)	local:31
siwfs-SignallingModify	map-ac sIWFSAllocation (12) version3 (3)	local:32
noteInternalHandover	map-ac handoverControl (11) version1 (1)	local:35
noteSubscriberPresent	map-ac mwdMngt (24) version1 (1)	local:48
alertServiceCentreWithoutResult	map-ac shortMsgAlert (23) version1 (1)	local:49
traceSubscriberActivity	map-ac handoverControl (11) version1 (1)	local:52
beginSubscriberActivity	map-ac networkFunctionalSs (18) version1 (1)	local:54

- -- The following error codes are reserved for errors
- -- existing in previous versions of the protocol

Error Name	AC used	Error Code	
unknownBaseStation invalidTargetBaseStation noRadioResourceAvailable	map-ac handoverControl (11) version1 (1) map-ac handoverControl (11) version1 (1) map-ac handoverControl (11) version1 (1)	local:2 local:23 local:24	

17.6 MAP operations and errors

17.6.1 Mobile Service Operations

MAP-MobileServiceOperations {

```
itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-MobileServiceOperations (5)
   version9 (9)}
DEFINITIONS
::=
BEGIN
EXPORTS
   -- location registration operations
  updateLocation,
  cancelLocation,
  purgeMS,
  sendIdentification,
   -- gprs location registration operations
  updateGprsLocation,
   -- subscriber information enquiry operations
  provideSubscriberInfo,
   -- any time information enquiry operations
  anyTimeInterrogation,
   -- any time information handling operations
   anyTimeSubscriptionInterrogation,
  anyTimeModification,
   -- subscriber data modification notification operations
  noteSubscriberDataModified,
   -- handover operations
   prepareHandover,
   sendEndSignal,
  processAccessSignalling,
   forwardAccessSignalling,
  prepareSubsequentHandover,
```

```
-- authentication management operations
   sendAuthenticationInfo,
  authenticationFailureReport,
   -- IMEI management operations
  checkIMEI,
   -- subscriber management operations
   insertSubscriberData,
   deleteSubscriberData,
   -- fault recovery operations
  reset,
   forwardCheckSS-Indication,
   restoreData,
-- gprs location information retrieval operations
   sendRoutingInfoForGprs,
   -- failure reporting operations
  failureReport,
   -- gprs notification operations
  noteMsPresentForGprs,
   -- Mobility Management operations
  noteMM-Event
IMPORTS
  OPERATION
FROM Remote-Operations-Information-Objects {
  joint-iso-itu-t remote-operations(4)
  informationObjects(5) version1(0) }
   systemFailure,
   dataMissing,
   unexpectedDataValue,
   unknownSubscriber,
  unknownMSC,
  unidentifiedSubscriber,
  unknownEquipment,
   roamingNotAllowed,
   ati-NotAllowed,
  noHandoverNumberAvailable,
   subsequentHandoverFailure,
  absentSubscriber,
  mm-EventNotSupported,
  atsi-NotAllowed,
   atm-NotAllowed.
  bearerServiceNotProvisioned,
   teleserviceNotProvisioned,
   callBarred,
   illegalSS-Operation,
   ss-ErrorStatus,
   ss-NotAvailable,
   ss-Incompatibility,
   ss-SubscriptionViolation,
   informationNotAvailable,
   targetCellOutsideGroupCallArea
FROM MAP-Errors {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-Errors (10) version9 (9)}
   UpdateLocationArg,
   UpdateLocationRes,
   CancelLocationArg,
   CancelLocationRes,
   PurgeMS-Arg,
   PurgeMS-Res,
   SendIdentificationArg,
   SendIdentificationRes,
   UpdateGprsLocationArg,
   UpdateGprsLocationRes,
   PrepareHO-Arg,
   PrepareHO-Res,
```

```
ForwardAccessSignalling-Arg,
   ProcessAccessSignalling-Arg,
   SendEndSignal-Arg,
   SendEndSignal-Res,
   PrepareSubsequentHO-Res,
   PrepareSubsequentHO-Arg,
   SendAuthenticationInfoArg,
   SendAuthenticationInfoRes,
   AuthenticationFailureReportArg,
   AuthenticationFailureReportRes,
   CheckIMEI-Arg,
   CheckIMEI-Res,
   InsertSubscriberDataArg,
   InsertSubscriberDataRes,
   DeleteSubscriberDataArg,
   DeleteSubscriberDataRes,
   ResetArg,
   RestoreDataArg,
   RestoreDataRes,
   ProvideSubscriberInfoArg,
   ProvideSubscriberInfoRes,
   AnyTimeSubscriptionInterrogationArg,
  AnyTimeSubscriptionInterrogationRes,
   AnyTimeModificationArg,
   AnyTimeModificationRes,
   NoteSubscriberDataModifiedArg,
   NoteSubscriberDataModifiedRes,
   AnyTimeInterrogationArg,
   AnyTimeInterrogationRes,
   SendRoutingInfoForGprsArg,
   SendRoutingInfoForGprsRes,
   FailureReportArg,
   FailureReportRes,
   NoteMsPresentForGprsArg,
   NoteMsPresentForGprsRes,
  NoteMM-EventArg,
  NoteMM-EventRes
FROM MAP-MS-DataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-MS-DataTypes (11) version9 (9)}
-- location registration operations
```

```
updateLocation OPERATION ::= {
    ARGUMENT
        UpdateLocationArg
    RESULT
        UpdateLocationRes
    ERRORS {
        systemFailure |
        dataMissing |
        unexpectedDataValue |
        unknownSubscriber |
        roamingNotAllowed}
    CODE local:2 }
```

```
sendIdentification OPERATION ::= {
    ARGUMENT
        SendIdentificationArg
    RESULT
        SendIdentificationRes
    ERRORS {
        dataMissing |
            unidentifiedSubscriber}
    CODE local:55 }
```

-- gprs location registration operations

-- subscriber information enquiry operations

-- any time information enquiry operations

```
anyTimeInterrogation OPERATION ::= {
    ARGUMENT
        AnyTimeInterrogationArg
    RESULT
        AnyTimeInterrogationRes
    ERRORS {
        systemFailure |
        ati-NotAllowed |
        dataMissing |
        unexpectedDataValue |
        unknownSubscriber}
    CODE local:71 }
```

-- any time information handling operations

```
anyTimeSubscriptionInterrogation OPERATION ::= {
                                                                              --Timer m
    ARGUMENT
         AnyTimeSubscriptionInterrogationArg
    RESULT
        AnyTimeSubscriptionInterrogationRes
    ERRORS {
         atsi-NotAllowed |
         dataMissing
         unexpectedDataValue |
         unknownSubscriber
         bearerServiceNotProvisioned |
         teleserviceNotProvisioned |
         callBarred |
         illegalSS-Operation |
         ss-NotAvailable |
         informationNotAvailable}
    CODE local:62 }
```

```
anyTimeModification OPERATION ::= {
                                                                              --Timer m
    ARGUMENT
         AnyTimeModificationArg
    RESULT
         {\tt AnyTimeModificationRes}
    ERRORS {
         atm-NotAllowed |
         dataMissing
         unexpectedDataValue |
         unknownSubscriber
         bearerServiceNotProvisioned |
         teleserviceNotProvisioned |
         callBarred |
         illegalSS-Operation |
         ss-SubscriptionViolation |
         ss-ErrorStatus
         ss-Incompatibility
         informationNotAvailable}
    CODE local:65 }
```

-- subscriber data modification notification operations

-- handover operations

```
prepareHandover OPERATION ::= {
    ARGUMENT
        PrepareHO-Arg
    RESULT
        PrepareHO-Res
    ERRORS {
        systemFailure |
        dataMissing |
        unexpectedDataValue |
        noHandoverNumberAvailable |
        targetCellOutsideGroupCallArea }
    CODE local:68 }
```

```
sendEndSignal OPERATION ::= {
    ARGUMENT
        SendEndSignal-Arg
    RESULT
        SendEndSignal-Res
    CODE local:29 }
```

-- authentication management operations

```
sendAuthenticationInfo OPERATION ::= {
                                                                            --Timer m
    ARGUMENT
         SendAuthenticationInfoArg
         -- optional
         -- within a dialogue sendAuthenticationInfoArg shall not be present in
         -- subsequent invoke components. If received in a subsequent invoke component
         -- it shall be discarded.
    RESULT
         SendAuthenticationInfoRes
         -- optional
         systemFailure |
         dataMissing
         unexpectedDataValue |
         unknownSubscriber}
    CODE local:56 }
```

```
authenticationFailureReport OPERATION ::= {
    ARGUMENT
        AuthenticationFailureReportArg
    RESULT
        AuthenticationFailureReportRes
        -- optional
    ERRORS {
        systemFailure |
        unexpectedDataValue |
        unknownSubscriber}
    CODE local:15 }
```

-- IMEI management operations

```
checkIMEI OPERATION ::= {
    ARGUMENT
    CheckIMEI-Arg
    RESULT
    CheckIMEI-Res
    ERRORS {
        systemFailure |
        dataMissing |
        unknownEquipment}
    CODE local:43 }
```

-- subscriber management operations

-- fault recovery operations

```
forwardCheckSS-Indication OPERATION ::= {
    CODE local:38 }
```

-- gprs location information retrieval operations

-- failure reporting operations

⁻⁻ gprs notification operations

```
noteMM-Event OPERATION ::= {
    ARGUMENT
    NoteMM-EventArg
    RESULT
    NoteMM-EventRes
    ERRORS {
        dataMissing |
            unexpectedDataValue |
            unknownSubscriber |
            mm-EventNotSupported}
    CODE local:89 }
```

17.6.2 Operation and Maintenance Operations

```
MAP-OperationAndMaintenanceOperations {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-OperationAndMaintenanceOperations (6)
   version9 (9)}
DEFINITIONS
: :=
BEGIN
EXPORTS
  activateTraceMode,
  deactivateTraceMode,
  sendIMSI
IMPORTS
  OPERATION
FROM Remote-Operations-Information-Objects {
  joint-iso-itu-t remote-operations(4)
  informationObjects(5) version1(0) }
  systemFailure,
  dataMissing,
   unexpectedDataValue,
  facilityNotSupported,
  unknownSubscriber,
  unidentifiedSubscriber,
  tracingBufferFull
FROM MAP-Errors {
  itu-t identified-organization (4) etsi (0) mobileDomain (0)
  gsm-Network (1) modules (3) map-Errors (10) version9 (9)}
  ActivateTraceModeArg,
  ActivateTraceModeRes
  DeactivateTraceModeArg,
  DeactivateTraceModeRes
FROM MAP-OM-DataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-OM-DataTypes (12) version9 (9)}
   ISDN-AddressString,
  IMSI
FROM MAP-CommonDataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
  gsm-Network (1) modules (3) map-CommonDataTypes (18) version9 (9)}
```

```
activateTraceMode OPERATION ::= {
    ARGUMENT
    ActivateTraceModeArg
    RESULT
    ActivateTraceModeRes
    -- optional
    ERRORS {
        systemFailure |
        dataMissing |
        unexpectedDataValue |
        facilityNotSupported |
        unidentifiedSubscriber |
        tracingBufferFull}
    CODE local:50 }
```

```
deactivateTraceMode OPERATION ::= {
    ARGUMENT
        DeactivateTraceModeArg
    RESULT
        DeactivateTraceModeRes
        -- optional
    ERRORS {
        systemFailure |
        dataMissing |
        unexpectedDataValue |
        facilityNotSupported |
        unidentifiedSubscriber}
    CODE local:51 }
```

```
sendIMSI OPERATION ::= {
    ARGUMENT
        ISDN-AddressString
    RESULT
        IMSI
    ERRORS {
        dataMissing |
        unexpectedDataValue |
        unknownSubscriber}
    CODE local:58 }
```

17.6.3 Call Handling Operations

```
MAP-CallHandlingOperations {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-CallHandlingOperations (7)
   version9 (9)}
DEFINITIONS
BEGIN
EXPORTS
  sendRoutingInfo,
  provideRoamingNumber,
  resumeCallHandling,
  setReportingState,
  statusReport,
  remoteUserFree,
  ist-Alert,
  ist-Command,
  releaseResources
IMPORTS
  OPERATION
FROM Remote-Operations-Information-Objects \{
  joint-iso-itu-t remote-operations(4)
  informationObjects(5) version1(0) }
   systemFailure
  dataMissing,
  unexpectedDataValue,
```

```
facilityNotSupported,
   or-NotAllowed,
  unknownSubscriber,
   numberChanged,
   bearerServiceNotProvisioned,
   teleserviceNotProvisioned,
   noRoamingNumberAvailable,
   absentSubscriber,
  busySubscriber,
   noSubscriberReply,
   callBarred,
   forwardingViolation,
   forwardingFailed,
   cug-Reject,
   resourceLimitation,
   incompatibleTerminal,
  unidentifiedSubscriber
FROM MAP-Errors {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-Errors (10) version9 (9)}
   SendRoutingInfoArg,
   SendRoutingInfoRes,
   ProvideRoamingNumberArg,
   ProvideRoamingNumberRes,
   ResumeCallHandlingArg,
   ResumeCallHandlingRes,
   SetReportingStateArg,
   SetReportingStateRes,
   StatusReportArg,
   StatusReportRes,
   RemoteUserFreeArg,
  RemoteUserFreeRes,
   IST-AlertArg,
   IST-AlertRes,
   IST-CommandArg,
   IST-CommandRes,
  ReleaseResourcesArg,
   ReleaseResourcesRes
FROM MAP-CH-DataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-CH-DataTypes (13) version9 (9)}
    ARGUMENT
         SendRoutingInfoArg
    RESULT
         SendRoutingInfoRes
     ERRORS {
         systemFailure |
```

```
sendRoutingInfo OPERATION ::= {
                                                                             --Timer m
 - The timer is set to the upper limit of the range if the GMSC supports pre-paging.
         dataMissing
         unexpectedDataValue
         facilityNotSupported |
         or-NotAllowed |
         unknownSubscriber |
         numberChanged |
         bearerServiceNotProvisioned |
         teleserviceNotProvisioned |
         absentSubscriber |
         busySubscriber
         noSubscriberReply |
         callBarred
         cug-Reject
         forwardingViolation}
     CODE local:22 }
```

```
provideRoamingNumber OPERATION ::= {
                                                                            --Timer m
-- The timer is set to the upper limit of the range if the HLR supports pre-paging.
    ARGUMENT
         ProvideRoamingNumberArg
    RESULT
        ProvideRoamingNumberRes
    ERRORS {
         systemFailure |
         dataMissing |
         unexpectedDataValue |
         facilityNotSupported |
         or-NotAllowed
         absentSubscriber
         noRoamingNumberAvailable}
    CODE local:4 }
```

```
resumeCallHandling OPERATION ::= {
    ARGUMENT
    ResumeCallHandlingArg
    RESULT
    ResumeCallHandlingRes
    -- optional
    ERRORS {
        forwardingFailed |
            or-NotAllowed |
            unexpectedDataValue |
            dataMissing }
    CODE local:6 }
```

```
setReportingState OPERATION ::= {
    ARGUMENT
    SetReportingStateArg
RESULT
    SetReportingStateRes
    -- optional
ERRORS {
    systemFailure |
    unidentifiedSubscriber |
    unexpectedDataValue |
    dataMissing |
    resourceLimitation |
    facilityNotSupported}
CODE local:73 }
```

```
statusReport OPERATION ::= {
    ARGUMENT
    StatusReportArg
RESULT
    StatusReportRes
    -- optional
ERRORS {
    unknownSubscriber |
    systemFailure |
    unexpectedDataValue |
    dataMissing}
CODE local:74 }
```

```
remoteUserFree OPERATION ::= {
    ARGUMENT
    RemoteUserFreeArg
    RESULT
    RemoteUserFreeRes
    ERRORS {
        unexpectedDataValue |
        dataMissing |
        incompatibleTerminal |
        absentSubscriber |
        systemFailure |
        busySubscriber}
    CODE local:75 }
```

```
ist-Alert OPERATION ::= {
    ARGUMENT
        IST-AlertArg
    RESULT
        IST-AlertRes
        -- optional
    ERRORS {
        unexpectedDataValue |
        resourceLimitation |
        unknownSubscriber |
        systemFailure |
        facilityNotSupported}
    CODE local:87 }
```

```
ist-Command OPERATION::= {
    ARGUMENT
        IST-CommandArg
    RESULT
        IST-CommandRes
        -- optional
    ERRORS {
        unexpectedDataValue |
        resourceLimitation |
        unknownSubscriber |
        systemFailure |
        facilityNotSupported}
    CODE local:88 }
```

```
releaseResources OPERATION::= {
    ARGUMENT
    ReleaseResourcesArg
    RESULT
    ReleaseResourcesRes
    -- optional
    ERRORS {
        unexpectedDataValue |
        systemFailure }
    CODE local:20 }
```

17.6.4 Supplementary service operations

```
MAP-SupplementaryServiceOperations {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-SupplementaryServiceOperations (8)
  version9 (9)}
DEFINITIONS
: :=
BEGIN
EXPORTS
  registerSS.
  eraseSS,
  activateSS,
  deactivateSS,
  interrogateSS,
  processUnstructuredSS-Request,
  unstructuredSS-Request,
  unstructuredSS-Notify,
  registerPassword,
  getPassword,
  ss-InvocationNotification,
  registerCC-Entry,
   eraseCC-Entry
IMPORTS
  OPERATION
FROM Remote-Operations-Information-Objects {
  joint-iso-itu-t remote-operations(4)
  informationObjects(5) version1(0) }
   systemFailure,
   dataMissing,
```

```
unexpectedDataValue,
  unknownSubscriber,
  bearerServiceNotProvisioned,
   teleserviceNotProvisioned,
   callBarred,
  illegalSS-Operation,
   ss-ErrorStatus,
  ss-NotAvailable
   ss-SubscriptionViolation,
   ss-Incompatibility,
  pw-RegistrationFailure,
  negativePW-Check,
  numberOfPW-AttemptsViolation,
   unknownAlphabet,
   ussd-Busy,
   absentSubscriber,
   illegalSubscriber,
   illegalEquipment,
   shortTermDenial,
   longTermDenial,
   facilityNotSupported
FROM MAP-Errors
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-Errors (10) version9 (9)}
  RegisterSS-Arg,
  SS-Info,
  SS-ForBS-Code,
   InterrogateSS-Res,
   USSD-Arg,
  USSD-Res,
  Password.
  GuidanceInfo,
   SS-InvocationNotificationArg,
   SS-InvocationNotificationRes,
  RegisterCC-EntryArg,
  RegisterCC-EntryRes,
  EraseCC-EntryArg,
  EraseCC-EntryRes
FROM MAP-SS-DataTypes {
  itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-SS-DataTypes (14) version9 (9)}
  SS-Code
FROM MAP-SS-Code {
  itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-SS-Code (15) version9 (9)}
```

-- supplementary service handling operations

```
registerSS OPERATION ::= {
                                                                             --Timer m
    ARGUMENT
        RegisterSS-Arg
    RESULT
        SS-Info
         -- optional
    ERRORS {
         systemFailure |
         dataMissing
         unexpectedDataValue |
         bearerServiceNotProvisioned |
         teleserviceNotProvisioned |
         callBarred |
         illegalSS-Operation |
         ss-ErrorStatus
         ss-Incompatibility}
    CODE local:10 }
```

```
eraseSS OPERATION ::= {
                                                                            --Timer m
    ARGUMENT
        SS-ForBS-Code
    RESULT
        SS-Info
         -- optional
    ERRORS {
        systemFailure |
         dataMissing
         unexpectedDataValue
         bearerServiceNotProvisioned |
         teleserviceNotProvisioned |
         callBarred |
         illegalSS-Operation |
         ss-ErrorStatus
    CODE local:11 }
```

```
activateSS OPERATION ::= {
                                                                             --Timer m
    ARGUMENT
        SS-ForBS-Code
    RESULT
         SS-Info
         -- optional
    ERRORS {
         systemFailure |
         dataMissing |
         unexpectedDataValue |
         bearerServiceNotProvisioned |
         teleserviceNotProvisioned |
         callBarred |
         illegalSS-Operation |
         ss-ErrorStatus
         ss-SubscriptionViolation |
         ss-Incompatibility |
         negativePW-Check
         numberOfPW-AttemptsViolation}
    CODE local:12 }
```

```
deactivateSS OPERATION ::= {
                                                                            --Timer m
    ARGUMENT
         SS-ForBS-Code
    RESULT
         SS-Info
         -- optional
    ERRORS {
         systemFailure |
         dataMissing |
         unexpectedDataValue
         bearerServiceNotProvisioned |
         teleserviceNotProvisioned |
         callBarred |
         illegalSS-Operation |
         ss-ErrorStatus
         ss-SubscriptionViolation |
         negativePW-Check
         numberOfPW-AttemptsViolation}
    CODE local:13
```

```
interrogateSS OPERATION ::= {
                                                                               --Timer m
    ARGUMENT
         SS-ForBS-Code
    RESULT
         InterrogateSS-Res
    ERRORS {
         systemFailure |
         dataMissing |
         unexpectedDataValue |
         bearerServiceNotProvisioned |
         teleserviceNotProvisioned |
         callBarred
         \verb|illegalSS-Operation||
         ss-NotAvailable}
    CODE local:14 }
```

```
unstructuredSS-Request OPERATION ::= {
                                                                             --Timer ml
    ARGUMENT
         USSD-Arg
    RESULT
         USSD-Res
         -- optional
    ERRORS {
         systemFailure |
         dataMissing
         unexpectedDataValue |
         absentSubscriber |
         illegalSubscriber |
         illegalEquipment |
         unknownAlphabet |
         ussd-Busy
    CODE local:60
```

```
unstructuredSS-Notify OPERATION ::= {
    ARGUMENT
    USSD-Arg
    RETURN RESULT TRUE
    ERRORS {
        systemFailure |
        dataMissing |
        unexpectedDataValue |
        absentSubscriber |
        illegalSubscriber |
        illegalEquipment |
        unknownAlphabet |
        ussd-Busy}
    CODE local:61 }
```

```
registerPassword OPERATION ::= {
                                                                             --Timer ml
    ARGUMENT
         SS-Code
    RESULT
         Password
    ERRORS {
         systemFailure |
         dataMissing
         unexpectedDataValue |
         callBarred |
         ss-SubscriptionViolation |
         pw-RegistrationFailure |
         negativePW-Check |
         numberOfPW-AttemptsViolation}
    LINKED {
         getPassword}
    CODE local:17 }
```

```
getPassword OPERATION ::= {
    ARGUMENT
    GuidanceInfo
    RESULT
    Password
    CODE local:18 }
```

```
ss-InvocationNotification OPERATION ::= {
    ARGUMENT
        SS-InvocationNotificationArg
    RESULT
        SS-InvocationNotificationRes
        -- optional
    ERRORS {
        dataMissing |
            unexpectedDataValue |
            unknownSubscriber}
    CODE local:72 }
```

```
registerCC-Entry OPERATION ::= {
                                                                              --Timer m
    ARGUMENT
         RegisterCC-EntryArg
    RESULT
         RegisterCC-EntryRes
    ERRORS {
         systemFailure |
         dataMissing
         unexpectedDataValue |
         callBarred |
         illegalSS-Operation |
         ss-ErrorStatus
         ss-Incompatibility |
         shortTermDenial |
         longTermDenial |
         facilityNotSupported}
    CODE local:76 }
```

17.6.5 Short message service operations

```
MAP-ShortMessageServiceOperations {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-ShortMessageServiceOperations (9)
   version9 (9)}
DEFINITIONS
::=
BEGIN
EXPORTS
  sendRoutingInfoForSM,
  mo-ForwardSM,
  mt-ForwardSM,
  reportSM-DeliveryStatus,
  alertServiceCentre,
  informServiceCentre,
   readyForSM
IMPORTS
  OPERATION
FROM Remote-Operations-Information-Objects \{
  joint-iso-itu-t remote-operations(4)
  informationObjects(5) version1(0) }
   systemFailure
   dataMissing,
   unexpectedDataValue,
```

```
facilityNotSupported,
  unknownSubscriber,
  unidentifiedSubscriber,
   illegalSubscriber,
   illegalEquipment,
   teleserviceNotProvisioned,
   callBarred,
   subscriberBusyForMT-SMS,
   sm-DeliveryFailure,
  messageWaitingListFull,
  absentSubscriberSM
FROM MAP-Errors {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-Errors (10) version9 (9)}
   RoutingInfoForSM-Arg,
  RoutingInfoForSM-Res,
  MO-ForwardSM-Arg,
  MO-ForwardSM-Res,
  MT-ForwardSM-Arg,
  MT-ForwardSM-Res,
  ReportSM-DeliveryStatusArg,
  ReportSM-DeliveryStatusRes,
   AlertServiceCentreArg,
   InformServiceCentreArg,
  ReadyForSM-Arg,
  ReadyForSM-Res
FROM MAP-SM-DataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
  gsm-Network (1) modules (3) map-SM-DataTypes (16) version9 (9)}
```

```
sendRoutingInfoForSM OPERATION ::= {
                                                                              --Timer m
    ARGUMENT
         RoutingInfoForSM-Arg
    RESULT
         RoutingInfoForSM-Res
    ERRORS {
         systemFailure |
         dataMissing |
         unexpectedDataValue |
         facilityNotSupported |
         unknownSubscriber |
         teleserviceNotProvisioned |
         callBarred |
         absentSubscriberSM}
    CODE local:45 }
```

```
mo-ForwardSM    OPERATION ::= {
          ARGUMENT
          MO-ForwardSM-Arg
          RESULT
          MO-ForwardSM-Res
          -- optional
          ERRORS {
                systemFailure |
                      unexpectedDataValue |
                     facilityNotSupported |
                      sm-DeliveryFailure}
          CODE local:46 }
```

```
mt-ForwardSM OPERATION ::= {
                                                                             --Timer ml
    ARGUMENT
        MT-ForwardSM-Arg
    RESULT
        MT-ForwardSM-Res
         -- optional
    ERRORS {
         systemFailure |
         dataMissing
         unexpectedDataValue |
         facilityNotSupported |
         unidentifiedSubscriber |
         illegalSubscriber |
         illegalEquipment |
         subscriberBusyForMT-SMS |
         sm-DeliveryFailure |
         absentSubscriberSM}
     CODE local:44 }
```

```
alertServiceCentre OPERATION ::= {
    ARGUMENT
    AlertServiceCentreArg
    RETURN RESULT TRUE
    ERRORS {
        systemFailure |
        dataMissing |
        unexpectedDataValue}
    CODE local:64 }
```

```
informServiceCentre OPERATION ::= {
          ARGUMENT
          InformServiceCentreArg
          CODE local:63 }
```

```
readyForSM OPERATION ::= {
    ARGUMENT
    ReadyForSM-Arg
    RESULT
    ReadyForSM-Res
    -- optional
    ERRORS {
    dataMissing |
    unexpectedDataValue |
    facilityNotSupported |
    unknownSubscriber}
    CODE local:66 }
```

17.6.6 Errors

```
MAP-Errors {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-Errors (10) version9 (9) }

DEFINITIONS
::=
BEGIN

EXPORTS
   -- generic errors
   systemFailure,
```

dataMissing,
unexpectedDataValue,
facilityNotSupported,
incompatibleTerminal,
resourceLimitation,

- -- identification and numbering errors unknownSubscriber, numberChanged, unknownMSC, unidentifiedSubscriber, unknownEquipment,
- -- subscription errors roamingNotAllowed, illegalSubscriber, illegalEquipment, bearerServiceNotProvisioned, teleserviceNotProvisioned,
- -- handover errors
 noHandoverNumberAvailable,
 subsequentHandoverFailure,
 targetCellOutsideGroupCallArea,
- -- operation and maintenance errors tracingBufferFull,
- -- call handling errors or-NotAllowed, noRoamingNumberAvailable, busySubscriber, noSubscriberReply, absentSubscriber, callBarred, forwardingViolation, forwardingFailed, cug-Reject,
- -- any time interrogation errors ati-NotAllowed,
- -- any time information handling errors
 atsi-NotAllowed,
 atm-NotAllowed,
 informationNotAvailable,
- -- supplementary service errors illegalSS-Operation, ss-ErrorStatus, ss-NotAvailable, ss-SubscriptionViolation, ss-Incompatibility, unknownAlphabet, ussd-Busy, pw-RegistrationFailure, negativePW-Check, numberOfPW-AttemptsViolation, shortTermDenial, longTermDenial,
- -- short message service errors subscriberBusyForMT-SMS, sm-DeliveryFailure, messageWaitingListFull, absentSubscriberSM,
- -- Group Call errors noGroupCallNumberAvailable,
- -- location service errors
 unauthorizedRequestingNetwork,
 unauthorizedLCSClient,
 positionMethodFailure,
 unknownOrUnreachableLCSClient,
- -- Mobility Management errors mm-EventNotSupported

;

```
IMPORTS
  ERROR
FROM Remote-Operations-Information-Objects {joint-iso-itu-t remote-operations(4)
  informationObjects(5) version1(0) }
  SS-Status
FROM MAP-SS-DataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-SS-DataTypes (14) version9 (9)}
   SS-IncompatibilityCause,
   PW-RegistrationFailureCause,
   SM-DeliveryFailureCause,
   SystemFailureParam,
   DataMissingParam,
   UnexpectedDataParam,
   FacilityNotSupParam,
   UnknownSubscriberParam,
   NumberChangedParam,
   UnidentifiedSubParam,
   RoamingNotAllowedParam,
   IllegalSubscriberParam,
   IllegalEquipmentParam,
   BearerServNotProvParam,
   TeleservNotProvParam,
   TracingBufferFullParam,
   NoRoamingNbParam,
   OR-NotAllowedParam,
   AbsentSubscriberParam,
   BusySubscriberParam,
  NoSubscriberReplyParam,
   CallBarredParam,
   ForwardingViolationParam,
   ForwardingFailedParam,
   CUG-RejectParam,
   ATI-NotAllowedParam,
   SubBusyForMT-SMS-Param,
   MessageWaitListFullParam,
   AbsentSubscriberSM-Param.
   ResourceLimitationParam,
  NoGroupCallNbParam,
   IncompatibleTerminalParam,
   ShortTermDenialParam,
   LongTermDenialParam.
   UnauthorizedRequestingNetwork-Param,
   UnauthorizedLCSClient-Param,
   PositionMethodFailure-Param,
   UnknownOrUnreachableLCSClient-Param,
  MM-EventNotSupported-Param,
   ATSI-NotAllowedParam,
  ATM-NotAllowedParam,
   IllegalSS-OperationParam,
   SS-NotAvailableParam,
  SS-SubscriptionViolationParam,
   InformationNotAvailableParam,
TargetCellOutsideGCA-Param
FROM MAP-ER-DataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-ER-DataTypes (17) version9 (9)}
-- generic errors
systemFailure ERROR ::= {
    PARAMETER
         SystemFailureParam
         -- optional
    CODE local:34 }
dataMissing ERROR ::= {
    PARAMETER
         DataMissingParam
         -- optional
          -- DataMissingParam must not be used in version <3
    CODE local:35 }
```

PARAMETER

```
unexpectedDataValue ERROR ::= {
    PARAMETER
         UnexpectedDataParam
         -- optional
          -- UnexpectedDataParam must not be used in version <3
    CODE local:36 }
facilityNotSupported ERROR ::= {
    PARAMETER
         FacilityNotSupParam
         -- optional
          -- FacilityNotSupParam must not be used in version <3
    CODE local:21 }
incompatibleTerminal ERROR ::= {
    PARAMETER
         IncompatibleTerminalParam
          -- optional
    CODE local:28 }
resourceLimitation ERROR ::= {
    PARAMETER
        ResourceLimitationParam
          -- optional
    CODE local:51 }
-- identification and numbering errors
unknownSubscriber ERROR ::= {
    PARAMETER
         UnknownSubscriberParam
          -- optional
          -- UnknownSubscriberParam must not be used in version <3
    CODE local:1 }
numberChanged ERROR ::= {
    PARAMETER
         NumberChangedParam
          -- optional
     CODE local:44 }
unknownMSC ERROR ::= {
    CODE local:3 }
unidentifiedSubscriber ERROR ::= {
    PARAMETER
         UnidentifiedSubParam
         -- optional
         -- UunidentifiedSubParam must not be used in version <3
    CODE local:5 }
unknownEquipment ERROR ::= {
    CODE local:7 }
-- subscription errors
roamingNotAllowed ERROR ::= {
     PARAMETER
         RoamingNotAllowedParam
    CODE local:8 }
illegalSubscriber ERROR ::= {
    PARAMETER
         IllegalSubscriberParam
          -- optional
          -- IllegalSubscriberParam must not be used in version <3
    CODE local:9 }
illegalEquipment ERROR ::= {
    PARAMETER
         IllegalEquipmentParam
          -- optional
          -- IllegalEquipmentParam must not be used in version <3
    CODE local:12 }
\verb|bearerServiceNotProvisioned| | ERROR : := \{ \\
```

```
BearerServNotProvParam
          -- optional
         -- BearerServNotProvParam must not be used in version <3
     CODE local:10 }
teleserviceNotProvisioned ERROR ::= {
    PARAMETER
         TeleservNot.ProvParam
         -- optional
         -- TeleservNotProvParam must not be used in version <3
-- handover errors
noHandoverNumberAvailable ERROR ::= {
    CODE local:25 }
subsequentHandoverFailure ERROR ::= {
    CODE local:26 }
targetCellOutsideGroupCallArea ERROR ::= {
    PARAMETER
         TargetCellOutsideGCA-Param
          -- optional
     CODE local:42 }
-- operation and maintenance errors
tracingBufferFull ERROR ::= {
   PARAMETER
         TracingBufferFullParam
          -- optional
     CODE local: 40 }
-- call handling errors
noRoamingNumberAvailable ERROR ::= {
    PARAMETER
         NoRoamingNbParam
         -- optional
     CODE local:39 }
absentSubscriber ERROR ::= {
    PARAMETER
         AbsentSubscriberParam
         -- optional
          -- AbsentSubscriberParam must not be used in version <3
     CODE local:27 }
busySubscriber ERROR ::= {
    PARAMETER
        BusySubscriberParam
          -- optional
     CODE local:45 }
noSubscriberReply ERROR ::= {
    PARAMETER
         NoSubscriberReplyParam
          -- optional
     CODE local:46 }
callBarred ERROR ::= {
    PARAMETER
         CallBarredParam
         -- optional
     CODE local:13 }
forwardingViolation ERROR ::= {
    PARAMETER
         ForwardingViolationParam
         -- optional
     CODE local:14 }
```

```
forwardingFailed ERROR ::= {
    PARAMETER
        ForwardingFailedParam
         -- optional
    CODE local:47 }
cug-Reject ERROR ::= {
    PARAMETER
         CUG-RejectParam
         -- optional
    CODE local:15 }
or-NotAllowed ERROR ::= {
    PARAMETER
        OR-NotAllowedParam
         -- optional
    CODE local:48 }
 - any time interrogation errors
ati-NotAllowed ERROR ::= {
    PARAMETER
        ATI-NotAllowedParam
         -- optional
    CODE local:49 }
 - any time information handling errors
atsi-NotAllowed ERROR ::= {
    PARAMETER
        ATSI-NotAllowedParam
         -- optional
    CODE local:60 }
atm-NotAllowed ERROR ::= {
    PARAMETER
       ATM-NotAllowedParam
         -- optional
    CODE local:61 }
PARAMETER
         InformationNotAvailableParam
         -- optional
    CODE local:62 }
-- supplementary service errors
illegalSS-Operation ERROR ::= {
    PARAMETER
         IllegalSS-OperationParam
         -- optional
         -- IllegalSS-OperationParam must not be used in version <3
    CODE local:16 }
ss-ErrorStatus ERROR ::= {
    PARAMETER
        SS-Status
         -- optional
    CODE local:17 }
ss-NotAvailable ERROR ::= {
    PARAMETER
         SS-NotAvailableParam
         -- optional
         -- SS-NotAvailableParam must not be used in version <3
    CODE local:18 }
ss-SubscriptionViolation ERROR ::= {
    PARAMETER
         SS-SubscriptionViolationParam
         -- optional
         -- SS-SubscriptionViolationParam must not be used in version <3
    CODE local:19 }
```

```
ss-Incompatibility ERROR ::= {
    PARAMETER
        SS-IncompatibilityCause
         -- optional
    CODE local:20 }
unknownAlphabet ERROR ::= {
    CODE local:71 }
ussd-Busy ERROR ::= {
    CODE local:72 }
pw-RegistrationFailure ERROR ::= {
    PARAMETER
         PW-RegistrationFailureCause
     CODE local:37 }
negativePW-Check ERROR ::= {
    CODE local:38 }
numberOfPW-AttemptsViolation ERROR ::= {
    CODE local:43 }
shortTermDenial ERROR ::= {
    PARAMETER
         ShortTermDenialParam
         -- optional
    CODE local:29 }
longTermDenial ERROR ::= {
    PARAMETER
         LongTermDenialParam
         -- optional
    CODE local:30 }
-- short message service errors
subscriberBusyForMT-SMS ERROR ::= {
    PARAMETER
         SubBusyForMT-SMS-Param
         -- optional
    CODE local:31 }
sm-DeliveryFailure ERROR ::= {
    PARAMETER
         SM-DeliveryFailureCause
     CODE local:32 }
messageWaitingListFull ERROR ::= {
     PARAMETER
         MessageWaitListFullParam
          -- optional
    CODE local:33 }
absentSubscriberSM ERROR ::= {
    PARAMETER
         AbsentSubscriberSM-Param
          -- optional
    CODE local:6 }
-- Group Call errors
noGroupCallNumberAvailable ERROR ::= {
    PARAMETER
         NoGroupCallNbParam
          -- optional
    CODE local:50 }
-- location service errors
unauthorizedRequestingNetwork ERROR ::= {
         UnauthorizedRequestingNetwork-Param
          -- optional
    CODE local:52 }
```

```
unauthorizedLCSClient ERROR ::= {
    PARAMETER
        UnauthorizedLCSClient-Param
        -- optional
        CODE local:53 }
```

```
positionMethodFailure ERROR ::= {
    PARAMETER
    PositionMethodFailure-Param
    -- optional
    CODE local:54 }
```

```
unknownOrUnreachableLCSClient ERROR ::= {
    PARAMETER
        UnknownOrUnreachableLCSClient-Param
        -- optional
        CODE local:58 }
```

END

17.6.7 Group Call operations

```
{\tt MAP-Group-Call-Operations} \ \ \{
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
  gsm-Network (1) modules (3) map-Group-Call-Operations (22)
  version9 (9)}
DEFINITIONS
: :=
BEGIN
EXPORTS
  prepareGroupCall,
   sendGroupCallEndSignal,
  forwardGroupCallSignalling,
  processGroupCallSignalling
IMPORTS
  OPERATION
FROM Remote-Operations-Information-Objects {
  joint-iso-itu-t remote-operations(4)
  informationObjects(5) version1(0) }
   systemFailure,
  unexpectedDataValue,
  noGroupCallNumberAvailable
FROM MAP-Errors {
  itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-Errors (10) version9 (9)}
   PrepareGroupCallArg,
   PrepareGroupCallRes,
   SendGroupCallEndSignalArg,
   SendGroupCallEndSignalRes,
  ForwardGroupCallSignallingArg,
  ProcessGroupCallSignallingArg
FROM MAP-GR-DataTypes \{
   itu-t identified-organization (4) etsi (0) mobile
Domain (0)
   gsm-Network (1) modules (3) map-GR-DataTypes (23) version9 (9)}
```

```
sendGroupCallEndSignal OPERATION ::= {
    ARGUMENT
        SendGroupCallEndSignalArg
    RESULT
        SendGroupCallEndSignalRes
    CODE local:40 }
```

```
processGroupCallSignalling OPERATION ::= {
          ARGUMENT
          ProcessGroupCallSignallingArg
          CODE local:41 }
```

```
forwardGroupCallSignalling OPERATION ::= {
    ARGUMENT
    ForwardGroupCallSignallingArg
    CODE local:42 }
```

END

17.6.8 Location service operations

```
MAP-LocationServiceOperations {
 1
2
3
4
       itu-t identified-organization (4) etsi (0) mobileDomain (0)
       gsm-Network (1) modules (3) map-LocationServiceOperations (24)
       version9 (9)}
 5
6
7
8
9
    DEFINITIONS
10
    BEGIN
11
12
    EXPORTS
13
       provideSubscriberLocation,
14
       sendRoutingInfoForLCS,
15
       subscriberLocationReport
16
17
18
   IMPORTS
19
       OPERATION
20
21
22
23
24
25
26
27
28
29
30
31
32
33
34
35
36
37
38
   FROM Remote-Operations-Information-Objects {
       joint-iso-itu-t remote-operations(4)
      informationObjects(5) version1(0) }
       systemFailure,
       dataMissing,
       unexpectedDataValue,
       facilityNotSupported,
       unknownSubscriber,
       absentSubscriber,
       unauthorizedRequestingNetwork,
       unauthorizedLCSClient,
       positionMethodFailure,
       resourceLimitation,
       unknownOrUnreachableLCSClient,
       unidentifiedSubscriber,
       illegalEquipment,
       illegalSubscriber
    FROM MAP-Errors {
39
       itu-t identified-organization (4) etsi (0) mobileDomain (0)
40
       gsm-Network (1) modules (3) map-Errors (10) version9 (9)}
41
42
43
       RoutingInfoForLCS-Arg,
       RoutingInfoForLCS-Res,
       ProvideSubscriberLocation-Arg,
       ProvideSubscriberLocation-Res,
       SubscriberLocationReport-Arg,
```

```
47
        SubscriberLocationReport-Res
48
    FROM MAP-LCS-DataTypes {
        itu-t identified-organization (4) etsi (0) mobileDomain (0)
50
51
52
53
54
55
56
57
58
59
        gsm-Network (1) modules (3) map-LCS-DataTypes (25) version9 (9)}
    sendRoutingInfoForLCS OPERATION ::= {
                                                                                        --Timer m
          ARGUMENT
               RoutingInfoForLCS-Arg
          RESULT
              RoutingInfoForLCS-Res
          ERRORS {
               systemFailure
60
               dataMissing
61
               unexpectedDataValue
62
               facilityNotSupported |
63
               unknownSubscriber
64
               absentSubscriber
65
               unauthorizedRequestingNetwork }
66
          CODE local:85 }
67
68
    provideSubscriberLocation OPERATION ::= {
                                                                                          --Timer ml
69
70
71
72
73
74
75
76
77
78
80
81
82
83
84
85
          ARGUMENT
               ProvideSubscriberLocation-Arg
          RESULT
               ProvideSubscriberLocation-Res
          ERRORS {
               systemFailure
               dataMissing
               unexpectedDataValue |
               facilityNotSupported
               unidentifiedSubscriber |
               illegalSubscriber |
               illegalEquipment
               absentSubscriber
               unauthorizedRequestingNetwork |
               unauthorizedLCSClient
               {\tt positionMethodFailure}
          CODE local:83
87
88
89
    subscriberLocationReport OPERATION ::= {
                                                                                        --Timer m
          ARGUMENT
               SubscriberLocationReport-Arg
90
          RESULT
91
92
93
94
               SubscriberLocationReport-Res
          ERRORS {
               systemFailure |
               dataMissing
95
               resourceLimitation |
96
               unexpectedDataValue |
97
98
               unknownSubscriber
               unauthorizedRequestingNetwork |
99
               unknownOrUnreachableLCSClient}
100
          CODE local:86 }
101
```

17.6.9 void

102 103

END

17.7 MAP constants and data types

17.7.1 Mobile Service data types

```
MAP-MS-DataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-MS-DataTypes (11) version9 (9) }
DEFINITIONS
IMPLICIT TAGS
::=
```

BEGIN

EXPORTS

```
-- location registration types
UpdateLocationArg,
UpdateLocationRes,
CancelLocationArg,
CancelLocationRes,
PurgeMS-Arg,
PurgeMS-Res,
SendIdentificationArg,
SendIdentificationRes,
UpdateGprsLocationArg,
UpdateGprsLocationRes,
IST-SupportIndicator,
SupportedLCS-CapabilitySets,
-- gprs location registration types
GSN-Address,
-- handover types
ForwardAccessSignalling-Arg,
PrepareHO-Arg,
PrepareHO-Res,
PrepareSubsequentHO-Arg,
PrepareSubsequentHO-Res,
ProcessAccessSignalling-Arg,
SendEndSignal-Arg,
SendEndSignal-Res,
-- authentication management types
SendAuthenticationInfoArg,
SendAuthenticationInfoRes,
AuthenticationFailureReportArg,
AuthenticationFailureReportRes,
-- security management types
Kc,
-- equipment management types
CheckIMEI-Arg,
CheckIMEI-Res,
-- subscriber management types
InsertSubscriberDataArg,
InsertSubscriberDataRes,
LSAIdentity,
DeleteSubscriberDataArg,
DeleteSubscriberDataRes,
Ext-QoS-Subscribed,
Ext2-QoS-Subscribed,
SubscriberData,
ODB-Data,
SubscriberStatus,
ZoneCodeList,
maxNumOfZoneCodes,
D-CSI,
O-BcsmCamelTDPCriteriaList,
T-BCSM-CAMEL-TDP-CriteriaList,
SS-CSI,
ServiceKey,
DefaultCallHandling,
CamelCapabilityHandling,
BasicServiceCriteria,
SupportedCamelPhases,
OfferedCamel4CSIs,
OfferedCamel4Functionalities,
maxNumOfCamelTDPData,
CUG-Index,
CUG-Info,
CUG-Interlock,
InterCUG-Restrictions,
IntraCUG-Options,
NotificationToMSUser,
QoS-Subscribed,
IST-AlertTimerValue,
```

```
T-CSI,
  T-BcsmTriggerDetectionPoint,
   -- fault recovery types
  ResetArg,
  RestoreDataArg,
  RestoreDataRes,
-- provide subscriber info types
   GeographicalInformation,
  MS-Classmark2,
  GPRSMSClass.
   -- subscriber information enquiry types
   ProvideSubscriberInfoArg,
   ProvideSubscriberInfoRes,
  SubscriberInfo.
  LocationInformation,
   LocationInformationGPRS,
  RAIdentity,
   SubscriberState,
  GPRSChargingID,
  MNPInfoRes,
  RouteingNumber,
   -- any time information enquiry types
  AnyTimeInterrogationArg,
   AnyTimeInterrogationRes,
   -- any time information handling types
  {\tt AnyTimeSubscriptionInterrogationArg,}
   AnyTimeSubscriptionInterrogationRes,
   AnyTimeModificationArg,
  AnyTimeModificationRes,
   -- subscriber data modification notification types
  NoteSubscriberDataModifiedArg,
  NoteSubscriberDataModifiedRes,
   -- gprs location information retrieval types
  SendRoutingInfoForGprsArg,
  SendRoutingInfoForGprsRes,
    -- failure reporting types
  FailureReportArg,
  FailureReportRes,
   -- gprs notification types
  NoteMsPresentForGprsArg,
  NoteMsPresentForGprsRes,
   -- Mobility Management types
  NoteMM-EventArg,
  NoteMM-EventRes,
  NumberPortabilityStatus
IMPORTS
  maxNumOfSS,
   SS-SubscriptionOption,
  SS-List,
  SS-ForBS-Code,
  Password
FROM MAP-SS-DataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
  gsm-Network (1) modules (3) map-SS-DataTypes (14) version9 (9)}
  SS-Code
FROM MAP-SS-Code {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-SS-Code (15) version9 (9)}
  Ext-BearerServiceCode
FROM MAP-BS-Code {
   itu-t identified-organization (4) etsi (0) mobile
Domain (0)
   gsm-Network (1) modules (3) map-BS-Code (20) version9 (9)}
```

-- location registration types

```
Ext-TeleserviceCode
FROM MAP-TS-Code {
  itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-TS-Code (19) version9 (9)}
  AddressString,
   ISDN-AddressString,
   ISDN-SubaddressString,
   FTN-AddressString,
   AccessNetworkSignalInfo,
  IMSI,
   IMEI.
  TMSI.
  HLR-List,
   LMSI,
   Identity,
   GlobalCellId.
   CellGlobalIdOrServiceAreaIdOrLAI,
   Ext-BasicServiceCode,
  NAEA-PreferredCI,
  EMLPP-Info,
  MC-SS-Info,
  SubscriberIdentity,
   AgeOfLocationInformation,
   LCSClientExternalID,
  LCSClientInternalID,
  Ext-SS-Status,
  LCSServiceTypeID,
   ASCI-CallReference,
  TBCD-STRING,
  LAIFixedLength
FROM MAP-CommonDataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-CommonDataTypes (18) version9 (9)}
  ExtensionContainer
FROM MAP-ExtensionDataTypes {
   itu-t identified-organization (4) etsi (0) mobile
Domain (0)
   gsm-Network (1) modules (3) map-ExtensionDataTypes (21) version9 (9)}
  AbsentSubscriberDiagnosticSM
FROM MAP-ER-DataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
  gsm-Network (1) modules (3) map-ER-DataTypes (17) version9 (9)}
  TracePropagationList
FROM MAP-OM-DataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-OM-DataTypes (12) version9 (9)}
```

<pre>UpdateLocationArg ::= SEQUENCE {</pre>				
imsi	IMSI,			
msc-Number	 ISDN-AddressString, 	[1] ISDN-AddressString,		
vlr-Number	ISDN-AddressString,			
lmsi	[10] LMSI	OPTIONAL,		
extensionContainer	ExtensionContainer	OPTIONAL,		
,				
vlr-Capability	<pre>[6] VLR-Capability</pre>	OPTIONAL,		
informPreviousNetworkEntity	[11] NULL	OPTIONAL,		
cs-LCS-NotSupportedByUE	[12] NULL	OPTIONAL,		
v-gmlc-Address	[2] GSN-Address	OPTIONAL,		
add-info	[13] ADD-Info	OPTIONAL }		

```
VLR-Capability ::= SEQUENCE{
    supportedCamelPhases
                                          [0] SupportedCamelPhases
                                                                            OPTIONAL,
    extensionContainer
                                         ExtensionContainer
                                                                            OPTIONAL,
                                          [2] NULL
    solsaSupportIndicator
                                                                            OPTIONAL,
    istSupportIndicator
                                          [1] IST-SupportIndicator
                                                                            OPTIONAL,
    superChargerSupportedInServingNetworkEntity
                                                   [3] SuperChargerInfo
                                                                            OPTIONAL,
    longFTN-Supported
                                          [4] NULL
                                                                            OPTIONAL,
    supportedLCS-CapabilitySets
                                          [5] SupportedLCS-CapabilitySets
                                                                            OPTIONAL.
    offeredCamel4CSIs
                                          [6] OfferedCamel4CSIs
                                                                            OPTIONAL
```

```
SuperChargerInfo ::= CHOICE {
                                             [0] NULL,
     sendSubscriberData
                                             [1] AgeIndicator }
     subscriberDataStored
AgeIndicator ::= OCTET STRING (SIZE (1..6))
     -- The internal structure of this parameter is implementation specific.
IST-SupportIndicator ::= ENUMERATED {
     basicISTSupported
                                             (0),
     istCommandSupported
                                             (1).
     . . . }
-- exception handling:
-- reception of values > 1 shall be mapped to ' istCommandSupported '
SupportedLCS-CapabilitySets ::= BIT STRING {
     lcsCapabilitySet1 (0),
     lcsCapabilitySet2 (1),
     lcsCapabilitySet3 (2),
     lcsCapabilitySet4 (3) } (SIZE (2..16))
-- Core network signalling capability set1 indicates LCS Release98 or Release99 version.
-- Core network signalling capability set2 indicates LCS Release4.
-- Core network signalling capability set3 indicates LCS Release5.
-- Core network signalling capability set4 indicates LCS Release6 or later version.
-- A node shall mark in the BIT STRING all LCS capability sets it supports.
-- If no bit is set then the sending node does not support LCS.
-- If the parameter is not sent by an VLR then the VLR may support at most capability set1.
-- If the parameter is not sent by an SGSN then no support for LCS is assumed.
-- An SGSN is not allowed to indicate support of capability set1.
-- Other bits than listed above shall be discarded.
UpdateLocationRes ::= SEQUENCE {
     hlr-Number
                                             ISDN-AddressString,
     extensionContainer
                                             ExtensionContainer
                                                                                  OPTIONAL,
     add-Capability
                                             NULL
                                                                                  OPTIONAL }
ADD-Info ::= SEQUENCE {
                                             [0] IMEI,
     imeisv
     skipSubscriberDataUpdate
                                             [1] NULL
                                                                                  OPTIONAL,
CancelLocationArg ::= [3] SEQUENCE {
     identity
                                             Identity,
     cancellationType
                                             CancellationType
                                                                                  OPTIONAL.
     extensionContainer
                                             ExtensionContainer
                                                                                  OPTIONAL,
CancellationType ::= ENUMERATED {
     updateProcedure
                                             (0),
     subscriptionWithdraw
                                             (1).
     -- The HLR shall not send values other than listed above
CancelLocationRes ::= SEQUENCE {
     extensionContainer
                                             ExtensionContainer
                                                                                  OPTIONAL,
PurgeMS-Arg ::= [3] SEQUENCE {
     imsi
                                             [0] ISDN-AddressString
     vlr-Number
                                                                                  OPTIONAL.
     sgsn-Number
                                             [1] ISDN-AddressString
                                                                                  OPTIONAL,
     extensionContainer
                                             ExtensionContainer
                                                                                  OPTIONAL,
PurgeMS-Res ::= SEQUENCE {
     freezeTMSI
                                             [0] NULL
                                                                                  OPTIONAL,
                                             [1] NULL
     freezeP-TMSI
                                                                                  OPTIONAL,
     {\tt extensionContainer}
                                             ExtensionContainer
                                                                                  OPTIONAL,
```

```
SendIdentificationArg ::= SEQUENCE {
                                           TMST.
                                           NumberOfRequestedVectors
     numberOfRequestedVectors
                                                                              OPTIONAL,
     -- within a dialogue numberOfRequestedVectors shall be present in
     -- the first service request and shall not be present in subsequent service requests.
     -- If received in a subsequent service request it shall be discarded.
     segmentationProhibited
                                           NULL
                                                                              OPTIONAL.
     extensionContainer
                                           ExtensionContainer
                                                                              OPTIONAL,
     msc-Number
                                           ISDN-AddressString
                                                                              OPTIONAL,
     previous-LAI
                                           [0] LAIFixedLength
                                                                              OPTIONAL,
     hopCounter
                                           [1] HopCounter
                                                                              OPTIONAL
HopCounter ::= INTEGER (0..3)
SendIdentificationRes ::= [3] SEQUENCE {
     imsi
                                           IMSI
                                                                              OPTIONAL,
     -- IMSI shall be present in the first (or only) service response of a dialogue.
     -- If multiple service requests are present in a dialogue then IMSI
     -- shall not be present in any service response other than the first one.
     authenticationSetList
                                                                              OPTIONAL,
                                          AuthenticationSetList
     {\tt currentSecurityContext}
                                           [2] CurrentSecurityContext
                                                                              OPTIONAL,
     extensionContainer
                                           [3] ExtensionContainer
                                                                              OPTIONAL,
-- authentication management types
AuthenticationSetList ::= CHOICE {
     tripletList
                                           [0] TripletList,
     quintupletList
                                           [1] QuintupletList }
TripletList ::= SEQUENCE SIZE (1..5) OF
                                           AuthenticationTriplet
QuintupletList ::= SEQUENCE SIZE (1..5) OF
                                           AuthenticationQuintuplet
AuthenticationTriplet ::= SEQUENCE {
                                           RAND.
     rand
     sres
                                           SRES,
     kc
                                           Kc,
AuthenticationQuintuplet ::= SEQUENCE {
                                           RAND,
     rand
     xres
                                           XRES.
     ck
                                           CK,
     ik
                                           IK,
                                           AUTN,
     autn
CurrentSecurityContext ::= CHOICE {
     gsm-SecurityContextData
                                           [0] GSM-SecurityContextData,
                                           [1] UMTS-SecurityContextData }
     umts-SecurityContextData
GSM-SecurityContextData ::= SEQUENCE {
                                           Kc,
     cksn
UMTS-SecurityContextData ::= SEQUENCE {
                                           CK,
     ck
     ik
                                           IK,
     ksi
                                           KSI,
RAND ::= OCTET STRING (SIZE (16))
SRES ::= OCTET STRING (SIZE (4))
Kc ::= OCTET STRING (SIZE (8))
XRES ::= OCTET STRING (SIZE (4..16))
CK ::= OCTET STRING (SIZE (16))
```

```
IK ::= OCTET STRING (SIZE (16))
AUTN ::= OCTET STRING (SIZE (16))
AUTS ::= OCTET STRING (SIZE (14))
Cksn ::= OCTET STRING (SIZE (1))
      -- The internal structure is defined in 3GPP TS 24.008
KSI ::= OCTET STRING (SIZE (1))
     -- The internal structure is defined in 3GPP TS 24.008
AuthenticationFailureReportArg ::= SEQUENCE
     imsi
                                            IMSI
     failureCause
                                            FailureCause,
     extensionContainer
                                            ExtensionContainer
                                                                                OPTIONAL,
     re-attempt
                                            BOOLEAN
                                                                                OPTIONAL,
     accessType
                                            AccessType
                                                                                OPTIONAL,
     rand
                                            RAND
                                                                                OPTIONAL,
     vlr-Number
                                            [0] ISDN-AddressString
                                                                                OPTIONAL,
     sgsn-Number
                                                ISDN-AddressString
                                                                                OPTIONAL
AccessType ::= ENUMERATED {
    call (0),
     emergencyCall (1),
     locationUpdating (2),
     supplementaryService (3),
     shortMessage (4),
     gprsAttach (5),
     routingAreaUpdating (6),
     serviceRequest (7),
     pdpContextActivation (8),
     pdpContextDeactivation (9),
     gprsDetach (10) }
      - exception handling:
      -- received values greater than 10 shall be ignored.
AuthenticationFailureReportRes ::= SEQUENCE {
                                                                                OPTIONAL,
     extensionContainer
                                            ExtensionContainer
FailureCause ::= ENUMERATED {
     wrongUserResponse (0),
     wrongNetworkSignature
-- gprs location registration types
UpdateGprsLocationArg ::= SEQUENCE {
                                            IMSI.
     imsi
     sgsn-Number
                                            ISDN-AddressString,
     sgsn-Address
                                            GSN-Address,
     extensionContainer
                                            ExtensionContainer
                                                                                OPTIONAL,
     sgsn-Capability
                                            [0] SGSN-Capability
                                                                                OPTIONAL.
     informPreviousNetworkEntity
                                            [1] NULL
                                                                                OPTIONAL,
     ps-LCS-NotSupportedByUE
                                            [2]
                                                NULL
                                                                                OPTIONAL,
                                                GSN-Address
     v-gmlc-Address
                                            [3]
                                                                                OPTIONAL,
     add-info
                                                ADD-Info
                                            [4]
                                                                                OPTIONAL
{\tt SGSN-Capability} \ ::= \ {\tt SEQUENCE} \big\{
     {\tt solsaSupportIndicator}
                                            NULL
                                                                                OPTIONAL.
     extensionContainer
                                            [1] ExtensionContainer
                                                                                OPTIONAL,
     superChargerSupportedInServingNetworkEntity
                                                     [2] SuperChargerInfo
                                                                                OPTIONAL ,
     gprsEnhancementsSupportIndicator
                                           [3] NULL
                                                                                OPTIONAL,
                                            [4] SupportedCamelPhases
     supportedCamelPhases
                                                                                OPTIONAL,
     supportedLCS-CapabilitySets
                                            [5] SupportedLCS-CapabilitySets
                                                                                OPTIONAL,
     offeredCamel4CSIs
                                            [6] OfferedCamel4CSIs
                                                                                OPTIONAL,
     \verb|smsCallBarringSupportIndicator| \\
                                            [7]
                                                NULL
                                                                                OPTIONAL
GSN-Address ::= OCTET STRING (SIZE (5..17))
      -- Octets are coded according to TS 3GPP TS 23.003 [17]
```

-- handover types

```
ForwardAccessSignalling-Arg ::= [3] SEQUENCE {
     an-APDU
                                              AccessNetworkSignalInfo,
     integrityProtectionInfo
                                              [0] IntegrityProtectionInformation OPTIONAL,
                                              [1] EncryptionInformation OPTIONAL,
     encryptionInfo
                                              [2] KeyStatus
[4] AllowedGSM-Algorithms
     kevStatus
                                                                                    OPTIONAL.
     allowedGSM-Algorithms
                                             [4] AllowedGSM-Algorithms OPTIONAL,
[5] AllowedUMTS-Algorithms OPTIONAL,
[6] RadioResourceInformation OPTIONAL,
[7] Puternal op Container
     allowedUMTS-Algorithms
     radioResourceInformation
     extensionContainer
                                             [3] ExtensionContainer
                                                                                    OPTIONAL,
                                             [7] RadioResourceList
     radioResourceList
                                                                                    OPTIONAL.
     bssmap-ServiceHandover
ranap-ServiceHandover
                                            [9] BSSMAP-ServiceHandover
[8] RANAP-ServiceHandover
                                                                                    OPTIONAL,
                                                                                    OPTIONAL,
     bssmap-ServiceHandoverList
                                             [10] BSSMAP-ServiceHandoverList
                                                                                    OPTIONAL,
     currentlyUsedCodec
                                             [11] Codec
[12] SupportedCodecsList
                                                                                    OPTIONAL.
     iuSupportedCodecsList
                                                                                    OPTIONAL,
     rab-ConfigurationIndicator
                                             [13] NULL
                                                                                    OPTIONAL,
     iuSelectedCodec
                                              [14] Codec
                                                                                    OPTIONAL,
     alternativeChannelType
                                             [15] RadioResourceInformation
                                                                                    OPTIONAL,
                                            [17] TracePropagationList
                                                                                    OPTIONAL 3
     tracePropagationList
```

```
AllowedGSM-Algorithms ::= OCTET STRING (SIZE (1))

-- internal structure is coded as Algorithm identifier octet from

-- Permitted Algorithms defined in 3GPP TS 48.008

-- A node shall mark all GSM algorithms that are allowed in MSC-B
```

```
AllowedUMTS-Algorithms ::= SEQUENCE {
    integrityProtectionAlgorithms [0] PermittedIntegrityProtectionAlgorithms
    OPTIONAL,
    encryptionAlgorithms [1] PermittedEncryptionAlgorithms OPTIONAL,
    extensionContainer [2] ExtensionContainer OPTIONAL,
    ...}
```

```
PermittedIntegrityProtectionAlgorithms ::=

OCTET STRING (SIZE (1..maxPermittedIntegrityProtectionAlgorithmsLength))

-- Octets contain a complete PermittedIntegrityProtectionAlgorithms data type

-- as defined in 3GPP TS 25.413, encoded according to the encoding scheme

-- mandated by 3GPP TS 25.413.

-- Padding bits are included, if needed, in the least significant bits of the

-- last octet of the octet string.
```

maxPermittedIntegrityProtectionAlgorithmsLength INTEGER ::= 9

```
PermittedEncryptionAlgorithms ::=

OCTET STRING (SIZE (1..maxPermittedEncryptionAlgorithmsLength))

-- Octets contain a complete PermittedEncryptionAlgorithms data type

-- as defined in 3GPP TS 25.413, encoded according to the encoding scheme

-- mandated by 3GPP TS 25.413

-- Padding bits are included, if needed, in the least significant bits of the

-- last octet of the octet string.
```

maxPermittedEncryptionAlgorithmsLength INTEGER ::= 9

```
KeyStatus ::= ENUMERATED {
    old (0),
    new (1),
    ...}
    -- exception handling:
    -- received values in range 2-31 shall be treated as "old"
    -- received values greater than 31 shall be treated as "new"
```

```
PrepareHO-Arg ::= [3] SEQUENCE {
                                         [0] GlobalCellId
    targetCellId
                                                                           OPTIONAL.
                                                                          OPTIONAL,
    ho-NumberNotRequired
                                        NITIT.
    targetRNCId
                                         [1] RNCId
                                                                           OPTIONAL,
    an-APDU
                                         [2] AccessNetworkSignalInfo
                                                                          OPTIONAL,
    multipleBearerRequested
                                         [3] NULL
                                                                          OPTIONAL,
                                        [4] IMSI OPTIONAL,
[5] IntegrityProtectionInformation OPTIONAL,
    imsi
    integrityProtectionInfo
    encryptionInfo
                                        [6] EncryptionInformation
                                                                           OPTIONAL,
                                        [6] RadioResourceInformation OPTIONAL,
[9] AllowedGSM-Algorithms OPTIONAL,
OPTIONAL,
    radioResourceInformation
    allowedGSM-Algorithms
                                        [10] AllowedUMTS-Algorithms
    allowedUMTS-Algorithms
                                                                          OPTIONAL.
                                                                          OPTIONAL,
    radioResourceList
                                        [11] RadioResourceList
    extensionContainer
                                        [8] ExtensionContainer
                                                                          OPTIONAL,
    rab-Id
                                        [12] RAB-Id
                                                                          OPTIONAL.
                                        [13] BSSMAP-ServiceHandover
    bssmap-ServiceHandover
                                                                          OPTIONAL,
    ranap-ServiceHandover
                                         [14] RANAP-ServiceHandover
                                                                           OPTIONAL,
    bssmap-ServiceHandoverList [15] BSSMAP-ServiceHandoverList OPTIONAL,
    asciCallReference
                                        [20] ASCI-CallReference
                                                                           OPTIONAL,
                                        [16] GERAN-Classmark
                                                                           OPTIONAL,
    geran-classmark
    iuCurrentlyUsedCodec
                                        [17] Codec
                                                                           OPTIONAL,
    iuSupportedCodecsList
                                         [18] SupportedCodecsList
                                                                          OPTIONAL,
                                     [19] NULL
    rab-ConfigurationIndicator
                                                                          OPTIONAL.
    uesbi-Iu
                                         [21] UESBI-Iu
                                                                           OPTIONAL.
                                         [22] IMEI
                                                                          OPTIONAL,
    imeisv
    alternativeChannelType
                                [23] RadioResourceInformation OPTIONAL,
                                       [25] TracePropagationList
    tracePropagationList
                                                                          OPTIONAL
```

BSSMAP-ServiceHandoverList ::= SEQUENCE SIZE (1.. maxNumOfServiceHandovers) OF BSSMAP-ServiceHandoverInfo

```
BSSMAP-ServiceHandoverInfo ::= SEQUENCE {
   bssmap-ServiceHandover BSSMAP-ServiceHandover,
   rab-Id RAB-Id,
   -- RAB Identity is needed to relate the service handovers with the radio access bearers.
   ...}
```

maxNumOfServiceHandovers INTEGER ::= 7

```
BSSMAP-ServiceHandover ::= OCTET STRING (SIZE (1))

-- Octets are coded according the Service Handover information element in
-- 3GPP TS 48.008.
```

```
RANAP-ServiceHandover ::= OCTET STRING (SIZE (1))

-- Octet contains a complete Service-Handover data type

-- as defined in 3GPP TS 25.413, encoded according to the encoding scheme

-- mandated by 3GPP TS 25.413

-- Padding bits are included in the least significant bits.
```

```
RadioResourceList ::= SEQUENCE SIZE (1.. maxNumOfRadioResources) OF
RadioResource
```

maxNumOfRadioResources INTEGER ::= 7

```
PrepareHO-Res ::= [3] SEQUENCE {
    handoverNumber
                                       [0] ISDN-AddressString
                                                                         OPTIONAL,
    relocationNumberList
                                        [1] RelocationNumberList
                                                                         OPTIONAL,
                                       [2] AccessNetworkSignalInfo
    an-APDU
                                                                         OPTIONAL.
    multicallBearerInfo
                                        [3] MulticallBearerInfo
                                                                         OPTIONAL,
    multipleBearerNotSupported
                                       NULL
                                                                         OPTIONAL.
    selectedUMTS-Algorithms
                                       [5] SelectedUMTS-Algorithms
                                                                        OPTIONAL,
    chosenRadioResourceInformation
                                       [6] ChosenRadioResourceInformation OPTIONAL,
                                       [4] ExtensionContainer
    extensionContainer
                                                                        OPTIONAL,
    iuSelectedCodec
                                       [7] Codec
                                                                         OPTIONAL,
    iuAvailableCodecsList
                                        [8] CodecList
                                                                         OPTIONAL
```

extensionContainer

```
SelectedUMTS-Algorithms ::= SEQUENCE {
                                          [0] ChosenIntegrityProtectionAlgorithm
[1] ChosenEncryptionAlgorithm OPTION
     integrityProtectionAlgorithm
                                                                                    OPTIONAL.
     encryptionAlgorithm
                                                                             OPTIONAL,
     extensionContainer
                                           [2] ExtensionContainer
                                                                              OPTIONAL,
ChosenIntegrityProtectionAlgorithm ::= OCTET STRING (SIZE (1))
     -- Octet contains a complete IntegrityProtectionAlgorithm data type
     -- as defined in 3GPP TS 25.413, encoded according to the encoding scheme
     -- mandated by 3GPP TS 25.413
     -- Padding bits are included in the least significant bits.
ChosenEncryptionAlgorithm ::= OCTET STRING (SIZE (1))
     -- Octet contains a complete EncryptionAlgorithm data type
     -- as defined in 3GPP TS 25.413, encoded according to the encoding scheme
     -- mandated by 3GPP TS 25.413
     -- Padding bits are included in the least significant bits.
ChosenRadioResourceInformation ::= SEQUENCE {
     chosenChannelInfo
                                           [0] ChosenChannelInfo
                                                                              OPTIONAL,
                                           [1] ChosenSpeechVersion
     chosenSpeechVersion
                                                                              OPTIONAL.
ChosenChannelInfo ::= OCTET STRING (SIZE (1))
     -- Octets are coded according the Chosen Channel information element in 3GPP TS 48.008
ChosenSpeechVersion ::= OCTET STRING (SIZE (1))
     -- Octets are coded according the Speech Version (chosen) information element in 3GPP TS
     -- 48.008
PrepareSubsequentHO-Arg ::= [3] SEQUENCE {
     targetCellId
                                           [0] GlobalCellId
                                                                              OPTIONAL,
     targetMSC-Number
                                           [1] ISDN-AddressString,
     targetRNCId
                                           [2] RNCId
                                                                              OPTIONAL.
                                           [3] AccessNetworkSignalInfo
     an-APDU
                                                                              OPTIONAL.
     selectedRab-Id
                                           [4] RAB-Id
                                                                              OPTIONAL,
     extensionContainer
                                           [5] ExtensionContainer
                                                                              OPTIONAL,
     geran-classmark
                                           [6] GERAN-Classmark
                                                                              OPTIONAL.
     rab-ConfigurationIndicator
                                           [7] NULL
                                                                              OPTIONAL
PrepareSubsequentHO-Res ::= [3] SEQUENCE {
     an-APDU
                                           AccessNetworkSignalInfo,
     extensionContainer
                                           [0] ExtensionContainer
                                                                              OPTIONAL,
ProcessAccessSignalling-Arg ::= [3] SEQUENCE {
     an-APDU
                                          AccessNetworkSignalInfo.
     selectedUMTS-Algorithms
                                           [1] SelectedUMTS-Algorithms
                                                                              OPTIONAL.
     selectedGSM-Algorithm
                                           [2] SelectedGSM-Algorithm
                                                                              OPTIONAL,
     chosenRadioResourceInformation
                                           [3] ChosenRadioResourceInformation OPTIONAL,
                                                                              OPTIONAL,
     selectedRab-Id
                                           [4] RAB-Id
     extensionContainer
                                           [0] ExtensionContainer
                                                                              OPTIONAL.
     iUSelectedCodec
                                                                              OPTIONAL,
                                           [5] Codec
     iuAvailableCodecsList
                                           [6] CodecList
                                                                              OPTIONAL
SupportedCodecsList ::= SEQUENCE {
    utranCodecList
                                           [0] CodecList
                                                                              OPTIONAL,
    geranCodecList
                                           [1] CodecList
                                                                              OPTIONAL.
                                           [2] ExtensionContainer
     extensionContainer
                                                                              OPTIONAL,
CodecList ::= SEQUENCE {
     codec1
                                           [1] Codec,
     codec2
                                           [2] Codec
                                                                              OPTIONAL,
     codec3
                                           [3] Codec
                                                                              OPTIONAL,
     codec4
                                           [4] Codec
                                                                              OPTIONAL.
     codec5
                                           [5] Codec
                                                                              OPTIONAL,
     codec6
                                           [6] Codec
                                                                              OPTIONAL,
    codec7
                                           [7] Codec
                                                                              OPTIONAL.
     codec8
                                           [8] Codec
                                                                              OPTIONAL.
```

Codecs are sent in priority order where codec1 has highest priority

[9] ExtensionContainer

OPTIONAL,

```
337
Codec ::= OCTET STRING (SIZE (1..4))
     -- The internal structure is defined as follows:
                                          Coded as Codec Identification code in 3GPP TS 26.103
     -- octet 1
     -- octets 2,3,4
                                          Parameters for the Codec as defined in 3GPP TS
                                          26.103, if available, length depending on the codec
GERAN-Classmark ::= OCTET STRING (SIZE (2..87))
     -- Octets are coded according the GERAN Classmark information element in 3GPP TS 48.008
SelectedGSM-Algorithm ::= OCTET STRING (SIZE (1))
     -- internal structure is coded as Algorithm identifier octet from Chosen Encryption
     -- Algorithm defined in 3GPP TS 48.008
     -- A node shall mark only the selected GSM algorithm
SendEndSignal-Arg ::= [3] SEQUENCE {
    an-APDU
                                         AccessNetworkSignalInfo,
     {\tt extensionContainer}
                                          [0] ExtensionContainer
                                                                           OPTIONAL,
SendEndSignal-Res ::= SEQUENCE {
     extensionContainer
                                         [0] ExtensionContainer
                                                                            OPTIONAL,
RNCId ::= OCTET STRING (SIZE (7))
     -- The internal structure is defined as follows:
     -- octet 1 bits 4321
                                         Mobile Country Code 1st digit
               bits 8765
                                         Mobile Country Code 2nd digit
     -- octet 2 bits 4321
                                         Mobile Country Code 3rd digit
                                        Mobile Network Code 3rd digit
               bits 8765
                                         or filler (1111) for 2 digit MNCs
     -- octet 3 bits 4321
                                         Mobile Network Code 1st digit
               bits 8765
                                         Mobile Network Code 2nd digit
     -- octets 4 and 5
                                         Location Area Code according to 3GPP TS 24.008
                                         RNC Id value according to 3GPP TS 25.413
     -- octets 6 and 7
RelocationNumberList ::= SEQUENCE SIZE (1..maxNumOfRelocationNumber) OF
                                          RelocationNumber
MulticallBearerInfo ::= INTEGER (1..maxNumOfRelocationNumber)
RelocationNumber ::= SEQUENCE {
                                          ISDN-AddressString,
     handoverNumber
     rab-Id
                                          RAB-Id.
     -- RAB Identity is needed to relate the calls with the radio access bearers.
RAB-Id ::= INTEGER (1..maxNrOfRABs)
maxNrOfRABs INTEGER ::= 255
maxNumOfRelocationNumber INTEGER ::= 7
RadioResourceInformation ::= OCTET STRING (SIZE (3..13))
     -- Octets are coded according the Channel Type information element in 3GPP TS 48.008
IntegrityProtectionInformation ::= OCTET STRING (SIZE (18..maxNumOfIntegrityInfo))
     -- Octets contain a complete IntegrityProtectionInformation data type
     -- as defined in 3GPP TS 25.413, encoded according to the encoding scheme
     -- mandated by 3GPP TS 25.413
     -- Padding bits are included, if needed, in the least significant bits of the
     -- last octet of the octet string.
maxNumOfIntegrityInfo INTEGER ::= 100
EncryptionInformation ::= OCTET STRING (SIZE (18..maxNumOfEncryptionInfo))
     -- Octets contain a complete EncryptionInformation data type
     -- as defined in 3GPP TS 25.413, encoded according to the encoding scheme
     -- mandated by 3GPP TS 25.413
```

```
maxNumOfEncryptionInfo INTEGER ::= 100
```

-- last octet of the octet string.

-- authentication management types

-- Padding bits are included, if needed, in the least significant bits of the

```
SendAuthenticationInfoArg ::= SEQUENCE {
                                          [0] TMST.
     numberOfRequestedVectors
                                          NumberOfRequestedVectors,
     segmentationProhibited
                                          NULL
                                                                             OPTIONAL,
     immediateResponsePreferred
                                          [1] NULL
                                                                              OPTIONAL,
     re-synchronisationInfo
                                          Re-synchronisationInfo
                                                                             OPTIONAL,
     extensionContainer
                                          [2] ExtensionContainer
                                                                             OPTIONAL.
     requestingNodeType
                                          [3] RequestingNodeType
                                                                             OPTIONAL,
     requestingPLMN-Id
                                          [4] PLMN-Id
                                                                             OPTIONAL
PLMN-Id ::= OCTET STRING (SIZE (3))
     -- The internal structure is defined as follows:
     -- octet 1 bits 4321
                                          Mobile Country Code 1st digit
               bits 8765
                                          Mobile Country Code 2nd digit
     -- octet 2 bits 4321
                                          Mobile Country Code 3rd digit
                                          Mobile Network Code 3rd digit
               bits 8765
                                          or filler (1111) for 2 digit MNCs
     -- octet 3 bits 4321
                                          Mobile Network Code 1st digit
               bits 8765
                                          Mobile Network Code 2nd digit
NumberOfRequestedVectors ::= INTEGER (1..5)
Re-synchronisationInfo ::= SEQUENCE {
                                          RAND,
     auts
                                          AUTS,
SendAuthenticationInfoRes ::= [3] SEQUENCE {
     authenticationSetList
                                          AuthenticationSetList
                                                                             OPTIONAL.
     extensionContainer
                                          ExtensionContainer
                                                                             OPTIONAL,
RequestingNodeType ::= ENUMERATED {
    vlr (0),
     sgsn (1),
     ...}
     -- exception handling:
     -- received values in the range 2-15 shall be treated as "vlr"
     -- received values greater than 15 shall be treated as "sgsn"
-- equipment management types
CheckIMEI-Arg ::= SEQUENCE {
     imei
                                          IMEI.
     requestedEquipmentInfo
                                          RequestedEquipmentInfo,
     extensionContainer
                                          ExtensionContainer
                                                                             OPTIONAL,
CheckIMEI-Res ::= SEQUENCE {
                                                                             OPTIONAL.
     equipmentStatus
                                          EquipmentStatus
                                                                             OPTIONAL,
     bmuef
                                          UESBI-Iu
     extensionContainer
                                          [0] ExtensionContainer
                                                                             OPTIONAL.
     . . . }
RequestedEquipmentInfo::= BIT STRING {
     equipmentStatus (0),
     bmuef (1) } (SIZE (2..8))
     -- exception handling: reception of unknown bit assignments in the
     -- RequestedEquipmentInfo data type shall be discarded by the receiver
UESBI-Iu ::= SEQUENCE {
     uesbi-IuA [0] UESBI-IuA
                                                                             OPTIONAL,
     uesbi-IuB [1] UESBI-IuB
                                                                             OPTIONAL,
     . . . }
UESBI-IuA
                                               ::= BIT STRING (SIZE(1..128))
 -- See 3GPP TS 25.413
UESBI-IuB
                                               ::= BIT STRING (SIZE(1..128))
-- See 3GPP TS 25.413
EquipmentStatus ::= ENUMERATED {
     whiteListed (0),
     blackListed (1),
     greyListed (2)}
```

-- subscriber management types

```
InsertSubscriberDataArg ::= SEQUENCE {
                                             [0] IMSI
                                                                                  OPTIONAL,
     COMPONENTS OF
                                             SubscriberData,
     extensionContainer
                                             [14] ExtensionContainer
                                                                                  OPTIONAL,
    naea-PreferredCI
                                             [15] NAEA-PreferredCI
                                                                                  OPTIONAL,
     -- naea-PreferredCI is included at the discretion of the HLR operator.
     gprsSubscriptionData
                                            [16] GPRSSubscriptionData
     roamingRestrictedInSgsnDueToUnsupportedFeature [23]
                                                                                 NULL
                                                                                  OPTIONAL.
    networkAccessMode
                                             [24] NetworkAccessMode
                                                                                 OPTIONAL.
     lsaInformation
                                            [25] LSAInformation
                                                                                 OPTIONAL,
     lmu-Indicator
                                             [21] NULL
                                                                                 OPTIONAL,
     lcsInformation
                                             [22] LCSInformation
                                                                                 OPTIONAL.
     istAlertTimer
                                            [26] IST-AlertTimerValue
                                                                                 OPTIONAL,
                                             [27] AgeIndicator
     superChargerSupportedInHLR
                                                                                 OPTIONAL,
    mc-SS-Info
cs-AllocationRetentionPriority
sgsn-CAMEL-SubscriptionInfo
                                            [28] MC-SS-Info
                                                                                 OPTIONAL,
                                            [29] CS-AllocationRetentionPriority
                                                                                     OPTIONAL,
                                            [17] SGSN-CAMEL-SubscriptionInfo OPTIONAL,
[18] ChargingCharacteristics OPTIONAL,
[19] AccessRestrictionData OPTIONAL
     accessRestrictionData
     -- If the Network Access Mode parameter is sent, it shall be present only in
     -- the first sequence if segmentation is used
```

```
AccessRestrictionData ::= BIT STRING {
   utranNotAllowed (0),
   geranNotAllowed (1) } (SIZE (2..8))
   -- exception handling:
   -- bits 2 to 7 shall be ignored if received and not understood
```

```
CS-AllocationRetentionPriority ::= OCTET STRING (SIZE (1))

-- This data type encodes each priority level defined in TS 23.107 as the binary value

-- of the priority level.
```

IST-AlertTimerValue ::= INTEGER (15..255)

```
LCSInformation ::= SEQUENCE {
    gmlc-List [0]
                                         GMLC-List OPTIONAL,
                                         [1] LCS-PrivacyExceptionList
[2] MOLR-List
    lcs-PrivacyExceptionList
                                                                            OPTIONAL,
    molr-List
                                                                            OPTIONAL.
                                         [3] LCS-PrivacyExceptionList
    add-lcs-PrivacyExceptionList
                                                                           OPTIONAL }
    -- add-lcs-PrivacyExceptionList may be sent only if lcs-PrivacyExceptionList is
    -- present and contains four instances of LCS-PrivacyClass. If the mentioned condition
    -- is not satisfied the receiving node shall discard add-lcs-PrivacyExceptionList.
    -- If an LCS-PrivacyClass is received both in lcs-PrivacyExceptionList and in
    -- add-lcs-PrivacyExceptionList with the same SS-Code, then the error unexpected
    -- data value shall be returned.
```

```
GMLC-List ::= SEQUENCE SIZE (1..maxNumOfGMLC) OF

ISDN-AddressString

-- if segmentation is used, the complete GMLC-List shall be sent in one segment
```

```
maxNumOfGMLC INTEGER ::= 5
```

```
GPRSDataList ::= SEQUENCE SIZE (1..maxNumOfPDP-Contexts) OF
PDP-Context
```

```
maxNumOfPDP-Contexts INTEGER ::= 50
```

```
PDP-Context ::= SEQUENCE {
    pdp-ContextId
                                        Context Id.
    pdp-Type
                                        [16] PDP-Type,
    pdp-Address
                                        [17] PDP-Address
                                                                         OPTIONAL,
    gos-Subscribed
                                        [18] OoS-Subscribed.
    vplmnAddressAllowed
                                        [19] NULL OPTIONAL,
                                        [20] APN,
    apn
    extensionContainer
                                        [21] ExtensionContainer
                                                                        OPTIONAL,
    ext-QoS-Subscribed
                                        [0] Ext-QoS-Subscribed
    pdp-ChargingCharacteristics
                                        [1] ChargingCharacteristics
                                                                        OPTIONAL,
                                        [2] Ext2-QoS-Subscribed
    ext2-OoS-Subscribed
    -- ext2-QoS-Subscribed may be present only if ext-QoS-Subscribed is present.
```

ContextId ::= INTEGER (1..maxNumOfPDP-Contexts)

```
SGSN-CAMEL-SubscriptionInfo ::= SEQUENCE {
    gprs-CSI
                                           [0] GPRS-CSI
                                                                              OPTIONAL.
                                           [1] SMS-CSI
     mo-sms-CSI
                                                                              OPTIONAL.
     extensionContainer
                                           [2] ExtensionContainer
                                                                              OPTIONAL,
     mt-sms-CSI
                                           [3] SMS-CSI
                                                                              OPTIONAL.
                                           [4] MT-smsCAMELTDP-CriteriaList
[5] MG-CSI
     mt-smsCAMELTDP-CriteriaList
                                                                              OPTIONAL,
     mq-csi
                                                                              OPTIONAL
```

```
GPRS-CSI ::= SEQUENCE {
    gprs-CamelTDPDataList
                                         [0] GPRS-CamelTDPDataList
                                                                             OPTIONAL,
    camelCapabilityHandling
                                          [1] CamelCapabilityHandling
                                                                             OPTIONAL,
                                          [2] ExtensionContainer
    extensionContainer
                                                                             OPTIONAL.
                                          [3] NULL
[4] NULL
                                                                             OPTIONAL,
    notificationToCSE
    csi-Active
                                                                             OPTIONAL,
    . . . }
    notificationToCSE and csi-Active shall not be present when GPRS-CSI is sent to SGSN.
    They may only be included in ATSI/ATM ack/NSDC message.
    GPRS-CamelTDPData and camelCapabilityHandling shall be present in
    the GPRS-CSI sequence.
    If GPRS-CSI is segmented, gprs-CamelTDPDataList and camelCapabilityHandling shall be
    present in the first segment
```

```
GPRS-CamelTDPDataList ::= SEQUENCE SIZE (1..maxNumOfCamelTDPData) OF
GPRS-CamelTDPData
-- GPRS-CamelTDPDataList shall not contain more than one instance of
-- GPRS-CamelTDPData containing the same value for gprs-TriggerDetectionPoint.
```

```
GPRS-CamelTDPData ::= SEQUENCE {
    gprs-TriggerDetectionPoint [0] GPRS-TriggerDetectionPoint,
    serviceKey [1] ServiceKey,
    gsmSCF-Address [2] ISDN-AddressString,
    defaultSessionHandling [3] DefaultGPRS-Handling,
    extensionContainer [4] ExtensionContainer OPTIONAL,
    ...
}
```

```
DefaultGPRS-Handling ::= ENUMERATED {
    continueTransaction (0) ,
    releaseTransaction (1) ,
    ...}
-- exception handling:
-- reception of values in range 2-31 shall be treated as "continueTransaction"
-- reception of values greater than 31 shall be treated as "releaseTransaction"
```

```
GPRS-TriggerDetectionPoint ::= ENUMERATED {
                                                (1),
     attach
     attachChangeOfPosition
                                                (2),
     pdp-ContextEstablishment
                                                (11),
     pdp-ContextEstablishmentAcknowledgement
                                                (12),
    pdp-ContextChangeOfPosition
                                                (14).
-- exception handling:
-- For GPRS-CamelTDPData sequences containing this parameter with any
-- other value than the ones listed the receiver shall ignore the whole
 -- GPRS-CamelTDPDatasequence.
APN ::= OCTET STRING (SIZE (2..63))
     -- Octets are coded according to TS 3GPP TS 23.003 [17]
PDP-Type ::= OCTET STRING (SIZE (2))
       Octets are coded according to TS 3GPP TS 29.060 [105]
PDP-Address ::= OCTET STRING (SIZE (1..16))
      -- Octets are coded according to TS 3GPP TS 29.060 [105]
     -- The possible size values are:
     -- 1-7 octets X.25 address type
     -- 4 octets IPv4 address type
     -- 16 octets Ipv6 address type
QoS-Subscribed ::= OCTET STRING (SIZE (3))
     -- Octets are coded according to TS 3GPP TS 24.008 [35] Quality of Service Octets
      -- 3-5.
Ext-QoS-Subscribed ::= OCTET STRING (SIZE (1..9))
     -- OCTET 1:
     -- Allocation/Retention Priority (This octet encodes each priority level defined in
            23.107 as the binary value of the priority level, declaration in 29.060)
     -- Octets 2-9 are coded according to 3GPP TS 24.008 [35] Quality of Service Octets
Ext2-QoS-Subscribed ::= OCTET STRING (SIZE (1..3))
     -- Octets 1-3 are coded according to 3GPP TS 24.008 [35] Quality of Service Octets 14-16.
-- If Quality of Service information is structured with 14 octet length, then
     -- Octet 1 is coded according to 3GPP TS 24.008 [35] Quality of Service Octet 14
ChargingCharacteristics ::= OCTET STRING (SIZE (2))
    -- Octets are coded according to 3GPP TS 32.215.
LSAOnlyAccessIndicator ::= ENUMERATED {
    accessOutsideLSAsAllowed (0),
     accessOutsideLSAsRestricted (1) }
LSADataList ::= SEQUENCE SIZE (1..maxNumOfLSAs) OF
                                           LSAData
maxNumOfLSAs INTEGER ::= 20
LSAData ::= SEQUENCE {
     lsaIdentity
                                           [0] LSAIdentity,
     lsaAttributes
                                           [1] LSAAttributes,
     lsaActiveModeIndicator
                                           [2] NULL
                                                                               OPTIONAL,
     extensionContainer
                                           [3] ExtensionContainer
                                                                               OPTIONAL,
LSAInformation ::= SEQUENCE {
     completeDataListIncluded
                                           NULL
                                                                               OPTIONAL,
          -- If segmentation is used, completeDataListIncluded may only be present in the
          -- first segment.
     lsaOnlvAccessIndicator
                                           [1] LSAOnlyAccessIndicator
                                                                               OPTIONAL.
     lsaDataList
                                           [2] LSADataList
                                                                               OPTIONAL.
     extensionContainer
                                           [3] ExtensionContainer
                                                                               OPTIONAL,
     . . . }
LSAIdentity ::= OCTET STRING (SIZE (3))
     -- Octets are coded according to TS 3GPP TS 23.003 [17]
```

```
LSAAttributes ::= OCTET STRING (SIZE (1))
    -- Octets are coded according to TS 3GPP TS 48.008 [49]
SubscriberData ::= SEQUENCE {
    msisdn
                                         [1] ISDN-AddressString
                                                                           OPTIONAL,
    category
                                         [2] Category
                                                                           OPTIONAL,
                                         [3] SubscriberStatus
    subscriberStatus
                                                                           OPTIONAL,
                                         [4] BearerServiceList
    bearerServiceList.
                                                                           OPTIONAL.
    -- The exception handling for reception of unsupported / not allocated
    -- bearerServiceCodes is defined in section 8.8.1
                                         [6] TeleserviceList
                                                                           OPTIONAL,
     -- The exception handling for reception of unsupported / not allocated
```

-- teleserviceCodes is defined in section 8.8.1 provisionedSS [7] Ext-SS-InfoList OPTIONAL, odb-Data [8] ODB-Data OPTIONAL, roamingRestrictionDueToUnsupportedFeature [9] NULL OPTIONAL, regionalSubscriptionData [10] ZoneCodeList OPTIONAL, [11] VBSDataList [12] VGCSDataList vbsSubscriptionData OPTIONAL, OPTIONAL, vgcsSubscriptionData vlrCamelSubscriptionInfo [13] VlrCamelSubscriptionInfo OPTIONAL

Category ::= OCTET STRING (SIZE (1))
-- The internal structure is defined in ITU-T Rec Q.763.

```
SubscriberStatus ::= ENUMERATED {
    serviceGranted (0),
    operatorDeterminedBarring (1)}
```

```
BearerServiceList ::= SEQUENCE SIZE (1..maxNumOfBearerServices) OF

Ext-BearerServiceCode
```

```
maxNumOfBearerServices INTEGER ::= 50
```

```
TeleserviceList ::= SEQUENCE SIZE (1..maxNumOfTeleservices) OF

Ext-TeleserviceCode
```

maxNumOfTeleservices INTEGER ::= 20

```
ODB-GeneralData ::= BIT STRING {
     alloG-CallsBarred (0),
     internationalOGCallsBarred (1),
     internationalOGCallsNotToHPLMN-CountryBarred (2),
     interzonalOGCallsBarred (6),
     interzonalOGCallsNotToHPLMN-CountryBarred (7),
     interzonalOGCallsAndInternationalOGCallsNotToHPLMN-CountryBarred (8),
    premiumRateInformationOGCallsBarred (3),
    premiumRateEntertainementOGCallsBarred (4),
     ss-AccessBarred (5),
    allECT-Barred (9),
     chargeableECT-Barred (10),
     internationalECT-Barred (11).
     interzonalECT-Barred (12),
     doublyChargeableECT-Barred (13),
    multipleECT-Barred (14),
     allPacketOrientedServicesBarred (15),
    roamerAccessToHPLMN-AP-Barred (16),
roamerAccessToVPLMN-AP-Barred (17),
     roamingOutsidePLMNOG-CallsBarred (18),
     allIC-CallsBarred (19),
     roamingOutsidePLMNIC-CallsBarred (20),
     roamingOutsidePLMNICountryIC-CallsBarred (21),
     roamingOutsidePLMN-Barred (22),
     roamingOutsidePLMN-CountryBarred (23),
     registrationAllCF-Barred (24),
     registrationCFNotToHPLMN-Barred (25),
     registrationInterzonalCF-Barred (26),
    registrationInterzonalCFNotToHPLMN-Barred (27),
    registrationInternationalCF-Barred (28)} (SIZE (15..32))
-- exception handling: reception of unknown bit assignments in the
     -- ODB-GeneralData type shall be treated like unsupported ODB-GeneralData
     -- When the ODB-GeneralData type is removed from the HLR for a given subscriber,
     -- in NoteSubscriberDataModified operation sent toward the gsmSCF
     -- all bits shall be set to 'O'
```

```
ODB-HPLMN-Data ::= BIT STRING {
    plmn-SpecificBarringType1 (0),
    plmn-SpecificBarringType2 (1),
    plmn-SpecificBarringType3 (2),
    plmn-SpecificBarringType4 (3)} (SIZE (4..32))
    -- exception handling: reception of unknown bit assignments in the
    -- ODB-HPLMN-Data type shall be treated like unsupported ODB-HPLMN-Data
    -- When the ODB-HPLMN-Data type is removed from the HLR for a given subscriber,
    -- in NoteSubscriberDataModified operation sent toward the gsmSCF
    -- all bits shall be set to 'O'.
```

```
Ext-SS-InfoList ::= SEQUENCE SIZE (1..maxNumOfSS) OF
Ext-SS-Info
```

```
        Ext-SS-Info ::= CHOICE {
        [0] Ext-ForwInfo,

        forwardingInfo
        [1] Ext-CallBarInfo,

        cug-Info
        [2] CUG-Info,

        ss-Data
        [3] Ext-SS-Data,

        emlpp-Info
        [4] EMLPP-Info}
```

```
Ext-ForwFeature ::= SEQUENCE {
    basicService
                                      Ext-BasicServiceCode
                                                                     OPTIONAL.
                                      [4] Ext-SS-Status,
    ss-Status
    forwardedToNumber
                                    [5] ISDN-AddressString
                                                                     OPTIONAL,
    -- When this data type is sent from an HLR which supports CAMEL Phase 2
    -- to a VLR that supports CAMEL Phase 2 the VLR shall not check the
    -- format of the number
                                     [8] ISDN-SubaddressString OPTIONAL,
[6] Ext-ForwOptions OPTIONAL,
    forwardedToSubaddress
                                     [9] ExtensionContainer
    forwardingOptions
                                     [6] Ext-ForwOptions
    noReplyConditionTime
                                                                     OPTIONAL,
    extensionContainer
                                                                     OPTIONAL,
    longForwardedToNumber
                                    [10] FTN-AddressString OPTIONAL }
```

```
Ext-ForwOptions ::= OCTET STRING (SIZE (1..5))

-- OCTET 1:

-- bit 8: notification to forwarding party
-- 0 no notification
-- 1 notification
-- bit 7: redirecting presentation
-- 0 no presentation
-- 1 presentation
-- 1 presentation
-- bit 6: notification to calling party
-- 0 no notification
-- 1 notification
-- bit 5: 0 (unused)
-- bits 43: forwarding reason
-- 00 ms not reachable
-- 01 ms busy
-- 10 no reply
-- 11 unconditional
-- bits 21: 00 (unused)
-- OCTETS 2-5: reserved for future use. They shall be discarded if
-- received and not understood.
```

```
Ext-NoRepCondTime ::= INTEGER (1..100)

-- Only values 5-30 are used.

-- Values in the ranges 1-4 and 31-100 are reserved for future use

-- If received:

-- values 1-4 shall be mapped on to value 5

-- values 31-100 shall be mapped on to value 30
```

```
Ext-CallBarFeatureList ::= SEQUENCE SIZE (1..maxNumOfExt-BasicServiceGroups) OF Ext-CallBarringFeature
```

<pre>Ext-CallBarringFeature ::= SEQUENCE {</pre>		
basicService	Ext-BasicServiceCode	OPTIONAL,
ss-Status	<pre>[4] Ext-SS-Status,</pre>	
extensionContainer	ExtensionContainer	OPTIONAL,
}		

```
CUG-SubscriptionList ::= SEQUENCE SIZE (0..maxNumOfCUG) OF

CUG-Subscription
```

```
CUG-Subscription ::= SEQUENCE {
     cug-Index CUG-Index,
                                         CUG-Interlock,
     cuq-Interlock
     intraCUG-Options
                                         IntraCUG-Options,
     basicServiceGroupList
                                         Ext-BasicServiceGroupList
                                                                            OPTIONAL,
     extensionContainer
                                         [0] ExtensionContainer
                                                                            OPTIONAL,
CUG-Index ::= INTEGER (0..32767)
     -- The internal structure is defined in ETS 300 138.
CUG-Interlock ::= OCTET STRING (SIZE (4))
IntraCUG-Options ::= ENUMERATED {
    noCUG-Restrictions (0),
     cugIC-CallBarred (1),
     cugOG-CallBarred (2) }
maxNumOfCUG INTEGER ::= 10
CUG-FeatureList ::= SEQUENCE SIZE (1..maxNumOfExt-BasicServiceGroups) OF
                                         CUG-Feature
Ext-BasicServiceGroupList ::= SEQUENCE SIZE (1..maxNumOfExt-BasicServiceGroups) OF
                                         Ext-BasicServiceCode
maxNumOfExt-BasicServiceGroups INTEGER ::= 32
CUG-Feature ::= SEQUENCE {
    basicService
                                         Ext-BasicServiceCode
                                                                            OPTIONAL,
     preferentialCUG-Indicator
                                         CUG-Index OPTIONAL,
     interCUG-Restrictions
                                         InterCUG-Restrictions,
     extensionContainer
                                         ExtensionContainer
                                                                            OPTIONAL,
InterCUG-Restrictions ::= OCTET STRING (SIZE (1))
     -- bits 876543: 000000 (unused)
     -- Exception handling:
     -- bits 876543 shall be ignored if received and not understood
     -- bits 21
     -- 00 CUG only facilities
         01 CUG with outgoing access
        10 CUG with incoming access
         11 CUG with both outgoing and incoming access
Ext-SS-Data ::= SEQUENCE {
     ss-Code
                                         SS-Code,
     ss-Status [4] Ext-SS-Status,
     ss-SubscriptionOption
                                         SS-SubscriptionOption
                                                                            OPTIONAL,
     basicServiceGroupList
                                         Ext-BasicServiceGroupList
                                                                            OPTIONAL,
                                         [5] ExtensionContainer
                                                                            OPTIONAL.
     extensionContainer
LCS-PrivacyExceptionList ::= SEQUENCE SIZE (1..maxNumOfPrivacyClass) OF
                                         LCS-PrivacyClass
```

```
maxNumOfPrivacyClass INTEGER ::= 4
```

```
LCS-PrivacyClass ::= SEQUENCE {
                                         SS-Code,
    ss-Code
    ss-Status
                                         Ext-SS-Status,
                                         [0] NotificationToMSUser
    notificationToMSUser
    -- notificationToMSUser may be sent only for SS-codes callSessionRelated
    -- and callSessionUnrelated. If not received for SS-codes callSessionRelated
    -- and callSessionUnrelated.
    -- the default values according to 3GPP TS 23.271 shall be assumed.
    externalClientList
                                         [1] ExternalClientList
    -- externalClientList may be sent only for SS-code callSessionUnrelated to a
    -- visited node that does not support LCS Release 4 or later versions.
    -- externalClientList may be sent only for SS-codes callSessionUnrelated and
    -- callSessionRelated to a visited node that supports LCS Release 4 or later versions.
                                        [2] PLMNClientList
    plmnClientList
     -- plmnClientList may be sent only for SS-code plmnoperator.
    extensionContainer
                                        [3] ExtensionContainer
                                                                          OPTIONAL,
                                        [4] Ext-ExternalClientList
    ext-externalClientList
                                                                         OPTIONAL.
    -- Ext-externalClientList may be sent only if the visited node supports LCS Release 4 or
    -- later versions, the user did specify more than 5 clients, and White Book SCCP is used.
    serviceTypeList
                                         [5] ServiceTypeList
                                                                           OPTIONAL
     -- serviceTypeList may be sent only for SS-code serviceType and if the visited node
    -- supports LCS Release 5 or later versions.
    -- if segmentation is used, the complete LCS-PrivacyClass shall be sent in one segment
```

```
maxNumOfExternalClient INTEGER ::= 5
```

```
maxNumOfPLMNClient INTEGER ::= 5
```

maxNumOfExt-ExternalClient INTEGER ::= 35

```
NotificationToMSUser ::= ENUMERATED {
    notifyLocationAllowed (0),
    notifyAndVerify-LocationAllowedIfNoResponse (1),
    notifyAndVerify-LocationNotAllowedIfNoResponse(2),
    ...,
    locationNotAllowed (3) }
-- exception handling:
-- At reception of any other value than the ones listed the receiver shall ignore
-- NotificationToMSUser.
```

```
ServiceTypeList ::= SEQUENCE SIZE (1..maxNumOfServiceType) OF

ServiceType
```

```
maxNumOfServiceType INTEGER ::= 32
```

specificCSI-Withdraw

chargingCharacteristicsWithdraw

```
ServiceType ::= SEQUENCE {
                                          LCSServiceTypeID,
     serviceTvpeIdentitv
     gmlc-Restriction
                                          [0] GMLC-Restriction
                                                                             OPTIONAL,
                                          [1] NotificationToMSUser
     notificationToMSUser
                                                                            OPTIONAL,
     -- If notificationToMSUser is not received, the default value according to
     -- 3GPP TS 23.271 shall be assumed.
     extensionContainer
                                          [2] ExtensionContainer
                                                                             OPTIONAL.
MOLR-List ::= SEQUENCE SIZE (1..maxNumOfMOLR-Class) OF
maxNumOfMOLR-Class INTEGER ::= 3
MOLR-Class ::= SEQUENCE {
     ss-Code
                                          SS-Code.
     ss-Status
                                          Ext-SS-Status,
     extensionContainer
                                          [0] ExtensionContainer
                                                                             OPTIONAL.
ZoneCodeList ::= SEQUENCE SIZE (1..maxNumOfZoneCodes)
ZoneCode ::= OCTET STRING (SIZE (2))
    -- internal structure is defined in TS 3GPP TS 23.003 [17]
maxNumOfZoneCodes INTEGER ::= 10
InsertSubscriberDataRes ::= SEQUENCE {
     teleserviceList
                                          [1] TeleserviceList
                                                                             OPTIONAL,
     bearerServiceList
                                          [2] BearerServiceList
                                                                             OPTIONAL,
                                          [3] SS-List
                                                                             OPTIONAL,
     ss-List
     odb-GeneralData
                                          [4] ODB-GeneralData
                                                                             OPTIONAL,
     {\tt regional Subscription Response}
                                          [5] RegionalSubscriptionResponse
                                                                             OPTIONAL,
     supportedCamelPhases
                                          [6] SupportedCamelPhases
                                                                             OPTIONAL,
     extensionContainer
                                          [7] ExtensionContainer
                                                                             OPTIONAL.
                                          [8] OfferedCamel4CSIs
     offeredCamel4CSIs
                                                                             OPTIONAL }
RegionalSubscriptionResponse ::= ENUMERATED {
                                          (0),
     networkNode-AreaRestricted
     tooManyZoneCodes
                                          (1),
     zoneCodesConflict
                                          (2)
     {\tt regionalSubscNotSupported}
                                           (3)
	exttt{DeleteSubscriberDataArg}:= 	exttt{SEQUENCE} \ ig\{
                                          [0] IMSI,
     imsi
     basicServiceList
                                          [1] BasicServiceList
                                                                             OPTIONAL,
     -- The exception handling for reception of unsupported/not allocated
     -- basicServiceCodes is defined in section 6.8.2
                                          [2] SS-List
                                                                             OPTIONAL.
     ss-List
     roamingRestrictionDueToUnsupportedFeature [4] NULL
                                                                             OPTIONAL,
     regionalSubscriptionIdentifier [5] ZoneCode
                                                                             OPTIONAL,
     vbsGroupIndication
                                          [7] NULL
                                                                             OPTIONAL,
                                          [8] NULL OPTIONAL,
     vqcsGroupIndication
     camelSubscriptionInfoWithdraw
                                          [9] NULL OPTIONAL,
     {\tt extensionContainer}
                                          [6] ExtensionContainer OPTIONAL,
     gprsSubscriptionDataWithdraw
                                          [10] GPRSSubscriptionDataWithdraw OPTIONAL,
     roamingRestrictedInSgsnDueToUnsuppportedFeature [11] NULL
                                                                             OPTIONAL.
     lsaInformationWithdraw
                                          [12] LSAInformationWithdraw
                                                                             OPTIONAL,
     gmlc-ListWithdraw
                                          [13] NULL
                                                                             OPTIONAL,
     istInformationWithdraw
                                          [14] NULL
                                                                             OPTIONAL,
```

[15] SpecificCSI-Withdraw

[16] NULL

OPTIONAL,

OPTIONAL

```
SpecificCSI-Withdraw ::= BIT STRING {
     o-csi (0),
     ss-csi (1),
     tif-csi (2),
     d-csi (3),
     vt-csi (4),
     mo-sms-csi (5),
     m-csi (6),
     gprs-csi (7),
     t-csi (8),
     mt-sms-csi (9),
     mg-csi (10),
     o-IM-CSI (11)
     d-IM-CSI (12),
     vt-IM-CSI (13) } (SIZE(8..32))
-- exception handling:
-- bits 11 to 31 shall be ignored if received by a non-IP Multimedia Core Network entity.
-- bits 0-10 and 14-31 shall be ignored if received by an IP Multimedia Core Network entity.
-- bits 11-13 are only applicable in an IP Multimedia Core Network.
 -- Bit 8 and bits 11-13 are only applicable for the NoteSubscriberDataModified operation.
GPRSSubscriptionDataWithdraw ::= CHOICE {
                                          NULL,
     allGPRSData
     contextIdList
                                          ContextIdList }
ContextIdList ::= SEQUENCE SIZE (1..maxNumOfPDP-Contexts) OF
LSAInformationWithdraw ::= CHOICE {
     allLSAData
                                          NULL,
     lsaIdentityList
                                          LSAIdentityList ]
LSAIdentityList ::= SEQUENCE SIZE (1..maxNumOfLSAs) OF
                                          LSAIdentity
BasicServiceList ::= SEQUENCE SIZE (1..maxNumOfBasicServices) OF
                                          Ext-BasicServiceCode
maxNumOfBasicServices INTEGER ::= 70
DeleteSubscriberDataRes ::= SEQUENCE {
     regionalSubscriptionResponse
                                           [0] RegionalSubscriptionResponse
                                                                              OPTIONAL.
     extensionContainer
                                          ExtensionContainer
                                                                              OPTIONAL,
VlrCamelSubscriptionInfo ::= SEQUENCE {
     o-CSI
                                           [0] O-CSI
                                                                              OPTIONAL.
                                           [1] ExtensionContainer
                                                                              OPTIONAL,
     extensionContainer
     ss-CSI
                                           [2] SS-CSI
                                                                              OPTIONAL,
     o-BcsmCamelTDP-CriteriaList
                                           [4] O-BcsmCamelTDPCriteriaList
                                                                              OPTIONAL,
     tif-CSI
                                           [3] NULL
                                                                              OPTIONAL,
                                           [5] M-CSI
     m-CSI
                                                                              OPTIONAL.
                                           [6] SMS-CSI
     mo-sms-CSI
                                                                              OPTIONAL,
                                                                              OPTIONAL,
     vt-CSI
                                           [7] T-CSI
     t-BCSM-CAMEL-TDP-CriteriaList
                                           [8] T-BCSM-CAMEL-TDP-CriteriaList OPTIONAL,
                                           [9] D-CSI
                                                                              OPTIONAL,
     d-CSI
                                           [10] SMS-CSI
     mt.-sms-CSI
                                                                              OPTIONAL.
     mt-smsCAMELTDP-CriteriaList
                                           [11] MT-smsCAMELTDP-CriteriaList OPTIONAL
MT-smsCAMELTDP-CriteriaList ::= SEQUENCE SIZE (1.. maxNumOfCamelTDPData) OF
    MT-smsCAMELTDP-Criteria
MT-smsCAMELTDP-Criteria ::= SEQUENCE {
     sms-TriggerDetectionPoint
                                          SMS-TriggerDetectionPoint,
                                           [0] TPDU-TypeCriterion
     tpdu-TypeCriterion
                                                                               OPTIONAL,
TPDU-TypeCriterion ::= SEQUENCE SIZE (1..maxNumOfTPDUTypes) OF
     MT-SMS-TPDU-Type
maxNumOfTPDUTypes INTEGER ::= 5
```

```
D-CSI ::= SEOUENCE {
     dp-AnalysedInfoCriteriaList
                                          [0] DP-AnalysedInfoCriteriaList
                                                                             OPTIONAL,
                                          [1] CamelCapabilityHandling
     camelCapabilityHandling
                                                                             OPTIONAL,
     extensionContainer
                                          [2] ExtensionContainer
                                                                             OPTIONAL,
                                          [3] NULL
[4] NULL
    notificationToCSE
                                                                             OPTIONAL.
    csi-Active
                                                                             OPTIONAL,
     ...}
    notificationToCSE and csi-Active shall not be present when D-CSI is sent to VLR/GMSC.
    They may only be included in ATSI/ATM ack/NSDC message.
    {\tt DP-AnalysedInfoCriteria\ and\ } camel{\tt CapabilityHandling\ shall\ be\ present\ in}
    the D-CSI sequence.
    If D-CSI is segmented, then the first segment shall contain dp-AnalysedInfoCriteriaList
    and camelCapabilityHandling. Subsequent segments shall not contain
     camelCapabilityHandling, but may contain dp-AnalysedInfoCriteriaList
```

```
DP-AnalysedInfoCriteriaList ::= SEQUENCE SIZE (1..maxNumOfDP-AnalysedInfoCriteria) OF
DP-AnalysedInfoCriterium
```

maxNumOfDP-AnalysedInfoCriteria INTEGER ::= 10

maxNumOfCamelSSEvents INTEGER ::= 10

```
O-CSI ::= SEQUENCE {
    o-BcsmCamelTDPDataList
                                         O-BcsmCamelTDPDataList,
    extensionContainer
                                         ExtensionContainer
                                                                            OPTIONAL,
    camelCapabilityHandling
                                          [0] CamelCapabilityHandling
                                                                            OPTIONAL,
    notificationToCSE
                                          [1] NULL
                                                                            OPTIONAL,
                                          [2] NULL
                                                                            OPTIONAL)
    csiActive
    notificationtoCSE and csiActive shall not be present when O-CSI is sent to VLR/GMSC.
    They may only be included in ATSI/ATM ack/NSDC message.
    O-CSI shall not be segmented.
```

```
O-BcsmCamelTDPDataList ::= SEQUENCE SIZE (1..maxNumOfCamelTDPData) OF
O-BcsmCamelTDPData
-- O-BcsmCamelTDPDataList shall not contain more than one instance of
-- O-BcsmCamelTDPData containing the same value for o-BcsmTriggerDetectionPoint.
-- For CAMEL Phase 2, this means that only one instance of O-BcsmCamelTDPData is allowed
-- with o-BcsmTriggerDetectionPoint being equal to DP2.
```

maxNumOfCamelTDPData INTEGER ::= 10

ServiceKey ::= INTEGER (0..2147483647)

```
O-BcsmTriggerDetectionPoint ::= ENUMERATED {
    collectedInfo (2),
    ...,
    routeSelectFailure (4) }
    -- exception handling:
    -- For O-BcsmCameITDPData sequences containing this parameter with any
    -- other value than the ones listed the receiver shall ignore the whole
    -- O-BcsmCameITDPDatasequence.
    -- For O-BcsmCameITDP-Criteria sequences containing this parameter with any
    -- other value than the ones listed the receiver shall ignore the whole
    -- O-BcsmCameITDP-Criteria sequence.
```

```
O-BcsmCamelTDPCriteriaList ::= SEQUENCE SIZE (1..maxNumOfCamelTDPData) OF O-BcsmCamelTDP-Criteria
```

```
T-BCSM-CAMEL-TDP-CriteriaList ::= SEQUENCE SIZE (1..maxNumOfCamelTDPData) OF T-BCSM-CAMEL-TDP-Criteria
```

```
O-BcsmCamelTDP-Criteria ::= SEQUENCE {
    o-BcsmTriggerDetectionPoint
                                         O-BcsmTriggerDetectionPoint,
    destinationNumberCriteria
                                         [0] DestinationNumberCriteria
                                                                           OPTIONAL,
    basicServiceCriteria
                                         [1] BasicServiceCriteria
                                                                           OPTIONAL.
    callTypeCriteria
                                         [2] CallTypeCriteria
                                                                           OPTIONAL,
     o-CauseValueCriteria
                                          [3] O-CauseValueCriteria
                                                                            OPTIONAL,
    extensionContainer
                                         [4] ExtensionContainer
                                                                           OPTIONAL
```

```
DestinationNumberList ::= SEQUENCE SIZE (1..maxNumOfCamelDestinationNumbers) OF

ISDN-AddressString

-- The receiving entity shall not check the format of a number in

-- the dialled number list
```

```
DestinationNumberLengthList ::= SEQUENCE SIZE (1..maxNumOfCamelDestinationNumberLengths) OF
                                               INTEGER(1..maxNumOfISDN-AddressDigits)
BasicServiceCriteria ::= SEQUENCE SIZE(1..maxNumOfCamelBasicServiceCriteria) OF
     Ext-BasicServiceCode
maxNumOfISDN-AddressDigits INTEGER ::= 15
maxNumOfCamelDestinationNumberLengths INTEGER ::= 3
maxNumOfCamelBasicServiceCriteria INTEGER ::= 5
                      ::= ENUMERATED {
CallTypeCriteria
     forwarded
                                           (0)
     notForwarded
                                           (1)
                ::= ENUMERATED {
MatchType
     inhibiting
                                           (0),
     enabling
                                           (1)
O-CauseValueCriteria ::= SEQUENCE SIZE(1..maxNumOfCAMEL-O-CauseValueCriteria) OF
    CauseValue
\textbf{T-CauseValueCriteria} \quad ::= \ \texttt{SEQUENCE} \ \ \texttt{SIZE} \ (1... \texttt{maxNumOfCAMEL-T-CauseValueCriteria}) \ \ \texttt{OF} \ \ \\
    CauseValue
maxNumOfCAMEL-O-CauseValueCriteria INTEGER ::= 5
maxNumOfCAMEL-T-CauseValueCriteria INTEGER ::= 5
CauseValue ::= OCTET STRING (SIZE(1))
 - Type extracted from Cause parameter in ITU-T Recommendation Q.763.
   For the use of cause value refer to ITU-T Recommendation Q.850.
DefaultCallHandling ::= ENUMERATED {
     continueCall (0) ,
     releaseCall (1) ,
     . . . }
     -- exception handling:
     -- reception of values in range 2-31 shall be treated as "continueCall"
     -- reception of values greater than 31 shall be treated as "releaseCall"
CamelCapabilityHandling ::= INTEGER(1..16)
     -- value 1 = CAMEL phase 1,
     -- value 2 = CAMEL phase 2,
     -- value 3 = CAMEL Phase 3,
     -- value 4 = CAMEL phase 4:
     -- reception of values greater than 4 shall be treated as CAMEL phase 4.
SupportedCamelPhases ::= BIT STRING {
     phase1 (0),
     phase2 (1),
     phase3 (2),
     phase4 (3)} (SIZE (1..16))
-- A node shall mark in the BIT STRING all CAMEL Phases it supports.
 -- Other values than listed above shall be discarded.
OfferedCamel4CSIs ::= BIT STRING {
                                           (0),
     o-csi
     d-csi
                                           (1),
     vt-csi
                                           (2),
                                           (3),
     t-csi
     mt-sms-csi
                                           (4),
                                           (5),
     mg-csi
     psi-enhancements
                                           (6)
} (SIZE (7..16))
 -- A node supporting Camel phase 4 shall mark in the BIT STRING all Camel4 CSIs
-- it offers.
 -- Other values than listed above shall be discarded.
```

```
OfferedCamel4Functionalities ::= BIT STRING {
    initiateCallAttempt
                                          (0),
    splitLeg
                                          (1),
    moveLeg
                                          (2),
                                          (3),
    disconnectLeg
    entityReleased
                                          (4),
    dfc-WithArgument
                                          (5),
    playTone
                                          (6),
    dtmf-MidCall
                                          (7),
    chargingIndicator
                                          (8),
    alertingDP
                                          (9).
    locationAtAlerting
                                          (10),
                                          (11),
    changeOfPositionDP
    or-Interactions
                                          (12),
    warningToneEnhancements
                                          (13),
    cf-Enhancements
                                          (14),
                                        (15),
    subscribedEnhancedDialledServices
    servingNetworkEnhancedDialledServices (16),
    criteriaForChangeOfPositionDP (17),
    serviceChangeDP
                                          (18)
} (SIZE (15..64))
 - A node supporting Camel phase 4 shall mark in the BIT STRING all CAMEL4
-- functionalities it offers.
-- Other values than listed above shall be discarded.
```

```
SMS-CSI ::= SEQUENCE {
    sms-CAMEL-TDP-DataList
                                         [0] SMS-CAMEL-TDP-DataList
                                                                            OPTIONAL,
     camelCapabilityHandling
                                         [1] CamelCapabilityHandling
                                                                            OPTIONAL,
     extensionContainer
                                          [2] ExtensionContainer
                                                                            OPTIONAL,
                                          [3] NULL
    notificationToCSE
                                                                            OPTIONAL,
    csi-Active
                                          [4] NULL
                                                                            OPTIONAL.
     . . . }
    notificationToCSE and csi-Active shall not be present
_ _
     when MO-SMS-CSI or MT-SMS-CSI is sent to VLR or SGSN.
     They may only be included in ATSI/ATM ack/NSDC message.
    SMS-CAMEL-TDP-Data and camelCapabilityHandling shall be present in
    the SMS-CSI sequence.
    If SMS-CSI is segmented, sms-CAMEL-TDP-DataList and camelCapabilityHandling shall be
_ _
    present in the first segment
```

```
SMS-CAMEL-TDP-DataList ::= SEQUENCE SIZE (1..maxNumOfCamelTDPData) OF
SMS-CAMEL-TDP-Data
-- SMS-CAMEL-TDP-DataList shall not contain more than one instance of
-- SMS-CAMEL-TDP-Data containing the same value for sms-TriggerDetectionPoint.
```

```
SMS-CAMEL-TDP-Data ::= SEQUENCE {
    sms-TriggerDetectionPoint [0] SMS-TriggerDetectionPoint,
    serviceKey [1] ServiceKey,
    gsmSCF-Address [2] ISDN-AddressString,
    defaultSMS-Handling [3] DefaultSMS-Handling,
    extensionContainer [4] ExtensionContainer OPTIONAL,
    ...
    }
```

```
SMS-TriggerDetectionPoint ::= ENUMERATED {
    sms-CollectedInfo (1),
     . . . ,
    sms-DeliveryRequest (2)
    exception handling:
    For SMS-CAMEL-TDP-Data and MT-smsCAMELTDP-Criteria sequences containing this
    parameter with any other value than the ones listed the receiver shall ignore
    the whole sequence.
    If this parameter is received with any other value than sms-CollectedInfo
_ _
    in an SMS-CAMEL-TDP-Data sequence contained in mo-sms-CSI, then the receiver shall
    ignore the whole SMS-CAMEL-TDP-Data sequence.
_ _
_ _
    If this parameter is received with any other value than sms-DeliveryRequest
_ _
    in an SMS-CAMEL-TDP-Data sequence contained in mt-sms-CSI then the receiver shall
_ _
    ignore the whole SMS-CAMEL-TDP-Data sequence.
    If this parameter is received with any other value than sms-DeliveryRequest
    in an MT-smsCAMELTDP-Criteria sequence then the receiver shall
     ignore the whole MT-smsCAMELTDP-Criteria sequence.
```

```
DefaultSMS-Handling ::= ENUMERATED {
    continueTransaction (0) ,
    releaseTransaction (1) ,
    ...}
-- exception handling:
-- reception of values in range 2-31 shall be treated as "continueTransaction"
-- reception of values greater than 31 shall be treated as "releaseTransaction"
```

```
M-CSI ::= SEQUENCE {
    mobilityTriggers
                                          MobilityTriggers,
     serviceKey
                                          ServiceKey,
                                          [0] ISDN-AddressString,
    gsmSCF-Address
                                          [1] ExtensionContainer
     extensionContainer
                                                                            OPTIONAL.
                                          [2] MIII.I.
    notificationToCSE
                                                                             OPTIONAL.
    csi-Active
                                          [3] NULL
                                                                             OPTIONAL,
     ...}
    notificationToCSE and csi-Active shall not be present when M-CSI is sent to VLR.
     They may only be included in ATSI/ATM ack/NSDC message.
```

```
MG-CSI ::= SEQUENCE {
    mobilityTriggers
                                          MobilityTriggers,
    serviceKey
                                          ServiceKey,
    gsmSCF-Address
                                          [0] ISDN-AddressString,
                                          [1] ExtensionContainer
    extensionContainer
                                                                             OPTIONAL,
                                          [2] NULL
    notificationToCSE
                                                                             OPTIONAL.
    csi-Active
                                                                             OPTIONAL.
                                          [3] NULL
    notificationToCSE and csi-Active shall not be present when MG-CSI is sent to SGSN.
    They may only be included in ATSI/ATM ack/NSDC message.
```

```
MobilityTriggers ::= SEQUENCE SIZE (1..maxNumOfMobilityTriggers) OF MM-Code
```

maxNumOfMobilityTriggers INTEGER ::= 10

```
MM-Code ::= OCTET STRING (SIZE (1))
 -- This type is used to indicate a Mobility Management event.
           Actions for the following MM-Code values are defined in CAMEL Phase 4:
 - -
           CS domain MM events:
                                                                                                        MM-Code ::= '00000000'B
          Location-update-in-same-VLR
           Location-update-to-other-VLR
                                                                                                             MM-Code ::= '00000001'B
                                                                                                            MM-Code ::= '00000010'B
 --
           IMSI-Attach
                                                                                                              MM-Code ::= '00000011'B
 - -
            MS-initiated-TMST-Detach
 - -
            Network-initiated-IMSI-Detach
                                                                                                               MM-Code ::= '00000100'B
            PS domain MM events:
            Routeing-Area-update-in-same-SGSN
                                                                                                           MM-Code ::= '10000000'B
 - -
 - -
            Routeing-Area-update-to-other-SGSN-update-from-new-SGSN
 - -
                                                                                                               MM-Code ::= '10000001'B
            Routeing-Area-update-to-other-SGSN-disconnect-by-detach
 - -
                                                                                                              MM-Code ::= '10000010'B
 - -
                                                                                                              MM-Code ::= '10000011'B
            GPRS-Attach
            Network-initiated from Network-initiated from
            MS-initiated-GPRS-Detach
 - -
 - -
            Network-initiated-transfer-to-MS-not-reachable-for-paging
 - -
                                                                                                              MM-Code ::= '10000110'B
            If the MSC receives any other MM-code than the ones listed above for the
             CS domain, then the MSC shall ignore that MM-code.
             If the SGSN receives any other MM-code than the ones listed above for the
             PS domain, then the SGSN shall ignore that MM-code.
```

```
T-CSI ::= SEQUENCE {
    t-BcsmCamelTDPDataList
                                         T-BcsmCamelTDPDataList,
     extensionContainer
                                         ExtensionContainer
                                                                            OPTIONAL,
     camelCapabilityHandling
                                         [0] CamelCapabilityHandling
                                                                            OPTIONAL,
                                         [1] NULL
    notificationToCSE
                                                                            OPTIONAL.
                                         [2] NIII.I.
    csi-Active
                                                                            OPTIONAL)
    notificationToCSE and csi-Active shall not be present when VT-CSI/T-CSI is sent
    to VLR/GMSC.
     They may only be included in ATSI/ATM ack/NSDC message.
     T-CSI shall not be segmented.
```

```
T-BcsmCamelTDPDataList ::= SEQUENCE SIZE (1..maxNumOfCamelTDPData) OF
     T-BcsmCamelTDPData
     --- T-BcsmCamelTDPDataList shall not contain more than one instance of
     --- T-BcsmCamelTDPData containing the same value for t-BcsmTriggerDetectionPoint.
     --- For CAMEL Phase 2, this means that only one instance of T-BcsmCamelTDPData is allowed
     --- with t-BcsmTriggerDetectionPoint being equal to DP12.
     --- For CAMEL Phase 3, more TDP"s are allowed.
T-BcsmCamelTDPData ::= SEQUENCE {
     t-BcsmTriggerDetectionPoint
                                          T-BcsmTriggerDetectionPoint,
     serviceKey
                                          ServiceKey,
                                           [0] ISDN-AddressString,
     gsmSCF-Address
                                           [1] DefaultCallHandling,
     defaultCallHandling
                                           [2] ExtensionContainer
                                                                              OPTIONAL.
     extensionContainer
T-BcsmTriggerDetectionPoint ::= ENUMERATED {
     termAttemptAuthorized (12),
     tBusy (13),
     tNoAnswer (14)}
     -- exception handling:
     -- For T-BcsmCamelTTPData sequences containing this parameter with any other
     -- value than the ones listed above, the receiver shall ignore the whole
     -- T-BcsmCamelTDPData sequence.
-- gprs location information retrieval types
SendRoutingInfoForGprsArg ::= SEQUENCE {
                                                [0] IMSI,
     imsi
                                                [1] GSN-Address
     ggsn-Address
                                                                              OPTIONAL,
     ggsn-Number
                                                    ISDN-AddressString,
                                                [2]
     extensionContainer
                                                [3] ExtensionContainer
                                                                              OPTIONAL.
SendRoutingInfoForGprsRes ::= SEQUENCE {
     sgsn-Address
                                                [0] GSN-Address,
                                               [1] GSN-Address OPTIONAL,
[2] AbsentSubscriberDiagnosticSM OPTIONAL,
     ggsn-Address
     mobileNotReachableReason
                                                                           OPTIONAL,
     extensionContainer
                                               [3] ExtensionContainer
-- failure report types
FailureReportArg ::= SEQUENCE {
                                                [0] IMSI,
     imsi
     ggsn-Number
                                                [1] ISDN-AddressString
     ggsn-Address
                                                [2] GSN-Address
                                                                              OPTIONAL,
     extensionContainer
                                                [3] ExtensionContainer
                                                                              OPTIONAL,
FailureReportRes ::= SEQUENCE {
     ggsn-Address
                                               [0] GSN-Address
                                                                              OPTIONAL,
     extensionContainer
                                                [1] ExtensionContainer
                                                                              OPTIONAL,
-- gprs notification types
NoteMsPresentForGprsArg ::= SEQUENCE {
     imsi
                                                [0] IMSI,
     sgsn-Address
                                                [1] GSN-Address,
     ggsn-Address
                                                [2] GSN-Address
                                                                              OPTIONAL,
     extensionContainer
                                                [3] ExtensionContainer
                                                                              OPTIONAL,
NoteMsPresentForGprsRes ::= SEQUENCE {
     extensionContainer
                                               [0] ExtensionContainer
                                                                              OPTIONAL,
-- fault recovery types
ResetArg ::= SEQUENCE {
     hlr-Number
                                          ISDN-AddressString,
     hlr-List
                                          HLR-List
                                                                              OPTIONAL,
```

```
RestoreDataArg ::= SEQUENCE {
     imsi
                                          TMST.
                                                                             OPTIONAL,
     lmsi
                                          TMST
     extensionContainer
                                          ExtensionContainer
                                                                             OPTIONAL,
     vlr-Capability
                                          [6] VLR-Capability
                                                                             OPTIONAL }
RestoreDataRes ::= SEQUENCE {
    hlr-Number
                                          ISDN-AddressString,
     msNotReachable
                                          NULL
                                                                             OPTIONAL,
     extensionContainer
                                          ExtensionContainer
                                                                             OPTIONAL,
 - VBS/VGCS types
VBSDataList ::= SEQUENCE SIZE (1..maxNumOfVBSGroupIds) OF
                                         VoiceBroadcastData
VGCSDataList ::= SEQUENCE SIZE (1..maxNumOfVGCSGroupIds) OF
                                         VoiceGroupCallData
maxNumOfVBSGroupIds INTEGER ::= 50
maxNumOfVGCSGroupIds INTEGER ::= 50
VoiceGroupCallData ::= SEQUENCE {
     groupId
                                          GroupId,
     extensionContainer
                                          ExtensionContainer
                                                                             OPTIONAL,
VoiceBroadcastData ::= SEQUENCE {
    groupid
                                          GroupId,
     broadcastInitEntitlement
                                          NULL
                                                                             OPTIONAL.
     extensionContainer
                                          ExtensionContainer
                                                                             OPTIONAL,
GroupId ::= TBCD-STRING (SIZE (3))
    -- When Group-Id is less than six characters in length, the TBCD filler (1111)
     -- is used to fill unused half octets.
     -- Refers to the Group Identification as specified in 3GPP TS 23.003
     -- and 3GPP TS 43.068/ 43.069
-- provide subscriber info types
ProvideSubscriberInfoArg ::= SEQUENCE {
            [0] IMSI,
     imsi
              [1] LMSI
                                          OPTIONAL,
     lmsi
     requestedInfo
                                          [2] RequestedInfo,
     extensionContainer
                                          [3] ExtensionContainer
                                                                             OPTIONAL,
ProvideSubscriberInfoRes ::= SEQUENCE {
     subscriberInfo
                                          SubscriberInfo,
     extensionContainer
                                          ExtensionContainer
                                                                             OPTIONAL.
SubscriberInfo ::= SEQUENCE {
     locationInformation
                                          [0] LocationInformation
                                                                             OPTIONAL,
     subscriberState
                                          [1] SubscriberState
                                                                             OPTIONAL,
     extensionContainer
                                          [2] ExtensionContainer
                                                                             OPTIONAL,
     locationInformationGPRS
                                          [3] LocationInformationGPRS
                                                                             OPTIONAL.
                                                                             OPTIONAL,
     ps-SubscriberState
                                          [4] PS-SubscriberState
                                          [5] IMEI
                                                                             OPTIONAL,
     imei
     ms-Classmark2
                                          [6] MS-Classmark2
                                                                             OPTIONAL,
     gprs-MS-Class
                                          [7] GPRSMSClass
                                                                             OPTIONAL.
                                          [8] MNPInfoRes
     mnpInfoRes
                                                                             OPTIONAL }
     If the HLR receives locationInformation, subscriberState or ms-Classmark2 from an SGSN
    it shall discard them.
     If the HLR receives locationInformationGPRS, ps-SubscriberState or gprs-MS-Class from
     a VLR it shall discard them.
     If the HLR receives parameters which it has not requested, it shall discard them.
```

```
MNPInfoRes ::= SEQUENCE {
    routeingNumber
                                         [0] RouteingNumber
                                                                           OPTIONAL.
                                         [1] IMSI
    imsi
                                                                          OPTIONAL,
                                         [2] ISDN-AddressString
    msisdn
                                                                          OPTIONAL,
    numberPortabilityStatus
                                         [3] NumberPortabilityStatus
                                                                          OPTIONAL,
    extensionContainer
                                        [4] ExtensionContainer
                                                                          OPTIONAL,
    The IMSI parameter contains a generic IMSI, i.e. it is not tied necessarily to the
    Subscriber. MCC and MNC values in this IMSI shall point to the Subscription Network of
    the Subscriber. See 3GPP TS 23.066 [108].
```

```
RouteingNumber ::= TBCD-STRING (SIZE (1..5))
```

```
MS-Classmark2 ::= OCTET STRING (SIZE (3))

-- This parameter carries the value part of the MS Classmark 2 IE defined in

-- 3GPP TS 24.008 [35].
```

```
GPRSMSClass ::= SEQUENCE {

    mSNetworkCapability [0] MSNetworkCapability,

    mSRadioAccessCapability [1] MSRadioAccessCapability OPTIONAL
}
```

```
MSNetworkCapability ::= OCTET STRING (SIZE (1..8))

-- This parameter carries the value part of the MS Network Capability IE defined in

-- 3GPP TS 24.008 [35].
```

```
MSRadioAccessCapability ::= OCTET STRING (SIZE (1..50))

-- This parameter carries the value part of the MS Radio Access Capability IE defined in
-- 3GPP TS 24.008 [35].
```

```
RequestedInfo ::= SEQUENCE {
    locationInformation
                                         [0] NULL
                                                                           OPTIONAL,
    subscriberState
                                         [1] NULL
                                                                           OPTIONAL,
    extensionContainer
                                        [2] ExtensionContainer
                                                                          OPTIONAL,
    currentLocation
                                         [3] NULL
                                                                           OPTIONAL,
    requestedDomain
                                         [4] DomainType
                                                                           OPTIONAL,
                                         [6] NULL
    imei
                                                                           OPTIONAL,
                                         [5] NULL
                                                                           OPTIONAL,
    ms-classmark
    mnpRequestedInfo
                                         [7] NULL
                                                                           OPTIONAL }
    currentLocation shall be absent if locationInformation is absent
```

```
LocationInformation ::= SEQUENCE {
    ageOfLocationInformation
                                         AgeOfLocationInformation
                                                                           OPTIONAL.
                                         [0] GeographicalInformation
                                                                         OPTIONAL,
    geographicalInformation
                                         [1] ISDN-AddressString
    vlr-number
                                                                         OPTIONAL,
    locationNumber
                                         [2] LocationNumber
                                                                          OPTIONAL,
    cellGlobalIdOrServiceAreaIdOrLAI
                                         [3] CellGlobalIdOrServiceAreaIdOrLAI OPTIONAL,
    extensionContainer
                                         [4] ExtensionContainer
                                                                          OPTIONAL.
    selectedLSA-Id
                                         [5] LSAIdentity
                                                                          OPTIONAL,
    msc-Number
                                         [6] ISDN-AddressString
                                                                          OPTIONAL,
    geodeticInformation
                                         [7] GeodeticInformation
                                                                          OPTIONAL,
                                         [8] NULL
    currentLocationRetrieved
                                                                           OPTIONAL.
    sai-Present
                                         [9] NIII.I.
                                                                           OPTIONAL }
-- sai-Present indicates that the cellGlobalIdOrServiceAreaIdOrLAI parameter contains
-- a Service Area Identity.
-- currentLocationRetrieved shall be present
-- if the location information were retrieved after a successfull paging.
```

```
LocationInformationGPRS ::= SEQUENCE {
     cellGlobalIdOrServiceAreaIdOrLAI
                                           [0] CellGlobalIdOrServiceAreaIdOrLAI OPTIONAL,
                                           [1] RAIdentity
     routeingAreaIdentity
                                                                              OPTIONAL,
     geographicalInformation
                                           [2] GeographicalInformation
                                                                              OPTIONAL,
                                           [3] ISDN-AddressString
[4] LSAIdentity
     sasn-Number
                                                                              OPTIONAL.
     selectedLSAIdentity
                                                                              OPTIONAL.
     extensionContainer
                                           [5] ExtensionContainer
                                                                              OPTIONAL,
     sai-Present
                                           [6] NULL
                                                                               OPTIONAL.
                                           [7] GeodeticInformation [8] NULL
     geodeticInformation
                                                                               OPTIONAL.
     currentLocationRetrieved ageOfLocationInformation
                                                                               OPTIONAL,
                                           [9] AgeOfLocationInformation
                                                                               OPTIONAL }
-- sai-Present indicates that the cellGlobalIdOrServiceAreaIdOrLAI parameter contains
-- a Service Area Identity.
-- currentLocationRetrieved shall be present if the location information
-- was retrieved after successful paging.
```

```
RAIdentity ::= OCTET STRING (SIZE (6))
-- Routing Area Identity is coded in accordance with 3GPP TS 29.060 [105].
-- It shall contain the value part defined in 3GPP TS 29.060 only. I.e. the 3GPP TS 29.060
-- type identifier octet shall not be included.
```

```
GeographicalInformation ::= OCTET STRING (SIZE (8))
-- Refers to geographical Information defined in 3GPP TS 23.032.
-- Only the description of an ellipsoid point with uncertainty circle
-- as specified in 3GPP TS 23.032 is allowed to be used
-- The internal structure according to 3GPP TS 23.032 is as follows:
-- Type of shape (ellipsoid point with uncertainty circle) 1 octet
-- Degrees of Latitude 3 octets
-- Degrees of Longitude 3 octets
-- Uncertainty code 1 octet
```

```
GeodeticInformation ::= OCTET STRING (SIZE (10))
    Refers to Calling Geodetic Location defined in Q.763 (1999).
     Only the description of an ellipsoid point with uncertainty circle
_ _
     as specified in Q.763 (1999) is allowed to be used
_ _
     The internal structure according to Q.763 (1999) is as follows:
         Screening and presentation indicators
                                                                              1 octet
         Type of shape (ellipsoid point with uncertainty circle)
                                                                              1 octet
- -
         Degrees of Latitude
                                                                              3 octets
_ _
         Degrees of Longitude
                                                                              3 octets
_ _
         Uncertainty code
                                                                              1 octet
         Confidence
                                                                              1 octet
```

```
LocationNumber ::= OCTET STRING (SIZE (2..10))
-- the internal structure is defined in ITU-T Rec Q.763
```

```
SubscriberState ::= CHOICE {
    assumedIdle [0] NULL,
    camelBusy [1] NULL,
    netDetNotReachable NotReachableReason,
    notProvidedFromVLR [2] NULL}
```

```
PS-SubscriberState ::= CHOICE {
    notProvidedFromSGSN [0] NULL,
    ps-Detached [1] NULL,
    ps-AttachedNotReachableForPaging [2] NULL,
    ps-AttachedReachableForPaging [3] NULL,
    ps-PDP-ActiveNotReachableForPaging [4] PDP-ContextInfoList,
    ps-PDP-ActiveReachableForPaging [5] PDP-ContextInfoList,
    netDetNotReachable NotReachableReason }
```

```
PDP-ContextInfoList ::= SEQUENCE SIZE (1..maxNumOfPDP-Contexts) OF
PDP-ContextInfo
```

```
PDP-ContextInfo ::= SEQUENCE {
     pdp-ContextIdentifier
                                            [0] ContextId,
     pdp-ContextActive
                                            [1] NULL
                                                                                OPTIONAL.
                                            [2] PDP-Type,
     pdp-Type
     pdp-Address
                                            [3] PDP-Address
                                                                                OPTIONAL,
                                            [4] APN
     apn-Subscribed
                                                                                OPTIONAL,
     apn-InUse
                                            [5] APN
                                                                                OPTIONAL,
                                            [6] NSAPI
                                                                                OPTIONAL.
     nsapi
                                            [7] TransactionId [8] TEID
     transactionId
                                                                                OPTIONAL,
     teid-ForGnAndGp
                                                                                OPTIONAL,
                                            [9] TEID
     teid-ForIu
                                                                                OPTIONAL,
     ggsn-Address
                                            [10] GSN-Address
                                                                                OPTIONAL,
     gos-Subscribed
                                            [11] Ext-QoS-Subscribed
                                                                                OPTIONAL.
                                            [12] Ext-QoS-Subscribed
                                                                                OPTIONAL,
     gos-Requested
     qos-Negotiated
                                            [13] Ext-QoS-Subscribed
                                                                                OPTIONAL,
                                           [14] GPRSChargingID
     chargingId
     chargingCharacteristics
                                            [15] ChargingCharacteristics
                                                                               OPTIONAL,
     rnc-Address
                                            [16] GSN-Address
                                                                                OPTIONAL.
     extensionContainer
                                            [17] ExtensionContainer
                                                                                OPTIONAL,
     qos2-Subscribed
                                            [18] Ext2-QoS-Subscribed
                                                                                OPTIONAL,
     -- qos2-Subscribed may be present only if qos-Subscribed is present.
                                           [19] Ext2-QoS-Subscribed
     gos2-Requested
                                                                                OPTIONAL,
     -- qos2-Requested may be present only if qos-Requested is present.
qos2-Negotiated [20] Ext2-QoS-Subscribed
                                                                                OPTIONAL
      -- qos2-Negotiated may be present only if qos-Negotiated is present.
```

```
NSAPI ::= INTEGER (0..15)
-- This type is used to indicate the Network layer Service Access Point
```

```
TransactionId ::= OCTET STRING (SIZE (1..2))
-- This type carries the value part of the transaction identifier which is used in the
-- session management messages on the access interface. The encoding is defined in
-- 3GPP TS 24.008
```

```
TEID ::= OCTET STRING (SIZE (4))

-- This type carries the value part of the Tunnel Endpoint Identifier which is used to

-- distinguish between different tunnels between the same pair of entities which communicate

-- using the GPRS Tunnelling Protocol The encoding is defined in 3GPP TS 29.060.
```

```
GPRSChargingID ::= OCTET STRING (SIZE (4))

-- The Charging ID is a unique four octet value generated by the GGSN when

-- a PDP Context is activated. A Charging ID is generated for each activated context.

-- The encoding is defined in 3GPP TS 29.060.
```

```
NotReachableReason ::= ENUMERATED {
    msPurged (0),
    imsiDetached (1),
    restrictedArea (2),
    notRegistered (3)}
```

-- any time interrogation info types

-- any time information handling types

AnyTimeSubscriptionInterrogationRes	··= SEOU	ENCE {	
callForwardingData		CallForwardingData	OPTIONAL,
callBarringData		CallBarringData	OPTIONAL,
odb-Info	[3]	ODB-Info	OPTIONAL,
camel-SubscriptionInfo	[4]	CAMEL-SubscriptionInfo	OPTIONAL,
supportedVLR-CAMEL-Phases	[5]	SupportedCamelPhases	OPTIONAL,
supportedSGSN-CAMEL-Phases	[6]	SupportedCamelPhases	OPTIONAL,
extensionContainer	[7]	ExtensionContainer	OPTIONAL,
• • • • •			
offeredCamel4CSIsInVLR	[8]	OfferedCamel4CSIs	OPTIONAL,
offeredCamel4CSIsInSGSN	[9]	OfferedCamel4CSIs	OPTIONAL }

```
RequestedSubscriptionInfo ::= SEQUENCE {
    requestedSS-Info
                                          [1] SS-ForBS-Code
                                                                             OPTIONAL,
    odb
                                          [2] NULL
                                                                             OPTIONAL,
    requestedCAMEL-SubscriptionInfo
                                                                                 OPTIONAL,
                                          [3] RequestedCAMEL-SubscriptionInfo
                                          [4] NULL
    supportedVLR-CAMEL-Phases
                                                                             OPTIONAL,
     supportedSGSN-CAMEL-Phases
                                          [5] NULL
                                                                             OPTIONAL.
     extensionContainer
                                          [6] ExtensionContainer
                                                                             OPTIONAL,
    additionalRequestedCAMEL-SubscriptionInfo
                                          [7] AdditionalRequestedCAMEL-SubscriptionInfo
                                                                             OPTIONAL
```

```
RequestedCAMEL-SubscriptionInfo ::= ENUMERATED
     o-CSI
     t-CSI
                                              (1),
     vt-CSI
                                             (2),
     tif-CSI
                                             (3),
                                             (4),
     gprs-CSI
                                             (5),
     mo-sms-CSI
     ss-CSI
                                             (6),
     m-CSI
                                             (7)
     d-csi
                                             (8)
```

```
WrongPasswordAttemptsCounter ::= INTEGER (0..4)
```

```
ODB-Info ::= SEQUENCE {
     odb-Data
                                           ODB-Data.
                                                                              OPTIONAL,
     notificationToCSE
                                           NULL
     extensionContainer
                                           ExtensionContainer
                                                                              OPTIONAL,
     . . . }
CAMEL-SubscriptionInfo ::= SEQUENCE {
     o-CSI
                                           [0] O-CSI
                                                                              OPTIONAL.
                                           [1] O-BcsmCamelTDPCriteriaList
     o-BcsmCamelTDP-CriteriaList
                                                                              OPTIONAL,
     d-CSI
                                           [2] D-CSI
                                                                              OPTIONAL,
     t-CSI
                                           [3]
                                               T-CSI
                                                                              OPTIONAL,
                                           [4] T-BCSM-CAMEL-TDP-CriteriaList OPTIONAL,
     t-BCSM-CAMEL-TDP-CriteriaList
     vt.-CSI
                                           [5] T-CSI OPTIONAL,[6] T-BCSM-CAMEL-TDP-CriteriaList OPTIONAL,
     vt-BCSM-CAMEL-TDP-CriteriaList
     tif-CSI
                                           [7] NULL
                                                                              OPTIONAL,
     tif-CSI-NotificationToCSE
                                           [8]
                                               NULL
                                                                              OPTIONAL,
     aprs-CSI
                                           [9] GPRS-CSI
                                                                              OPTIONAL,
                                           [10] SMS-CSI
     mo-sms-CSI
                                                                              OPTIONAL.
     ss-CSI
                                           [11] SS-CSI
                                                                              OPTIONAL,
     m-CSI
                                           [12] M-CSI
                                                                              OPTIONAL,
     extensionContainer
                                           [13] ExtensionContainer
                                                                              OPTIONAL,
     specificCSIDeletedList
                                           [14] SpecificCSI-Withdraw
                                                                              OPTIONAL.
                                           [15] SMS-CSI
     mt-sms-CSI
                                                                              OPTIONAL,
     mt-smsCAMELTDP-CriteriaList
                                          [16] MT-smsCAMELTDP-CriteriaList
                                                                              OPTIONAL,
     mg-csi
                                           [17] MG-CSI
                                                                              OPTIONAL,
     o-IM-CSI
                                           [18] O-CSI
                                                                              OPTIONAL,
     o-IM-BcsmCamelTDP-CriteriaList
                                           [19] O-BcsmCamelTDPCriteriaList
                                                                              OPTIONAL,
                                           [20] D-CSI
     d-IM-CSI
                                                                              OPTIONAL,
                                           [21] T-CSI
                                                                              OPTIONAL,
     vt-IM-CSI
     vt-IM-BCSM-CAMEL-TDP-CriteriaList
                                           [22] T-BCSM-CAMEL-TDP-CriteriaList OPTIONAL
AnyTimeModificationArg ::= SEQUENCE {
     subscriberIdentity
                                           [0] SubscriberIdentity,
     gsmSCF-Address
                                           [1] ISDN-AddressString,
     modificationRequestFor-CF-Info
                                               ModificationRequestFor-CF-Info OPTIONAL,
                                           [3] ModificationRequestFor-CB-Info OPTIONAL,
     modificationRequestFor-CB-Info
                                           [4] ModificationRequestFor-CSI OPTIONAL,
[5] ExtensionContainer OPTIONAL,
     modificationRequestFor-CSI
     extensionContainer
     longFTN-Supported
                                           [6] NULL
                                                                              OPTIONAL,
     modificationRequestFor-ODB-data
                                           [7] ModificationRequestFor-ODB-data OPTIONAL }
AnyTimeModificationRes ::= SEQUENCE {
     ss-InfoFor-CSE
                                           [0] Ext-SS-InfoFor-CSE
                                                                              OPTIONAL,
                                                                              OPTIONAL,
     camel-SubscriptionInfo
                                           [1] CAMEL-SubscriptionInfo
     extensionContainer
                                           [2] ExtensionContainer
                                                                              OPTIONAL,
                                           [3] ODB-Info
                                                                              OPTIONAL }
     odb-Info
ModificationRequestFor-CF-Info ::= SEQUENCE {
                                           [0] SS-Code,
[1] Ext-BasicServiceCode
     ss-Code
     basicService
                                                                              OPTIONAL.
     ss-Status
                                           [2] Ext-SS-Status
                                                                              OPTIONAL,
     forwardedToNumber
                                           [3]
                                               AddressString
                                                                              OPTIONAL,
                                           [4] ISDN-SubaddressString
     forwardedToSubaddress
                                                                              OPTIONAL,
     noReplyConditionTime
                                           [5] Ext-NoRepCondTime
                                                                              OPTIONAL,
                                           [6] ModificationInstruction
     modifyNotificationToCSE
                                                                              OPTIONAL.
     extensionContainer
                                           [7] ExtensionContainer
                                                                              OPTIONAL,
ModificationRequestFor-CB-Info ::= SEQUENCE {
     ss-Code
                                           [0]
                                               SS-Code,
     basicService
                                           [1] Ext-BasicServiceCode
                                                                              OPTIONAL,
                                           [2] Ext-SS-Status
[3] Password
                                                                              OPTIONAL,
     ss-Status
     password
                                                                              OPTIONAL,
     wrongPasswordAttemptsCounter
                                           [4] WrongPasswordAttemptsCounter OPTIONAL,
     modifyNotificationToCSE
                                               ModificationInstruction
                                           [5]
                                                                              OPTIONAL,
                                           [6] ExtensionContainer
     extensionContainer
                                                                              OPTIONAL,
ModificationRequestFor-ODB-data ::= SEQUENCE {
                                           [0]
     odb-data
                                               ODB-Data
                                                                              OPTIONAL,
     modifyNotificationToCSE
                                           [1]
                                               ModificationInstruction
                                                                              OPTIONAL,
     extensionContainer
                                           [2] ExtensionContainer
                                                                              OPTIONAL,
```

```
ModificationRequestFor-CSI ::= SEQUENCE {
                                            [0] RequestedCAMEL-SubscriptionInfo,
[1] ModificationInstruction OPTIONAL,
[2] ModificationInstruction OPTIONAL,
     requestedCamel-SubscriptionInfo
     modifyNotificationToCSE
     modifyCSI-State
     extensionContainer
                                            [3] ExtensionContainer
     additionalRequestedCAMEL-SubscriptionInfo
                                            [4] AdditionalRequestedCAMEL-SubscriptionInfo
-- requestedCamel-SubscriptionInfo shall be discarded if
-- additionalRequestedCAMEL-SubscriptionInfo is received
ModificationInstruction ::= ENUMERATED {
                                            (0)
     deactivate
     activate
-- subscriber data modification notification types
NoteSubscriberDataModifiedArg ::= SEQUENCE {
     imsi
                                            IMSI.
     msisdn
                                            ISDN-AddressString,
     forwardingInfoFor-CSE
                                            [0] Ext-ForwardingInfoFor-CSE
                                                                                OPTIONAL,
                                            [1] Ext-CallBarringInfoFor-CSE
     callBarringInfoFor-CSE
                                            [2] ODB-Info
                                                                                OPTIONAL,
     odb-Info
     camel-SubscriptionInfo
                                            [3] CAMEL-SubscriptionInfo
                                                                                OPTIONAL.
     allInformationSent
                                            [4] NULL
                                                                                OPTIONAL,
     extensionContainer
                                            ExtensionContainer
                                                                                OPTIONAL,
NoteSubscriberDataModifiedRes ::= SEQUENCE {
     extensionContainer
                                            ExtensionContainer
                                                                                OPTIONAL,
-- mobility management event notificatioon info types
NoteMM-EventArg::= SEQUENCE {
     serviceKey
                                            ServiceKey,
                                            [0] MM-Code,
     eventMet.
     imsi
                                            [1]
                                                IMSI,
     msisdn
                                            [2] ISDN-AddressString,
                                            [3] LocationInformation
[5] SupportedCamelPhases
     locationInformation
                                                                                OPTIONAL,
                                                                              OPTIONAL,
     supportedCAMELPhases
     extensionContainer
                                                                                OPTIONAL,
                                            [6] ExtensionContainer
     locationInformationGPRS
                                            [7] LocationInformationGPRS
                                                                                OPTIONAL,
     offeredCamel4Functionalities
                                           [8] OfferedCamel4Functionalities OPTIONAL
NoteMM-EventRes ::= SEQUENCE {
     extensionContainer
                                            ExtensionContainer
                                                                                OPTIONAL,
Ext-SS-InfoFor-CSE ::= CHOICE {
                                            [0] Ext-ForwardingInfoFor-CSE,
    forwardingInfoFor-CSE
     callBarringInfoFor-CSE
                                            [1] Ext-CallBarringInfoFor-CSE
```

17.7.2 Operation and maintenance data types

```
MAP-OM-DataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-OM-DataTypes (12) version9 (9)}
DEFINITIONS
IMPLICIT TAGS
BEGIN
EXPORTS
   ActivateTraceModeArg,
   ActivateTraceModeRes,
   DeactivateTraceModeArg,
   DeactivateTraceModeRes,
   TracePropagationList
IMPORTS
   AddressString,
   IMSI
FROM MAP-CommonDataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-CommonDataTypes (18) version9 (9)}
   ExtensionContainer
FROM MAP-ExtensionDataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-ExtensionDataTypes (21) version9 (9) }
ActivateTraceModeArg ::= SEQUENCE {
     imsi
                                           [0] IMSI
                                                                              OPTIONAL,
     traceReference
                                           [1] TraceReference,
     traceType
                                           [2] TraceType,
                                                                              OPTIONAL.
     omc-Id
                                           [3] AddressString
     extensionContainer
                                           [4] ExtensionContainer
                                                                              OPTIONAL,
     traceReference2
                                           [5] TraceReference2
                                                                              OPTIONAL,
     traceDepthList
                                           [6] TraceDepthList
                                                                              OPTIONAL,
     traceNE-TypeList
                                                                              OPTIONAL,
                                           [7] TraceNE-TypeList
                                           [8] TraceInterfaceList
                                                                              OPTIONAL,
     traceInterfaceList
     traceEventList
                                           [9] TraceEventList
                                                                              OPTIONAL
TraceReference ::= OCTET STRING (SIZE (1..2))
TraceReference2 ::= OCTET STRING (SIZE (3))
TraceRecordingSessionReference ::= OCTET STRING (SIZE (2))
TraceType ::= INTEGER
     (0..255)
     -- Trace types are fully defined in 3GPP TS 52.008. [61]
TraceDepthList ::= SEQUENCE {
                                           [0] TraceDepth [1] TraceDepth
     msc-s-TraceDepth
                                                                              OPTIONAL.
                                                                              OPTIONAL,
     mgw-TraceDepth
     sgsn-TraceDepth
                                           [2] TraceDepth
                                                                              OPTIONAL,
     ggsn-TraceDepth
                                           [3] TraceDepth
                                                                              OPTIONAL,
                                           [4] TraceDepth
     rnc-TraceDepth
                                                                              OPTIONAL,
     bmsc-TraceDepth
                                                                              OPTIONAL.
                                           [5] TraceDepth
TraceDepth ::= ENUMERATED {
     minimum (0),
     medium (1),
     maximum (2),
-- The value medium is applicable only for RNC. For other network elements, if value medium
   is received, value minimum shall be applied.
```

```
TraceNE-TypeList ::= BIT STRING {
    msc-s (0),
    mgw (1),
    sgsn (2),
    ggsn (3),
    rnc (4),
    bm-sc (5)} (SIZE (6..16))
-- Other bits than listed above shall be discarded.
```

```
TraceInterfaceList ::= SEQUENCE {
     msc-s-List
                                           [0] MSC-S-InterfaceList
                                                                              OPTIONAL,
     mgw-List
                                           [1] MGW-InterfaceList
                                                                              OPTIONAL,
                                           [2] SGSN-InterfaceList
     sgsn-List
                                                                              OPTIONAL.
     ggsn-List
                                           [3] GGSN-InterfaceList
                                                                              OPTIONAL,
     rnc-List
                                           [4] RNC-InterfaceList
                                                                              OPTIONAL,
     bmsc-List
                                           [5] BMSC-InterfaceList
                                                                              OPTIONAL,
```

```
MSC-S-InterfaceList ::= BIT STRING {
    a (0),
    iu (1),
    mc (2),
    map-g (3),
    map-b (4),
    map-e (5),
    map-f (6),
    cap (7),
    map-d (8),
    map-c (9)} (SIZE (10..16))
-- Other bits than listed above shall be discarded.
```

```
MGW-InterfaceList ::= BIT STRING {
    mc (0),
    nb-up (1),
    iu-up (2)} (SIZE (3..8))
-- Other bits than listed above shall be discarded.
```

```
SGSN-InterfaceList ::= BIT STRING {
    gb (0),
    iu (1),
    gn (2),
    map-gr (3),
    map-gd (4),
    map-gf (5),
    gs (6),
    ge (7)} (SIZE (8..16))
-- Other bits than listed above shall be discarded.
```

```
GGSN-InterfaceList ::= BIT STRING {
    gn (0),
    gi (1),
    gmb (2)} (SIZE (3..8))
-- Other bits than listed above shall be discarded.
```

```
RNC-InterfaceList ::= BIT STRING {
    iu (0),
    iur (1),
    iub (2),
    uu (3)} (SIZE (4..8))
-- Other bits than listed above shall be discarded.
```

```
BMSC-InterfaceList ::= BIT STRING {
   gmb (0)} (SIZE (1..8))
-- Other bits than listed above shall be discarded.
```

```
TraceEventList ::= SEQUENCE {
    msc-s-List
                                           [0] MSC-S-EventList
                                                                              OPTIONAL,
                                           [1] MGW-EventList
                                                                              OPTIONAL,
    mqw-List
    sgsn-List
                                           [2] SGSN-EventList
                                                                              OPTIONAL,
    ggsn-List
                                           [3] GGSN-EventList
                                                                              OPTIONAL,
    bmsc-List
                                           [4] BMSC-EventList
                                                                              OPTIONAL,
```

```
MSC-S-EventList ::= BIT STRING {
    mo-mtCall (0),
    mo-mt-sms (1),
    lu-imsiAttach-imsiDetach (2),
    handovers (3),
    ss (4)} (SIZE (5..16))
-- Other bits than listed above shall be discarded.
```

```
MGW-EventList ::= BIT STRING {
    context (0)} (SIZE (1..8))
-- Other bits than listed above shall be discarded.
```

```
SGSN-EventList ::= BIT STRING {
    pdpContext (0),
    mo-mt-sms (1),
    rau-gprsAttach-gprsDetach (2),
    mbmsContext (3)} (SIZE (4..16))
-- Other bits than listed above shall be discarded.
```

```
GGSN-EventList ::= BIT STRING {
   pdpContext (0),
   mbmsContext (1)} (SIZE (2..8))
-- Other bits than listed above shall be discarded.
```

```
BMSC-EventList ::= BIT STRING {
    mbmsMulticastServiceActivation (0) } (SIZE (1..8))
-- Other bits than listed above shall be discarded.
```

```
TracePropagationList ::= SEQUENCE {
    traceReference
                                          [0] TraceReference
                                                                             OPTIONAL,
                                          [1] TraceType
                                                                             OPTIONAL,
    traceType
    traceReference2
                                          [2] TraceReference2
                                                                            OPTIONAL,
    traceRecordingSessionReference
                                          [3] TraceRecordingSessionReference OPTIONAL,
                                          [4] TraceDepth
    rnc-TraceDepth
                                                                            OPTIONAL,
    rnc-InterfaceList
                                          [5] RNC-InterfaceList
                                                                             OPTIONAL,
                                          [6] TraceDepth
    msc-s-TraceDepth
                                                                             OPTIONAL,
    msc-s-InterfaceList
                                          [7] MSC-S-InterfaceList
                                                                             OPTIONAL,
    msc-s-EventList
                                          [8] MSC-S-EventList
                                                                             OPTIONAL,
                                          [9] TraceDepth
    mgw-TraceDepth
                                                                            OPTIONAL,
    mgw-InterfaceList
                                          [10] MGW-InterfaceList
                                                                             OPTIONAL,
    mgw-EventList
                                          [11] MGW-EventList
                                                                             OPTIONAL,
```

```
ActivateTraceModeRes ::= SEQUENCE {
    extensionContainer [0] ExtensionContainer OPTIONAL,
    ...,
    traceSupportIndicator [1] NULL OPTIONAL
}
```

17.7.3 Call handling data types

```
MAP-CH-DataTypes {
  itu-t identified-organization (4) etsi (0) mobileDomain (0)
  gsm-Network (1) modules (3) map-CH-DataTypes (13) version9 (9) }
DEFINITIONS
IMPLICIT TAGS
::=
BEGIN
```

```
EXPORTS
  SendRoutingInfoArg,
   SendRoutingInfoRes,
   ProvideRoamingNumberArg,
   ProvideRoamingNumberRes,
   ResumeCallHandlingArg,
  ResumeCallHandlingRes,
  NumberOfForwarding,
   SuppressionOfAnnouncement,
   CallReferenceNumber,
   SetReportingStateArg,
   SetReportingStateRes,
   StatusReportArg,
   StatusReportRes,
   RemoteUserFreeArg,
   RemoteUserFreeRes,
   IST-AlertArg,
   IST-AlertRes,
   IST-CommandArg,
  IST-CommandRes,
  UU-Data,
  ReleaseResourcesArg,
  ReleaseResourcesRes
IMPORTS
   SubscriberInfo,
   SupportedCamelPhases,
   OfferedCamel4CSIs,
   CUG-Interlock,
  O-CSI,
  D-CSI,
   O-BcsmCamelTDPCriteriaList,
   T-BCSM-CAMEL-TDP-CriteriaList,
   IST-SupportIndicator,
   IST-AlertTimerValue,
  T-CSI,
  NumberPortabilityStatus
FROM MAP-MS-DataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-MS-DataTypes (11) version9 (9)}
   ForwardingOptions,
   SS-List,
   CCBS-Feature
FROM MAP-SS-DataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-SS-DataTypes (14) version9 (9)}
   ISDN-AddressString,
   ISDN-SubaddressString,
   FTN-AddressString,
   ExternalSignalInfo
   Ext-ExternalSignalInfo,
   IMSI,
  LMSI
   Ext-BasicServiceCode,
   AlertingPattern,
  NAEA-PreferredCI
FROM MAP-CommonDataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-CommonDataTypes (18) version9 (9)}
  ExtensionContainer
FROM MAP-ExtensionDataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-ExtensionDataTypes (21) version9 (9)}
CUG-CheckInfo ::= SEQUENCE {
                                          CUG-Interlock,
    cuq-Interlock
                                                                             OPTIONAL,
    cug-OutgoingAccess
                                          NULL
                                                                             OPTIONAL,
    extensionContainer
                                          ExtensionContainer
```

```
NumberOfForwarding ::= INTEGER (1..5)
```

```
SendRoutingInfoArg ::= SEQUENCE {
                                        [0] ISDN-AddressString,
    msisdn
                                        [1] CUG-CheckInfo
                                                                         OPTIONAL,
    cuq-CheckInfo
    numberOfForwarding
                                        [2] NumberOfForwarding
                                                                        OPTIONAL,
                                        [3] InterrogationType,
    interrogationType
                                       [4] NULL
                                                                         OPTIONAL,
    or-Interrogation
                                       [5] OR-Phase
    or-Capability
                                                                        OPTIONAL.
    qmsc-OrGsmSCF-Address
                                       [6] ISDN-AddressString,
    callReferenceNumber
                                       [7] CallReferenceNumber
                                                                         OPTIONAL,
    forwardingReason
                                       [8] ForwardingReason
                                                                         OPTIONAL,
    basicServiceGroup
                                       [9] Ext-BasicServiceCode
                                                                        OPTIONAL,
    networkSignalInfo
                                       [10] ExternalSignalInfo
                                                                        OPTIONAL.
                                                                        OPTIONAL,
    camelInfo
                                       [11] CamelInfo
    suppressionOfAnnouncement
                                       [12] SuppressionOfAnnouncement OPTIONAL,
    extensionContainer
                                       [13] ExtensionContainer
                                                                        OPTIONAL,
    alertingPattern
                                       [14] AlertingPattern
                                                                       OPTIONAL,
    ccbs-Call
                                        [15] NULL
                                                                          OPTIONAL,
    supportedCCBS-Phase
                                       [16] SupportedCCBS-Phase
                                                                       OPTIONAL,
                                       [17] Ext-ExternalSignalInfo
[18] IST-SupportIndicator
    additionalSignalInfo
                                                                        OPTIONAL,
                                       [18] IST-SupportIndicator
    istSupportIndicator
                                                                        OPTIONAL,
                                      [19] NULL
    pre-pagingSupported
                                                                         OPTIONAL,
    callDiversionTreatmentIndicator
                                       [20] CallDiversionTreatmentIndicator OPTIONAL,
                                       [21] NULL
                                                                         OPTIONAL,
    longFTN-Supported
    suppress-VT-CSI
                                       [22] NULL
                                                                         OPTIONAL.
                                       [23] NULL
    suppressIncomingCallBarring
                                                                         OPTIONAL,
    gsmSCF-InitiatedCall
                                       [24] NULL
                                                                         OPTIONAL,
    basicServiceGroup2
                                        [25] Ext-BasicServiceCode
                                                                         OPTIONAL,
    networkSignalInfo2
                                       [26] ExternalSignalInfo
                                                                         OPTIONAL
```

SuppressionOfAnnouncement ::= NULL

```
InterrogationType ::= ENUMERATED {
   basicCall (0),
   forwarding (1)}
```

```
OR-Phase ::= INTEGER (1..127)
```

CallReferenceNumber ::= OCTET STRING (SIZE (1..8))

```
ForwardingReason ::= ENUMERATED {
   notReachable (0),
   busy (1),
   noReply (2)}
```

```
SupportedCCBS-Phase ::= INTEGER (1..127)
-- exception handling:
-- Only value 1 is used.
-- Values in the ranges 2-127 are reserved for future use.
-- If received values 2-127 shall be mapped on to value 1.
```

```
CallDiversionTreatmentIndicator ::= OCTET STRING (SIZE(1))
-- callDiversionAllowed (xxxx xx01)
-- callDiversionNotAllowed (xxxx xx10)
-- network default is call diversion allowed
```

```
SendRoutingInfoRes ::= [3] SEQUENCE {
                                         [9] TMST
                                                                            OPTIONAL.
    imsi
     -- IMSI must be present if SendRoutingInfoRes is not segmented.
     -- If the TC-Result-NL segmentation option is taken the IMSI must be
     -- present in one segmented transmission of SendRoutingInfoRes.
    extendedRoutingInfo
                                        ExtendedRoutingInfo
                                                                            OPTIONAL.
                                         [3] CUG-CheckInfo
    cua-CheckInfo
                                                                            OPTIONAL.
                                         [6] NULL
    cuqSubscriptionFlag
                                                                            OPTIONAL.
    subscriberInfo
                                         [7] SubscriberInfo
                                                                            OPTIONAL,
    ss-List
                                         [1] SS-List
                                                                            OPTIONAL,
    basicService
                                         [5] Ext-BasicServiceCode
                                                                           OPTIONAL,
                                         [4] NULL
    forwardingInterrogationRequired
                                                                            OPTIONAL.
                                         [2] ISDN-AddressString
                                                                           OPTIONAL,
    mac-Address
    extensionContainer
                                         [0] ExtensionContainer
                                                                           OPTIONAL,
    naea-PreferredCI
                                         [10] NAEA-PreferredCI
                                                                           OPTIONAL.
     -- naea-PreferredCI is included at the discretion of the HLR operator.
    ccbs-Indicators
                                          [11] CCBS-Indicators
                                                                            OPTIONAL,
                                         [12] ISDN-AddressString
                                                                            OPTIONAL.
                                         [13] NumberPortabilityStatus
[14] IST-AlertTimerValue
    numberPortabilityStatus
                                                                           OPTIONAL,
    istAlertTimer
                                                                           OPTIONAL,
    supportedCamelPhasesInVMSC
                                        [15] SupportedCamelPhases
                                                                           OPTIONAL,
                                         [16] OfferedCamel4CSIs
    offeredCamel4CSIsInVMSC
                                                                            OPTIONAL,
                                         [17] RoutingInfo
    routingInfo2
                                                                           OPTIONAL.
                                         [18] SS-List
[19] Ext-BasicServiceCode
    ss-List2
                                                                            OPTIONAL.
    basicService2
                                                                           OPTIONAL.
    allowedServices
                                         [20] AllowedServices
                                                                            OPTIONAL,
     unavailabilityCause
                                          [21] UnavailabilityCause
                                                                            OPTIONAL,
                                         [22] NULL
    releaseResourcesSupported
                                                                            OPTIONAL
```

```
UnavailabilityCause ::= ENUMERATED {
    bearerServiceNotProvisioned
                                          (1),
    teleserviceNotProvisioned
                                           (2),
     absentSubscriber
                                           (3),
    busySubscriber
                                           (4),
    callBarred
                                           (5),
    cug-Reject
                                           (6),
     . . . }
         exception handling:
         Reception of other values than the ones listed shall result in the service
         being unavailable for that call.
```

```
ForwardingData ::= SEQUENCE {
                                        [5] ISDN-AddressString
                                                                           OPTIONAL.
    forwardedToNumber
    -- When this datatype is sent from an HLR which supports CAMEL Phase 2
    -- to a GMSC which supports CAMEL Phase 2 the GMSC shall not check the
    -- format of the number
    forwardedToSubaddress
                                         [4] ISDN-SubaddressString
                                                                           OPTIONAL.
                                         [6] ForwardingOptions
    forwardingOptions
                                                                           OPTIONAL.
    extensionContainer
                                         [7] ExtensionContainer
                                                                           OPTIONAL,
    longForwardedToNumber
                                        [8] FTN-AddressString
                                                                           OPTIONAL }
```

```
ProvideRoamingNumberArg ::= SEQUENCE {
     imsi
                                           [0] IMSI,
                                           [1] ISDN-AddressString,
    msc-Number
     msisdn
                                           [2] ISDN-AddressString
                                                                              OPTIONAL,
     lmsi
                                           [4] LMSI
                                                                              OPTIONAL,
    gsm-BearerCapability
                                           [5] ExternalSignalInfo
                                                                              OPTIONAL,
                                           [6] ExternalSignalInfo
     networkSignalInfo
                                                                              OPTIONAL.
     suppressionOfAnnouncement
                                                                              OPTIONAL,
                                           [7] SuppressionOfAnnouncement
     gmsc-Address
                                           [8] ISDN-AddressString
                                                                              OPTIONAL,
     callReferenceNumber
                                           [9] CallReferenceNumber
                                                                              OPTIONAL,
    or-Interrogation
                                           [10] NULL
                                                                              OPTIONAL,
     extensionContainer
                                          [11] ExtensionContainer
                                                                              OPTIONAL.
     alertingPattern
                                           [12] AlertingPattern
                                                                              OPTIONAL,
     ccbs-Call
                                           [13] NULL
                                                                              OPTIONAL,
     supportedCamelPhasesInInterrogatingNode [15] SupportedCamelPhases
                                                                              OPTIONAL.
     additionalSignalInfo
                                           [14] Ext-ExternalSignalInfo
                                                                              OPTIONAL,
     orNotSupportedInGMSC
                                           [16] NULL
                                                                              OPTIONAL,
    pre-pagingSupported
                                           [17] NULL
                                                                              OPTIONAL.
     longFTN-Supported
                                           [18] NULL
                                                                              OPTIONAL,
                                           [19] NULL
     suppress-VT-CSI
                                                                              OPTIONAL,
     offeredCamel4CSIsInInterrogatingNode [20] OfferedCamel4CSIs
                                                                              OPTIONAL
ProvideRoamingNumberRes ::= SEQUENCE {
                                           ISDN-AddressString,
     roamingNumber
     extensionContainer
                                          ExtensionContainer
                                                                              OPTIONAL,
     releaseResourcesSupported
                                          NULL
                                                                              OPTIONAL }
ResumeCallHandlingArg ::= SEQUENCE {
     callReferenceNumber
                                           [0] CallReferenceNumber
                                                                              OPTIONAL,
     basicServiceGroup
                                           [1] Ext-BasicServiceCode
                                                                              OPTIONAL,
     forwardingData
                                           [2] ForwardingData
                                                                              OPTIONAL,
                                           [3] IMSI
                                                                              OPTIONAL,
     imsi
     cug-CheckInfo
                                           [4] CUG-CheckInfo
                                                                              OPTIONAL,
     o-CSI
                                           [5] O-CSI
                                                                              OPTIONAL,
     extensionContainer
                                           [7] ExtensionContainer
                                                                              OPTIONAL,
                                           [8] NULL
[9] ISDN-AddressString
    ccbs-Possible
                                                                              OPTIONAL,
    msisdn
                                                                              OPTIONAL,
     uu-Data
                                           [10] UU-Data
                                                                              OPTIONAL,
     allInformationSent
                                           [11] NULL
                                                                              OPTIONAL,
     d-csi
                                           [12] D-CSI
                                                                              OPTIONAL,
     o-BcsmCamelTDPCriteriaList
                                           [13] O-BcsmCamelTDPCriteriaList
                                                                              OPTIONAL.
    basicServiceGroup2
                                           [14] Ext-BasicServiceCode
                                                                              OPTIONAL
UU-Data ::= SEQUENCE {
                                           [0] UUIndicator
    uuIndicator
                                                                              OPTIONAL,
                                           [1] UUI
                                                                              OPTIONAL,
    uui
                                           [2] NULL
                                                                              OPTIONAL,
     uusCFInteraction
     extensionContainer
                                           [3] ExtensionContainer
                                                                              OPTIONAL,
UUIndicator ::= OCTET STRING (SIZE (1))
     -- Octets are coded according to ETS 300 356
     ::= OCTET STRING (SIZE (1..131))
      -- Octets are coded according to ETS 300 356
ResumeCallHandlingRes ::= SEQUENCE {
                                          ExtensionContainer
     extensionContainer
                                                                              OPTIONAL.
     . . . }
CamelInfo ::= SEQUENCE {
     supportedCamelPhases
                                           SupportedCamelPhases,
     suppress-T-CSI
                                                                              OPTIONAL,
                                          NULL
     extensionContainer
                                          ExtensionContainer
                                                                              OPTIONAL,
    offeredCamel4CSIs
                                                                              OPTIONAL }
                                           [0] OfferedCamel4CSIs
ExtendedRoutingInfo ::= CHOICE {
    routingInfo
                                          RoutingInfo,
     camelRoutingInfo
                                           [8] CamelRoutingInfo}
```

```
CamelRoutingInfo ::= SEQUENCE {
                                           ForwardingData
     forwardingData
                                                                               OPTIONAL.
                                           [0] GmscCamelSubscriptionInfo,
     gmscCamelSubscriptionInfo
     extensionContainer
                                           [1] ExtensionContainer
                                                                               OPTIONAL,
GmscCamelSubscriptionInfo ::= SEQUENCE {
     t-CSI
                                           [0] T-CSI OPTIONAL,
     o-CSI
                                           [1] O-CSI OPTIONAL,
     extensionContainer
                                           [2] ExtensionContainer
                                                                               OPTIONAL,
     o-BcsmCamelTDP-CriteriaList
                                           [3] O-BcsmCamelTDPCriteriaList
                                                                               OPTIONAL,
     t-BCSM-CAMEL-TDP-CriteriaList
                                           [4] T-BCSM-CAMEL-TDP-CriteriaList OPTIONAL,
                                                D-CSI
     d-csi
                                           [5]
                                                                               OPTIONAL 
SetReportingStateArg ::= SEQUENCE {
     imsi
                                           [0]
                                                IMSI
                                                                               OPTIONAL,
                                                LMSI
                                                                               OPTIONAL,
     lmsi
                                           [1]
     ccbs-Monitoring
                                                ReportingState
                                                                               OPTIONAL,
                                           [2]
     extensionContainer
                                           [3] ExtensionContainer
                                                                               OPTIONAL.
ReportingState ::= ENUMERATED {
     stopMonitoring
                                           (0),
     startMonitoring
                                           (1),
     ...}
     -- exception handling:
     -- reception of values 2-10 shall be mapped to 'stopMonitoring'
     -- reception of values > 10 shall be mapped to 'startMonitoring'
SetReportingStateRes ::= SEQUENCE{
     ccbs-SubscriberStatus
                                           [0] CCBS-SubscriberStatus
                                                                               OPTIONAL,
     extensionContainer
                                           [1] ExtensionContainer
                                                                               OPTIONAL,
CCBS-SubscriberStatus ::= ENUMERATED {
     ccbsNotIdle
                                           (0),
     ccbsIdle
                                           (1),
     ccbsNotReachable
                                           (2),
     . . . }
     -- exception handling:
-- reception of values 3-10 shall be mapped to 'ccbsNotIdle'
     -- reception of values 11-20 shall be mapped to 'ccbsIdle'
         reception of values > 20 shall be mapped to 'ccbsNotReachable'
StatusReportArg ::= SEQUENCE{
     imsi
                                           [0] IMSI,
                                           [1] EventReportData
     eventReportData
                                                                               OPTIONAL,
                                                                               OPTIONAL,
     callReportdata
                                           [2] CallReportData
     extensionContainer
                                           [3] ExtensionContainer
                                                                               OPTIONAL,
EventReportData ::= SEQUENCE{
     ccbs-SubscriberStatus
                                           [0] CCBS-SubscriberStatus
                                                                               OPTIONAL,
     extensionContainer
                                           [1] ExtensionContainer
                                                                               OPTIONAL,
CallReportData ::= SEQUENCE{
                                           [0] MonitoringMode
                                                                               OPTIONAL,
     monitoringMode
                                                                               OPTIONAL,
     callOutcome
                                           [1] CallOutcome
     extensionContainer
                                           [2] ExtensionContainer
                                                                               OPTIONAL,
MonitoringMode ::= ENUMERATED {
     a-side
                                           (0),
     b-side
                                           (1),
     . . . }
         exception handling:
        reception of values 2-10 shall be mapped 'a-side'
```

reception of values > 10 shall be mapped to 'b-side'

```
CallOutcome ::= ENUMERATED {
                                               (0),
     success
     failure
                                               (1),
     busy
                                               (2),
     . . . }
         exception handling:
     -- reception of values 3-10 shall be mapped to 'success'
-- reception of values 11-20 shall be mapped to 'failure'
     -- reception of values > 20 shall be mapped to 'busy'
StatusReportRes ::= SEQUENCE {
     extensionContainer
                                               [0] ExtensionContainer
                                                                                      OPTIONAL,
RemoteUserFreeArg ::= SEQUENCE{
                                               [0] IMSI,
     imsi
     callInfo
                                               [1] ExternalSignalInfo,
     ccbs-Feature
                                               [2] CCBS-Feature,
     translatedB-Number
                                               [3]
                                                    ISDN-AddressString,
                                               [4] NULL
     replaceB-Number
                                                                                     OPTIONAL,
                                               [5] AlertingPattern
     alertingPattern
                                                                                      OPTIONAL,
                                               [6] ExtensionContainer
     {\tt extensionContainer}
                                                                                      OPTIONAL,
RemoteUserFreeRes ::= SEQUENCE{
     ruf-Out.come
                                               [0] RUF-Outcome,
     extensionContainer
                                               [1] ExtensionContainer
                                                                                     OPTIONAL.
RUF-Outcome ::= ENUMERATED{
     accepted (0),
     rejected (1),
     noResponseFromFreeMS (2), -- T4 Expiry noResponseFromBusyMS (3), -- T10 Expiry
     udubFromFreeMS (4),
     udubFromBusyMS (5),
     . . . }
     -- exception handling:
     -- reception of values 6-20 shall be mapped to 'accepted'
     -- reception of values 21-30 shall be mapped to 'rejected'
     -- reception of values 31-40 shall be mapped to 'noResponseFromFreeMS'
     -- reception of values 41-50 shall be mapped to 'noResponseFromBusyMS'
     -- reception of values 51-60 shall be mapped to 'udubFromFreeMS'
-- reception of values > 60 shall be mapped to 'udubFromBusyMS'
IST-AlertArg ::= SEQUENCE{
                                              [0] IMSI.
     imsi
     extensionContainer
                                               [1] ExtensionContainer
                                                                                      OPTIONAL,
     . . . }
IST-AlertRes ::= SEQUENCE{
                                               [0] IST-AlertTimerValue
     istAlertTimer
                                                                                      OPTIONAL,
                                              [1] NULL
     istInformationWithdraw
                                                                                      OPTIONAL,
                                               [2] CallTerminationIndicator
     callTerminationIndicator
                                                                                      OPTIONAL,
                                               [3] ExtensionContainer
     {\tt extensionContainer}
                                                                                      OPTIONAL,
IST-CommandArg ::= SEQUENCE{
                                               [0] IMSI,
     extensionContainer
                                               [1] ExtensionContainer
                                                                                     OPTIONAL,
IST-CommandRes ::= SEQUENCE{
     extensionContainer
                                                                                      OPTIONAL,
                                               ExtensionContainer
CallTerminationIndicator ::= ENUMERATED {
     terminateCallActivityReferred
                                               (0),
     terminateAllCallActivities
                                               (1),
     . . . }
     -- exception handling:
     -- reception of values 2-10 shall be mapped to 'terminateCallActivityReferred'
-- reception of values > 10 shall be mapped to 'terminateAllCallActivities'
     -- In MSCs not supporting linkage of all call activities, any value received shall
      -- be interpreted as ' terminateCallActivityReferred '
```

17.7.4 Supplementary service data types

```
MAP-SS-DataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-SS-DataTypes (14) version9 (9)}
DEFINITIONS
IMPLICIT TAGS
BEGIN
EXPORTS
  RegisterSS-Arg,
  SS-Info,
  SS-Status
  SS-SubscriptionOption,
  SS-ForBS-Code,
   InterrogateSS-Res,
  USSD-Arg,
  USSD-Res,
  USSD-DataCodingScheme,
  USSD-String,
  Password,
  GuidanceInfo.
  SS-List,
  SS-InfoList,
  OverrideCategory,
  CliRestrictionOption,
  NoReplyConditionTime,
  ForwardingOptions,
  maxNumOfSS,
  SS-Data,
  SS-InvocationNotificationArg,
  SS-InvocationNotificationRes
   CCBS-Feature,
  RegisterCC-EntryArg,
  RegisterCC-EntryRes,
  EraseCC-EntryArg,
  EraseCC-EntryRes
IMPORTS
  AddressString,
  ISDN-AddressString,
   ISDN-SubaddressString,
  FTN-AddressString,
  IMSI,
  BasicServiceCode,
  AlertingPattern,
  EMLPP-Priority,
  MaxMC-Bearers,
  MC-Bearers,
  ExternalSignalInfo
FROM MAP-CommonDataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
  gsm-Network (1) modules (3) map-CommonDataTypes (18) version9 (9)}
  ExtensionContainer
FROM MAP-ExtensionDataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-ExtensionDataTypes (21) version9 (9)}
  SS-Code
```

```
FROM MAP-SS-Code {
  itu-t identified-organization (4) etsi (0) mobileDomain (0)
  gsm-Network (1) modules (3) map-SS-Code (15) version9 (9)};
```

```
RegisterSS-Arg ::= SEQUENCE {
                                         SS-Code,
    ss-Code
    basicService
                                         BasicServiceCode
                                                                           OPTIONAL,
    forwardedToNumber
                                         [4] AddressString
                                                                           OPTIONAL,
                                         [6] ISDN-SubaddressString
    forwardedToSubaddress
                                                                           OPTIONAL,
    noReplyConditionTime
                                        [5] NoReplyConditionTime
                                                                          OPTIONAL,
    defaultPriority
                                        [7] EMLPP-Priority
                                                                           OPTIONAL,
    nbrUser
                                         [8] MC-Bearers
                                                                           OPTIONAL,
                                         [9] NULL
    longFTN-Supported
                                                                           OPTIONAL
```

NoReplyConditionTime ::= INTEGER (5..30)

```
ForwardingFeatureList ::=

SEQUENCE SIZE (1..maxNumOfBasicServiceGroups) OF

ForwardingFeature
```

```
ForwardingFeature ::= SEQUENCE {
    basicService
                                        BasicServiceCode
                                                                          OPTIONAL,
    ss-Status
                                         [4] SS-Status
                                                                          OPTIONAL,
                                         [5] ISDN-AddressString
    forwardedToNumber
                                                                          OPTIONAL,
    forwardedToSubaddress
                                        [8] ISDN-SubaddressString
                                                                          OPTIONAL,
    forwardingOptions
                                         [6] ForwardingOptions
                                                                          OPTIONAL,
    noReplyConditionTime
                                        [7] NoReplyConditionTime
                                                                          OPTIONAL,
    longForwardedToNumber
                                      [9] FTN-AddressString
                                                                          OPTIONAL }
```

```
SS-Status ::= OCTET STRING (SIZE (1))

-- bits 8765: 0000 (unused)
-- bits 4321: Used to convey the "P bit", "R bit", "A bit" and "Q bit",
-- representing supplementary service state information
-- as defined in TS 3GPP TS 23.011 [22]

-- bit 4: "Q bit"

-- bit 3: "P bit"

-- bit 2: "R bit"

-- bit 1: "A bit"
```

```
ForwardingOptions ::= OCTET STRING (SIZE (1))
     -- bit 8: notification to forwarding party
     -- 0 no notification
-- 1 notification
     -- bit 7: redirecting presentation
     -- 0 no presentation
-- 1 presentation
     -- bit 6: notification to calling party
     -- 0 no notification
-- 1 notification
     -- bit 5: 0 (unused)
     -- bits 43: forwarding reason
     -- 00 ms not reachable
     -- 01 ms busy
        10 no reply
11 unconditional when used in a SRI Result,
             or call deflection when used in a RCH Argument
     -- bits 21: 00 (unused)
CallBarringInfo ::= SEQUENCE {
     ss-Code
                                           SS-Code
                                                                                OPTIONAL,
     callBarringFeatureList
                                           CallBarringFeatureList,
CallBarringFeatureList ::= SEQUENCE SIZE (1..maxNumOfBasicServiceGroups) OF
                                           CallBarringFeature
CallBarringFeature ::= SEQUENCE {
     basicService
                                           BasicServiceCode
                                                                                OPTIONAL,
     ss-Status [4] SS-Status
                                           OPTIONAL,
SS-Data ::= SEQUENCE {
    ss-Code
                                           SS-Code
                                                                                OPTIONAL.
                                           [4] SS-Status
     ss-Status
                                                                                OPTIONAL,
     ss-SubscriptionOption
                                           SS-SubscriptionOption
                                                                                OPTIONAL,
                                                                               OPTIONAL,
     basicServiceGroupList
                                           BasicServiceGroupList
     defaultPriority
                                                                                OPTIONAL,
                                           EMLPP-Priority
     nbrUser
                                            [5] MC-Bearers
                                                                                OPTIONAL
SS-SubscriptionOption ::= CHOICE {
     cliRestrictionOption
                                            [2] CliRestrictionOption,
     overrideCategory
                                            [1] OverrideCategory}
CliRestrictionOption ::= ENUMERATED {
     permanent (0),
     temporaryDefaultRestricted (1),
     temporaryDefaultAllowed (2)}
{\tt OverrideCategory} \; ::= \; {\tt ENUMERATED} \; \big\{
     overrideEnabled (0),
     overrideDisabled (1)
SS-ForBS-Code ::= SEQUENCE {
     ss-Code
                                           SS-Code,
     basicService
                                           BasicServiceCode
                                                                                OPTIONAL.
     longFTN-Supported
                                            [4] NULL
                                                                                OPTIONAL }
GenericServiceInfo ::= SEQUENCE {
    ss-Status SS-Status,
     cliRestrictionOption
                                           CliRestrictionOption
                                                                                OPTIONAL,
     maximumEntitledPriority
                                            [0] EMLPP-Priority
                                                                                OPTIONAL.
     defaultPriority
                                            [1] EMLPP-Priority
                                                                                OPTIONAL,
     ccbs-FeatureList
                                            [2] CCBS-FeatureList
                                                                                OPTIONAL,
     nbrSB
                                            [3] MaxMC-Bearers
                                                                                OPTIONAL,
                                            [4] MC-Bearers
                                                                                OPTIONAL,
     nbrUser
     nbrSN
                                            [5] MC-Bearers
                                                                                OPTIONAL
```

```
CCBS-FeatureList ::= SEQUENCE SIZE (1..maxNumOfCCBS-Requests) OF
                                        CCBS-Feature
maxNumOfCCBS-Requests INTEGER ::= 5
CCBS-Feature ::= SEQUENCE {
                                         [0] CCBS-Index
     ccbs-Index
                                                                          OPTIONAL.
     b-subscriberNumber
                                        [1] ISDN-AddressString
                                                                          OPTIONAL,
                                         [2] ISDN-SubaddressString
     b-subscriberSubaddress
                                                                          OPTIONAL,
     basicServiceGroup
                                        [3] BasicServiceCode
                                                                          OPTIONAL,
CCBS-Index ::= INTEGER (1..maxNumOfCCBS-Requests)
InterrogateSS-Res ::= CHOICE {
                                         [0] SS-Status,
     ss-Status
     basicServiceGroupList
                                         [2] BasicServiceGroupList,
     forwardingFeatureList
                                         [3] ForwardingFeatureList,
     genericServiceInfo
                                         [4] GenericServiceInfo
USSD-Arg ::= SEQUENCE {
    ussd-DataCodingScheme
                                        USSD-DataCodingScheme,
     ussd-String
                                        USSD-String,
     alertingPattern
                                        AlertingPattern
                                                                          OPTIONAL,
                                         [0] ISDN-AddressString
     msisdn
                                                                          OPTIONAL
USSD-Res ::= SEQUENCE {
     ussd-DataCodingScheme
                                        USSD-DataCodingScheme,
     ussd-String
                                        USSD-String,
USSD-DataCodingScheme ::= OCTET STRING (SIZE (1))
     -- The structure of the USSD-DataCodingScheme is defined by
     -- the Cell Broadcast Data Coding Scheme as described in
     -- TS 3GPP TS 23.038 [25]
USSD-String ::= OCTET STRING (SIZE (1..maxUSSD-StringLength))
     -- The structure of the contents of the USSD-String is dependent
     -- on the USSD-DataCodingScheme as described in TS 3GPP TS 23.038 [25]
maxUSSD-StringLength INTEGER ::= 160
GuidanceInfo ::= ENUMERATED {
    enterPW (0),
     enterNewPW (1),
     enterNewPW-Again (2) }
     -- How this information is really delivered to the subscriber
     -- (display, announcement, \ldots) is not part of this
     -- specification.
SS-List ::= SEQUENCE SIZE (1..maxNumOfSS) OF
                                        SS-Code
maxNumOfSS INTEGER ::= 30
SS-InfoList ::= SEQUENCE SIZE (1..maxNumOfSS) OF
                                        SS-Info
BasicServiceGroupList ::= SEQUENCE SIZE (1..maxNumOfBasicServiceGroups) OF
                                        BasicServiceCode
maxNumOfBasicServiceGroups INTEGER ::= 13
```

```
SS-InvocationNotificationArg ::= SEQUENCE {
                                          [0] IMSI,
     imsi
                                          [1] ISDN-AddressString,
     msisdn
     ss-Event
                                          [2] SS-Code,
     -- The following SS-Code values are allowed :
                                          SS-Code ::= '00110001'B
     -- ect
                                          SS-Code ::= '01010001'B
     -- multiPTY
                                          SS-Code ::= '00100100'B
     -- cd
                                          SS-Code ::= '01000100'B
     -- ccbs
     ss-EventSpecification
                                          [3] SS-EventSpecification
                                                                             OPTIONAL,
     extensionContainer
                                          [4] ExtensionContainer
                                                                             OPTIONAL,
     b-subscriberNumber
                                          [5] ISDN-AddressString
                                                                             OPTIONAL.
     ccbs-RequestState
                                          [6] CCBS-RequestState
                                                                             OPTIONAL
CCBS-RequestState ::= ENUMERATED {
    request (0),
     recall
               (1),
              (2),
     active
     completed (3),
     suspended (4),
     frozen
              (5),
     deleted (6)
SS-InvocationNotificationRes ::= SEQUENCE {
                                                                             OPTIONAL,
     extensionContainer
                                          ExtensionContainer
SS-EventSpecification ::= SEQUENCE SIZE (1..maxEventSpecification) OF
                                          AddressString
maxEventSpecification INTEGER ::= 2
RegisterCC-EntryArg ::= SEQUENCE {
     ss-Code
                                          [0] SS-Code,
     ccbs-Data
                                          [1] CCBS-Data
                                                                             OPTIONAL,
CCBS-Data ::= SEQUENCE {
     ccbs-Feature
                                          [0] CCBS-Feature,
                                          [1] ISDN-AddressString,
     translatedB-Number
     serviceIndicator
                                          [2] ServiceIndicator
                                                                             OPTIONAL,
     callInfo
                                          [3] ExternalSignalInfo,
     networkSignalInfo
                                          [4] ExternalSignalInfo,
ServiceIndicator ::= BIT STRING {
    clir-invoked (0),
     camel-invoked (1) } (SIZE(2..32))
     -- exception handling:
     -- bits 2 to 31 shall be ignored if received and not understood
RegisterCC-EntryRes ::= SEQUENCE {
    ccbs-Feature
                                          [0] CCBS-Feature
                                                                             OPTIONAL,
EraseCC-EntryArg ::= SEQUENCE {
     ss-Code
                                          [0] SS-Code,
     ccbs-Index
                                          [1] CCBS-Index
                                                                             OPTIONAL,
     . . . }
EraseCC-EntryRes ::= SEQUENCE {
                                          [0] SS-Code,
    ss-Code
                                          [1] SS-Status
     ss-Status
                                                                             OPTIONAL,
```

17.7.5 Supplementary service codes

```
MAP-SS-Code {
  itu-t identified-organization (4) etsi (0) mobileDomain (0)
  gsm-Network (1) modules (3) map-SS-Code (15) version9 (9) }
```

DEFINITIONS

: :=

BEGIN

```
SS-Code ::= OCTET STRING (SIZE (1))

-- This type is used to represent the code identifying a single
-- supplementary service, a group of supplementary services, or
-- all supplementary services. The services and abbreviations
-- used are defined in TS 3GPP TS 22.004 [5]. The internal structure is
-- defined as follows:
--
-- bits 87654321: group (bits 8765), and specific service
-- (bits 4321)
```

```
allss SS-Code ::= '00000000'B
-- reserved for possible future use
-- all SS
```

```
allLineIdentificationSS
                                         SS-Code ::= '00010000'B
     -- reserved for possible future use
     -- all line identification SS
clip
                                         SS-Code ::= '00010001'B
     -- calling line identification presentation
clir
                                         SS-Code ::= '00010010'B
     -- calling line identification restriction
                                         SS-Code ::= '00010011'B
colp
     -- connected line identification presentation
                                         SS-Code ::= '00010100'B
colr
     -- connected line identification restriction
mci
                                         SS-Code ::= '00010101'B
     -- reserved for possible future use
     -- malicious call identification
allNameIdentificationSS
                                        SS-Code ::= '00011000'B
     -- all name identification SS
                                       SS-Code ::= '00011001'B
     -- calling name presentation
     -- SS-Codes '00011010'B to '00011111'B are reserved for future
     -- NameIdentification Supplementary Service use.
```

```
allForwardingSS
                                         SS-Code ::= '00100000'B
    -- all forwarding SS
                                         SS-Code ::= '00100001'B
     -- call forwarding unconditional
allCondForwardingSS
                                         SS-Code ::= '00101000'B
     -- all conditional forwarding SS
                                         SS-Code ::= '00101001'B
    -- call forwarding on mobile subscriber busy
cfnry
                                         SS-Code ::= '00101010'B
     -- call forwarding on no reply
                                         SS-Code ::= '00101011'B
    -- call forwarding on mobile subscriber not reachable
                                         SS-Code ::= '00100100'B
cd
   -- call deflection
```

```
allCallCompletionSS
                                           SS-Code ::= '01000000'B
     -- reserved for possible future use
-- all Call completion SS
                                           SS-Code ::= '01000001'B
     -- call waiting
                                           SS-Code ::= '01000010'B
hold
     -- call hold
                                           SS-Code ::= '01000011'B
ccbs-A
     -- completion of call to busy subscribers, originating side
ccbs-B
                                           SS-Code ::= '01000100'B
    -- completion of call to busy subscribers, destination side
     -- this SS-Code is used only in InsertSubscriberData and DeleteSubscriberData
mc
                                           SS-Code ::= '01000101'B
     -- multicall
```

allMultiPartySS	SS-Code ::= '01010000'B
reserved for possible future use	
all multiparty SS	
multiPTY	SS-Code ::= '01010001'B
multiparty	

allCommunityOfInterest-SS	SS-Code ::= '01100000'B
reserved for possible future use	
all community of interest SS	
cug	SS-Code ::= '01100001'B
closed user group	

allC	hargingSS	SS-Code ::= '01110000'B
	reserved for possible future use	
	all charging SS	
aoci		SS-Code ::= '01110001'B
	advice of charge information	
aocc		SS-Code ::= '01110010'B
	advice of charge charging	

allAdditionalInfoTransferSS	SS-Code	::=	'10000000'B		
reserved for possible future use					
all additional information transfer SS					
uus1	SS-Code	::=	'10000001'B		
UUS1 user-to-user signalling					
uus2	SS-Code	::=	'10000010'B		
UUS2 user-to-user signalling					
uus3	SS-Code	::=	'10000011'B		
UUS3 user-to-user signalling					

```
SS-Code ::= '10010000'B
allBarringSS
    -- all barring SS
barringOfOutgoingCalls
                                         SS-Code ::= '10010001'B
      - barring of outgoing calls
                                         SS-Code ::= '10010010'B
     -- barring of all outgoing calls
                                         SS-Code ::= '10010011'B
    -- barring of outgoing international calls
boicExHC
                                         SS-Code ::= '10010100'B
    -- barring of outgoing international calls except those directed
    -- to the home PLMN Country
barringOfIncomingCalls
                                        SS-Code ::= '10011001'B
     -- barring of incoming calls
                                         SS-Code ::= '10011010'B
    -- barring of all incoming calls
bicRoam
                                         SS-Code ::= '10011011'B
    -- barring of incoming calls when roaming outside home PLMN
    -- Country
```

```
SS-Code ::= '11110000'B
allPLMN-specificSS
plmn-specificSS-1
                                          SS-Code ::= '11110001'B
plmn-specificSS-2
                                          SS-Code ::= '11110010'B
plmn-specificSS-3
                                          SS-Code ::= '11110011'B
plmn-specificSS-4
                                          SS-Code ::= '11110100'B
plmn-specificSS-5
                                          SS-Code ::= '11110101'B
plmn-specificSS-6
                                          SS-Code ::= '11110110'B
                                          SS-Code ::= '11110111'B
plmn-specificSS-7
                                          SS-Code ::= '11111000'B
plmn-specificSS-8
plmn-specificSS-9
                                          SS-Code ::= '11111001'B
plmn-specificSS-A
                                          SS-Code ::= '11111010'B
                                          SS-Code ::= '11111011'B
plmn-specificSS-B
plmn-specificSS-C
                                          SS-Code ::= '11111100'B
plmn-specificSS-D
                                          SS-Code ::= '111111101'B
plmn-specificSS-E
                                          SS-Code ::= '111111110'B
                                          SS-Code ::= '111111111'B
plmn-specificSS-F
```

```
allLCSPrivacyException
                                          SS-Code ::= '10110000'B
    -- all LCS Privacy Exception Classes
                                          SS-Code ::= '10110001'B
universal
     -- allow location by any LCS client
                                          SS-Code ::= '10110010'B
callSessionRelated
     -- allow location by any value added LCS client to which a call/session
     -- is established from the target MS
                                          SS-Code ::= '10110011'B
callSessionUnrelated
      - allow location by designated external value added LCS clients
                                          SS-Code ::= '10110100'B
plmnoperator
      - allow location by designated PLMN operator LCS clients
                                          SS-Code ::= '10110101'B
serviceType
    -- allow location by LCS clients of a designated LCS service type
```

```
allMOLR-SS
SS-Code ::= '11000000'B

-- all Mobile Originating Location Request Classes

basicSelfLocation
SS-Code ::= '11000001'B

-- allow an MS to request its own location
autonomousSelfLocation
SS-Code ::= '11000010'B

-- allow an MS to perform self location without interaction
-- with the PLMN for a predetermined period of time

transferToThirdParty
SS-Code ::= '11000011'B

-- allow an MS to request transfer of its location to another LCS client
```

17.7.6 Short message data types

```
MAP-SM-DataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-SM-DataTypes (16) version9 (9)}
DEFINITIONS
IMPLICIT TAGS
BEGIN
EXPORTS
  RoutingInfoForSM-Arg,
   RoutingInfoForSM-Res,
  MO-ForwardSM-Arg,
  MO-ForwardSM-Res.
  MT-ForwardSM-Arg,
  MT-ForwardSM-Res,
   ReportSM-DeliveryStatusArg,
   ReportSM-DeliveryStatusRes,
  AlertServiceCentreArg,
   InformServiceCentreArg,
   ReadyForSM-Arg,
   ReadyForSM-Res,
   SM-DeliveryOutcome,
  AlertReason,
```

```
Additional-Number
;
IMPORTS
   AddressString,
   ISDN-AddressString,
   SignalInfo.
   IMSI.
   LMSI
FROM MAP-CommonDataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-CommonDataTypes (18) version9 (9)}
   AbsentSubscriberDiagnosticSM
FROM MAP-ER-DataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-ER-DataTypes (17) version9 (9)}
   ExtensionContainer
FROM MAP-ExtensionDataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-ExtensionDataTypes (21) version9 (9)}
RoutingInfoForSM-Arg : := SEQUENCE {
    msisdn
                                          [0] ISDN-AddressString,
     sm-RP-PRI
                                          [1] BOOLEAN,
    serviceCentreAddress
                                          [2] AddressString,
    extensionContainer
                                          [6] ExtensionContainer
                                                                            OPTIONAL.
    gprsSupportIndicator
                                          [7] NULL
                                                                             OPTIONAL,
      -- gprsSupportIndicator is set only if the SMS-GMSC supports
     -- receiving of two numbers from the HLR
                                                                             OPTIONAL,
     sm-RP-MTI
                                          [8] SM-RP-MTI
     sm-RP-SMEA
                                          [9] SM-RP-SMEA
                                                                             OPTIONAL
SM-RP-MTI ::= INTEGER (0..10)
     -- 0 SMS Deliver
     -- 1 SMS Status Report
     -- other values are reserved for future use and shall be discarded if
     -- received
SM-RP-SMEA ::= OCTET STRING (SIZE (1..12))
     -- this parameter contains an address field which is encoded
     -- as defined in 3GPP TS 23.040. An address field contains 3 elements :
           address-length
              type-of-address
             address-value
RoutingInfoForSM-Res ::= SEQUENCE {
                                          IMSI.
     imsi
     locationInfoWithLMSI
                                          [0] LocationInfoWithLMSI,
     extensionContainer
                                          [4] ExtensionContainer
                                                                             OPTIONAL,
LocationInfoWithLMSI ::= SEQUENCE {
    networkNode-Number
                                          [1] ISDN-AddressString,
    lmsi
                                          LMSI
                                                                             OPTIONAL.
     {\tt extensionContainer}
                                          ExtensionContainer
                                                                             OPTIONAL,
     gprsNodeIndicator
                                          [5] NULL
                                                                             OPTIONAL.
     -- gprsNodeIndicator is set only if the SGSN number is sent as the
     -- Network Node Number
     additional-Number
                                          [6] Additional-Number
                                                                             OPTIONAL
      -- NetworkNode-number can be either msc-number or sgsn-number
Additional-Number ::= CHOICE {
    msc-Number
                                          [0] ISDN-AddressString,
     sgsn-Number
                                          [1] ISDN-AddressString}
     -- additional-number can be either msc-number or sgsn-number
     -- if received networkNode-number is msc-number then the
     -- additional number is sgsn-number
     -- if received networkNode-number is sgsn-number then the
     -- additional number is msc-number
```

```
MO-ForwardSM-Arg ::= SEQUENCE {
     sm-RP-DA
                                            SM-RP-DA.
     sm-RP-OA
                                            SM-RP-OA,
     sm-RP-UI
                                            SignalInfo,
     extensionContainer
                                            ExtensionContainer
                                                                                 OPTIONAL,
     imsi
                                            TMST
                                                                                 OPTIONAL }
MO-ForwardSM-Res ::= SEQUENCE {
     sm-RP-UI
                                            SignalInfo
                                                                                 OPTIONAL,
     extensionContainer
                                            ExtensionContainer
                                                                                  OPTIONAL,
MT-ForwardSM-Arg ::= SEQUENCE {
     sm-RP-DA
                                            SM-RP-DA,
                                            SM-RP-OA,
     sm-RP-OA
     sm-RP-UI
                                            SignalInfo,
     moreMessagesToSend
                                                                                 OPTIONAL,
                                            NULL
     extensionContainer
                                            ExtensionContainer
                                                                                 OPTIONAL,
MT-ForwardSM-Res ::= SEQUENCE {
     sm-RP-UI
                                            SignalInfo
                                                                                 OPTIONAL.
     extensionContainer
                                            ExtensionContainer
                                                                                 OPTIONAL,
SM-RP-DA ::= CHOICE {
                                             [0] IMSI,
     imsi
                                             [1] LMSI,
     lmsi
     serviceCentreAddressDA
                                             [4] AddressString,
     noSM-RP-DA
                                             [5] NULL}
SM-RP-OA ::= CHOICE {
     msisdn
                                             [2] ISDN-AddressString,
     serviceCentreAddressOA
                                             [4] AddressString,
     noSM-RP-OA
                                             [5] NULL}
ReportSM-DeliveryStatusArg ::= SEQUENCE {
                                            ISDN-AddressString,
     msisdn
     serviceCentreAddress
                                            AddressString,
     sm-DeliveryOutcome
                                            SM-DeliveryOutcome,
     absentSubscriberDiagnosticSM
                                            [0] AbsentSubscriberDiagnosticSM
                                                                                 OPTIONAL,
                                                                                 OPTIONAL,
     extensionContainer
                                            [1] ExtensionContainer
     gprsSupportIndicator
                                             [2] NULL
                                                                                 OPTIONAL,
     -- gprsSupportIndicator is set only if the SMS-GMSC supports
-- handling of two delivery outcomes
     deliveryOutcomeIndicator
                                            [3] NULL
                                                                                 OPTIONAL.
     -- DeliveryOutcomeIndicator is set when the SM-DeliveryOutcome
     -- is for GPRS
                                       [4] SM-DeliveryOutcome
     additionalSM-DeliveryOutcome
                                                                                 OPTIONAL,
     -- If received, additionalSM-DeliveryOutcome is for GPRS
     -- If DeliveryOutcomeIndicator is set, then AdditionalSM-DeliveryOutcome shall be absent additionalAbsentSubscriberDiagnosticSM [5] AbsentSubscriberDiagnosticSM OPTIONAL
     -- If received additionalAbsentSubscriberDiagnosticSM is for GPRS
     -- If DeliveryOutcomeIndicator is set, then AdditionalAbsentSubscriberDiagnosticSM
     -- shall be absent
SM-DeliveryOutcome ::= ENUMERATED {
     memoryCapacityExceeded (0),
     absentSubscriber (1),
     successfulTransfer (2) }
ReportSM-DeliveryStatusRes ::= SEQUENCE {
     storedMSISDN
                                             ISDN-AddressString
                                                                                 OPTIONAL,
                                                                                 OPTIONAL,
     extensionContainer
                                            ExtensionContainer
AlertServiceCentreArg ::= SEQUENCE {
     msisdn
                                             ISDN-AddressString,
     serviceCentreAddress
                                            AddressString,
```

```
InformServiceCentreArg ::= SEQUENCE {
                                         ISDN-AddressString
    storedMSTSDN
                                                                            OPTIONAL.
    mw-Status MW-Status
                                         OPTIONAL,
    extensionContainer
                                         ExtensionContainer
                                                                            OPTIONAL.
    absentSubscriberDiagnosticSM
                                         AbsentSubscriberDiagnosticSM
                                                                            OPTIONAL,
                                             [0] AbsentSubscriberDiagnosticSM OPTIONAL }
    additionalAbsentSubscriberDiagnosticSM
     -- additionalAbsentSubscriberDiagnosticSM may be present only if
     -- absentSubscriberDiagnosticSM is present.
     -- if included, additionalAbsentSubscriberDiagnosticSM is for GPRS and
     -- absentSubscriberDiagnosticSM is for non-GPRS
```

```
MW-Status ::= BIT STRING {
    sc-AddressNotIncluded (0),
    mnrf-Set (1),
    mcef-Set (2),
    mnrg-Set (3)} (SIZE (6..16))
    -- exception handling:
    -- bits 4 to 15 shall be ignored if received and not understood
```

```
AlertReason ::= ENUMERATED {
    ms-Present (0),
    memoryAvailable (1)}
```

ENI

17.7.7 Error data types

```
MAP-ER-DataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-ER-DataTypes (17) version9 (9)}
DEFINITIONS
IMPLICIT TAGS
: :=
BEGIN
EXPORTS
  RoamingNotAllowedParam,
   CallBarredParam,
   CUG-RejectParam,
   SS-IncompatibilityCause,
   PW-RegistrationFailureCause,
   SM-DeliveryFailureCause,
   SystemFailureParam,
   DataMissingParam,
   UnexpectedDataParam,
   FacilityNotSupParam,
   OR-NotAllowedParam,
   UnknownSubscriberParam,
   NumberChangedParam,
   UnidentifiedSubParam,
   IllegalSubscriberParam,
   IllegalEquipmentParam,
   BearerServNotProvParam,
   TeleservNotProvParam,
   TracingBufferFullParam,
  NoRoamingNbParam,
   AbsentSubscriberParam,
   BusySubscriberParam,
  NoSubscriberReplyParam,
   ForwardingViolationParam,
```

```
ForwardingFailedParam,
   ATI-NotAllowedParam,
   SubBusyForMT-SMS-Param,
   MessageWaitListFullParam,
   AbsentSubscriberSM-Param,
   AbsentSubscriberDiagnosticSM,
   ResourceLimitationParam,
   NoGroupCallNbParam,
   IncompatibleTerminalParam,
   ShortTermDenialParam,
   LongTermDenialParam,
   UnauthorizedRequestingNetwork-Param,
   UnauthorizedLCSClient-Param,
   PositionMethodFailure-Param,
   UnknownOrUnreachableLCSClient-Param,
   MM-EventNotSupported-Param,
   ATSI-NotAllowedParam,
  ATM-NotAllowedParam,
   IllegalSS-OperationParam,
   SS-NotAvailableParam,
   SS-SubscriptionViolationParam,
   InformationNotAvailableParam,
  TargetCellOutsideGCA-Param
IMPORTS
  SS-Status
FROM MAP-SS-DataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-SS-DataTypes (14) version9 (9)}
   SignalInfo,
   BasicServiceCode,
  NetworkResource,
  AdditionalNetworkResource
FROM MAP-CommonDataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-CommonDataTypes (18) version9 (9)}
  SS-Code
FROM MAP-SS-Code {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-SS-Code (15) version9 (9)}
  ExtensionContainer
FROM MAP-ExtensionDataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-ExtensionDataTypes (21) version9 (9)}
RoamingNotAllowedParam ::= SEQUENCE {
    roamingNotAllowedCause
                                          RoamingNotAllowedCause,
    extensionContainer
                                          ExtensionContainer
                                                                             OPTIONAL,
RoamingNotAllowedCause ::= ENUMERATED {
    plmnRoamingNotAllowed (0),
    operatorDeterminedBarring
CallBarredParam ::= CHOICE {
                                          CallBarringCause,
    callBarringCause
     -- call BarringCause must not be used in version 3 and higher
     extensibleCallBarredParam
                                          ExtensibleCallBarredParam
      - extensibleCallBarredParam must not be used in version <3
CallBarringCause ::= ENUMERATED {
    barringServiceActive
                           (0),
    operatorBarring
```

```
ExtensibleCallBarredParam ::= SEQUENCE {
     callBarringCause
                                            CallBarringCause
                                                                                OPTIONAL.
     extensionContainer
                                           ExtensionContainer
                                                                                OPTIONAL,
     unauthorisedMessageOriginator
                                            [1] NULL
                                                                                OPTIONAL }
CUG-RejectParam ::= SEQUENCE {
    cuq-RejectCause
                                            CUG-RejectCause
                                                                                OPTIONAL.
     extensionContainer
                                           ExtensionContainer
                                                                                OPTIONAL,
CUG-RejectCause ::= ENUMERATED {
     incomingCallsBarredWithinCUG (0),
     subscriberNotMemberOfCUG (1),
     requestedBasicServiceViolatesCUG-Constraints (5),
     calledPartySS-InteractionViolation (7) }
SS-IncompatibilityCause ::= SEQUENCE {
     ss-Code
                                            [1] SS-Code
                                                                                OPTIONAL,
     basicService
                                           BasicServiceCode
                                                                                OPTIONAL,
                                            [4] SS-Status
     ss-Status
                                                                                OPTIONAL,
PW-RegistrationFailureCause ::= ENUMERATED {
    undetermined (0), invalidFormat (1),
     newPasswordsMismatch (2) }
SM-EnumeratedDeliveryFailureCause ::= ENUMERATED {
    memoryCapacityExceeded (0),
    equipmentProtocolError (1),
equipmentNotSM-Equipped (2),
     unknownServiceCentre (3),
     sc-Congestion (4),
     invalidSME-Address (5),
     subscriberNotSC-Subscriber (6) }
SM-DeliveryFailureCause ::= SEQUENCE {
     sm-EnumeratedDeliveryFailureCause
                                           {\tt SM-EnumeratedDeliveryFailureCause,}
                                                                                OPTIONAL.
     diagnosticInfo
                                           SignalInfo
     extensionContainer
                                           ExtensionContainer
                                                                                OPTIONAL.
AbsentSubscriberSM-Param ::= SEQUENCE {
    absentSubscriberDiagnosticSM
                                           AbsentSubscriberDiagnosticSM
                                                                                OPTIONAL,
     -- AbsentSubscriberDiagnosticSM can be either for non-GPRS
     -- or for GPRS
     extensionContainer
                                           ExtensionContainer
                                                                                OPTIONAL,
     additionalAbsentSubscriberDiagnosticSM
                                                [0] AbsentSubscriberDiagnosticSM OPTIONAL }
     -- if received, additionalAbsentSubscriberDiagnosticSM
-- is for GPRS and absentSubscriberDiagnosticSM is
     -- for non-GPRS
AbsentSubscriberDiagnosticSM ::= INTEGER (0..255)
     -- AbsentSubscriberDiagnosticSM values are defined in 3GPP TS 23.040
SystemFailureParam ::= CHOICE {
    networkResource
                                           NetworkResource,
     -- networkResource must not be used in version 3
     extensibleSystemFailureParam ExtensibleSystemFailureParam
     -- extensibleSystemFailureParam must not be used in version <3
ExtensibleSystemFailureParam ::= SEQUENCE {
    networkResource
                                                                                OPTIONAL,
                                           NetworkResource
     extensionContainer
                                           ExtensionContainer
                                                                                OPTIONAL,
     additionalNetworkResource
                                           [0] AdditionalNetworkResource
                                                                                OPTIONAL }
DataMissingParam ::= SEQUENCE {
     extensionContainer
                                           ExtensionContainer
                                                                                OPTIONAL,
```

,						
<pre>UnexpectedDataParam ::= SEQUENCE { extensionContainer }</pre>	ExtensionContainer	OPTIONAL,				
<pre>FacilityNotSupParam ::= SEQUENCE { extensionContainer ,</pre>	ExtensionContainer	OPTIONAL,				
shapeOfLocationEstimateNotSupportedneededLcsCapabilityNotSupportedInSc		OPTIONAL, OPTIONAL }				
<pre>OR-NotAllowedParam ::= SEQUENCE { extensionContainer }</pre>	ExtensionContainer	OPTIONAL,				
<pre>UnknownSubscriberParam ::= SEQUENCE { extensionContainer ,</pre>	ExtensionContainer	OPTIONAL,				
unknownSubscriberDiagnostic	UnknownSubscriberDiagnostic	OPTIONAL}				
UnknownSubscriberDiagnostic ::= ENUMERATED { imsiUnknown (0), gprsSubscriptionUnknown (1), , npdbMismatch (2)} if unknown values are received in UnknownSubscriberDiagnostic they shall be discarded						
<pre>NumberChangedParam ::= SEQUENCE { extensionContainer }</pre>	ExtensionContainer	OPTIONAL,				
<pre>UnidentifiedSubParam ::= SEQUENCE { extensionContainer }</pre>	ExtensionContainer	OPTIONAL,				
<pre>IllegalSubscriberParam ::= SEQUENCE { extensionContainer }</pre>	ExtensionContainer	OPTIONAL,				
<pre>IllegalEquipmentParam ::= SEQUENCE { extensionContainer }</pre>	ExtensionContainer	OPTIONAL,				
<pre>BearerServNotProvParam ::= SEQUENCE { extensionContainer }</pre>	ExtensionContainer	OPTIONAL,				
<pre>TeleservNotProvParam ::= SEQUENCE { extensionContainer }</pre>	ExtensionContainer	OPTIONAL,				
<pre>TracingBufferFullParam ::= SEQUENCE { extensionContainer }</pre>	ExtensionContainer	OPTIONAL,				
NoRoamingNbParam ::= SEQUENCE { extensionContainer }	ExtensionContainer	OPTIONAL,				
AbsentSubscriberParam ::= SEQUENCE { extensionContainer	ExtensionContainer	OPTIONAL,				
absentSubscriberReason	[0] AbsentSubscriberReason	OPTIONAL}				

```
AbsentSubscriberReason ::= ENUMERATED {
     imsiDetach (0),
     restrictedArea (1),
    noPageResponse (2),
    purgedMS (3) }
-- exception handling: at reception of other values than the ones listed the
-- AbsentSubscriberReason shall be ignored.
-- The AbsentSubscriberReason: purgedMS is defined for the Super-Charger feature
-- (see TS 23.116). If this value is received in a Provide Roaming Number response
-- it shall be mapped to the AbsentSubscriberReason: imsiDetach in the Send Routeing
-- <u>Information response</u>
BusySubscriberParam ::= SEQUENCE {
     extensionContainer
                                           ExtensionContainer
                                                                               OPTIONAL,
     ccbs-Possible
                                           [0] NULL
                                                                               OPTIONAL,
     ccbs-Busy
                                                                               OPTIONAL }
                                            [1] NULL
NoSubscriberReplyParam ::= SEQUENCE {
                                           ExtensionContainer
                                                                               OPTIONAL,
     extensionContainer
ForwardingViolationParam ::= SEQUENCE {
     extensionContainer
                                                                               OPTIONAL,
                                           ExtensionContainer
ForwardingFailedParam ::= SEQUENCE {
    extensionContainer
                                           ExtensionContainer
                                                                               OPTIONAL,
ATI-NotAllowedParam ::= SEQUENCE {
     extensionContainer
                                           ExtensionContainer
                                                                               OPTIONAL,
ATSI-NotAllowedParam ::= SEQUENCE {
     extensionContainer
                                           ExtensionContainer
                                                                               OPTIONAL,
ATM-NotAllowedParam ::= SEQUENCE {
                                           ExtensionContainer
                                                                               OPTIONAL.
     extensionContainer
IllegalSS-OperationParam ::= SEQUENCE {
     {\tt extensionContainer}
                                           ExtensionContainer
                                                                               OPTIONAL,
SS-NotAvailableParam ::= SEQUENCE {
     extensionContainer
                                           ExtensionContainer
                                                                               OPTIONAL,
SS-SubscriptionViolationParam ::= SEQUENCE {
     {\tt extensionContainer}
                                           ExtensionContainer
                                                                               OPTIONAL,
InformationNotAvailableParam ::= SEQUENCE {
     {\tt extensionContainer}
                                           ExtensionContainer
                                                                               OPTIONAL,
SubBusyForMT-SMS-Param ::= SEQUENCE {
     extensionContainer
                                           ExtensionContainer
                                                                               OPTIONAL,
     gprsConnectionSuspended
                                           NULL
                                                                               OPTIONAL }
     -- If GprsConnectionSuspended is not understood it shall
     -- be discarded
MessageWaitListFullParam ::= SEQUENCE {
     extensionContainer
                                           ExtensionContainer
                                                                               OPTIONAL,
	exttt{ResourceLimitationParam}:= 	exttt{SEQUENCE} \ ig\{
     extensionContainer
                                                                               OPTIONAL,
                                           ExtensionContainer
```

```
NoGroupCallNbParam ::= SEQUENCE {
     extensionContainer
                                            ExtensionContainer
                                                                                 OPTIONAL.
IncompatibleTerminalParam ::= SEQUENCE {
     extensionContainer
                                                                                 OPTIONAL,
                                            ExtensionContainer
ShortTermDenialParam ::= SEQUENCE {
LongTermDenialParam ::= SEQUENCE {
UnauthorizedRequestingNetwork-Param ::= SEQUENCE {
     extensionContainer
                                            ExtensionContainer
                                                                                 OPTIONAL,
UnauthorizedLCSClient-Param ::= SEQUENCE {
     unauthorizedLCSClient-Diagnostic
                                            [0] UnauthorizedLCSClient-Diagnostic
     extensionContainer
                                            [1] ExtensionContainer
                                                                                     OPTIONAL,
UnauthorizedLCSClient-Diagnostic ::= ENUMERATED {
     noAdditionalInformation (0),
     clientNotInMSPrivacyExceptionList (1),
     callToClientNotSetup (2),
     privacyOverrideNotApplicable (3),
     disallowedByLocalRegulatoryRequirements (4),
     unauthorizedPrivacyClass (5),
     unauthorizedCallSessionUnrelatedExternalClient (6),
     unauthorizedCallSessionRelatedExternalClient (7) }
     exception handling:
     any unrecognized value shall be ignored
PositionMethodFailure-Param ::= SEQUENCE {
     positionMethodFailure-Diagnostic
                                             [0] PositionMethodFailure-Diagnostic OPTIONAL,
     extensionContainer
                                            [1] ExtensionContainer
PositionMethodFailure-Diagnostic ::= ENUMERATED {
     congestion (0),
     insufficientResources (1),
      \begin{array}{ll} insufficient \texttt{MeasurementData} & (2)\,,\\ inconsistent \texttt{MeasurementData} & (3)\,, \end{array} 
     locationProcedureNotCompleted (4),
     locationProcedureNotSupportedByTargetMS (5),
     qoSNotAttainable (6),
     positionMethodNotAvailableInNetwork (7),
     positionMethodNotAvailableInLocationArea (8),
     ...}
     exception handling:
     any unrecognized value shall be ignored
UnknownOrUnreachableLCSClient-Param ::= SEQUENCE {
     extensionContainer
                                            ExtensionContainer
                                                                                 OPTIONAL,
MM-EventNotSupported-Param ::= SEQUENCE {
     extensionContainer
                                            ExtensionContainer
                                                                                 OPTIONAL.
TargetCellOutsideGCA-Param ::= SEQUENCE {
     extensionContainer
                                            ExtensionContainer
                                                                                 OPTIONAL,
```

17.7.8 Common data types

```
MAP-CommonDataTypes {
  itu-t identified-organization (4) etsi (0) mobileDomain (0)
  gsm-Network (1) modules (3) map-CommonDataTypes (18) version9 (9)}
```

```
DEFINITIONS
IMPLICIT TAGS
: :=
BEGIN
EXPORTS
   -- general data types and values
  AddressString,
  ISDN-AddressString,
  maxISDN-AddressLength,
  FTN-AddressString,
  ISDN-SubaddressString,
  ExternalSignalInfo,
  Ext-ExternalSignalInfo,
  AccessNetworkSignalInfo,
  SignalInfo,
  maxSignalInfoLength,
  AlertingPattern,
  TBCD-STRING,
   -- data types for numbering and identification
  IMSI,
  TMSI
   Identity,
   SubscriberId,
  IMEI,
  HLR-List,
  LMSI,
   GlobalCellId,
  NetworkResource,
  AdditionalNetworkResource,
  NAEA-PreferredCI,
  NAEA-CIC,
  ASCI-CallReference,
  SubscriberIdentity,
   -- data types for CAMEL
  CellGlobalIdOrServiceAreaIdOrLAI,
   CellGlobalIdOrServiceAreaIdFixedLength,
  LAIFixedLength,
   -- data types for subscriber management
  BasicServiceCode,
  Ext-BasicServiceCode,
  EMLPP-Info,
  EMLPP-Priority,
  MC-SS-Info,
  MaxMC-Bearers,
  MC-Bearers,
  Ext-SS-Status,
   -- data types for geographic location
  AgeOfLocationInformation,
  LCSClientExternalID,
  LCSClientInternalID,
  LCSServiceTypeID
IMPORTS
  TeleserviceCode,
  Ext-TeleserviceCode
FROM MAP-TS-Code {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
  gsm-Network (1) modules (3) map-TS-Code (19) version9 (9)}
  BearerServiceCode,
  Ext-BearerServiceCode
FROM MAP-BS-Code {
  itu-t identified-organization (4) etsi (0) mobileDomain (0)
  gsm-Network (1) modules (3) map-BS-Code (20) version9 (9)}
  SS-Code
FROM MAP-SS-Code {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
```

gsm-Network (1) modules (3) map-SS-Code (15) version9 (9)}

```
ExtensionContainer
FROM MAP-ExtensionDataTypes {
  itu-t identified-organization (4) etsi (0) mobileDomain (0)
  gsm-Network (1) modules (3) map-ExtensionDataTypes (21) version9 (9)}
-- general data types
TBCD-STRING ::= OCTET STRING
     -- This type (Telephony Binary Coded Decimal String) is used to
     -- represent several digits from 0 through 9, *, #, a, b, c, two
     -- digits per octet, each digit encoded 0000 to 1001 (0 to 9),
-- 1010 (*), 1011 (#), 1100 (a), 1101 (b) or 1110 (c); 1111 used
     -- as filler when there is an odd number of digits.
     -- bits 8765 of octet n encoding digit 2n
     -- bits 4321 of octet n encoding digit 2(n-1) +1
AddressString ::= OCTET STRING (SIZE (1..maxAddressLength))
     -- This type is used to represent a number for addressing
     -- purposes. It is composed of
     -- a) one octet for nature of address, and numbering plan
              indicator.
     -- b) digits of an address encoded as TBCD-String.
            The first octet includes a one bit extension indicator, a
              3 bits nature of address indicator and a 4 bits numbering
              plan indicator, encoded as follows:
     -- bit 8: 1 (no extension)
     -- bits 765: nature of address indicator
         000 unknown
        001 international number
         010 national significant number
         011 network specific number
        100 subscriber number
        101 reserved
110 abbreviated number
        111 reserved for extension
     -- bits 4321: numbering plan indicator
         0000 unknown
        0001 ISDN/Telephony Numbering Plan (Rec ITU-T E.164)
         0010 spare
0011 data numbering plan (ITU-T Rec X.121)
        0100 telex numbering plan (ITU-T Rec F.69)
         0101 spare
0110 land mobile numbering plan (ITU-T Rec E.212)
        0111 spare
1000 national numbering plan
        1001 private numbering plan
        1111 reserved for extension
     -- all other values are reserved.
              The following octets representing digits of an address
              encoded as a TBCD-STRING.
```

maxAddressLength INTEGER ::= 20

```
maxISDN-AddressLength INTEGER ::= 9
```

```
FTN-AddressString ::=

AddressString (SIZE (1..maxFTN-AddressLength))

-- This type is used to represent forwarded-to numbers.

-- If NAI = international the first digits represent the country code (CC)

-- and the network destination code (NDC) as for E.164.
```

```
maxFTN-AddressLength INTEGER ::= 15
```

```
ISDN-SubaddressString ::=
              OCTET STRING (SIZE (1..maxISDN-SubaddressLength))
     -- This type is used to represent ISDN subaddresses.
     -- It is composed of
         a) one octet for type of subaddress and odd/even indicator.b) 20 octets for subaddress information.
     -- a) The first octet includes a one bit extension indicator, a
              3 bits type of subaddress and a one bit odd/even indicator,
               encoded as follows:
     -- bit 8: 1 (no extension)
     -- bits 765: type of subaddress
              000 NSAP (X.213/ISO 8348 AD2)
               010 User Specified
              All other values are reserved
     -- bit 4: odd/even indicator
              0 even number of address signals
              1 odd number of address signals
              The odd/even indicator is used when the type of subaddress
              is "user specified" and the coding is BCD.
     -- bits 321: 000 (unused)
     -- b) Subaddress information.
          The NSAP X.213/ISO8348AD2 address shall be formatted as specified
         by octet 4 which contains the Authority and Format Identifier
         (AFI). The encoding is made according to the "preferred binary
         encoding" as defined in X.213/ISO834AD2. For the definition
         of this type of subaddress, see ITU-T Rec I.334.
        For User-specific subaddress, this field is encoded according
         to the user specification, subject to a maximum length of 20 octets. When interworking with X.25 networks BCD coding should
          be applied.
```

maxISDN-SubaddressLength INTEGER ::= 21

SignalInfo ::= OCTET STRING (SIZE (1..maxSignalInfoLength))

```
maxSignalInfoLength INTEGER ::= 200

-- This NamedValue represents the theoretical maximum number of octets which is
-- available to carry a single instance of the SignalInfo data type,
-- without requiring segmentation to cope with the network layer service.
-- However, the actual maximum size available for an instance of the data
-- type may be lower, especially when other information elements
-- have to be included in the same component.
```

```
ProtocolId ::= ENUMERATED {
    gsm-0408 (1),
    gsm-0806 (2),
    gsm-BSSMAP (3),
    -- Value 3 is reserved and must not be used
    ets-300102-1 (4)}
```

```
Ext-ProtocolId ::= ENUMERATED {
    ets-300356 (1),
    ...
    }
-- exception handling:
-- For Ext-ExternalSignalInfo sequences containing this parameter with any
-- other value than the ones listed the receiver shall ignore the whole
-- Ext-ExternalSignalInfo sequence.
```

LongSignalInfo ::= OCTET STRING (SIZE (1..maxLongSignalInfoLength))

```
maxLongSignalInfoLength INTEGER ::= 2560

-- This Named Value represents the maximum number of octets which is available
-- to carry a single instance of the LongSignalInfo data type using
-- White Book SCCP with the maximum number of segments.
-- It takes account of the octets used by the lower layers of the protocol, and
-- other information elements which may be included in the same component.
```

```
AccessNetworkProtocolId ::= ENUMERATED {
   ts3G-48006 (1),
   ts3G-25413 (2),
   ...}
   -- exception handling:
   -- For AccessNetworkSignalInfo sequences containing this parameter with any
   -- other value than the ones listed the receiver shall ignore the whole
   -- AccessNetworkSignalInfo sequence.
```

```
AlertingPattern ::= OCTET STRING (SIZE (1) )
     -- This type is used to represent Alerting Pattern
         bits 8765 : 0000 (unused)
         bits 43 : type of Pattern
             00 level
     _ _
              01 category
              10 category
              all other values are reserved.
     -- bits 21 : type of alerting
alertingLevel-0
                 AlertingPattern ::= '00000000'B
alertingLevel-1 AlertingPattern ::= '00000001'B
                 AlertingPattern ::= '00000010'B
alertingLevel-2
     -- all other values of Alerting level are reserved
     -- Alerting Levels are defined in GSM 02.07
alertingCategory-1 AlertingPattern ::= '00000100'B
alertingCategory-2 AlertingPattern ::= '00000101'B
alertingCategory-3 AlertingPattern ::= '00000110'B
alertingCategory-4 AlertingPattern ::= '00000111'B
                     AlertingPattern ::= '00001000'B
alertingCategory-5
     -- all other values of Alerting Category are reserved
     -- Alerting categories are defined in GSM 02.07
```

-- data types for numbering and identification

```
IMSI ::= TBCD-STRING (SIZE (3..8))
    -- digits of MCC, MNC, MSIN are concatenated in this order.
```

```
ASCI-CallReference ::= TBCD-STRING (SIZE (1..8))
     -- digits of VGCS/VBC-area, Group-ID are concatenated in this order.
TMSI ::= OCTET STRING (SIZE (1..4))
SubscriberId ::= CHOICE {
     imsi
                                             [0] TMST.
     tmsi
                                             [1] TMSI}
IMEI ::= TBCD-STRING (SIZE (8))
     -- Refers to International Mobile Station Equipment Identity
          and Software Version Number (SVN) defined in TS 3GPP TS 23.003 [17].
         If the SVN is not present the last octet shall contain the
     -- digit 0 and a filler.
          If present the SVN shall be included in the last octet.
HLR-Id ::= IMSI
     -- leading digits of IMSI, i.e. (MCC, MNC, leading digits of
      -- MSIN) forming HLR Id defined in TS 3GPP TS 23.003 [17].
HLR-List ::= SEQUENCE SIZE (1..maxNumOfHLR-Id) OF
maxNumOfHLR-Id INTEGER ::= 50
LMSI ::= OCTET STRING (SIZE (4))
GlobalCellId ::= OCTET STRING (SIZE (5..7))
     -- Refers to Cell Global Identification defined in TS 3GPP TS 23.003 [17].
     -- The internal structure is defined as follows:
                                    Mobile Country Code 1<sup>st</sup> digit
     -- octet 1 bits 4321
                                            Mobile Country Code 2<sup>nd</sup> digit
                bits 8765
                                           Mobile Country Code 3<sup>rd</sup> digit
Mobile Network Code 3<sup>rd</sup> digit
     -- octet 2 bits 4321
                bits 8765
                                           or filler (1111) for 2 digit MNCs
Mobile Network Code 1<sup>st</sup> digit
Mobile Network Code 2<sup>nd</sup> digit
     -- octet 3 bits 4321
                bits 8765
     -- octets 4 and 5
                                            Location Area Code according to TS 3GPP TS 24.008
 [35]
     -- octets 6 and 7
                                            Cell Identity (CI) according to TS 3GPP TS 24.008
NetworkResource ::= ENUMERATED {
     plmn (0),
     hlr (1),
     vlr (2),
pvlr (3),
     controllingMSC (4),
     vmsc (5),
eir (6),
     rss (7)}
AdditionalNetworkResource ::= ENUMERATED {
     sgsn (0),
     ggsn (1),
     gmlc (2),
     gsmSCF (3),
     nplr (4),
     auc (5),
     -- if unknown value is received in AdditionalNetworkResource
     -- it shall be ignored.
NAEA-PreferredCI ::= SEQUENCE {
     naea-PreferredCIC
                                            [0] NAEA-CIC,
     extensionContainer
                                             [1] ExtensionContainer
                                                                                 OPTIONAL,
     <u>..</u>.}
NAEA-CIC ::= OCTET STRING (SIZE (3))
     -- The internal structure is defined by the Carrier Identification
     -- parameter in ANSI T1.113.3. Carrier codes between '000' and '999' may
     -- be encoded as 3 digits using '000' to '999' or as 4 digits using
     -- '0000' to '0999'. Carrier codes between '1000' and '9999' are encoded
     -- using 4 digits.
```

routeFinding

whereAmI

```
SubscriberIdentity ::= CHOICE {
     imsi
                                           [0] IMSI,
                                           [1] ISDN-AddressString
     msisdn
LCSClientExternalID ::= SEQUENCE {
     externalAddress
                                           [0] ISDN-AddressString
                                                                              OPTIONAL,
     extensionContainer
                                           [1] ExtensionContainer
                                                                              OPTIONAL,
LCSClientInternalID ::= ENUMERATED {
    broadcastService
                                           (0),
     o-andM-HPLMN
                                           (1),
     o-andM-VPLMN
                                           (2),
     anonymousLocation
                                           (3),
     targetMSsubscribedService
                                           (4),
  for a CAMEL phase 3 PLMN operator client, the value targetMSsubscribedService shall be used
LCSServiceTypeID ::= INTEGER (0..127)
     -- the integer values 0-63 are reserved for Standard LCS service types
     -- the integer values 64-127 are reserved for Non Standard LCS service types
-- Standard LCS Service Types
emergencyServices
                                               LCSServiceTypeID ::= 0
emergencyAlertServices
                                               LCSServiceTypeID ::= 1
personTracking
                                               LCSServiceTypeID ::= 2
fleetManagement
                                               LCSServiceTypeID ::= 3
assetManagement
                                               LCSServiceTypeID ::= 4
                                               LCSServiceTypeID ::= 5
trafficCongestionReporting
roadsideAssistance
                                               LCSServiceTypeID ::= 6
{\tt routing To Nearest Commercial Enterprise}
                                               LCSServiceTypeID ::= 7
navigation
                                               LCSServiceTypeID ::= 8
     --this service type is reserved for use in previous releases
citySightseeing
                                               LCSServiceTypeID ::= 9
localizedAdvertising
                                               LCSServiceTypeID ::= 10
mobileYellowPages
                                               LCSServiceTypeID ::= 11
trafficAndPublicTransportationInfo
                                               LCSServiceTypeID ::= 12
                                               LCSServiceTypeID ::= 13
weather
{\tt assetAndServiceFinding}
                                               LCSServiceTypeID ::= 14
gaming
                                               LCSServiceTypeID ::= 15
findYourFriend
                                               LCSServiceTypeID ::= 16
dating
                                               LCSServiceTypeID ::= 17
                                               LCSServiceTypeID ::= 18
chatting
```

The values of LCSServiceTypeID are defined according to 3GPP TS 22.071.

LCSServiceTypeID ::= 19

LCSServiceTypeID ::= 20

```
-- Non Standard LCS Service Types
serv64
                                                LCSServiceTypeID ::= 64
serv65
                                                LCSServiceTypeID ::= 65
serv66
                                                LCSServiceTypeID ::= 66
serv67
                                                LCSServiceTypeID ::= 67
serv68
                                                LCSServiceTypeID ::= 68
                                                LCSServiceTypeID ::= 69
serv69
serv70
                                                LCSServiceTypeID ::= 70
serv71
                                                LCSServiceTypeID ::= 71
serv72
                                                LCSServiceTypeID ::= 72
serv73
                                                LCSServiceTypeID ::= 73
                                                LCSServiceTypeID ::= 74
serv74
serv75
                                                LCSServiceTypeID ::= 75
serv76
                                                LCSServiceTypeID ::= 76
serv77
                                                LCSServiceTypeID ::= 77
                                                LCSServiceTypeID ::= 78
serv78
serv79
                                                LCSServiceTypeID ::= 79
serv80
                                                LCSServiceTypeID ::= 80
                                                LCSServiceTypeID ::= 81
serv81
serv82
                                                LCSServiceTypeID ::= 82
                                                LCSServiceTypeID ::= 83
serv83
serv84
                                                LCSServiceTypeID ::= 84
serv85
                                                LCSServiceTypeID ::= 85
                                                LCSServiceTypeID ::= 86
serv86
serv87
                                                LCSServiceTypeID ::= 87
                                                LCSServiceTypeID ::= 88
serv88
serv89
                                                LCSServiceTypeID ::= 89
serv90
                                                LCSServiceTypeID ::= 90
                                                LCSServiceTypeID ::= 91
serv91
                                                LCSServiceTypeID ::= 92
serv92
serv93
                                                LCSServiceTypeID ::= 93
serv94
                                                LCSServiceTypeID ::= 94
serv95
                                                LCSServiceTypeID ::= 95
                                                LCSServiceTypeID ::= 96
serv96
                                                LCSServiceTypeID ::= 97
serv97
serv98
                                                LCSServiceTypeID ::= 98
serv99
                                                LCSServiceTypeID ::= 99
serv100
                                                LCSServiceTypeID ::= 100
                                                LCSServiceTypeID ::= 101
serv101
                                                LCSServiceTypeID ::= 102
serv102
                                                LCSServiceTypeID ::= 103
serv103
serv104
                                                LCSServiceTypeID ::= 104
serv105
                                                LCSServiceTypeID ::= 105
                                                LCSServiceTypeID ::= 106
serv106
                                                LCSServiceTypeID ::= 107
serv107
                                                LCSServiceTypeID ::= 108
serv108
serv109
                                                LCSServiceTypeID ::= 109
serv110
                                                LCSServiceTypeID ::= 110
                                                LCSServiceTypeID ::= 111
serv111
serv112
                                                LCSServiceTypeID ::= 112
                                                LCSServiceTypeID ::= 113
serv113
serv114
                                                LCSServiceTypeID ::= 114
                                                LCSServiceTypeID ::= 115
serv115
                                                LCSServiceTypeID ::= 116
serv116
                                                LCSServiceTypeID ::= 117
serv117
                                                LCSServiceTypeID ::= 118
serv118
serv119
                                                LCSServiceTypeID ::= 119
                                                LCSServiceTypeID ::= 120
serv120
                                                LCSServiceTypeID ::= 121
serv121
                                                LCSServiceTypeID ::= 122
serv122
serv123
                                                LCSServiceTypeID ::= 123
serv124
                                                LCSServiceTypeID ::= 124
serv125
                                                LCSServiceTypeID ::= 125
serv126
                                                LCSServiceTypeID ::= 126
                                                LCSServiceTypeID ::= 127
serv127
```

-- data types for CAMEL

```
CellGlobalIdOrServiceAreaIdOrLAI ::= CHOICE {
    cellGlobalIdOrServiceAreaIdFixedLength [0] CellGlobalIdOrServiceAreaIdFixedLength,
    laiFixedLength [1] LAIFixedLength}
```

```
CellGlobalIdOrServiceAreaIdFixedLength ::= OCTET STRING (SIZE (7))
       -- Refers to Cell Global Identification or Service Are Identification
       -- defined in 3GPP TS 23.003.
       -- The internal structure is defined as follows:
                                                       Mobile Country Code 1st digit
       -- octet 1 bits 4321
                                                        Mobile Country Code 2nd digit
                    bits 8765
                                                      Mobile Country Code 3<sup>rd</sup> digit
Mobile Network Code 3<sup>rd</sup> digit
       -- octet 2 bits 4321
      - -
                    bits 8765
                                                      or filler (1111) for 2 digit MNCs
Mobile Network Code 1<sup>st</sup> digit
Mobile Network Code 2<sup>nd</sup> digit
       -- octet 3 bits 4321
                   bits 8765
       -- octets 4 and 5
                                                        Location Area Code according to 3GPP TS 24.008
                                                        Cell Identity (CI) value or
       -- octets 6 and 7
                                                        Service Area Code (SAC) value
                                                        according to 3GPP TS 23.003
LAIFixedLength ::= OCTET STRING (SIZE (5))
      -- Refers to Location Area Identification defined in TS 3GPP TS 23.003 [17].
       -- The internal structure is defined as follows:
                                                      Mobile Country Code 1<sup>st</sup> digit
Mobile Country Code 2<sup>nd</sup> digit
Mobile Country Code 3<sup>rd</sup> digit
Mobile Network Code 3<sup>rd</sup> digit
       -- octet 1 bits 4321
                    bits 8765
       -- octet 2 bits 4321
      --
                    bits 8765
                                                       or filler (1111) for 2 digit MNCs
Mobile Network Code 1<sup>st</sup> digit
Mobile Network Code 2<sup>nd</sup> digit
       -- octet 3 bits 4321
                    bits 8765
```

-- data types for subscriber management

-- octets 4 and 5

[35]

Location Area Code according to TS 3GPP TS 24.008

```
Ext-BasicServiceCode ::= CHOICE {
    ext-BearerService [2] Ext-BearerServiceCode,
    ext-Teleservice [3] Ext-TeleserviceCode}
```

```
EMLPP-Priority ::= INTEGER (0..15)
    -- The mapping from the values A,B,0,1,2,3,4 to the integer-value is
    -- specified as follows where A is the highest and 4 is the lowest
    -- priority level
    -- the integer values 7-15 are spare and shall be mapped to value 4
```

```
priorityLevelA
priorityLevelB
priorityLevel0
priorityLevel1
priorityLevel1
priorityLevel2
priorityLevel3
priorityLevel4
EMLPP-Priority ::= 6
EMLPP-Priority ::= 5
EMLPP-Priority ::= 0
EMLPP-Priority ::= 1
EMLPP-Priority ::= 2
EMLPP-Priority ::= 3
EMLPP-Priority ::= 3
EMLPP-Priority ::= 4
```

```
MaxMC-Bearers ::= INTEGER (2..maxNumOfMC-Bearers)
```

```
MC-Bearers ::= INTEGER (1..maxNumOfMC-Bearers)
```

```
maxNumOfMC-Bearers INTEGER ::= 7
```

```
Ext-SS-Status ::= OCTET STRING (SIZE (1..5))

-- OCTET 1:
-- bits 8765: 0000 (unused)
-- bits 4321: Used to convey the "P bit", "R bit", "A bit" and "Q bit",
-- representing supplementary service state information
-- as defined in TS 3GPP TS 23.011 [22]

-- bit 4: "Q bit"

-- bit 3: "P bit"

-- bit 2: "R bit"

-- bit 1: "A bit"

-- OCTETS 2-5: reserved for future use. They shall be discarded if
-- received and not understood.
```

-- data types for geographic location

```
AgeOfLocationInformation ::= INTEGER (0..32767)

-- the value represents the elapsed time in minutes since the last
-- network contact of the mobile station (i.e. the actuality of the
-- location information).

-- value '0' indicates that the MS is currently in contact with the
-- network
-- value '32767' indicates that the location information is at least
-- 32767 minutes old
```

END

17.7.9 Teleservice Codes

```
MAP-TS-Code {
  itu-t identified-organization (4) etsi (0) mobileDomain (0)
  gsm-Network (1) modules (3) map-TS-Code (19) version9 (9) }

DEFINITIONS
::=
BEGIN
```

```
TeleserviceCode ::= OCTET STRING (SIZE (1))

-- This type is used to represent the code identifying a single
-- teleservice, a group of teleservices, or all teleservices. The
-- services are defined in TS GSM 22.003 [4].

-- The internal structure is defined as follows:

-- bits 87654321: group (bits 8765) and specific service
-- (bits 4321)
```

```
Ext-TeleserviceCode ::= OCTET STRING (SIZE (1..5))

-- This type is used to represent the code identifying a single
-- teleservice, a group of teleservices, or all teleservices. The
-- services are defined in TS GSM 22.003 [4].

-- The internal structure is defined as follows:

-- OCTET 1:
-- bits 87654321: group (bits 8765) and specific service
-- (bits 4321)

-- OCTETS 2-5: reserved for future use. If received the
-- Ext-TeleserviceCode shall be
-- treated according to the exception handling defined for the
-- operation that uses this type.

-- Ext-TeleserviceCode includes all values defined for TeleserviceCode.
```

```
allTeleservices TeleserviceCode ::= '000000000'B
```

```
allSpeechTransmissionServices
                                          TeleserviceCode ::= '00010000'B
                                          TeleserviceCode ::= '00010001'B
telephonv
                                          TeleserviceCode ::= '00010010'B
emergencyCalls
                                          TeleserviceCode ::= '00100000'B
allShortMessageServices
shortMessageMT-PP
                                          TeleserviceCode ::= '00100001'B
                                          TeleserviceCode ::= '00100010'B
shortMessageMO-PP
allFacsimileTransmissionServices
                                          TeleserviceCode ::= '01100000'B
                                          TeleserviceCode ::= '01100001'B
facsimileGroup3AndAlterSpeech
                                          TeleserviceCode ::= '01100010'B
automaticFacsimileGroup3
                                          TeleserviceCode ::= '01100011'B
facsimileGroup4
```

allVoiceGroupCallServices	TeleserviceCode ::= '10010000'B	
voiceGroupCall	TeleserviceCode ::= '10010001'B	
voiceBroadcastCall	TeleserviceCode ::= '10010010'B	

allPLMN-specificTS	TeleserviceCode ::= '11010000'B
plmn-specificTS-1	TeleserviceCode ::= '11010001'B
plmn-specificTS-2	TeleserviceCode ::= '11010010'B
plmn-specificTS-3	TeleserviceCode ::= '11010011'B
plmn-specificTS-4	<pre>TeleserviceCode ::= '11010100'B</pre>
plmn-specificTS-5	TeleserviceCode ::= '11010101'B
plmn-specificTS-6	<pre>TeleserviceCode ::= '11010110'B</pre>
plmn-specificTS-7	<pre>TeleserviceCode ::= '11010111'B</pre>
plmn-specificTS-8	<pre>TeleserviceCode ::= '11011000'B</pre>
plmn-specificTS-9	TeleserviceCode ::= '11011001'B
plmn-specificTS-A	TeleserviceCode ::= '11011010'B
plmn-specificTS-B	TeleserviceCode ::= '11011011'B
plmn-specificTS-C	TeleserviceCode ::= '11011100'B
plmn-specificTS-D	TeleserviceCode ::= '11011101'B
plmn-specificTS-E	TeleserviceCode ::= '11011110'B
plmn-specificTS-F	TeleserviceCode ::= '11011111'B

END

17.7.10 Bearer Service Codes

```
MAP-BS-Code {
  itu-t identified-organization (4) etsi (0) mobileDomain (0)
  gsm-Network (1) modules (3) map-BS-Code (20) version9 (9) }

DEFINITIONS
::=
BEGIN
```

```
BearerServiceCode ::= OCTET STRING (SIZE (1))

-- This type is used to represent the code identifying a single
-- bearer service, a group of bearer services, or all bearer
-- services. The services are defined in TS 3GPP TS 22.002 [3].
-- The internal structure is defined as follows:
--
-- plmm-specific bearer services:
-- bits 87654321: defined by the HPLMN operator

-- rest of bearer services:
-- bit 8: 0 (unused)
-- bits 7654321: group (bits 7654), and rate, if applicable
-- (bits 321)
```

```
Ext-BearerServiceCode ::= OCTET STRING (SIZE (1..5))
     -- This type is used to represent the code identifying a single
     -- bearer service, a group of bearer services, or all bearer
     -- services. The services are defined in TS 3GPP TS 22.002 [3].
     -- The internal structure is defined as follows:
     -- OCTET 1:
     -- plmn-specific bearer services:
     -- bits 87654321: defined by the HPLMN operator
     -- rest of bearer services:
     -- bit 8: 0 (unused)
     -- bits 7654321: group (bits 7654), and rate, if applicable
     -- (bits 321)
    -- OCTETS 2-5: reserved for future use. If received the
    -- Ext-TeleserviceCode shall be
    -- treated according to the exception handling defined for the
     -- operation that uses this type.
    -- Ext-BearerServiceCode includes all values defined for BearerServiceCode.
```

allBearerServices	BearerServiceCode ::= '00000000'B
allDataCDA-Services	<pre>BearerServiceCode ::= '00010000'B</pre>
dataCDA-300bps	<pre>BearerServiceCode ::= '00010001'B</pre>
dataCDA-1200bps	BearerServiceCode ::= '00010010'B
dataCDA-1200-75bps	BearerServiceCode ::= '00010011'B
dataCDA-2400bps	BearerServiceCode ::= '00010100'B
dataCDA-4800bps	BearerServiceCode ::= '00010101'B
dataCDA-9600bps	BearerServiceCode ::= '00010110'B
general-dataCDA	BearerServiceCode ::= '00010111'B
allDataCDS-Services	BearerServiceCode ::= '00011000'B
dataCDS-1200bps	<pre>BearerServiceCode ::= '00011010'B</pre>
dataCDS-2400bps	<pre>BearerServiceCode ::= '00011100'B</pre>
dataCDS-4800bps	BearerServiceCode ::= '00011101'B
dataCDS-9600bps	BearerServiceCode ::= '00011110'B
general-dataCDS	<pre>BearerServiceCode ::= '00011111'B</pre>
allPadAccessCA-Services	BearerServiceCode ::= '00100000'B
padAccessCA-300bps	BearerServiceCode ::= '00100001'B
padAccessCA-1200bps	BearerServiceCode ::= '00100010'B
padAccessCA-1200-75bps	BearerServiceCode ::= '00100011'B
padAccessCA-2400bps	BearerServiceCode ::= '00100100'B
padAccessCA-4800bps	BearerServiceCode ::= '00100101'B
padAccessCA-9600bps	BearerServiceCode ::= '00100110'B
general-padAccessCA	BearerServiceCode ::= '00100111'B
allDataPDS-Services	BearerServiceCode ::= '00101000'B
dataPDS-2400bps	BearerServiceCode ::= '00101100'B
dataPDS-4800bps	BearerServiceCode ::= '00101101'B
dataPDS-9600bps	BearerServiceCode ::= '00101110'B
general-dataPDS	<pre>BearerServiceCode ::= '00101111'B</pre>
allAlternateSpeech-DataCDA	BearerServiceCode ::= '00110000'B
allAlternateSpeech-DataCDS	BearerServiceCode ::= '00111000'B
alling climate by each Datacob	Dealerservicecode volition b
allSpeechFollowedByDataCDA	BearerServiceCode ::= '01000000'B
allpheeculotiomedphacachy	pearerpervicecode ::= 01000000 p
all Grand by Tall and JDarbar GDG	D
allSpeechFollowedByDataCDS	BearerServiceCode ::= '01001000'B

```
-- The following non-hierarchical Compound Bearer Service
-- Groups are defined in TS 3GPP TS 22.030:
                                            BearerServiceCode ::= '01010000'B
allDataCircuitAsynchronous
     -- covers "allDataCDA-Services", "allAlternateSpeech-DataCDA" and
     -- "allSpeechFollowedByDataCDA"
                                            BearerServiceCode ::= '01100000'B
allAsvnchronousServices
     -- covers "allDataCDA-Services", "allAlternateSpeech-DataCDA",
-- "allSpeechFollowedByDataCDA" and "allPadAccessCDA-Services"
allDataCircuitSynchronous
                                            BearerServiceCode ::= '01011000'B
    -- covers "allDataCDS-Services", "allAlternateSpeech-DataCDS" and
     -- "allSpeechFollowedByDataCDS"
allSynchronousServices
                                            BearerServiceCode ::= '01101000'B
     -- covers "allDataCDS-Services", "allAlternateSpeech-DataCDS",
     -- "allSpeechFollowedByDataCDS" and "allDataPDS-Services"
-- Compound Bearer Service Group Codes are only used in call
-- independent supplementary service operations, i.e. they
-- are not used in InsertSubscriberData or in
-- DeleteSubscriberData messages.
```

```
allPLMN-specificBS
                                          BearerServiceCode ::= '11010000'B
plmn-specificBS-1
                                          BearerServiceCode ::= '11010001'B
                                          BearerServiceCode ::= '11010010'B
plmn-specificBS-2
                                          BearerServiceCode ::= '11010011'B
plmn-specificBS-3
                                          BearerServiceCode ::= '11010100'B
plmn-specificBS-4
plmn-specificBS-5
                                          BearerServiceCode ::= '11010101'B
                                          BearerServiceCode ::= '11010110'B
plmn-specificBS-6
                                          BearerServiceCode ::= '11010111'B
plmn-specificBS-7
                                          BearerServiceCode ::= '11011000'B
plmn-specificBS-8
                                          BearerServiceCode ::= '11011001'B
plmn-specificBS-9
plmn-specificBS-A
                                          BearerServiceCode ::= '11011010'B
                                          BearerServiceCode ::= '11011011'B
plmn-specificBS-B
                                          BearerServiceCode ::= '11011100'B
plmn-specificBS-C
plmn-specificBS-D
                                          BearerServiceCode ::= '11011101'B
                                          BearerServiceCode ::= '11011110'B
plmn-specificBS-E
plmn-specificBS-F
                                          BearerServiceCode ::= '11011111'B
```

END

17.7.11 Extension data types

```
MAP-ExtensionDataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-ExtensionDataTypes (21) version9 (9) }

DEFINITIONS

IMPLICIT TAGS

::=

BEGIN

EXPORTS

   PrivateExtension,
   ExtensionContainer,
   SLR-ArgExtensionContainer;

-- IOC for private MAP extensions
```

-- data types

```
SLR-ArgExtensionContainer ::= SEQUENCE {
    privateExtensionList [0] PrivateExtensionList OPTIONAL,
    slr-Arg-PCS-Extensions [1] SLR-Arg-PCS-Extensions OPTIONAL,
    ...}
```

PrivateExtensionList ::= SEQUENCE SIZE (1..maxNumOfPrivateExtensions) OF
PrivateExtension

maxNumOfPrivateExtensions INTEGER ::= 10

```
PCS-Extensions ::= SEQUENCE {
    ...}
```

```
SLR-Arg-PCS-Extensions ::= SEQUENCE {
    ...,
    na-ESRK-Request [0] NULL OPTIONAL }
```

END

17.7.12 Group Call data types

```
MAP-GR-DataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
   gsm-Network (1) modules (3) map-GR-DataTypes (23) version9 (9)}
DEFINITIONS
IMPLICIT TAGS
BEGIN
EXPORTS
  PrepareGroupCallArg,
  PrepareGroupCallRes,
  SendGroupCallEndSignalArg,
  SendGroupCallEndSignalRes,
  ForwardGroupCallSignallingArg,
   ProcessGroupCallSignallingArg
IMPORTS
  ISDN-AddressString,
  EMLPP-Priority,
  ASCI-CallReference
FROM MAP-CommonDataTypes {
  itu-t identified-organization (4) etsi (0) mobileDomain (0)
  gsm-Network (1) modules (3) map-CommonDataTypes (18) version9 (9)}
  Ext-TeleserviceCode
FROM MAP-TS-Code {
  itu-t identified-organization (4) etsi (0) mobileDomain (0)
  gsm-Network (1) modules (3) map-TS-Code (19) version9 (9)}
FROM MAP-MS-DataTypes {
  itu-t identified-organization (4) etsi (0) mobileDomain (0)
  gsm-Network (1) modules (3) map-MS-DataTypes (11) version9 (9)}
  ExtensionContainer
FROM MAP-ExtensionDataTypes {
   itu-t identified-organization (4) etsi (0) mobileDomain (0)
```

```
gsm-Network (1) modules (3) map-ExtensionDataTypes (21) version9 (9) \};
```

```
PrepareGroupCallArg ::= SEQUENCE {
    teleservice
                                            Ext-TeleserviceCode,
     asciCallReference
                                            ASCI-CallReference,
                                            CODEC-Info.
     codec-Info
    cipheringAlgorithm
                                            CipheringAlgorithm,
     groupKeyNumber-Vk-Id
                                            [0] GroupKeyNumber
                                                                                OPTIONAL,
                                           [1] Kc
                                                                                OPTIONAL,
    groupKey
     -- this parameter shall not be sent and shall be discarded if received priority [2] EMLPP-Priority
                                                                                OPTIONAL,
     uplinkFree
                                           [3] NULL
                                                                                OPTIONAL,
     extensionContainer
                                            [4] ExtensionContainer
                                                                                OPTIONAL,
     vstk
                                            [5] VSTK
                                                                                OPTIONAL,
     vstk-rand
                                            [6] VSTK-RAND
                                                                                OPTIONAL
```

```
VSTK ::= OCTET STRING (SIZE (16))
```

```
VSTK-RAND ::= OCTET STRING (SIZE (5))
-- The 36 bit value is carried in bit 7 of octet 1 to bit 4 of octet 5
-- bits 3, 2, 1, and 0 of octet 5 are padded with zeros.
```

<pre>PrepareGroupCallRes ::= SEQUENCE {</pre>		
groupCallNumber extensionContainer	ISDN-AddressString, ExtensionContainer	OPTIONAL,
}		·

SendGroupCallEndSignalArg ::= SEQUENCE {				
imsi	IMSI	OPTIONAL,		
extensionContainer	ExtensionContainer	OPTIONAL,		
}				

ForwardGroupCallSignallingArg ::=	SEQUENCE {	
imsi	IMSI	OPTIONAL,
uplinkRequestAck	[0] NULL	OPTIONAL,
uplinkReleaseIndication	[1] NULL	OPTIONAL,
uplinkRejectCommand	[2] NULL	OPTIONAL,
uplinkSeizedCommand	[3] NULL	OPTIONAL,
uplinkReleaseCommand	[4] NULL	OPTIONAL,
extensionContainer	ExtensionContainer	OPTIONAL,
• • • •		
stateAttributes	[5] StateAttributes	OPTIONAL }

```
GroupKeyNumber ::= INTEGER (0..15)
```

```
CODEC-Info ::= OCTET STRING (SIZE (5..10))
-- Refers to channel type
-- coded according to 3GPP TS 48.008 [49] and including Element identifier and Length
```

```
CipheringAlgorithm ::= OCTET STRING (SIZE (1))
     -- Refers to 'permitted algorithms' in 'encryption information'
     -- coded according to 3GPP TS 48.008 [49]:
     -- Bits 8-1
     -- 8765 4321
     -- 0000 0001
                                           No encryption
     -- 0000 0010
                                           GSM A5/1
     -- 0000 0100
                                           GSM A5/2
     -- 0000 1000
                                           GSM A5/3
     -- 0001 0000
                                           GSM A5/4
                                           GSM A5/5
     -- 0010 0000
     -- 0100 0000
                                           GSM A5/6
     -- 1000 0000
                                           GSM A5/7
```

END

17.7.13 Location service data types

```
MAP-LCS-DataTypes {
 2
3
4
5
       itu-t identified-organization (4) etsi (0) mobileDomain (0)
       gsm-Network (1) modules (3) map-LCS-DataTypes (25) version9 (9)}
    DEFINITIONS
 6
7
8
9
    IMPLICIT TAGS
    : :=
    BEGIN
10
   EXPORTS
11
       RoutingInfoForLCS-Arg,
12
       RoutingInfoForLCS-Res
13
       ProvideSubscriberLocation-Arg,
       ProvideSubscriberLocation-Res,
15
       SubscriberLocationReport-Arg,
16
17
       SubscriberLocationReport-Res,
       LocationType,
       DeferredLocationEventType,
18
19
20
21
22
23
24
25
26
27
28
29
30
31
32
33
34
35
36
37
38
39
40
41
       LCSClientName,
       LCS-OoS,
       Horizontal-Accuracy,
       ResponseTime,
       Ext-GeographicalInformation,
       SupportedGADShapes,
       {\tt Add-GeographicalInformation,}\\
       LCSRequestorID,
       LCS-ReferenceNumber,
       LCSCodeword,
       AreaEventInfo
    IMPORTS
       AddressString,
       ISDN-AddressString,
       IMEI,
       IMSI,
       SubscriberIdentity,
       AgeOfLocationInformation,
       LCSClientExternalID,
       LCSClientInternalID,
42
       LCSServiceTypeID,
       CellGlobalIdOrServiceAreaIdOrLAI
    FROM MAP-CommonDataTypes
45
       itu-t identified-organization (4) etsi (0) mobileDomain (0)
46
       gsm-Network (1) modules (3) map-CommonDataTypes (18) version9 (9)}
47
```

```
ExtensionContainer,
 49
        SLR-ArgExtensionContainer
50
51
52
53
54
55
56
57
58
59
60
61
    FROM MAP-ExtensionDataTypes {
        itu-t identified-organization (4) etsi (0) mobileDomain (0)
        gsm-Network (1) modules (3) map-ExtensionDataTypes (21) version9 (9)}
        USSD-DataCodingScheme,
        USSD-String
     FROM MAP-SS-DataTypes {
        itu-t identified-organization (4) etsi (0) mobileDomain (0) gsm-Network (1) modules (3)
        map-SS-DataTypes (14) version9 (9) }
        APN.
        GSN-Address,
 62
        SupportedLCS-CapabilitySets
 63
     FROM MAP-MS-DataTypes {
 64
        itu-t identified-organization (4) etsi (0) mobileDomain (0)
65
        gsm-Network (1) modules (3) map-MS-DataTypes (11) version9 (9)}
 66
 67
        Additional-Number
 68
     FROM MAP-SM-DataTypes {
69
70
71
72
73
        itu-t identified-organization (4) etsi (0) mobileDomain (0)
        gsm-Network (1) modules (3) map-SM-DataTypes (16) version9 (9)}
74
75
76
77
78
    RoutingInfoForLCS-Arg ::= SEQUENCE {
          mlcNumber
                                                  [0] ISDN-AddressString,
          targetMS
                                                  [1] SubscriberIdentity,
          extensionContainer
                                                  [2] ExtensionContainer
                                                                                      OPTIONAL.
 79
80
81
82
83
84
85
86
87
    RoutingInfoForLCS-Res ::= SEQUENCE {
                                                  [0] SubscriberIdentity,
          targetMS
          lcsLocationInfo
                                                  [1] LCSLocationInfo,
          extensionContainer
                                                  [2] ExtensionContainer
                                                                                      OPTIONAL,
                                                  [3] GSN-Address
          v-qmlc-Address
                                                                                      OPTIONAL.
          h-gmlc-Address
                                                  [4]
                                                      GSN-Address
                                                                                      OPTIONAL,
          ppr-Address
                                                      GSN-Address
                                                                                      OPTIONAL,
                                                  [5]
 88
          additional-v-gmlc-Address
                                                  [6]
                                                      GSN-Address
                                                                                      OPTIONAL
 89
 90
    LCSLocationInfo ::= SEQUENCE {
91
          networkNode-Number
                                                 ISDN-AddressString,
 92
          -- NetworkNode-number can be either msc-number or sgsn-number
93
94
95
          lmsi
                                                  [0] LMSI
                                                                                      OPTIONAL,
          extensionContainer
                                                  [1] ExtensionContainer
                                                                                      OPTIONAL,
 96
          gprsNodeIndicator
                                                  [2] NULL
                                                                                      OPTIONAL.
 97
          -- gprsNodeIndicator is set only if the SGSN number is sent as the Network Node Number
98
99
                                                                                      OPTIONAL,
          additional-Number
                                                  [3] Additional-Number
          supportedLCS-CapabilitySets
                                                      SupportedLCS-CapabilitySets
                                                                                      OPTIONAL,
100
          additional-LCS-CapabilitySets
                                                  [5] SupportedLCS-CapabilitySets OPTIONAL
101
102
```

```
103
    ProvideSubscriberLocation-Arg ::= SEQUENCE {
104
          locationType
                                                LocationType,
105
                                                ISDN-AddressString,
         mlc-Number
106
          lcs-ClientID
                                                [0] LCS-ClientID
                                                                                    OPTIONAL,
107
         privacyOverride
                                                [1] NULL
                                                                                    OPTIONAL,
108
         imsi
                                                [2] IMSI
                                                                                    OPTIONAL,
109
          msisdn
                                                [3] ISDN-AddressString
                                                                                    OPTIONAL.
                                                [4] LMSI
110
         lmsi
                                                                                    OPTIONAL,
                                                                                    OPTIONAL,
111
          imei
                                                [5] IMEI
112
          lcs-Priority
                                                [6] LCS-Priority
                                                                                    OPTIONAL,
113
         lcs-QoS
                                                [7] LCS-QoS
                                                                                    OPTIONAL,
114
                                                [8] ExtensionContainer
          extensionContainer
                                                                                    OPTIONAL,
115
116
          supportedGADShapes
                                               [9] SupportedGADShapes
                                                                                    OPTIONAL,
117
          lcs-ReferenceNumber
                                                [10] LCS-ReferenceNumber
                                                                                    OPTIONAL,
          lcsServiceTypeID
                                                [11] LCSServiceTypeID
118
                                                                                    OPTIONAL.
119
120
121
122
123
                                                [12] LCSCodeword
          lcsCodeword
                                                                                    OPTIONAL,
          lcs-PrivacyCheck
                                                [13] LCS-PrivacyCheck
                                                                                    OPTIONAL,
          areaEventInfo
                                                [14] AreaEventInfo
                                                                                    OPTIONAL.
         h-gmlc-Address
                                                [15] GSN-Address
                                                                                    OPTIONAL }
124
125
          -- one of imsi or msisdn is mandatory
          -- If a location estimate type indicates activate deferred location or cancel deferred
126
          -- location, a lcs-Reference number shall be included.
127
128
    LocationType ::= SEQUENCE {
129
         locationEstimateType
                                                [0] LocationEstimateType,
130
131
          deferredLocationEventType
                                                [1] DeferredLocationEventType
                                                                                    OPTIONAL 
132
133
134
    LocationEstimateType ::= ENUMERATED {
          currentLocation
                                                (0),
135
          currentOrLastKnownLocation
                                                (1),
136
          initialLocation
                                                (2),
137
138
139
                                                (3),
          activateDeferredLocation
                                                (4) }
          cancelDeferredLocation
140
          exception handling:
141
          a ProvideSubscriberLocation-Arg containing an unrecognized LocationEstimateType
142
          shall be rejected by the receiver with a return error cause of unexpected data value
143
144
    DeferredLocationEventType ::= BIT STRING {
145
                                                (0),
         msAvailable
146
          enteringIntoArea
                                                (1),
147
          leavingFromArea
                                                (2),
148
                                                (3) } (SIZE (1..16))
         beingInsideArea
149
     -- beingInsideArea is always treated as oneTimeEvent regardless of the possible value
150
151
     -- of occurrenceInfo inside areaEventInfo.
     -- exception handling:
152
     -- a ProvideSubscriberLocation-Arg containing other values than listed above in
153
     -- DeferredLocationEventType shall be rejected by the receiver with a return error cause of
154
     -- unexpected data value.
155
156
    LCS-ClientID ::= SEQUENCE {
157
158
          lcsClientType
                                                [0] LCSClientType,
          lcsClientExternalID
                                                [1] LCSClientExternalID
                                                                                    OPTIONAL,
159
          lcsClientDialedByMS
                                                [2] AddressString
                                                                                    OPTIONAL,
160
          lcsClientInternalID
                                                [3] LCSClientInternalID
                                                                                    OPTIONAL,
161
                                                [4] LCSClientName
                                                                                    OPTIONAL.
          lcsClientName
162
163
          lcsAPN
                                                [5] APN
                                                                                    OPTIONAL,
164
                                                [6] LCSRequestorID
          lcsRequestorID
                                                                                    OPTIONAL
165
166
    LCSClientType ::= ENUMERATED {
167
          emergencyServices
                                                (0),
168
          valueAddedServices
                                                (1),
169
          plmnOperatorServices
                                                (2),
170
          {\tt lawfulInterceptServices}
                                                (3),
171
          ...}
172
              exception handling:
173
              unrecognized values may be ignored if the LCS client uses the privacy override
174
              otherwise, an unrecognized value shall be treated as unexpected data by a receiver
175
              a return error shall then be returned if received in a MAP invoke
176
```

```
177
    LCSClientName ::= SEQUENCE {
178
          dataCodingScheme
                                                 [0] USSD-DataCodingScheme,
179
          nameString
                                                 [2] NameString,
180
181
          lcs-FormatIndicator
                                                 [3] LCS-FormatIndicator
                                                                                     OPTIONAL }
182
183
     -- The USSD-DataCodingScheme shall indicate use of the default alphabet through the
184
     -- following encoding
185
     -- bit 7 6 5 4 3 2 1 0
186
               0 0 0 0 1 1 1 1
187
188 NameString ::= USSD-String (SIZE (1..maxNameStringLength))
189
190 maxNameStringLength INTEGER ::= 63
191
192 LCSRequestorID ::= SEQUENCE {
193
          dataCodingScheme
                                                 [0] USSD-DataCodingScheme,
194
          requestorIDString
                                                 [1] RequestorIDString,
195
196
          lcs-FormatIndicator
                                                 [2] LCS-FormatIndicator
                                                                                OPTIONAL }
197
198
    RequestorIDString ::= USSD-String (SIZE (1..maxRequestorIDStringLength))
199
200 maxRequestorIDStringLength INTEGER ::= 63
201
202
203
    LCS-FormatIndicator ::= ENUMERATED {
                                                 (0),
          logicalName
204
205
          e-mailAddress
                                                 (1),
          msisdn
                                                 (2).
206
                                                 (3),
          url
207
208
          sipUrl
                                                 (4),
209
210
211
212
    LCS-Priority ::= OCTET STRING (SIZE (1))
          -- 0 = highest priority
          -- 1 = normal priority
213
          -- all other values treated as 1
214
215
    LCS-QoS ::= SEQUENCE {
216
217
218
219
220
          horizontal-accuracy
                                                 [0] Horizontal-Accuracy
                                                                                     OPTIONAL,
          verticalCoordinateRequest
                                                 [1] NULL
                                                                                     OPTIONAL,
          vertical-accuracy
                                                 [2] Vertical-Accuracy
                                                                                     OPTIONAL.
          responseTime
                                                 [3] ResponseTime
                                                                                     OPTIONAL,
          extensionContainer
                                                 [4] ExtensionContainer
                                                                                     OPTIONAL,
221
222
223
    Horizontal-Accuracy ::= OCTET STRING (SIZE (1))
223
224
225
226
227
228
        -- bit 8 = 0
          -- bits 7-1 = 7 bit Uncertainty Code defined in 3GPP TS 23.032. The horizontal location
          -- error should be less than the error indicated by the uncertainty code with 67%
          -- confidence.
229
    Vertical-Accuracy ::= OCTET STRING (SIZE (1))
239
230
231
232
233
234
          -- bit 8 = 0
          -- bits 7-1 = 7 bit Vertical Uncertainty Code defined in 3GPP TS 23.032.
          -- The vertical location error should be less than the error indicated
          -- by the uncertainty code with 67% confidence.
235
236
237
    ResponseTime ::= SEQUENCE {
          responseTimeCategory
                                                 ResponseTimeCategory,
238
239
          note: an expandable SEQUENCE simplifies later addition of a numeric response time.
240
    ResponseTimeCategory ::= ENUMERATED {
241
242
243
          lowdelay (0),
          delaytolerant (1),
          . . . }
244
          exception handling:
<del>2</del>45
          an unrecognized value shall be treated the same as value 1 (delaytolerant)
246
```

```
247
248
    SupportedGADShapes ::= BIT STRING {
          ellipsoidPoint (0),
249
          ellipsoidPointWithUncertaintyCircle (1),
250
251
252
253
254
          ellipsoidPointWithUncertaintyEllipse (2),
          polygon (3),
          ellipsoidPointWithAltitude (4),
          ellipsoidPointWithAltitudeAndUncertaintyElipsoid (5),
          ellipsoidArc (6) } (SIZE (7..16))
255
256
     -- A node shall mark in the BIT STRING all Shapes defined in 3GPP TS 23.032 it supports.
     -- exception handling: bits 7 to 15 shall be ignored if received.
257
258 LCS-ReferenceNumber::= OCTET STRING (SIZE(1))
259
260
261
     LCSCodeword ::= SEQUENCE {
          dataCodingScheme
                                                  [0] USSD-DataCodingScheme,
262
263
          lcsCodewordString
                                                  [1] LCSCodewordString,
264
265
    LCSCodewordString ::= USSD-String (SIZE (1..maxLCSCodewordStringLength))
266
267
    maxLCSCodewordStringLength INTEGER ::= 20
268
269
     LCS-PrivacyCheck ::= SEQUENCE {
270
271
272
          callSessionUnrelated
                                                  [0] PrivacyCheckRelatedAction,
          callSessionRelated
                                                  [1] PrivacyCheckRelatedAction
                                                                                      OPTIONAL,
273
274
275
276
277
278
279
280
281
282
283
    PrivacyCheckRelatedAction ::= ENUMERATED {
          allowedWithoutNotification (0),
          allowedWithNotification (1),
          allowedIfNoResponse (2),
          restrictedIfNoResponse (3),
          notAllowed (4),
          . . . }
          exception handling:
          a ProvideSubscriberLocation-Arg containing an unrecognized PrivacyCheckRelatedAction
          shall be rejected by the receiver with a return error cause of unexpected data value
284
285
286
287
     AreaEventInfo ::= SEQUENCE {
          areaDefinition
                                                  [0] AreaDefinition,
                                                                                      OPTIONAL,
          occurrenceInfo
                                                  [1] OccurrenceInfo
288
289
                                                                                      OPTIONAL,
          intervalTime
                                                  [2] IntervalTime
290
291
292
     AreaDefinition ::= SEQUENCE {
          areaList
                                                  [0] AreaList,
293
294
295
    AreaList ::= SEQUENCE SIZE (1..maxNumOfAreas) OF Area
296
297
    maxNumOfAreas INTEGER ::= 10
298
299
     Area ::= SEQUENCE {
300
          areaType
                                                  [0] AreaType,
301
          areaIdentification
                                                  [1] AreaIdentification,
302
303
304
     AreaType ::= ENUMERATED {
305
          countryCode
                                                  (0),
306
          plmnId
                                                  (1),
307
          locationAreaId
                                                  (2),
308
          routingAreaId
                                                  (3),
309
          cellGlobalId
                                                  (4),
310
311
          utranCellId
                                                  (5) }
312
```

```
313 AreaIdentification ::= OCTET STRING (SIZE (2..7))
314
          -- The internal structure is defined as follows:
315
                                                Mobile Country Code 1st digit
          -- octet 1 bits 4321
                                                Mobile Country Code 2<sup>nd</sup> digit
316
                    bits 8765
                                                Mobile Country Code 3rd digit
317
          -- octet 2 bits 4321
318
                                               Mobile Network Code 3<sup>rd</sup> digit if 3 digit MNC included
                     bits 8765
319
          --
                                                or filler (1111)
320
                                               Mobile Network Code 1st digit
          -- octet 3 bits 4321
                                               Mobile Network Code 2<sup>nd</sup> digit
321
                   bits 8765
322
323
          -- octets 4 and 5
                                                Location Area Code (LAC) for Local Area Id,
                                               Routing Area Id and Cell Global Id
                                               Routing Area Code (RAC) for Routing Area Id
Cell Identity (CI) for Cell Global Id
324
          -- octet 6
325
          -- octets 6 and 7
326
          -- octets 4 until 7
                                                Utran Cell Identity (UC-Id) for Utran Cell Id
327
328
329
    OccurrenceInfo ::= ENUMERATED {
330
          oneTimeEvent
                                                (0),
331
          multipleTimeEvent
                                                (1),
332
333
334
    IntervalTime ::= INTEGER (1..32767)
335
         -- minimum interval time between area reports in seconds
336
337
    ProvideSubscriberLocation-Res ::= SEQUENCE {
338
          locationEstimate
                                                Ext-GeographicalInformation,
339
          ageOfLocationEstimate
                                                [0] AgeOfLocationInformation
                                                                                    OPTIONAL.
340
          extensionContainer
                                                [1] ExtensionContainer
                                                                                    OPTIONAL,
341
342
          add-LocationEstimate
                                                [2] Add-GeographicalInformation
                                                                                    OPTIONAL,
343
          deferredmt-lrResponseIndicator
                                                [3] NULL
                                                                                    OPTIONAL.
344
          geranPositioningData
                                                [4] PositioningDataInformation
                                                                                    OPTIONAL.
345
          utranPositioningData
                                                [5] UtranPositioningDataInfo
                                                                                    OPTIONAL,
346
          cellIdOrSai
                                                [6] CellGlobalIdOrServiceAreaIdOrLAI OPTIONAL,
347
          sai-Present
                                                [7] NULL
                                                                                    OPTIONAL,
348
         accuracyFulfilmentIndicator
                                                [8] AccuracyFulfilmentIndicator
                                                                                    OPTIONAL }
349
350
     -- if deferredmt-lrResponseIndicator is set, locationEstimate is ignored.
351
352
     -- the add-LocationEstimate parameter shall not be sent to a node that did not indicate the
353
     -- geographic shapes supported in the ProvideSubscriberLocation-Arg
354
     -- The locationEstimate and the add-locationEstimate parameters shall not be sent if
355
     \hbox{\it -- the supported GADS hapes parameter has been received in Provide Subscriber Location-Arg}
356
     -- and the shape encoded in locationEstimate or add-LocationEstimate is not marked
357
     -- as supported in supportedGADShapes. In such a case ProvideSubscriberLocation
     -- shall be rejected with error FacilityNotSupported with additional indication
358
359
     -- shapeOfLocationEstimateNotSupported.
360
     -- sai-Present indicates that the cellIdOrSai parameter contains a Service Area Identity.
361
362
    AccuracyFulfilmentIndicator ::= ENUMERATED {
363
          requestedAccuracyFulfilled (0),
364
          requestedAccuracyNotFulfilled (1),
365
```

```
Ext-GeographicalInformation ::= OCTET STRING (SIZE (1..maxExt-GeographicalInformation))
367
368
          -- Refers to geographical Information defined in 3GPP TS 23.032.
369
          -- This is composed of 1 or more octets with an internal structure according to
370
          -- 3GPP TS 23.032
371
          -- Octet 1: Type of shape, only the following shapes in 3GPP TS 23.032 are allowed:
372
                    (a) Ellipsoid point with uncertainty circle
373
                    (b) Ellipsoid point with uncertainty ellipse
374
                    (c) Ellipsoid point with altitude and uncertainty ellipsoid
375
          --
                    (d) Ellipsoid Arc
376
                    (e) Ellipsoid Point
377
          -- Any other value in octet 1 shall be treated as invalid
378
          -- Octets 2 to 8 for case (a) - Ellipsoid point with uncertainty circle
379
                   Degrees of Latitude
                                                                                      3 octets
380
                    Degrees of Longitude
381
                   Uncertainty code
                                                                                      1 octet
382
          -- Octets 2 to 11 for case (b) - Ellipsoid point with uncertainty ellipse:
383
384
          -- Degrees of Latitude
                    Degrees of Longitude
385
                  Uncertainty semi-major axis
386
          --
                   Uncertainty semi-minor axis
                                                                                      1 octet
387
              Angle of major axis
Confidence
                                                                                      1 octet
388
                                                                                      1 octet
389
          -- Octets 2 to 14 for case (c) - Ellipsoid point with altitude and uncertainty ellipsoid
390
                                                                                      3 octets
          -- Degrees of Latitude
391
          --
                   Degrees of Longitude
                                                                                      3 octets
392
                   Altitude
                                                                                      2 octets
          -- Uncertainty semi-major axis
-- Uncertainty semi-minor axis
-- Angle of major axis
-- Uncertainty altitude
-- Confidence
393
                                                                                      1 octet
394
395
                                                                                      1 octet
396
                                                                                      1 octet
397
                                                                                      1 octet
398
          -- Octets 2 to 13 for case (d) - Ellipsoid Arc
399
          -- Degrees of Latitude
-- Degrees of Longitude
                                                                                      3 octets
400
                                                                                      3 octets
          -- Inner radius
-- Uncertainty radius
-- Offset angle
-- Included angle
-- Confidence
401
                                                                                      2 octets
402
                                                                                      1 octet
403
                                                                                      1 octet
404
                                                                                      1 octet
405
                                                                                      1 octet
406
          -- Octets 2 to 7 for case (e) - Ellipsoid Point
407
              Degrees of Latitude
                                                                                      3 octets
408
          --
                   Degrees of Longitude
                                                                                      3 octets
409
410
411
          -- An Ext-GeographicalInformation parameter comprising more than one octet and
412
          -- containing any other shape or an incorrect number of octets or coding according
413
          -- to 3GPP TS 23.032 shall be treated as invalid data by a receiver.
414
415
          -- An Ext-GeographicalInformation parameter comprising one octet shall be discarded
416
          -- by the receiver if an Add-GeographicalInformation parameter is received
417
          -- in the same message.
418
419
          -- An Ext-GeographicalInformation parameter comprising one octet shall be treated as
420
          -- invalid data by the receiver if an Add-GeographicalInformation parameter is not
421
          -- received in the same message.
422
```

```
maxExt-GeographicalInformation INTEGER ::= 20
```

-- the maximum length allows for further shapes in 3GPP TS 23.032 to be included in later -- versions of 3GPP TS 29.002

```
PositioningDataInformation ::= OCTET STRING (SIZE (2..maxPositioningDataInformation))
```

- -- Refers to the Positioning Data defined in 3GPP TS 49.031.
- -- This is composed of 2 or more octets with an internal structure according to
- -- 3GPP TS 49.031.

423

424

425

426 427 428

429

430

431 432

433 434 435

436

437

438

439 440

 $\begin{array}{c} 441 \\ 442 \end{array}$

```
maxPositioningDataInformation INTEGER ::= 10
```

```
UtranPositioningDataInfo ::= OCTET STRING (SIZE (3..maxUtranPositioningDataInfo))
```

- -- Refers to the Position Data defined in 3GPP TS 25.413.
- -- This is composed of the positioning Data Discriminator and the positioning Data Set
- -- included in positionData as defined in 3GPP TS 25.413.

```
maxUtranPositioningDataInfo INTEGER ::= 11
```

507

508

509

510

511 512 513

514

```
443
    Add-GeographicalInformation ::= OCTET STRING (SIZE (1..maxAdd-GeographicalInformation))
444
         -- Refers to geographical Information defined in 3GPP TS 23.032.
445
         -- This is composed of 1 or more octets with an internal structure according to
446
          -- 3GPP TS 23.032
447
          -- Octet 1: Type of shape, all the shapes defined in 3GPP TS 23.032 are allowed:
448
          -- Octets 2 to n (where n is the total number of octets necessary to encode the shape
449
          -- according to 3GPP TS 23.032) are used to encode the shape itself in accordance with
450
    the
451
          -- encoding defined in 3GPP TS 23.032
452
453
         -- An Add-GeographicalInformation parameter, whether valid or invalid, received
454
          -- together with a valid Ext-GeographicalInformation parameter in the same message
455
          -- shall be discarded.
456
457
          -- An Add-GeographicalInformation parameter containing any shape not defined in
458
459
          -- 3GPP TS 23.032 or an incorrect number of octets or coding according to
          -- 3GPP TS 23.032 shall be treated as invalid data by a receiver if not received
460
          -- together with a valid Ext-GeographicalInformation parameter in the same message
461
```

```
462
    maxAdd-GeographicalInformation INTEGER ::= 91
         -- the maximum length allows support for all the shapes currently defined in 3GPP TS
464
```

```
465
466
    SubscriberLocationReport-Arg ::= SEQUENCE {
467
         lcs-Event
                                              LCS-Event,
468
         lcs-ClientID
                                              LCS-ClientID.
469
         lcsLocationInfo
                                              LCSLocationInfo,
470
         msisdn
                                               [0] ISDN-AddressString
                                                                                OPTIONAL,
471
                                               [1] IMSI
         imsi
                                                                                 OPTIONAL,
472
                                               [2] IMEI
                                                                                 OPTIONAL.
         imei
473
                                               [3] ISDN-AddressString
         na-ESRD
                                                                                 OPTIONAL.
474
475
         na-ESRK
                                               [4] ISDN-AddressString
                                                                                 OPTIONAL.
         locationEstimate
                                               [5] Ext-GeographicalInformation OPTIONAL,
                                              [6] AgeOfLocationInformation
476
477
         ageOfLocationEstimate
                                                                                 OPTIONAL,
         slr-ArgExtensionContainer
                                              [7] SLR-ArgExtensionContainer
                                                                                OPTIONAL.
478
479
         add-LocationEstimate
                                              [8] Add-GeographicalInformation OPTIONAL,
480
         deferredmt-lrData
                                              [9] Deferredmt-lrData
                                                                                 OPTIONAL,
481
         lcs-ReferenceNumber
                                              [10] LCS-ReferenceNumber
                                                                                 OPTIONAL,
482
         geranPositioningData
                                              [11] PositioningDataInformation OPTIONAL,
483
         utranPositioningData
                                              [12] UtranPositioningDataInfo
                                                                                 OPTIONAL,
484
         cellIdOrSai
                                               [13] CellGlobalIdOrServiceAreaIdOrLAI OPTIONAL,
485
         h-gmlc-Address
                                                                                OPTIONAL,
                                              [14] GSN-Address
486
         lcsServiceTypeID
                                               [15] LCSServiceTypeID
                                                                                 OPTIONAL,
487
         sai-Present
                                               [17] NULL
                                                                                 OPTIONAL.
488
         pseudonymIndicator
                                               [18] NULL
                                                                                 OPTIONAL,
489
         accuracyFulfilmentIndicator
                                               [19] AccuracyFulfilmentIndicator OPTIONAL }
490
491
         -- one of msisdn or imsi is mandatory
         -- a location estimate that is valid for the locationEstimate parameter should
492
493
         -- be transferred in this parameter in preference to the add-LocationEstimate.
494
         -- the deferredmt-lrData parameter shall be included if and only if the lcs-Event
495
         -- indicates a deferredmt-lrResponse.
496
         -- if the lcs-Event indicates a deferredmt-lrResponse then the locationEstimate
497
         -- and the add-locationEstimate parameters shall not be sent if the
498
         -- supportedGADShapes parameter had been received in ProvideSubscriberLocation-Arg
499
         -- and the shape encoded in locationEstimate or add-LocationEstimate was not marked
500
         -- as supported in supportedGADShapes. In such a case terminationCause
501
         -- in deferredmt-lrData shall be present with value
502
         -- shapeOfLocationEstimateNotSupported.
503
         -- If a lcs event indicates deferred mt-lr response, the lcs-Reference number shall be
504
         -- included.
505
          -- sai-Present indicates that the cellIdOrSai parameter contains a Service Area Identity.
506
```

```
Deferredmt-lrData ::= SEQUENCE {
     deferredLocationEventType
                                          DeferredLocationEventType,
                                          [0] TerminationCause
                                                                            OPTIONAL.
     terminationCause
     lcsLocationInfo
                                          [1] LCSLocationInfo
                                                                            OPTIONAL,
     -- lcsLocationInfo may be included only if a terminationCause is present
     -- indicating mt-lrRestart.
```

END

```
515
    LCS-Event ::= ENUMERATED {
516
517
          emergencyCallOrigination (0),
          emergencyCallRelease (1),
518
519
520
521
522
          mo-lr (2),
          deferredmt-lrResponse (3) }
               exception handling:
               a SubscriberLocationReport-Arg containing an unrecognized LCS-Event
523
               shall be rejected by a receiver with a return error cause of unexpected data value
524
525
526
527
528
    TerminationCause ::= ENUMERATED {
          normal (0),
          errorundefined (1),
          internalTimeout (2),
528
529
530
531
532
533
          congestion (3),
          mt-lrRestart (4),
          privacyViolation (5),
          shapeOfLocationEstimateNotSupported (6) }
534
535
536
537
538
539
540
     -- mt-lrRestart shall be used to trigger the GMLC to restart the location procedure,
     -- either because the sending node knows that the terminal has moved under coverage
     -- of another MSC or SGSN (e.g. Send Identification received), or because the subscriber
     -- has been deregistered due to a Cancel Location received from HLR.
     -- exception handling
     -- an unrecognized value shall be treated the same as value 1 (errorundefined)
541
542
543
544
    SubscriberLocationReport-Res ::= SEQUENCE {
          extensionContainer
                                                  ExtensionContainer
                                                                                       OPTIONAL,
545
546
547
          na-ESRK
                                                  [0] ISDN-AddressString
                                                                                       OPTIONAL,
          na-ESRD
                                                  [1] ISDN-AddressString
                                                                                       OPTIONAL }
548
     -- na-ESRK and na-ESRD are mutually exclusive
549
550
551
     -- exception handling
        receipt of both na-ESRK and na-ESRD shall be treated the same as a return error
552
```

17.7.14 void

18 General on MAP user procedures

18.1 Introduction

Clauses 18 to 25 describe the use of MAP services for GSM signalling procedures. GSM signalling procedures may involve one or several interfaces running one or several application protocols. The present document addresses only the signalling procedures which require at least the use of one MAP service.

When a signalling procedure takes place in the network, an application process invocation is created in each system component involved. Part of the application process invocation acts as a MAP user and handles one or several MAP dialogues. For each dialogue it employs an instance of the MAP service provider. It may also use other communication services to exchange information on other interfaces, but detailed description of these aspects is outside the scope of the present document.

18.2 Common aspects of user procedure descriptions

18.2.1 General conventions

For each signalling procedure the present document provides a brief textual overview accompanied by a flow diagram which represent the functional interactions between system components. Functional interactions are labelled using the MAP service name when the interaction results from a service request or by this service name followed by the symbol "ack" when this interaction results from a service response.

For each of the system components involved, the present document also provides a detailed textual description of the application process behaviour as well as an SDL diagram. SDL diagrams describe the sequence of events, as seen by the MAP-User, which occurs at MAP service provider boundaries as well as external events which occur at other interfaces and which impact on the previous sequence.

External events do not necessarily correspond to the messages of other protocols used in the system component. The MAP-user procedures are described as if a set of interworking functions (IWF) between the MAP-user and the other protocol entities was implemented (see figure 18.2/1). Such interworking functions are assumed to perform either an identity mapping or some processing or translation as required to eliminate information irrelevant to the MAP-user.

The mapping of service primitives on to protocol elements is described in clauses 14 to 17.

GSM signalling procedures are built from one or more sub-procedures (e.g. authentication, ciphering, ...). Sub-procedures from which signalling procedures are built are represented using SDL MACRO descriptions.

In case of any discrepancy between the textual descriptions and the SDL descriptions, the latter take precedence.

18.2.2 Naming conventions

Events related to MAP are represented by MAP service primitives. The signal names used in the SDL diagrams are derived from the service primitive names defined in clauses 7 to 12, with some lexical transformations for readability and parsability purposes (blanks between words are replaced by underscores, the first letter of each word is capitalised).

Events received and sent on other interfaces are named by appending the message or signal name to a symbol representing the interface type, with some lexical transformations for readability and parsability purposes (blanks between words are replaced by underscores, the first letter of each word is capitalised).

The following symbols are used to represent the interface types:

"I": For interfaces to the fixed network. "I" stands for ISUP interface.

"A": For interfaces between the MSC and the BSS (i.e. A-interfaces);

"Gb": For interfaces between the SGSN and the BSS (i.e. Gb-interfaces);

"OM": For network management interfaces (communication with OMC, MML interface, ...);

"SC": For interfaces to a Service Centre;

"HO_CA": For internal interfaces to the Handover Control Application.

"US": For a local USSD application.

These naming conventions can be summarised by the following BNF description:

<Event_Name> ::= <MAP_Primitive> | <External_Event>

<MAP_Specific> | <MAP_Notice>

<MAP_Open> ::= MAP_Open_Req | MAP_Open_Ind | MAP_Open_Rsp | MAP_Open_Cnf

<MAP_Close_Req | MAP_Close_Ind

<MAP_U_Abort> ::= MAP_U_Abort_Req | MAP_U_Abort_Ind

<MAP_P_Abort> ::= MAP_P_Abort_Ind

<MAP_Notice> ::= MAP_Notice_Ind

<MAP_Specific> ::= <MAP_Req> | <MAP_Ind> | <MAP_Rsp> | <MAP_Cnf>

<MAP_Req> ::= MAP_<Service_Name>_Req

<MAP_Ind> ::= MAP_<Service_Name>_Ind

<MAP_Rsp> ::= MAP_<Service_Name>_Rsp

<MAP_Cnf> ::= MAP_<Service_Name>_Cnf

<External_Event> ::= <Interface_Type>_<External_Signal>

<Interface_Type> ::= I | A | Gb | OM | SC | HO AC | US

<External_Signal> ::= <Lexical_Unit>

<Service Name> ::= <Lexical Unit>

<Lexical_Unit> ::= <Lexical_Component> | <Lexical_Unit>_ <Lexical_Component>

<Lexical_Component> ::= <Upper_Case_Letter><Letter_Or_Digit_List>

<Letter_Or_Digit_List> ::= <Letter_Or_Digit> | <Letter_Or_Digit_List> <Letter_Or_Digit>

<Letter_Or_Digit> ::= <Letter> | <Digit>

<Letter> ::= <Lower_Case_Letter> | <Upper_Case_Letter>

<Lower_Case_Letter> ::= a|b|c|d|e|f|g|h|i|j|k|l|m|n|o|p|q|r|s|t|u|v|w|x|y|z

<Digit> ::= 1|2|3|4|5|6|7|8|9|0

Figure 18.2/1: Interfaces applicable to the MAP-User

18.2.3 Convention on primitives parameters

18.2.3.1 Open service

When the originating and destination reference parameters shall be included in the MAP-OPEN request primitive, their value are indicated as a comment to the signal which represents this primitive.

18.2.3.2 Close service

When a pre-arranged released is requested, a comment is attached to the signal which represents the MAP-CLOSE request primitive. In the absence of comment, a normal release is assumed.

18.2.4 Version handling at dialogue establishment

Unless explicitly indicated in subsequent clauses, the following principles regarding version handling procedures at dialogue establishment are applied by the MAP-user.

18.2.4.1 Behaviour at the initiating side

When a MAP user signalling procedure has to be executed, the MAP-user issues a MAP-OPEN request primitive with an appropriate application-context-name. If several names are supported (i.e. several versions) a suitable one is selected using the procedures described in clause 5.

If version n is selected (where 1 < n <= highest existing version) and a MAP-OPEN Confirm primitive is received in response to the MAP-OPEN request with a result parameter set to "refused" and a diagnostic parameter indicating "application context not supported" or "potential version incompatibility problem", the MAP-User issues a new MAP-OPEN request primitive with the equivalent version y context (where 1 <= y < n). This is informally represented in the SDL diagrams by task symbols indicating 'Perform Vr procedure".

18.2.4.2 Behaviour at the responding side

On receipt of a MAP-OPEN indication primitive, the MAP-User analyses the application-context-name and executes the procedure associated with the requested version context. For example, if it refers to a version one context, the associated V1 procedure is executed; if it refers to a version two context, the associated V2 procedure is executed; etc.

18.2.5 Abort Handling

Unless explicitly indicated in subsequent clauses, the following principles are applied by the MAP-user regarding abort handling procedures:

On receipt of a MAP-P-ABORT indication or MAP-U-ABORT Indication primitive from any MAP-provider invocation, the MAP-User issues a MAP-U-ABORT Request primitive to each MAP-provider invocation associated with the same user procedure.

If applicable a decision is made to decide if the affected user procedure has to be retried or not.

18.2.6 SDL conventions

The MAP SDLs make use of a number of SDL concepts and conventions, where not all of them may be widely known. Therefore, this clause outlines the use of a few concepts and conventions to improve understanding of the MAP SDLs.

The MAP User SDLs make use of SDL Processes, Procedures and Macros. Processes are independent from each other even if one process starts another one: The actions of both of them have no ordering in time. SDL Procedures and Macros are just used to ease writing of the specification: They contain parts of a behaviour used in several places, and the corresponding Procedure/Macro definition has to be expanded at the position of the Procedure/Macro call.

All Processes are started at system initialisation and live forever, unless process creation/termination is indicated explicitly (i.e. a process is created by some other process).

The direction of Input/Output Signals in the SDL graphs is used to indicate the entity to which/from which communication is directed. If a process A communicates in parallel with processes B and C, all Inputs/Outputs to/from B are directed to one side, whereas communication with C is directed to the other side. However, there has been no formal convention used that communication to a certain entity (e.g. a HLR) will always be directed to a certain side (e.g. right).

In each state all those Input Signals are listed, which result in an action and/or state change. If an Input Signal is not listed in a state, receipt of this input should lead to an implicit consumption without any action or state change (according to the SDL rules). This implicit consumption is mainly used for receipt of the MAP DELIMITER indication and for receipt of a MAP CLOSE indication, except for a premature MAP CLOSE.

18.3 Interaction between MAP Provider and MAP Users

Each MAP User is defined by at least one SDL process. On the dialogue initiating side, the MAP User will create a new instance of a MAP Provider implicit by issuing a MAP-OPEN request. This instance corresponds to a TC Dialogue and lives as long as the dialogue exists (see also clause 14.3). There is a fixed relation between MAP User and this Provider instance, i.e. all MAP service primitives from the MAP User for this dialogue are sent to this instance and all TC components received by this MAP Provider are mapped onto service primitives sent to this MAP User.

On the receiving side a MAP Provider instance is created implicit by receipt of a TC BEGIN indication. The corresponding MAP User is determined by the Application Context name included in this primitive, i.e. each Application Context is associated with one and only one MAP User. An instance of this User will be created implicitly by receiving a MAP-OPEN indication. Note that in some cases there exist several SDL Processes for one MAP User (Application Context), e.g. the processes Register_SS_HLR, Erase_SS_HLR, Activate_SS_HLR, Deactivate_SS_HLR, Interrogate_SS_HLR, and Register_Password for the AC Network_Functional_SS_Handling. In these cases, a coordinator process is introduced acting as a MAP User, which in turn starts a sub-process depending on the first MAP service primitive received.

19 Mobility procedures

19.1 Location management Procedures

The signalling procedures in this subclause support:

- Interworking between the VLR and the HLR and between the VLR and the previous VLR (PVLR) when a non-GPRS subscriber performs a location update to a new VLR service area;
- Interworking between the SGSN, the HLR and the VLR when a subscriber with both GPRS and non-GPRS subscriptions performs a routeing area update in an SGSN and the Gs interface is implemented;
- Interworking between the SGSN and the VLR when a GPRS subscriber performs a routeing area update to a new SGSN service area;
- Interworking between the HLR and the VLR and between the HLR and the SGSN to delete a subscriber record from the VLR or the SGSN;
- Interworking between the VLR and the HLR and between the SGSN and the HLR to report to the HLR that a subscriber record has been purged from the VLR or the SGSN.

The MAP co-ordinating process in the HLR to handle a dialogue opened with the network location updating context is shown in figure 19.1/1. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Receive_Open_Ind see clause 25.1.1.




Figure 19.1/1: Process Location_Management_Coordinator_HLR

19.1.1 Location updating

19.1.1.1 General


The stage 2 specification for GPRS is in 3GPP TS 23.060 [104]. The interworking between the MAP signalling procedures and the GPRS procedures in the SGSN and the HLR is shown by the transfer of signals between these procedures.

The message flow for successful inter-VLR location updating when the IMSI can be retrieved from the PVLR is shown in figure 19.1.1/2.

The message flow for successful inter-VLR location updating when the IMSI cannot be retrieved from the PVLR is shown in figure 19.1.1/3.

The message flow for successful GPRS Attach/RA update procedure (Gs interface not installed) is shown in figure 19.1.1/4.


The message flow for successful GPRS Attach/RA update procedure combined with a successful VLR location updating (Gs interface installed) is shown in figure 19.1.1/5.



PVLR = Previous VLR

- A_LU_REQUEST (Note 1) 1)
- 2) MAP_SEND_IDENTIFICATION_req/ind
- 3) MAP_SEND_IDENTIFICATION_rsp/cnf
- 4) MAP_UPDATE_LOCATION_req/ind
- 5) MAP_CANCEL_LOCATION_req/ind
- 6)
- MAP_CANCEL_LOCATION_rsp/cnf
 MAP_ACTIVATE_TRACE_MODE_req/ind (Note 2)
 MAP_ACTIVATE_TRACE_MODE_rsp/cnf (Note 2) 7)
- 8)
- MAP_INSERT_SUBSCRIBER_DATA_reg/ind 9)
- 10) MAP_INSERT_SUBSCRIBER_DATA_rsp/cnf
- MAP_UPDATE_LOCATION_rsp/cnf 11)
- 12) A_LU_CONFIRM (Note 1)
- NOTE 1: For details of the procedure on the radio path, see 3GPP TS 24.008 [35]. Services shown in dotted lines indicate the trigger provided by the signalling on the radio path, and the signalling triggered on the radio
- NOTE 2: Services printed in *italics* are optional.


Figure 19.1.1/2: Message flow for location updating to a new VLR area, when the IMSI can be retrieved from the previous VLR



PVLR = Previous VLR

- A_LU_REQUEST (Note 1) 1)
- 2)
- A_IDENTITY_REQUEST (Note 1)
 A_IDENTITY_RESPONSE (Note 1) 3)
- 4) MAP_UPDATE_LOCATION_req/ind
- 5) MAP_CANCEL_LOCATION_req/ind
- 6) MAP_CANCEL_LOCATION_rsp/cnf
- MAP_ACTIVATE_TRACE_MODE_req/ind (Note 2) 7)
- 8) MAP_ACTIVATE_TRACE_MODE_rsp/cnf (Note 2)
- MAP_INSERT_SUBSCRIBER_DATA_req/ind 9)
- MAP_INSERT_SUBSCRIBER_DATA_rsp/cnf 10)
- MAP_UPDATE_LOCATION_rsp/cnf 11)
- 12) A_LU_CONFIRM (Note 1)
- NOTE 1: For details of the procedure on the radio path, see 3GPP TS 24.008 [35]. Services shown in dotted lines indicate the trigger provided by the signalling on the radio path, and the signalling triggered on the radio path.
- NOTE 2: Services printed in *italics* are optional.


Figure 19.1.1/3: Message flow for location updating to a new VLR area, when the IMSI cannot be retrieved from the previous VLR



PSGSN = Previous SGSN

- 1) Gb_ATTACH_REQUEST or RA_UPDATE_REQUEST (Note 1, note 2)
- 2) MAP_UPDATE_GPRS_LOCATION_reg/ind
- 3) MAP_CANCEL_LOCATION_req/ind
- 4) MAP_CANCEL_LOCATION_rsp/cnf
- 5) MAP_ACTIVATE_TRACE_MODE_req/ind (Note 3)
- 6) MAP_ACTIVATE_TRACE_MODE_rsp/cnf (Note 3)
- 7) MAP_INSERT_SUBSCRIBER_DATA_req/ind
- 8) MAP_INSERT_SUBSCRIBER_DATA_rsp/cnf
- 9) MAP_UPDATE_GPRS_LOCATION_rsp/cnf
- 10) Gb_ATTACH_ACCEPT or RA_UPDATE_ACCEPT (Note 1)
- NOTE 1: For details of the procedure on the radio path, see 3GPP TS 24.008 [35]. The services shown in dotted lines indicate the trigger provided by the signalling on the radio path, and the signalling triggered on the radio path.
- NOTE 2: For security functions (authentication, ciphering, IMEI check) triggering refer to 3GPP TS 23.060 [104]. The MAP signalling invoked for these functions is described in clause 25 of the present document.
- NOTE 3: Services printed in *italics* are optional.
- NOTE 4: Refer to 3GPP TS 23.060 [104] for termination of the procedure and triggering of the signalling on the interface between the BSS and the SGSN.

Figure 19.1.1/4: Message flow for GPRS location updating (Gs interface not installed)



- 1) Gb_ATTACH_REQUEST or RA_UPDATE_REQUEST (Note 1, note 2)
- MAP_UPDATE_GPRS_LOCATION_req/ind 2)
- 3) MAP_CANCEL_LOCATION_req/ind
- 4) MAP_CANCEL_LOCATION_rsp/cnf
- 5)
- MAP_ACTIVATE_TRACE_MODE_req/ind (Note 3)
 MAP_ACTIVATE_TRACE_MODE_rsp/cnf (Note 3) 6)
- 7) MAP_INSERT_SUBSCRIBER_DATA_reg/ind
- 8) MAP_INSERT_SUBSCRIBER_DATA_rsp/cnf
- 9) MAP_UPDATE_GPRS_LOCATION_rsp/cnf
- Gs_LOCATION_UPDATE_REQUEST (Note 4) 10)
- MAP_UPDATE_LOCATION_req/ind (Note 5) 11)
- MAP_INSERT_SUBSCRIBER_DATA_req/ind 12)
- MAP_INSERT_SUBSCRIBER_DATA_rsp/cnf 13)
- 14) MAP_UPDATE_LOCATION_rsp/cnf
- Gs_LOCATION_UPDATE_ACCEPT (Note 4) 15)
- 16) Gb_ATTACH_ACCEPT or RA_UPDATE_ACCEPT (Note 1)
- 17) Gb_TMSI_REALLOCATION_COMPLETE (Note 1)
- Gs_TMSI_REALLOCATION_COMPLETE (Note 4) 18)
- NOTE 1: For details of the procedure on the radio path, see 3GPP TS 24.008 [35]. The services shown in dotted lines indicate the trigger provided by the signalling on the radio path, and the signalling triggered on the radio path.
- NOTE 2: For security functions (authentication, ciphering, IMEI check) triggering refer to 3GPP TS 23.060 [104]. MAP processes invoked for those procedures are described in subclause 25.5.
- NOTE 3: Services printed in *italics* are optional.

- NOTE 5: For details of the procedure on the path between the SGSN and the VLR, see 3GPP TS 29.018 [106]. The services shown in chain lines indicate the trigger provided by the signalling on the path between the SGSN and the VLR, and the signalling triggered on the path between the SGSN and the VLR.
- NOTE 4: Refer to 3GPP TS 23.060 [104] for termination of the procedure and triggering of the signalling on the interface between the BSS and the SGSN.
- NOTE 5: For simplicity, the Location Cancellation procedure towards the previous VLR and optional tracing activation towards the new VLR are not shown in this figure.

Figure 19.1.1/5: Message flow for GPRS location updating (Gs interface installed)

19.1.1.2 Procedures in the VLR

The MAP process in the VLR for location updating for a non-GPRS subscriber is shown in figure 19.1.1/6. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2; Check_Confirmation see subclause 25.2.2.

The MAP process in the VLR to retrieve the IMSI of a subscriber from the previous VLR (PVLR) is shown in figure 19.1.1/7. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2;
Check_Confirmation see subclause 25.2.2.

The process in the VLR for location updating for a GPRS subscriber when the Gs interface is installed is shown in figure 19.1.1/8.

The macro GPRS_Location_Update_Completion_VLR is shown in figure 19.1.1/9. The macro invokes a process not defined in this clause; the definition of this process can be found as follows:

Subscriber_Present_VLR see subclause 25.10.1.

The macro GPRS_Update_HLR_VLR is shown in figure 19.1.1/10. The macro invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2;
Check_Confirmation see subclause 25.2.2;
Insert_Subs_Data_VLR see subclause 25.7.1;
Activate Tracing VLR see subclause 25.9.4.

19.1.1.3 Procedure in the PVLR

The MAP process in the PVLR to handle a request for the IMSI of a subscriber from the new VLR is shown in figure 19.1.1/11. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Receive_Open_Ind see subclause 25.1.1.

19.1.1.4 Procedure in the SGSN

The MAP process in the SGSN for location updating for a GPRS subscriber is shown in figure 19.1.1/12. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2;
Check_Confirmation see subclause 25.2.2;
Insert Subs Data SGSN see subclause 25.7.2;

Activate_Tracing_SGSN see subclause 25.9.5.

Sheet 2: The procedure Check_User_Error_In_Serving_Network_Entity is specific to Super-Charger; it is specified in 3GPP TS 23.116 [110].

19.1.1.5 Procedures in the HLR

The MAP process in the HLR to handle a location updating request from a VLR is shown in figure 19.1.1/13. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Check_Confirmation see subclause 25.2.2.

The MAP process in the HLR to handle a location updating request from an SGSN is shown in figure 19.1.1/14. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Ind see subclause 25.1.1;
Check_Indication see subclause 25.2.1;
Check_Confirmation see subclause 25.2.2;
Control_Tracing_With_SGSN_HLR see subclause 25.9.7.

Sheet 2: The procedure Super_Charged_Cancel_Location_HLR is specific to Super-Charger; it is specified in 3GPP TS 23.116 [110]. If the HLR does not support the Super-Charger functionality, processing continues from the "No" exit of the test "Result=Pass?".

Sheet 2: The procedure Super_Charged_Location_Updating_HLR is specific to Super-Charger; it is specified in 3GPP TS 23.116 [110]. If the HLR does not support the Super-Charger functionality, processing continues from the "No" exit of the test "Result=Pass?".

The MAP process in the HLR to notify Short Message Service Centres that a subscriber is now reachable is shown in figure 19.1.1/15. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Alert Service Centre HLR see subclause 25.10.3.




Figure 19.1.1/6 (sheet 1 of 2): Process Update_Location_VLR




Figure 19.1.1/6 (sheet 2 of 2): Process Update_Location_VLR




Figure 19.1.1/7 (sheet 1 of 2): Process Send_Identification_VLR




Figure 19.1.1/7 (sheet 2 of 2): Process Send_Identification_VLR




Figure 19.1.1/8 (sheet 1 of 2): Process GPRS_Update_Location_Area_VLR




Figure 19.1.1/8 (sheet 2 of 2): Process GPRS_Update_Location_Area_VLR




Figure 19.1.1/9: Macro GPRS_Location_Update_Completion_VLR




Figure 19.1.1/10 (sheet 1 of 2): Macro GPRS_Update_HLR_VLR




Figure 19.1.1/10 (sheet 2 of 2): Macro GPRS_Update_HLR_VLR




Figure 19.1.1/11 (sheet 1 of 2): Process Send_Identification_PVLR




Figure 19.1.1/11 (sheet 2 of 2): Process Send_Identification_PVLR




Figure 19.1.1/12 (sheet 1 of 2): Process Update_GPRS_Location_SGSN




Figure 19.1.1/12 (sheet 2 of 2): Process Update_GPRS_Location_SGSN




Figure 19.1.1/13 (sheet 1 of 3): Process Update_Location_HLR




Figure 19.1.1/13 (sheet 2 of 3): Process Update_Location_HLR




Figure 19.1.1/13 (sheet 3 of 3): Process Update_Location_HLR




Figure 19.1.1/14 (sheet 1 of 2): Process Update_GPRS_Location_HLR




Figure 19.1.1/14 (sheet 2 of 2): Process Update_GPRS_Location_HLR




Figure 19.1.1/15: Process Subscriber_Present_HLR

19.1.2 Location Cancellation


19.1.2.1 General

Location cancellation is used to delete a subscriber record from the serving node (VLR or SGSN). The procedure is invoked:

- because the subscriber has registered with a new serving node, or
- because the HPLMN operator has decided to delete the subscriber record from the serving node, e.g. because the subscription has been withdrawn, or because roaming restrictions have been imposed. Location cancellation can be used to force location updating including updating of subscriber data in the serving node at the next subscriber access.

The message flow for location cancellation for a non-GPRS subscriber is shown in figure 19.1.2/1.


The message flow for location cancellation for a GPRS subscriber is shown in figure 19.1.2/2.



- 1) MAP_UPDATE_LOCATION_req/ind
- MAP_CANCEL_LOCATION_req/ind
- MAP_CANCEL_LOCATION_rsp/cnf

NOTE: The service shown in dotted lines indicates the trigger provided by other MAP signalling.

Figure 19.1.2/1: Message flow for Location Cancellation (non-GPRS)



- 1) MAP_UPDATE_GPRS_LOCATION_req/ind
- 2) MAP_CANCEL_LOCATION_req/ind
- 3) MAP_CANCEL_LOCATION_rsp/cnf

NOTE: The service shown in dotted lines indicates the trigger provided by other MAP signalling.

Figure 19.1.2/2: Message flow for Location Cancellation (GPRS)

19.1.2.2 Procedure in the HLR

The MAP process in the HLR to cancel the location information in a VLR is shown in figure 19.1.2/3. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2;

Check_Confirmation see subclause 25.2.2.

The MAP process in the HLR to cancel the location information in a VLR as an independent process invoked from another process is shown in figure 19.1.2/4.

The MAP process in the HLR to cancel the location information in an SGSN is shown in figure 19.1.2/5. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2;

Check_Confirmation see subclause 25.2.2.

The MAP process in the HLR to cancel the location information in an SGSN as an independent process invoked from another process is shown in figure 19.1.2/6.

19.1.2.3 Procedure in the VLR

The MAP process in the VLR to handle a location cancellation request is shown in figure 19.1.2/7. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Receive_Open_Ind see subclause 25.1.1.

19.1.2.4 Procedure in the SGSN

The MAP process in the SGSN to handle a location cancellation request is shown in figure 19.1.2/8. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Receive_Open_Ind see subclause 25.1.1.




Figure 19.1.2/3: Process Cancel_Location_HLR




Figure 19.1.2/4: Process Cancel_Location_Child_HLR




Figure 19.1.2/5: Process Cancel_GPRS_Location_HLR




Figure 19.1.2/6: Process Cancel_GPRS_Location_Child_HLR




Figure 19.1.2/7: Process Cancel_Location_VLR




Figure 19.1.2/8: Process Cancel_Location_SGSN

19.1.3 Void


19.1.4 MS Purging

19.1.4.1 General

O&M procedures in the VLR or SGSN can trigger MS purging either because of administrative action or because the MS has been inactive for an extended period. The O&M process in the VLR or in the SGSN should ensure that during the MS purging procedure any other attempt to access the MS record is blocked, to maintain consistency of data.


The message flow for a VLR to report MS purging to the HLR is shown in figure 19.1.4/1.

The message flow for an SGSN to report MS purging to the HLR is shown in figure 19.1.4/2.



- 1) MAP_PURGE_MS_req/ind
- 2) MAP_PURGE_MS_rsp/cnf

Figure 19.1.4/1: Message flow for MS purging (non-GPRS)



- 1) MAP_PURGE_MS_reg/ind
- 2) MAP_PURGE_MS_rsp/cnf

Figure 19.1.4/2: Message flow for MS purging (GPRS)

19.1.4.2 Procedure in the VLR

The MAP process in the VLR to report MS purging to the HLR is shown in figure 19.1.4/3. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2;
Check Confirmation see subclause 25.2.2.

19.1.4.3 Procedure in the SGSN

The MAP process in the SGSN to report MS purging to the HLR is shown in figure 19.1.4/4. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2;

Check_Confirmation see subclause 25.2.2.

Sheet 1: The procedure Purge_MS_In_Serving_Network_Entity is specific to Super-Charger; it is specified in 3GPP TS 23.116 [110]. If the HLR does not support the Super-Charger functionality, processing continues from the "No" exit of the test "Result=Pass?".

19.1.4.4 Procedure in the HLR

The MAP process in the HLR to handle a notification from a VLR or an SGSN that an MS record has been purged is shown in figure 19.1.4/5. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Ind see subclause 25.1.1;

Check_Indication see subclause 25.2.1.

If the notification was received from a VLR, the MAP process communicates with the location management application process specified in 3GPP TS 23.012 [23]; if the notification was received from an SGSN, the MAP process communicates with the GPRS mobility management application process specified in 3GPP TS 23.060 [104].




Figure 19.1.4/3: Process Purge_MS_VLR




Figure 19.1.4/4 (sheet 1 of 2): Process Purge_MS_SGSN




Figure 19.1.4/4 (sheet 2 of 2): Process Purge_MS_SGSN




Figure 19.1.4/5: Process Purge_MS_HLR

19.2 Handover procedures

19.2.1 General

In this subclause, the term "Inter-MSC handover" is used to denote handover or relocation between different MSCs.

The interfaces involved for Inter-MSC handover are shown in figure 19.2/1. There are two Inter-MSC handover procedures:

1) Basic Inter-MSC handover:

The call is handed over from the controlling MSC(MSC—A) to another MSC(MSC—B) (figure 19.2/1a).

Figure 19.2/2 shows the message flow for a successful handover from MSC-A to MSC—B, including a request for handover number allocation from MSC-B to VLR-B.


2) Subsequent Inter-MSC handover:

After the call has been handed over from MSC-A to MSC-B, a further handover either to MSC-A (figure 19.2/1a) or to a third MSC (MSC-B') (figure 19.2/1b) may be necessary in order to continue the call.

Figure 19.2/3 shows the message flow for a successful subsequent handover to MSC-B'. For a successful subsequent handover to MSC-A, the messages to and from MSC-B' and VLR-B' are omitted..




a) Basic handover procedure MSC-A to MSC-B and subsequent handover procedure MSC-B to MSC-A.



b) Subsequent handover procedure MSC-B to MSC-B'.


Figure 19.2/1: Interface structure for handover



- MAP_PREPARE_HANDOVER_req/ind 1)
- 2) 3) MAP_ALLOCATE_HANDOVER_NUMBER_req/ind
- MAP_SEND_HANDOVER_REPORT_reg/ind
- 4) MAP_PREPARE_HANDOVER_rsp/cnf
- 5) MAP_SEND_HANDOVER_REPORT_rsp/cnf (Note)
- 6) MAP_PROCESS_ACCESS_SIGNALLING_req/ind
- 7) MAP_SEND_END_SIGNAL_req/ind
- 8) MAP_FORWARD_ACCESS_SIGNALLING_req/ind
- 9) MAP_PROCESS_ACCESS_SIGNALLING_req/ind
- 10) MAP_SEND_END_SIGNAL_rsp/cnf

NOTE: This can be sent at any time after the connection between MSC-A and MSC-B is established.

Figure 19.2/2: Example of a successful basic handover procedure to MSC-B



- 1) MAP_PREPARE_HANDOVER_req/ind
- 2) MAP_ALLOCATE_HANDOVER_NUMBER_reg/ind
- 3) MAP_SEND_HANDOVER_REPORT_req/ind
- 4) MAP_PREPARE_HANDOVER_rsp/cnf
- 5) MAP_SEND_HANDOVER_REPORT_rsp/cnf (Note 1)
- 6) MAP_PROCESS_ACCESS_SIGNALLING_req/ind
- 7) MAP_SEND_END_SIGNAL_req/ind
- 8) MAP_PREPARE_SUBSEQUENT_HANDOVER_req/ind
- 9) MAP_PREPARE_HANDOVER_req/ind
- 10) MAP_ALLOCATE_HANDOVER_NUMBER_req/ind
- 11) MAP_SEND_HANDOVER_REPORT_req/ind
- 12) MAP_PREPARE_HANDOVER_rsp/cnf
- 13) MAP_SEND_HANDOVER_REPORT_rsp/cnf (Note 2)
- 14) MAP_PREPARE_SUBSEQUENT_HANDOVER_rsp/cnf
- 15) MAP_PROCESS_ACCESS_SIGNALLING_req/ind
- 16) MAP_SEND_END_SIGNAL_req/ind
- 17) MAP_SEND_END_SIGNAL_rsp/cnf (Note 3)
- NOTE 1: This can be sent at any time after the connection between MSC-A and MSC-B is established.
- NOTE 2: This can be sent at any time after the connection between MSC-A and MSC-B' is established.
- NOTE 3: At this stage, the subsequent handover is complete. Any further interworking between MSC-A and MSC-B is the same as the interworking between MSC-A and MSC-B after basic handover

Figure 19.2/3: Example of a successful subsequent handover to a third MSC

The MAP signalling procedures for inter-MSC handover support the allocation of a handover number or one or more relocation numbers and the transfer of encapsulated BSSAP or RANAP messages.

The minimum application context version for the MAP handover application context shall be:

- version 3 for inter-MSC UTRAN to UTRAN handover;
- version 3 for inter-MSC intersystem handover from GSM BSS to UTRAN;
- version 2 for inter-MSC intersystem handover from UTRAN to GSM BSS.

NOTE: If the MAP handover application context version 2 is used, subsequent handover to UTRAN is not possible.

The minimum application context version for the MAP handover application context should be version 2 for inter-MSC handover from GSM BSS to GSM BSS.

NOTE: If the MAP handover application context version 2 or lower is used, subsequent handover to UTRAN is not possible.

The BSSAP or RANAP messages encapsulated in MAP messages are processed by the Handover Control Application in each MSC. The information in the encapsulated BSSAP or RANAP messages is passed from the Handover Control Application to the MAP process at the sending end; the notation used in the SDL diagrams for the MAP processes is "HO_CA_MESSAGE_ind(Message transfer)". The information in the encapsulated BSSAP or RANAP messages is passed from the MAP process to the Handover Control Application at the sending end; the notation used in the SDL diagrams for the MAP processes is "HO_CA_MESSAGE_req(Message transfer)".

For details of the interworking between the A-interface and MAP procedures or the Iu-interface and MAP procedures, see 3GPP TS 23.009 [21] and 3GPP TS 29.010 [58].

19.2.2 Procedure in MSC-A

This subclause describes the inter-MSC handover procedure in MSC-A; it covers basic inter-MSC handover to another MSC (MSC-B) and subsequent inter-MSC handover to a third MSC (MSC-B') or back to the controlling MSC (MSC-A).

The MAP process in MSC-A to handle inter-MSC handover is shown in figure 19.2/4. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2;
Check_Indication see subclause 25.2.1.
Check Confirmation see subclause 25.2.2.

Communication between the MAP handover process and the Handover Control application is represented by the HO_CA_MESSAGE service. For a detailed description of the interworking between the Handover Control applications in different MSCs for the inter-MSC handover procedure, see 3GPP TS 23.009 [21].

19.2.2.1 Basic handover

The handling in MSC-A for basic inter-MSC handover is shown in sheets 1 to 6 of figure 19.2/4.

Sheet 1: The MAP_PREPARE_HANDOVER request may contain:

- an indication that handover number allocation is not required;
- the target Cell ID, for compatibility for handover to GSM;
- the target RNC ID, for SRNS relocation or inter-system handover from GSM to UMTS;
- the IMSI;
- UMTS encryption information and UMTS integrity protection information, which are necessary for inter-system handover from GSM to UMTS;

- GSM radio resource information (channel type).

The conditions for the presence of these parameters and the processing in MSC-B (3G_MSC-B) are described in detail in 3GPP TS 29.010 [58] and 3GPP TS 23.009 [21].

Sheet 2: The MAP_PREPARE_HANDOVER confirmation contains one of:

- no handover number, if the MAP_PREPARE_HANDOVER request included an indication that handover number allocation is not required;
- a handover number;
- one or more relocation numbers.

Sheet 2: The MAP_PREPARE_HANDOVER confirmation contains BSSAP or RANAP signalling information, which is passed to the Handover Control application in MSC-A.

Sheet 2: If the MAP_PREPARE_HANDOVER confirmation contains an indication that MSC-B does not support multiple bearers, the Handover Control application in MSC-A may request handover of one bearer to the same cell in MSC-B.

Sheet 5: If the original MAP_PREPARE_HANDOVER request included a parameter indicating that handover number allocation is not required, the Handover Control application in MSC-A may request a handover number (or one or more relocation numbers); this triggers a further MAP_PREPARE_HANDOVER request towards MSC-B

19.2.2.2 Handling of access signalling

The Handover Control application in MSC-A may forward access signalling to any of the MS, RNS-B or BSS-B using the MAP_FORWARD_ACCESS_SIGNALLING service; any of the MS, RNS-B or BSS-B may forward access signalling to the Handover Control application in MSC-A using the MAP_PROCESS_ACCESS_SIGNALLING service. These are non-confirmed services.

19.2.2.3 Subsequent handover

The handling in MSC-A for subsequent inter-MSC handover is shown in sheets 7 & 8 of figure 19.2/4. If the Handover Control Application determines that the call is to be handed over to a third MSC (MSC-B') it triggers another instance of the MAP process to handle the basic handover to MSC-B', and reports the result of the subsequent handover to the instance of the MAP process which handles the dialogue with MSC-B.

Sheet 8: While the MAP process in MSC-A is waiting for the completion of subsequent handover, it relays access signalling between the Handover Control application and the MS, RNS-B or BSS-B as described in subclause 19.2.2.2.

19.2.3 Procedure in MSC-B

This subclause describes the handover or relocation procedure in MSC-B; it covers basic handover or relocation from the controlling MSC (MSC-A) and subsequent handover or relocation.

The MAP process in MSC-B to handle handover or relocation is shown in figure 19.2/5. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Ind see subclause 25.1.1;
Receive_Open_Cnf see subclause 25.1.2;
Check_Indication see subclause 25.2.1.
Check_Confirmation see subclause 25.2.2.

Communication between the MAP handover process and the Handover Control application is represented by the HO_CA_MESSAGE service. For a detailed description of the interworking between the Handover Control applications in different MSCs for the inter-MSC handover procedure, see 3GPP TS 23.009 [21].

The ordering of allocation of handover number and radio resources shown in the SDL diagrams is not mandatory.

19.2.3.1 Basic handover

The handling in MSC-B for basic inter-MSC handover is shown in sheets 1 to 7 of figure 19.2/5.

Sheet 2: If the MAP_PREPARE_HANDOVER indication included a parameter requesting multiple bearers but MSC-B does not support multiple bearers, MSC-B sends a MAP_PREPARE_HANDOVER response indicating that multiple bearers are not supported, and waits for a possible MAP_PREPARE_HANDOVER indication requesting handover of a single bearer.

Sheet 6: If the original MAP_PREPARE_HANDOVER indication included a parameter indicating that handover number allocation is not required, MSC-A may send a further MAP_PREPARE_HANDOVER request to request the allocation of a handover number (or one or more relocation numbers).

19.2.3.2 Handling of access signalling

The Handover Control application in MSC-A may forward access signalling to any of the MS, RNS-B or BSS-B using the MAP_FORWARD_ACCESS_SIGNALLING service; any of the MS, RNS-B or BSS-B may forward access signalling to the Handover Control application in MSC-A using the MAP_PROCESS_ACCESS_SIGNALLING service. These are non-confirmed services. Signals to or from any of the MS, RNS-B or BSS-B are routed through the Handover Control application in MSC-B.

19.2.3.3 Subsequent handover

The handling in MSC-B for subsequent inter-MSC handover is shown in sheet 8 of figure 19.2/5.

While the MAP process in MSC-B is waiting for the completion of subsequent handover, it relays access signalling between MSC-A and the MS, RNS-B or BSS-B through the Handover Control application as described in subclause 19.2.3.2.

19.2.4 Macro Receive_Error_From_HO_CA

This macro is used by the handover processes in MSC-A and MSC-B to receive errors from the Handover Control Application at any state of a handover process.

19.2.5 Procedure in VLR-B

The process in VLR-B to handle a request for a handover number is shown in figure 19.2/7. The process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Ind see subclause 25.1.1;
Check Indication see subclause 25.2.1.




Figure 19.2/4 (sheet 1 of 8): Process HO_MSC_A




Figure 19.2/4 (sheet 2 of 8): Process HO_MSC_A




Figure 19.2/4 (sheet 3 of 8): Process HO_MSC_A




Figure 19.2/4 (sheet 4 of 8): Process HO_MSC_A




Figure 19.2/4 (sheet 5 of 8): Process HO_MSC_A




Figure 19.2/4 (sheet 6 of 8): Process HO_MSC_A




Figure 19.2/4 (sheet 7 of 8): Process HO_MSC_A




Figure 19.2/4 (sheet 8 of 8): Process HO_MSC_A




Figure 19.2/5 (sheet 1 of 8): Process HO_MSC_B




Figure 19.2/5 (sheet 2 of 8): Process HO_MSC_B




Figure 19.2/5 (sheet 3 of 8): Process HO_MSC_B




Figure 19.2/5 (sheet 4 of 8): Process HO_MSC_B




Figure 19.2/5 (sheet 5 of 8): Process HO_MSC_B




Figure 19.2/5 (sheet 6 of 8): Process HO_MSC_B




Figure 19.2/5 (sheet 7 of 8): Process HO_MSC_B




Figure 19.2/5 (sheet 8 of 8): Process HO_MSC_B




Figure 19.2/6: Macro Receive_error_from_HO_CA




Figure 19.2/7: Process HO_VLR_B

19.3 Fault recovery procedures


When a location register has restarted after a fault, the fault recovery procedures ensure that the subscriber data in the VLR or in the SGSN become consistent with the subscriber data that are stored in the HLR for the MS concerned and that the location information in the HLR, the VLR and the SGSN reflect accurately the current location of the MS.

The stage 2 specification of fault recovery procedures in location registers is 3GPP TS 23.007 [19].

19.3.1 VLR fault recovery procedures

19.3.1.1 General

Restoration of an IMSI record in a VLR can be triggered by a location registration request from the MS or by a request from the HLR for a roaming number to route a mobile terminated call to the MS. If the restoration is triggered by a location registration request from the MS, the VLR performs the location updating procedure described in 3GPP TS 23.012 [23] and subclause 19.1.1 of the present document. If the restoration is triggered by a request for a roaming number, the VLR provides the roaming number and triggers an independent dialogue to restore the subscriber data as described in 3GPP TS 23.018 [97]. The message flow for data restoration triggered by a request for a roaming number is shown in figure 19.3.1/1.



- 1) MAP_PROVIDE_ROAMING_NUMBER_reg/ind
- MAP PROVIDE ROAMING NUMBER rsp/cnf
- 3) MAP_SEND_AUTHENTICATION_INFO_req/ind (Note 1, note 2)
- 4) MAP_SEND_AUTHENTICATION_INFO_rsp/cnf (Note 1, note 2)
- 5) MAP_RESTORE_DATA_req/ind
- 6) MAP_ACTIVATE_TRACE_MODE_reg/ind (Note 1, note 3)
- 7) MAP_ACTIVATE_TRACE_MODE_rsp/cnf (Note 1, note 3)
- 8) MAP_INSERT_SUBSCRIBER_DATA_req/ind
- 9) MAP_INSERT_SUBSCRIBER_DATA_rsp/cnf
- 10) MAP_RESTORE_DATA_rsp/cnf

NOTE 1: Services printed in *italics* are optional.

NOTE 2: If authentication is required.

NOTE 3: If subscriber tracing is active in the HLR.

Figure 19.3/1: Message flow for VLR restoration at mobile terminated call set-up

19.3.1.2 Procedure in the VLR

The procedure in the VLR to handle a dialogue for subscriber data restoration is defined in subclause 21.2.6 of the present document.

19.3.1.3 Procedure in the HLR

The MAP process in the HLR to handle a request for data restoration in the VLR is shown in figure 19.3.1/2. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Check_Indication see subclause 25.2.1;

Control_Tracing_With_VLR_HLR see subclause 25.9.6.




Figure 19.3.1/2: Process Restore_Data_HLR

19.3.2 HLR fault recovery procedures

19.3.2.1 General


For the HLR, periodic back-up of data to non-volatile memory is mandatory.

Data that have been changed after the last back-up and before the restart of the HLR cannot be recovered by reload from the non-volatile memory. Therefore, a restoration procedure is triggered for each IMSI record that has been affected by the HLR fault at the first authenticated radio contact with the MS concerned.

As an implementation option, a notification can be forwarded to the MS to alert the subscriber to check the parameters for supplementary services that allow subscriber controlled input (MAP_FORWARD_CHECK_SS_INDICATION service). If the VLR receives this notification from the HLR it shall forward the notification to the MS. If the Gsinterface is implemented the VLR shall not forward this notification.

The message flow for HLR restoration for a non-GPRS subscriber is shown in figure 19.3.2/1.


The message flow for HLR restoration for a GPRS subscriber is shown in figure 19.3.2/2.



- MAP_RESET_reg/ind 1)
- 2) MAP_PROCESS_ACCESS_REQUEST_req/ind
- 3) MAP_UPDATE_LOCATION_req/ind
- 4)
- MAP_ACTIVATE_TRACE_MODE_req/ind (Note 1, Note 2)
 MAP_ACTIVATE_TRACE_MODE_rsp/cnf (Note 1, Note 2) 5)
- 6) MAP_INSERT_SUBSCRIBER_DATA_req/ind
- MAP_INSERT_SUBSCRIBER_DATA_rsp/cnf 7)
- MAP_UPDATE_LOCATION_rsp/cnf 8)
- 9) MAP_FORWARD_CHECK_SS_INDICATION_req/ind (Note 1)
- MAP_FORWARD_CHECK_SS_INDICATION_reg/ind (Note 1) 10)

NOTE 1: Services printed in *italics* are optional. NOTE 2: If subscriber tracing is active in the HLR.

Figure 19.3.2/1: Message flow for HLR restoration (non-GPRS)



- MAP_RESET_reg/ind 1)
- MAP_UPDATE_GPRS_LOCATION_req/ind 2)
- 3)
- MAP_ACTIVATE_TRACE_MODE_req/ind (Note 1, Note 2)
 MAP_ACTIVATE_TRACE_MODE_rsp/cnf (Note 1, Note 2) 4)
- MAP_INSERT_SUBSCRIBER_DATA_req/ind 5)
- MAP_INSERT_SUBSCRIBER_DATA_rsp/cnf 6)
- MAP UPDATE GPRS LOCATION rsp/cnf

NOTE 1: Services printed in *italics* are optional. NOTE 2: If subscriber tracing is active in the HLR.

Figure 19.3.2/2: Message flow for HLR restoration (GPRS)

19.3.2.2 Procedure in the HLR

The MAP process in the HLR to notify the relevant serving nodes that the HLR has restarted is shown in figure 19.3.2/3.

The SGSN address list includes one instance of the address of each SGSN in which (according to the HLR data retrieved from the non-volatile memory) there is at least one subscriber registered who is affected by the HLR restart.

The VLR address list includes one instance of the address of each VLR in which (according to the HLR data retrieved from the non-volatile memory) there is at least one subscriber registered who is affected by the HLR restart.

The MAP process in the HLR to notify a VLR that the HLR has restarted is shown in figure 19.3.2/4. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Receive Open Cnf see subclause 25.1.2.

The MAP process in the HLR to notify an SGSN that the HLR has restarted is shown in figure 19.3.2/5. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

see subclause 25.1.2. Receive_Open_Cnf

Procedure in the VLR 19.3.2.3

The MAP process in the VLR to handle a notification that an HLR has restarted is shown in figure 19.3.2/6. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Receive_Open_Ind see subclause 25.1.1. The VLR uses the HLR number or the HLR identity list included in the MAP_RESET indication to identify the IMSI records which are affected by the HLR restart.

19.3.2.4 Procedure in the SGSN

The MAP process in the SGSN to handle a notification that an HLR has restarted is shown in figure 19.3.2/6. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Receive_Open_Ind

see subclause 25.1.1.

The SGSN uses the HLR number or the HLR identity list included in the MAP_RESET indication to identify the IMSI records which are affected by the HLR restart.




Figure 19.3.2/3: Process Restart_HLR




Figure 19.3.2/4: Process Send_Reset_To_VLR_HLR




Figure 19.3.2/5: Process Send_Reset_To_SGSN_HLR




Figure 19.3.2/6: Process Receive_Reset_VLR





Figure 19.3.2/7: Process Receive_Reset_SGSN

19.4 Mobility Management event notification procedure

19.4.1 General

The Mobility Management event notification procedure is used to notify a gsmSCF about the successful completion of a Mobility Management event.

The message flow for Mobility Management event notification is shown in figure 19.4/1.



- MAP_REPORT_MM_EVENT_reg/ind
- 2) MAP_REPORT_MM_EVENT_rsp/cnf

Figure 19.5/1: Message flow for Mobility Management event notification

19.4.2 Procedure in the VLR or SGSN

The MAP process in the VLR or the SGSN to report a Mobility Management event to the gsmSCF is shown in figure 19.4/2. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2; Check_Confirmation: see subclause 25.2.2.

19.4.3 Procedure in the gsmSCF

The MAP process in the gsmSCF to handle the report of a Mobility Management event is shown in figure 19.4/3. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Receive_Open_Ind see subclause 25.1.1;




Figure 19.4/2: Process Notify_MM_Event_VLR_Or_SGSN




Figure 19.4/3: Process Notify_MM_Event_gsmSCF

19.4 HLR Insert Subscriber Data macros

19.5.1 Macro Insert_Subs_Data_Framed_HLR

This macro is used to transfer subscriber data to the VLR as part of an existing dialogue for location updating or data restoration. The macro invokes a macro and a process not defined in this clause; the definitions of the macro and the process can be found as follows:

Wait_For_Insert_Subs_Data_Cnf see subclause 25.7.5;
Send Insert Subs Data HLR: see subclause 25.7.7.

The HLR may wait for each MAP_INSERT_SUBSCRIBER_DATA request to be acknowledged before it sends the next request, or it may handle the requests and the confirmations in parallel.

If the VLR has indicated that it does not support a service or feature (e.g. Closed User Group or Advice Of Charge Charging Level) which the HLR operator regards as essential for the subscriber, the macro Wait_for_Insert_Subs_Data_Cnf takes the Replace_Service exit; the HLR sets the Roaming Restriction Due To Unsupported Feature flag to roaming restricted and sends Roaming Restriction Due To Unsupported Feature in a subsequent MAP_INSERT_SUBSCRIBER_DATA request.

If the HLR operator does not regard the unsupported service or feature as essential for the subscriber but the macro Wait_for_Insert_Subs_Data_Cnf takes the Replace_Service exit, the HLR sends the data for a replacement service in a subsequent MAP_INSERT_SUBSCRIBER_DATA request.

If subscriber data for CAMEL Phase 2 or later services are sent to a VLR which does not support the appropriate phase of CAMEL, the service behaviour may be unpredictable or incorrect. The HLR should therefore ensure that at the conclusion of a stand alone Insert Subscriber data procedure the data in the VLR do not require a capability that the VLR does not have. Possible mechanisms to ensure this are described in 3GPP TS 23.078 [98].

The HLR should send a Forwarded-to number which is not in E.164 international format to the VLR only when the HLR has ascertained that the VLR supports CAMEL Phase 2 or later. Thus, the ISD message containing the Forwarded-to number which is not in E.164 international format shall be sent to the VLR only if the HLR previously received confirmation from the VLR at Location Update that CAMEL Phase 2 or later is supported.

19.5.2 Macro Insert_GPRS_Subs_Data_Framed_HLR

This macro is used to transfer subscriber data to the SGSN as part of an existing dialogue for location updating. The macro invokes a macro and a process not defined in this clause; the definitions of the macro and the process can be found as follows:

Wait_For_Insert_GPRS_Subs_Data_Cnf see subclause 25.7.5; Send_Insert_Subs_Data_HLR: see subclause 25.7.7.

The HLR may wait for each MAP_INSERT_SUBSCRIBER_DATA request to be acknowledged before it sends the next request, or it may handle the requests and the confirmations in parallel.

If the SGSN has indicated that it does not support a service or feature which the HLR operator regards as essential for the subscriber, the macro Wait_for_Insert_GPRS_Subs_Data_Cnf takes the Replace_Service exit; the HLR sets the Roaming Restricted In SGSN Due To Unsupported Feature flag to roaming restricted and sends Roaming Restricted In SGSN Due To Unsupported Feature in a subsequent MAP_INSERT_SUBSCRIBER_DATA request.

If the HLR operator does not regard the unsupported service or feature as essential for the subscriber but the macro Wait_for_Insert_GPRS_Subs_Data_Cnf takes the Replace_Service exit, the HLR sends the data for a replacement service in a subsequent MAP_INSERT_SUBSCRIBER_DATA request.




Figure 19.5/1: Macro Insert_Subs_Data_Framed_HLR




Figure 19.5/2: Macro Insert_GPRS_Subs_Data_Framed_HLR

20 Operation and maintenance procedures

20.1 General

The Operation and Maintenance procedures are used to support operation and maintenance of the network.

The following procedures exist for operation and maintenance purposes:

- i) Tracing procedures;
- ii) Subscriber Data Management procedures;
- iii) Subscriber Identity procedure.

The following application contexts refer to complex MAP Users consisting of several processes:

- subscriberDataManagementContext;
- tracingContext.

Each of these two application contexts needs a co-ordinating process in the VLR or in the SGSN as described in the following subclauses.

20.1.1 Tracing Co-ordinator for the VLR

The Tracing Co-ordinator process in the VLR is shown the figure 20.1/1. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Receive_Open_Ind

see subclause 25.1.1.

20.1.2 Tracing Co-ordinator for the SGSN

The Tracing Co-ordinator process in the SGSN is shown in figure 20.1/2. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Receive_Open_Ind

see subclause 25.1.1.

20.1.3 Subscriber Data Management Co-ordinator for the VLR

The Subscriber Data Management Co-ordinator process in the VLR is shown in figure 20.1/3. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Receive_Open_Ind

see subclause 25.1.1.

20.1.4 Subscriber Data Management Co-ordinator for the SGSN

The Subscriber Data Management Co-ordinator process in the SGSN is shown in figure 20.1/4. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Receive_Open_Ind

see subclause 25.1.1.




Figure 20.1/1: Process Co_Tracing_VLR




Figure 20.1/2: Process Co_Tracing_SGSN




Figure 20.1/3: Process Co_SDM_VLR





Figure 20.1/4: Process Co_SDM_SGSN

20.2 Tracing procedures

Three types of tracing procedures exist:


- i) Subscriber tracing management procedures;
- ii) Subscriber tracing procedures;
- iii) Event tracing procedures.

The subscriber tracing management procedures are used to manage the status and the type of the tracing. The subscriber tracing activation procedure is used at location updating or data restoration when the trace mode of a subscriber is set active in the HLR or, as a stand alone procedure, when the subscriber is already registered and the trace mode becomes active in the HLR. The procedures to activate tracing in the VLR are shown in figures 20.2/1 and 20.2/3. The procedures to activate tracing in the SGSN are shown in figures 20.2/2 and 20.2/4.




- 1) Subscriber Tracing Activation
- 2)
- MAP_ACTIVATE_TRACE_MODE_req/ind MAP_ACTIVATE_TRACE_MODE_rsp/cnf
- Subscriber Tracing Activation Accepted

Figure 20.2/1: Stand-alone subscriber tracing activation procedure for non-GPRS




- **Subscriber Tracing Activation**
- 2) MAP_ACTIVATE_TRACE_MODE_reg/ind
- 3) MAP_ACTIVATE_TRACE_MODE_rsp/cnf
- 4) Subscriber Tracing Activation Accepted

Figure 20.2/2: Stand-alone subscriber tracing activation procedure for GPRS



- MAP_UPDATE_LOCATION or MAP_RESTORE_DATA_req/ind 1)
- MAP_ACTIVATE_TRACE_MODE_req/ind MAP_ACTIVATE_TRACE_MODE_rsp/cnf 2)
- 3)
- MAP_UPDATE_LOCATION_rsp/cnf or MAP_RESTORE_DATA_rsp/cnf

Figure 20.2/3: Subscriber tracing activation procedure at location updating or data restoration




- MAP_UPDATE_GPRS_LOCATION_req/ind 1)
- 2)
- MAP_ACTIVATE_TRACE_MODE_req/ind MAP_ACTIVATE_TRACE_MODE_rsp/cnf 3)
- MAP_UPDATE_GPRS_LOCATION_rsp/cnf

Figure 20.2/4: Subscriber tracing activation procedure at GPRS location updating


The MAP_ACTIVATE_TRACE_MODE request includes the IMSI, trace reference, trace type and identity of the OMC.

The subscriber tracing deactivation procedure is used when tracing of a subscriber in the VLR or in the SGSN is no longer required. The procedures are shown in figures 20.2/5 and 20.2/6.



- 1) Subscriber Tracing Deactivation
- 2) MAP_DEACTIVATE_TRACE_MODE_req/ind
- 3) MAP_DEACTIVATE_TRACE_MODE_rsp/cnf
- 4) Subscriber Tracing Deactivation Accepted


Figure 20.2/5: Subscriber tracing deactivation procedure for non-GPRS



- 1) Subscriber Tracing Deactivation
- 2) MAP_DEACTIVATE_TRACE_MODE_req/ind
- 3) MAP_DEACTIVATE_TRACE_MODE_rsp/cnf
- 4) Subscriber Tracing Deactivation Accepted

Figure 20.2/6: Subscriber tracing deactivation procedure for GPRS

The subscriber tracing procedures are used when the VLR detects any subscriber related activity for which the trace mode is activated, e.g. the VLR receives a MAP_PROCESS_ACCESS_REQUEST indication. The procedure is shown in figure 20.2/7.



- 1) MAP_PROCESS_ACCESS_REQUEST_req/ind
- 2) MAP_TRACE_SUBSCRIBER_ACTIVITY_req/ind
- Subscriber tracing information

Figure 20.2/7: Subscriber tracing procedure in the serving MSC

20.2.1 Subscriber tracing activation procedure

20.2.1.1 Procedures in the HLR

A subscriber tracing activation request from the OMC starts the appropriate process in the HLR:

ATM_With_VLR_HLR if tracing is required in the MSC/VLR, ATM_With_SGSN_HLR if tracing is required in the SGSN.

The process in the HLR to activate tracing in the VLR is shown in figure 20.2/8. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2;
Check_Confirmation see subclause 25.2.2.

Sheet 1: If the Repeat attempt counter has reached its limit, the test "Repeat Attempt" takes the "No" exit; otherwise the test takes the "Yes" exit. The number of repeat attempts and the interval between successive repeat attempts are operator options.

The process in the HLR to activate tracing in the SGSN is shown in figure 20.2/9. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2;
Check Confirmation see subclause 25.2.2.

Sheet 1: If the Repeat attempt counter has reached its limit, the test "Repeat Attempt" takes the "No" exit; otherwise the test takes the "Yes" exit. The number of repeat attempts and the interval between successive repeat attempts are operator options.

20.2.1.2 Procedure in the VLR

The process in the VLR to activate tracing in a stand-alone dialogue is shown in figure 20.2/10. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Check_Indication see subclause 25.2.1.

20.2.1.3 Procedure in the SGSN

The process in the SGSN to activate tracing in a stand-alone dialogue is shown in figure 20.2/11. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Check_Indication see subclause 25.2.1.

20.2.2 Subscriber tracing deactivation procedure

20.2.2.1 Procedures in the HLR

A subscriber tracing deactivation request from the OMC starts the appropriate process in the HLR: DTM_HLR_With_VLR if tracing is no longer required in the MSC/VLR, DTM_HLR_With_SGSN if tracing is no longer required in the SGSN.

The process in the HLR to deactivate tracing in the VLR is shown in figure 20.2/12. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2; Check_Confirmation see subclause 25.2.2.

Sheet 1: If the Repeat attempt counter has reached its limit, the test "Repeat Attempt" takes the "No" exit; otherwise the test takes the "Yes" exit. The number of repeat attempts and the interval between successive repeat attempts are operator options.

The process in the HLR to deactivate tracing in the SGSN is shown in figure 20.2/13. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2; Check_Confirmation see subclause 25.2.2.

Sheet 1: If the Repeat attempt counter has reached its limit, the test "Repeat Attempt" takes the "No" exit; otherwise the test takes the "Yes" exit. The number of repeat attempts and the interval between successive repeat attempts are operator options.

20.2.2.2 Procedure in the VLR

The process in the VLR to deactivate tracing is shown in figure 20.2/14. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Check_Indication see subclause 25.2.1.

20.2.2.3 Procedure in the SGSN

The process in the SGSN to deactivate tracing is shown in figure 20.2/15. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Check_Indication see subclause 25.2.1.




Figure 20.2/8 (sheet 1 of 2): Process ATM_With_VLR_HLR




Figure 20.2/8 (sheet 2 of 2): Process ATM_With_VLR_HLR




Figure 20.2/9 (sheet 1 of 2): Process ATM_with_SGSN_HLR




Figure 20.2/9 (sheet 2 of 2): Process ATM_with_SGSN_HLR




Figure 20.2/10: Process ATM_Standalone_VLR




Figure 20.2/11: Process ATM_Standalone_SGSN




Figure 20.2/12 (sheet 1 of 2): Process DTM_with_VLR_HLR




Figure 20.2/12 (sheet 2 of 2): Process DTM_with_VLR_HLR




Figure 20.2/13 (sheet 1 of 2): Process DTM_with_SGSN_HLR




Figure 20.2/13 (sheet 2 of 2): Process DTM_with_SGSN_HLR




Figure 20.2/14: Process DTM_Standalone_VLR





Figure 20.2/15: Process DTM_Standalone_SGSN

20.3 Subscriber data management procedures

Two types of subscriber data management procedures exist:

- 1) Subscriber Deletion;
- 2) Subscriber Data Modification.


The subscriber deletion and subscriber data modification procedures are initiated by the OMC (see figures 20.3/1, 20.3/2, 20.3/3 and 20.3/4).



- 1) Delete Subscriber
- 2) MAP_CANCEL_LOCATION_req/ind
- MAP_CANCEL_LOCATION_rsp/cnf
- 4) Subscriber Deleted

Figure 20.3/1: Subscriber deletion procedure for non-GPRS


In the subscriber deletion procedure for a non-GPRS subscriber the subscriber data are removed from the VLR and the HLR. The HLR uses the MAP_CANCEL_LOCATION service.



- 1) Delete GPRS Subscriber
- 2) MAP_CANCEL_LOCATION_req/ind
- 3) MAP_CANCEL_LOCATION_rsp/cnf
- 4) GPRS Subscriber Deleted

Figure 20.3/2: Subscriber deletion procedure for GPRS

In the subscriber deletion procedure for a GPRS subscriber the subscriber data are removed from the SGSN and the HLR. The HLR uses the MAP CANCEL LOCATION service.



- 1) Modify Subscriber Data
- MAP_CANCEL_LOCATION_req/ind, MAP_INSERT_SUBSCRIBER_DATA_req/ind or MAP_DELETE_SUBSCRIBER_DATA_req/ind
- 3) MAP_CANCEL_LOCATION_rsp/cnf, MAP_INSERT_SUBSCRIBER_DATA_rsp/cnf or MAP_DELETE_SUBSCRIBER_DATA_rsp/cnf
- 4) Subscriber Data Modified

Figure 20.3/3: Subscriber data modification procedure for non-GPRS

- 1) Modify Subscriber Data
- 2) MAP_CANCEL_LOCATION_req/ind, MAP_INSERT_SUBSCRIBER_DATA_req/ind or MAP_DELETE_SUBSCRIBER_DATA_req/ind
- MAP_CANCEL_LOCATION_rsp/cnf, MAP_INSERT_SUBSCRIBER_DATA_rsp/cnf or MAP_DELETE_SUBSCRIBER_DATA_rsp/cnf
- 4) Subscriber Data Modified

Figure 20.3/4: Subscriber data modification procedure for GPRS

In the subscriber data modification procedure the subscriber data are modified in the HLR and when necessary also in the VLR or in the SGSN. The HLR initiates one of the MAP_INSERT_SUBSCRIBER_DATA, MAP_DELETE_SUBSCRIBER_DATA or MAP_CANCEL_LOCATION services depending on the modified data.

20.3.1 Subscriber deletion procedure

20.3.1.1 Procedure in the HLR

The subscriber deletion process in the HLR is shown in figure 20.3/5. The MAP process invokes processes not defined in this clause; the definitions of these processes can be found as follows:

Cancel_GPRS_Location_Child_HLR see subclause 19.1.2.2;
Cancel Location Child HLR see subclause 19.1.2.2.

20.3.1.2 Procedure in the VLR

The subscriber deletion procedure in the VLR is described in subclause 19.1.2.3 of the present document.

20.3.1.3 Procedure in the SGSN

The subscriber deletion procedure in the SGSN is described in subclause 19.1. 2.4 of the present document.

20.3.2 Subscriber data modification procedure

20.3.2.1 Procedure in the HLR

The OMC can modify the subscriber data in several different ways. The modifications can be categorised in the following groups:

- 1) data shall be modified in the HLR; no effect in the VLR;
- 2) data shall be modified in both the HLR and the VLR;
- 3) withdrawal of a basic service or a supplementary service requiring change to VLR data;
- 4) modification affects the roaming permission for the subscriber and the subscriber record shall be removed from the VLR data base;
- 5) withdrawal of non-GPRS Subscription caused by a change of Network Access Mode;
- 6) data shall be modified in the HLR; no effect in the SGSN;
- 7) data shall be modified in both the HLR and the SGSN;
- withdrawal of GPRS subscription data or a basic service or a supplementary service requiring change to SGSN data;
- modification affects the roaming permission for the subscriber and the subscriber record shall be removed from the SGSN data base;
- 10) withdrawal of GPRS Subscription caused by a change of Network Access Mode;
- 11) authentication algorithm or authentication key of the subscriber is modified.

In cases 2 and 7 the HLR uses the MAP_INSERT_SUBSCRIBER_DATA service.

In cases 3 and 8 the HLR uses the MAP_DELETE_SUBSCRIBER_DATA service.

In cases 4, 5, 9, 10 and 11 the HLR uses the MAP_CANCEL_LOCATION service.

If the deletion of subscriber data fails, the HLR may repeat the request; the number of repeat attempts and the time in between are HLR operator options, depending on the error returned by the VLR or the SGSN.

The subscriber data modification process in the HLR is shown in figure 20.3/6. The MAP process invokes processes not defined in this clause; the definitions of these processes can be found as follows:

Insert_Subs_Data_Stand_Alone_HLR see subclause 25.7.3;
Cancel_Location_Child_HLR see subclause 19.1.2.2;
Insert_GPRS_Subs_Data_Stand_Alone_HLR see subclause 25.7.4;
Cancel_GPRS_Location_Child_HLR see subclause 19.1.2.2.

The macro Delete_Subscriber_Data_HLR is shown in figure 20.3/7. The macro invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2;
Check_Confirmation see subclause 25.2.2.

The macro Delete_GPRS_Subscriber_Data_HLR is shown in figure 20.3/8. The macro invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2;
Check_Confirmation see subclause 25.2.2.

20.3.2.2 Procedures in the VLR

The process in the VLR to update subscriber data in a stand-alone dialogue is shown in figure 20.3/9. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Check_Indication see subclause 25.2.1;
Insert_Subs_Data_VLR see subclause 25.7.1.

The process in the VLR to delete subscriber data is shown in figure 20.3/10. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Check_Indication see subclause 25.2.1.

20.3.2.3 Procedures in the SGSN

The process in the SGSN to update subscriber data in a stand-alone dialogue is shown in figure 20.3/11. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Check_Indication see subclause 25.2.1;
Insert_Subs_Data_SGSN see subclause 25.7.2.

The process in the SGSN to delete subscriber data is shown in figure 20.3/12. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Check_Indication see subclause 25.2.1.




Figure 20.3/5: Process Delete_Subscriber_HLR




Figure 20.3/6 (sheet 1 of 2): Process Modify_Data_HLR




Figure 20.3/6 (sheet 2 of 2): Process Modify_Data_HLR




Figure 20.3/7: Macro Delete_Subscriber_Data_HLR




Figure 20.3/8: Macro Delete_GPRS_Subscriber_Data_HLR




Figure 20.3/9 (sheet 1 of 2): Process Ins_Subs_Data_Stand_Alone_VLR




Figure 20.3/9 (sheet 2 of 2): Process Ins_Subs_Data_Stand_Alone_VLR




Figure 20.3/10: Process Delete_Subs_Data_VLR




Figure 20.3/11 (sheet 1 of 2): Process Ins_Subs_Data_Stand_Alone_SGSN




Figure 20.3/11 (sheet 2 of 2): Process Ins_Subs_Data_Stand_Alone_SGSN





Figure 20.3/12: Process Delete_Subs_Data_SGSN

Subscriber Identity procedure 20.4

In the subscriber identity procedure the IMSI of the subscriber is retrieved from the HLR. The procedure is shown in figure 20.4/1.



- 1) Identity request
- 2)
- MAP_SEND_IMSI_req/ind MAP_SEND_IMSI_rsp/cnf 3)
- 4) Identity confirm

Figure 20.4/1: The subscriber identity procedure

20.4.1 Procedure in the VLR

The subscriber identity process in the VLR is shown in figure 20.4/2. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2; Check_Confirmation see subclause 25.2.2.

20.4.2 Procedure in the HLR

The subscriber identity process in the HLR is shown in figure 20.4/3. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

see subclause 25.1.1; Receive_Open_Ind Check_Indication see subclause 25.2.1.




Figure 20.4/2: Process Send_IMSI_VLR




Figure 20.4/3: Process Send_IMSI_HLR

21 Call handling procedures

21.1 General

The MAP call handling procedures are used:

- to retrieve routeing information to handle a mobile terminating call;
- to transfer control of a call back to the GMSC if the call is to be forwarded;
- to retrieve and transfer information between anchor MSC and relay MSC for inter MSC group calls / broadcast calls:
- to handle the reporting of MS status for call completion services;
- to handle the notification of remote user free for CCBS;
- to handle the alerting and termination of ongoing call activities for a specific subscriber;
- to handle early release of no longer needed resources.

The procedures to handle a mobile originating call and a mobile terminating call after the call has arrived at the destination MSC do not require any signalling over a MAP interface. These procedures are specified in 3GPP TS 23.018 [97].

The stage 2 specification for the retrieval of routeing information to handle a mobile terminating call is in 3GPP TS 23.018 [97]; modifications to this procedure for CAMEL are specified in 3GPP TS 23.078 [98], for optimal routeing of a basic mobile-to-mobile call in 3GPP TS 23.079 [99] and for CCBS in 3GPP TS 23.093 [107]. The interworking between the MAP signalling procedures and the call handling procedures for each entity (GMSC, HLR and VLR) is shown by the transfer of signals between these procedures.

The stage 2 specification for the transfer of control of a call back to the GMSC if the call is to be forwarded is in 3GPP TS 23.079 [99]. The interworking between the MAP signalling procedures and the call handling procedures for each entity (VMSC and GMSC) is shown by the transfer of signals between these procedures.

The stage 2 specifications for inter MSC group calls / broadcast calls are in 3GPP TS 43.068 [100] and 3GPP TS 43.069 [101]. The interworking between the MAP signalling procedures and the group call /broadcast call procedures for each entity (Anchor MSC and Relay MSC) is shown by the transfer of signals between these procedures.


The interworking between the call handling procedures and signalling protocols other than MAP are shown in 3GPP TS 23.018, 3GPP TS 23.078 and 3GPP TS 23.079 [99].

The stage 2 specification for the handling of reporting of MS status for call completion services and notification of remote user free for CCBS is in 3GPP TS 23.093 [107].

21.2 Retrieval of routing information


21.2.1 General

The message flows for successful retrieval of routeing information for a mobile terminating call are shown in figure 21.2/1 (mobile terminating call which has not been optimally routed) and 21.2/2 (mobile-to-mobile call which has been optimally routed). The message flow for successful retrieval of routeing information for a gsmSCF initiated call is shown in figure 21.2/3.




- 1) I_IAM (Note 1)
- 2) MAP_SEND_ROUTING_INFORMATION_req/ind (Note 2)
- 3) MAP_PROVIDE_SUBSCRIBER_INFO_req/ind (Note 3, Note 4)
- 4) MAP_PROVIDE_SUBSCRIBER_INFO_rsp/cnf (Note 4)
- 5) MAP_SEND_ROUTING_INFORMATION_rsp/cnf (Note 4)
- 6) MAP_SEND_ROUTING_INFORMATION_req/ind (Note 4)
- 7) MAP_PROVIDE_ROAMING_NUMBER_req/ind
- 8) MAP PROVIDE ROAMING NUMBER rsp/cnf
- 9) MAP_SEND_ROUTING_INFORMATION_rsp/cnf
- 10) I_IAM (Note 1)
- 11) MAP_RESTORE_DATA_req/ind (Note 4)
- 12) MAP_INSERT_SUBSCRIBER_DATA_req/ind (Note 4)
- 13) MAP_INSERT_SUBSCRIBER_DATA_rsp/cnf (Note 4)
- 12) MAP_RESTORE_DATA_rsp/cnf (Note 4)
- NOTE 1: TUP or ISUP may be used in signalling between MSCs, depending on the network type between the MSCs. For further details on the TUP and ISUP procedures refer to the following ITU-T Recommendations and ETSI specification:
 - Q.721-725 Telephone User Part (TUP);
 - ETS 300 356-1 Integrated Services Digital Network (ISDN); Signalling System No.7; ISDN User Part (ISUP) version 2 for the international interface; Part 1: Basic services.
- NOTE 2: This service may also be used by an ISDN exchange for obtaining routing information from the HLR.
- NOTE 3: As a network operator option, the HLR sends MAP_PROVIDE_SÜBSCRİBER_INFORMATION to the VLR. For further details on the CAMEL procedures refer to 3GPP TS 23.078 [98].
- NOTE 4: Services printed in italics are optional.

Figure 21.2/1: Message flow for retrieval of routeing information (non-optimally routed call)



- 1) I_IAM (Note 1)
- 2) MAP_SEND_ROUTING_INFORMATION_reg/ind
- 3) MAP_PROVIDE_SUBSCRIBER_INFO_reg/ind (Note 2)
- 4) MAP_PROVIDE_SUBSCRIBER_INFO_rsp/cnf (Note 2)
- 5) MAP_PROVIDE_ROAMING_NUMBER_req/ind (Note 2)
- 6) MAP_PROVIDE_ROAMING_NUMBER_rsp/cnf (Note 2)
- 7) MAP_SEND_ROUTING_INFORMATION_rsp/cnf
- 8) I_IAM (Note 1)
- 9) MAP_RESTORE_DATA_reg/ind (Note 3)
- 10) MAP_INSERT_SUBSCRIBER_DATA_req/ind (Note 3)
- 11) MAP_INSERT_SUBSCRIBER_DATA_rsp/cnf (Note 3)
- 12) MAP_RESTORE_DATA_rsp/cnf (Note 3)
- NOTE 1: TUP or ISUP may be used in signalling between MSCs, depending on the network type between the MSCs. For further details on the TUP and ISUP procedures refer to the following ITU-T Recommendations & ETSI specification:
 - Q.721-725 Telephone User Part (TUP);
 - ETS 300 356-1 Integrated Services Digital Network (ISDN); Signalling System No.7; ISDN User Part (ISUP) version 2 for the international interface; Part 1: Basic services.
- NOTE 2: For Optimal Routeing phase 1, only one of the information flows for Provide Subscriber Info and Provide Roaming Number is used.
- NOTE 3: Services printed in italics are optional.

Figure 21.2/2: Message flow for retrieval of routeing information (optimally routed call)



- MAP_SEND_ROUTING_INFORMATION_req/ind
- 2) MAP_SEND_ROUTING_INFORMATION_rsp/cnf (Note 1)
- 3) MAP_SEND_ROUTING_INFORMATION_reg/ind (Note 1)
- 4) MAP_PROVIDE_ROAMING_NUMBER_req/ind
- 5) MAP_PROVIDE_ROAMING_NUMBER_rsp/cnf
- MAP_SEND_ROUTING_INFORMATION_rsp/cnf MAP_RESTORE_DATA_req/ind (Note 1) 6)
- 7)
- 8) MAP_INSERT_SUBSCRIBER_DATA_req/ind (Note 1)
- MAP_INSERT_SUBSCRIBER_DATA_rsp/cnf (Note 1) 9)
- MAP_RESTORE_DATA_rsp/cnf (Note 1)

NOTE 1: Services printed in *italics* are optional.

Figure 21.2/3: Message flow for retrieval of routeing information for a gsmSCF initiated call

The following MAP services are used to retrieve routing information:

MAP_SEND_ROUTING_INFORMATION see subclause 10.1; MAP PROVIDE ROAMING NUMBER see subclause 10.2; MAP_PROVIDE_SUBSCRIBER_INFO see subclause 8.11.2; MAP_RESTORE_DATA see subclause 8.10.3.

21.2.2 Procedure in the GMSC

The MAP process in the GMSC to retrieve routeing information for a mobile terminating call is shown in figure 21.2/6. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2; Check_Confirmation see subclause 25.2.2.

Sheet 1: if the MAP SEND ROUTING INFORMATION request included the OR Interrogation parameter, the test "OR interrogation?" takes the "Yes" exit; otherwise the test takes the "No" exit.

21.2.9 Process in the gsmSCF

For the purposes of retrieving routing information from the HLR, the gsmSCF takes the role of the GMSC and follows the process specified in subclause 21.2.2.

21.2.4 Procedure in the HLR

The MAP process in the HLR to retrieve routeing information for a mobile terminating call is shown in figure 21.2/7. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Ind see subclause 25.1.1;
Receive_Open_Cnf see subclause 25.1.2;
Check_Confirmation see subclause 25.2.2.

Sheet 3: if the MAP_PROVIDE_ROAMING_NUMBER request included the OR Interrogation parameter, the test "OR interrogation?" takes the "Yes" exit; otherwise the test takes the "No" exit.

21.2.5 Procedure in the VLR to provide a roaming number

The MAP process in the VLR to provide a roaming number for a mobile terminating call is shown in figure 21.2/8. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Receive_Open_Ind see subclause 25.1.1;

21.2.6 Procedure in the VLR to restore subscriber data

The MAP process in the HLR to restore subscriber data is shown in figure 21.2/9. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2;
Check_Confirmation see subclause 25.2.2;
Insert_Subs_Data_VLR see subclause 25.7.1;
Activate Tracing VLR see subclause 25.9.4.

21.2.7 Procedure in the VLR to provide subscriber information

The MAP process in the VLR to provide subscriber information for a mobile terminating call subject to CAMEL invocation is shown in figure 21.2/9. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Receive_Open_Ind see subclause 25.1.1;




Figure 21.2/6 (sheet 1 of 2): Process SRI_GMSC




Figure 21.2/6 (sheet 2 of 2): Process SRI_GMSC




Figure 21.2/7 (sheet 1 of 3): Process SRI_HLR




Figure 21.2/7 (sheet 2 of 3): Process SRI_HLR




Figure 21.2/7 (sheet 3 of 3): Process SRI_HLR




Figure 21.2/8: Process PRN_VLR




Figure 21.2/9: Process Restore_Data_VLR





Figure 21.2/10: Process PSI_VLR

21.3 Transfer of call handling

21.3.1 General

The message flow for successful transfer of call handling to forward a call is shown in figure 21.3/1.



- MAP_RESUME_CALL_HANDLING_req/ind
- 2) MAP_SEND_ROUTING_INFORMATION_req/ind (Note 2)
- 3) MAP_SEND_ROUTING_INFORMATION_rsp/cnf (Note 2)
- 4) MAP_RESUME_CALL_HANDLING_rsp/cnf
- 5) I_REL (Note 1)
- 6) I_IAM (Note 1)

NOTE 1: TUP or ISUP may be used in signalling between MSCs, depending on the network type between the MSCs. For further details on the TUP and ISUP procedures refer to the following ITU-T Recommendations & ETSI specification:

- Q.721-725 Telephone User Part (TUP);
- ETS 300 356-1 Integrated Services Digital Network (ISDN); Signalling System No.7; ISDN User Part (ISUP) version 2 for the international interface; Part 1: Basic services.

NOTE 2: Services printed in *italics* are optional.

Figure 21.3/1: Message flow for transfer of call handling

If the HLR indicated in the response to the original request for routeing information that forwarding interrogation is required, the GMSC executes the Send Routeing Information procedure with the HLR to obtain forwarding information; otherwise the GMSC uses the forwarding data which were sent in the MAP_RESUME_CALL_HANDLING req/ind.

21.3.2 Process in the VMSC

The MAP process in the VMSC to retrieve routeing information for a mobile terminating call is shown in figure 21.3/2. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2;

Check_Confirmation see subclause 25.2.2.

If the capacity of a message signal unit in the lower layers of the protocol is enough to carry all the information which has to be sent to the GMSC, the test "Segmentation needed?" takes the "No" exit; otherwise the test takes the "Yes" exit.

21.3.3 Process in the GMSC

The MAP process in the GMSC to handle a request for the GMSC to resume call handling is shown in figure 21.3/3. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Receive_Open_Ind see subclause 25.1.1;

If the parameter All Information Sent was present in the MAP_RESUME_CALL_HANDLING indication, the test "All Information Sent" takes the "Yes" exit; otherwise the test takes the "No" exit.




Figure 21.3/2: Process RCH_VMSC





Figure 21.3/3: Process RCH_GMSC

21.4 Inter MSC Group Call Procedures

21.4.1 General

The message flow for successful inter MSC group call / broadcast call set-up is shown in figure 21.4/1.



- 1) I_IAM (Note 1)
- 2) MAP_PREPARE_GROUP_CALL_req/ind
- 3) MAP_PREPARE_GROUP_CALL_rsp/cnf
- 4) I_IAM (Note 1)
- 5) MAP_SEND_GROUP_CALL_END_SIGNAL_req/ind
- 6) I_ACM (Note 1)
- 7) I_ACM (Note 1)
- 8) MAP_FORWARD_GROUP_CALL_SIGNALLING_req/ind (Note 2)
- 9) MAP_PROCESS_GROUP_CALL_SIGNALLING_req/ind (Note 2)
- 10) MAP SEND GROUP CALL END SIGNAL rsp/cnf
- 11) I_REL (Note 3)
- 12) I_REL (Note 3)
- NOTE 1: TUP or ISUP may be used in signalling between MSCs, depending on the network type between the MSCs. For further details on the TUP and ISUP procedures refer to the following ITU-T Recommendations and ETSI specification:
 - Q.721-725 Telephone User Part (TUP);
 - ETS 300 356-1 Integrated Services Digital Network (ISDN); Signalling System No.7; ISDN User Part (ISUP) version 2 for the international interface; Part 1: Basic services.
- NOTE 2: The MAP_FORWARD_GROUP_CALL_SIGNALLING and
 - MAP_PROCESS_GROUP_CALL_SIGNALLING services are not applicable for voice broadcast calls.
- NOTE 3: The call can be released from the PSTN/ISDN or the Relay MSC

Figure 21.4/1: Message flow for inter MSC group call / broadcast call

21.4.2 Process in the Anchor MSC

The MAP process in the Anchor MSC to retrieve and transfer information from / to the Relay MSC for VBS and VGCS calls is shown in figure 21.4/2. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2;
Check_Indication see subclause 25.2.1;
Check_Confirmation see subclause 25.2.2.

21.4.3 Process in the Relay MSC

The MAP process in the Relay MSC to receive and transfer information from / to the Anchor MSC for VBS and VGCS calls is shown in figure 21.4/3. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Ind see subclause 25.1.2;
Check_Indication see subclause 25.2.1.




Figure 21.4/2 (sheet 1 of 2): Process ASCI_Anchor_MSC




Figure 21.4/2 (sheet 2 of 2): Process ASCI_Anchor_MSC




Figure 21.4/3 (sheet 1 of 2): Process ASCI_Relay_MSC




Figure 21.4/3 (sheet 2 of 2): Process ASCI_Relay_MSC

21.5 Void

21.6 CCBS: monitoring and reporting the status of the subscriber


21.6.1 Reporting co-ordinator process in the VLR

The MAP co-ordinating process in the VLR to handle a dialogue opened with the reporting application context is shown in figure 21.6/6. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Receive_Open_Ind see subclause 25.1.1.

21.6.2 Setting the reporting state – stand-alone

The message flow for setting the reporting state in a stand-alone dialogue is shown in figure 21.6/1.



- MAP_SET_REPORTING_STATE_req/ind
- 2) MAP_SET_REPORTING_STATE_rsp/cnf

Figure 21.6/1: Message flow for setting the reporting state – stand-alone dialogue

21.6.2.1 Process in the HLR

The MAP process in the HLR to set the reporting state in the VLR in a stand-alone dialogue is shown in figure 21.6/7. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2; Check Confirmation see subclause 25.2.2.

The result of a request to stop reporting is not reported to the CCBS application in the HLR.


21.6.2.2 Process in the VLR

The MAP process in the VLR to set the reporting state is shown in figure 21.6/8.

The macro Set_Reporting_State_VLR is shown in figure 21.6/9.


21.6.3 Status Reporting

The message flows for reporting the status of a subscriber are shown in figures 21.6/2 and 21.6/3.



- MAP_STATUS_REPORT_req/ind 1)
- 2) MAP_STATUS_REPORT_rsp/cnf

Figure 21.6/2: Message flow for status reporting, when monitoring continues in the VLR



- MAP_STATUS_REPORT_req/ind 1)
- 2)
- MAP_STATUS_REPORT_rsp/cnf MAP_SET_REPORTING_STATE_req/ind 3)
- MAP_SET_REPORTING_STATE_rsp/cnf

Figure 21.6/3: Message flow for status reporting, when monitoring stops

The MAP_SET_REPORTING_STATE request is used to stop monitoring in the VLR. If the HLR requires the VLR to continue monitoring, it closes the dialogue without sending a MAP_SET_REPORTING_STATE request.

21.6.3.1 Process in the VLR

The MAP process in the VLR to send a status report to the HLR is shown in figure 21.6/10. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

see subclause 25.1.2; Receive_Open_Cnf Check_Confirmation see subclause 25.2.2.

This process can be used to report:

- an event, such as the user becoming free, or
- the result of a CCBS call attempt

to the HLR

21.6.3.2 Process in the HLR

The MAP process in the HLR to handle a status report is shown in figure 21.6/11. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Receive_Open_Ind see subclause 25.1.1;

It is an implementation option whether to send the MAP_DELIMITER request before invoking the macro Set_Reporting_State_HLR.


The macro Receive_Status_Report_HLR is shown in figure 21.6/12.

The macro Set_Reporting_State_HLR is shown in figure 21.6/13. The macro invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Check_Confirmation see subclause 25.2.2.


21.6.4 CCBS: Remote User Free

The message flows for handling remote user free are shown in figures 21.6/4 and 21.6/5.



- 1) MAP_REMOTE_USER_FREE_req/ind
- 2) MAP_REMOTE_USER_FREE_rsp/cnf

Figure 21.6/4: Remote User Free: recall not accepted



- 1) MAP_REMOTE_USER_FREE_req/ind
- 2) MAP_REMOTE_USER_FREE_rsp/cnf
- 3) MAP_STATUS_REPORT_req/ind
- MAP_STATUS_REPORT_rsp/cnf

Figure 21.6/5: Remote User Free: recall accepted

21.6.4.1 Process in the HLR

The MAP process in the HLR to handle Remote User Free is shown in figure 21.6/14. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2; Check_Confirmation see subclause 25.2.2.

21.6.3.2 Process in the VLR

The MAP process in the VLR to handle Remote User Free is shown in figure 21.6/15. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Check_Confirmation see subclause 25.2.2.




Figure 21.6/6: Process Reporting_Coord_VLR




Figure 21.6/7: Process Set_Reporting_State_Stand_Alone_HLR




Figure 21.6/8: Process Set_Reporting_State_VLR




Figure 21.6/9: Macro Receive_Set_Reporting_State_VLR




Figure 21.6/10 (sheet 1 of 2): Process Send_Status_Report_VLR




Figure 21.6/10 (sheet 2 of 2): Process Send_Status_Report_VLR




Figure 21.6/11: Process Status Report_HLR




Figure 21.6/12: Macro Receive_Status_Report_HLR




Figure 21.6/13: Macro Set_Reporting_State_HLR




Figure 21.6/14: Process Remote_User_Free_HLR




Figure 21.6/15 (sheet 1 of 2): Process Remote_User_Free_VLR




Figure 21.6/15 (sheet 2 of 2): Process Remote_User_Free_VLR

21.7 Void


21.8 Void

21.9 Immediate Service Termination (IST)

21.9.1 IST Alert

The Immediate Service Termination Alert procedure is used to keep track of the call activities performed by subscribers who are marked as being subject to IST monitoring and, possibly, to terminate the call activities for which the alert was sent, or all the call activities related to the subscriber for whom the alert was sent.

The message flow for alerting is shown in figure 21.9/1; the MSC may be a Visited MSC or a Gateway MSC.



- 1) MAP_IST_ALERT_req/ind
- 2) MAP_IST_ALERT_rsp/cnf

Figure 21.9/1: Message flow for IST Alert

21.9.1.1 Procedure in the MSC

The MAP process in the MSC (Visited MSC or Gateway MSC) is shown in figure 21.9/3. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2; Check Confirmation see subclause 25.2.2.

21.9.1.2 Procedure in the HLR


The MAP process in the HLR is shown in figure 21.9/4. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Receive_Open_Ind see subclause 25.1.1;

21.9.2 IST Command

The Immediate Service Termination Command procedure is used to terminate the call activities related to a subscriber.

The message flow for the IST Command procedure is shown in figure 21.9/2; the MSC may be a Visited MSC or a Gateway MSC.



- 1) MAP_IST_COMMAND_req/ind
- 2) MAP_IST_COMMAND_rsp/cnf

Figure 21.9/2: Message flow for IST Command

21.9.2.1 Procedure in the HLR

The MAP process in the HLR is shown in figure 21.9/5. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2; Check_Confirmation see subclause 25.2.2.

21.9.2.2 Procedure in the MSC

The MAP process in the MSC is shown in figure 21.9.6. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Receive_Open_Ind see subclause 25.1.1.




Figure 21.9/3: Process IST_Alert_MSC




Figure 21.9/4: Process IST_Alert_HLR




Figure 21.9/5: Process IST_Command_HLR





Figure 21.9/6: Process IST_Command_MSC

21.10 Resource Management

21.10.1 General

The message flow for successful release of resources is shown in figure 21.10/1.



- 1) I_IAM (Note 1)
- 2) MAP_SEND_ROUTING_INFORMATION_req/ind
- 3) MAP_PROVIDE_ROAMING_NUMBER_req/ind
- 4) I_REL (Note 1)
- 5) MAP_PROVIDE_ROAMING_NUMBER_rsp/cnf
- 6) MAP_SEND_ROUTING_INFORMATION_rsp/cnf
- 7) MAP_RELEASE_RESOURCES (Note 2)
- NOTE 1: TUP or ISUP may be used in signalling between MSCs, depending on the network type between the MSCs. For further details on the TUP and ISUP procedures refer to the following ITU-T Recommendations & ETSI specification:
 - Q.721-725 Telephone User Part (TUP);
 - ETS 300 356-1 Integrated Services Digital Network (ISDN); Signalling System No.7; ISDN User Part (ISUP) version 2 for the international interface; Part 1: Basic services.

NOTE 2: Services printed in *italics* are optional.

Figure 21.10/1: Message flow for early release of resources

21.3.2 Process in the GMSC

The MAP process in the GMSC to release resources is shown in figure 21.10/2. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2; Check_Confirmation see subclause 25.2.2.

21.3.3 Process in the VMSC

The MAP process in the VMSC to handle a request for the GMSC to release resources is shown in figure 21.10/3. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Receive_Open_Ind see subclause 25.1.1;




Figure 21.10/2: Process Release Resources_GMSC




Figure 21.10/3: Process Release Resources_VMSC

22 Supplementary services procedures

22.1 Supplementary service co-ordinator processes

22.1.1 Supplementary service co-ordinator process for the MSC

The co-ordinator process in the MSC to handle a CM connection request with CM service type Supplementary service activation is shown in figure 22.1/1. The process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Process_Access_Request_MSC see subclause 25.4.1.

22.1.2 Void

22.1.3 Functional supplementary service co-ordinator process for the HLR

The MAP co-ordinator process in the HLR to handle a dialogue opened with the networkFunctionalSS application context is shown in figure 22.1/3. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Receive_Open_Ind see subclause 25.1.1.

22.1.4 Call completion supplementary service co-ordinator process for the HLR

The MAP co-ordinator process in the HLR to handle a dialogue opened with the callCompletion application context is shown in figure 22.1/4. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Receive Open Ind see subclause 25.1.1.




Figure 22.1/1 (sheet 1 of 2): Process SS_Coordinator_MSC




Figure 22.1/1 (sheet 2 of 2): Process SS_Coordinator_MSC
Figure 22.1/2 void




Figure 22.1/3: Process SS_Coordinator_HLR




Figure 22.1/4: Process CC_Coordinator_HLR

22.2 Registration procedure

22.2.1 General

The registration procedure is used to register data related to a supplementary service in the HLR. The registration procedure is a fully transparent communication between the MS and the HLR, except that some services may be invoked as a result of the procedure, as described in the clauses below.


The registration procedure is shown in figure 22.2.1/1.

The following services may be used:

MAP_PROCESS_ACCESS_REQUEST (see clauses 8 and 25); MAP_TRACE_SUBSCRIBER_ACTIVITY (see clauses 9 and 25); MAP PROVIDE IMSI (see clauses 8 and 25); MAP_FORWARD_NEW_TMSI (see clauses 8 and 25); MAP_AUTHENTICATE (see clauses 8 and 25); MAP_SET_CIPHERING_MODE (see clauses 8 and 25); MAP_CHECK_IMEI (see clauses 8 and 25); MAP_READY_FOR_SM (see clauses 12 and 25); MAP_INSERT_SUBSCRIBER_DATA (see clauses 8 and 25);

The following service is certainly used:

MAP_REGISTER_SS (defined in clause 11).



- 1) A_CM_SERV_REQ (Note 1)
- 2) MAP_PROCESS_ACCESS_REQUEST (Note 2)
- 3) A_REGISTER_SS (Note 1)
- 4) MAP_REGISTER_SS_req/ind
- 5)
- MAP_REGISTER_SS_req/ind MAP_REGISTER_SS_rsp/cnf 6)
- 7) MAP_REGISTER_SS_rsp/cnf
- 8) A_REGISTER_SS ack (Note 1)
- MAP_INSERT_SUBSCRIBER_DATA_req/ind (Note 3) 9)
- 10) MAP_INSERT_SUBSCRIBER_DATA_rsp/cnf (Note 3)

NOTE 1: For details of the procedure on the radio path, see 3GPP TS 24.008 [35], 3GPP TS 24.010 [36], 3GPP TS 24.08x and 3GPP TS 24.09x. Services shown in dotted lines indicate the trigger provided by the signalling on the radio path, and the signalling triggered on the radio path.

NOTE 2: For details of the Process Access Request procedure, refer to subclause 25.4 in the present document.

NOTE 3: Services printed in *italics* are optional.

Figure 22.2.1/1: Message flow for supplementary service registration

22.2.2 Procedure in the MSC

The A_REGISTER_SS service indication received by the MAP process in the MSC contains the SS-Code and any parameters that are related to the supplementary service.

The MAP user transfers the received information to the VLR in the MAP_REGISTER_SS request without checking the contents of the service indication. Rules for the mapping are described in 3GPP TS 29.011 [59].

The information in the MAP_REGISTER_SS confirm from the VLR is relayed to the MS in the A_REGISTER_SS response message as described in 3GPP TS 24.08x, 3GPP TS 24.08x and 3GPP TS 29.011.

For call independent SS operations, each message shall contain only a single component. Messages which contain more than one component will be stopped at the air interface (as specified in 3GPP TS 29.011 [59]).

The registration process in the MSC is shown in figure 22.2.2/1.

22.2.3 Procedure in the VLR

The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Ind see subclause 25.1.1;
Receive_Open_Cnf see subclause 25.1.2;
Check_Confirmation see subclause 25.2.2;
Process Access Request VLR see subclause 25.4.2.

The MAP process in the VLR transfers the information received in the MAP_REGISTER_SS indication to the HLR in the MAP_REGISTER_SS request without checking the contents. The MAP_OPEN request includes the IMSI of the subscriber as the destination reference and the VLR number as the originating reference.

If the MAP_REGISTER_SS confirm is properly formed and contains a result or a user error, the MAP process in the VLR shall transfer the information contained in this primitive to the MSC in the MAP_REGISTER_SS response.

For call independent SS operations, each message shall contain only a single component. Messages which contain more than one component will be stopped at the air interface (as specified in 3GPP TS 29.011 [59]).

The registration process in the VLR is shown in figure 22.2.3/1.

22.2.4 Procedure in the HLR

The MAP process invokes a macro and a process not defined in this clause; the definitions of the macro and process can be found as follows:

Check_Indication see subclause 25.2.1;
Insert_Subs_Data_Stand_Alone_HLR see subclause 25.7.3.

The supplementary service request shall be processed according to 3GPP TS 23.011 [22] and the 23.08x and 23.09x-series of technical specifications. This handling may lead to a successful result, a partially successful result or an error being returned.

For call independent SS operations, each message shall contain only a single component. Messages which contain more than one component will be stopped at the air interface (as specified in 3GPP TS 29.011 [59]):

The registration process in the HLR is shown in figure 22.2.4/1.




Figure 22.2.2/1: Process Register_SS_MSC




Figure 22.2.3/1 (sheet 1 of 2): Process Register_SS_VLR




Figure 22.2.3/1 (sheet 2 of 2): Process Register_SS_VLR




Figure 22.2.4/1: Process Register_SS_HLR

22.3 Erasure procedure

22.3.1 General

The erasure procedure is used to erase data related to a supplementary service in the HLR. The erasure procedure is a fully transparent communication between the MS and the HLR, except that some services may be invoked as a result of the procedure, as described in the clauses below.


The erasure procedure is shown in figure 22.3.1/1.

The following services may be used:

MAP_PROCESS_ACCESS_REQUEST (see clauses 8 and 25); MAP_TRACE_SUBSCRIBER_ACTIVITY (see clauses 9 and 25); MAP_PROVIDE_IMSI (see clauses 8 and 25); MAP_FORWARD_NEW_TMSI (see clauses 8 and 25); MAP_AUTHENTICATE (see clauses 8 and 25); MAP_SET_CIPHERING_MODE (see clauses 8 and 25); MAP_CHECK_IMEI (see clauses 8 and 25); MAP_READY_FOR_SM (see clauses 12 and 25); MAP_INSERT_SUBSCRIBER_DATA (see clauses 8 and 25);

The following service is certainly used:

MAP_ERASE_SS (defined in clause 11).



- 1) A_CM_SERV_REQ (Note 1)
- 2) MAP_PROCESS_ACCESS_REQUEST (Note 2)
- 3) A_ERASE_SS (Note 1)
- 4) MAP_ERASE_SS_req/ind
- MAP_ERASE_SS_req/ind MAP_ERASE_SS_rsp/cnf 5)
- 6)
- MAP_ERASE_SS_rsp/cnf 7)
- 8) A_ERASE_SS ack (Note 1)
- MAP_INSERT_SUBSCRIBER_DATA_req/ind (Note 3) 9)
- MAP_INSERT_SUBSCRIBER_DATA_rsp/cnf (Note 3) 10)

- NOTE 1: For details of the procedure on the radio path, see 3GPP TS 24.008 [35], 3GPP TS 24.010 [36], 3GPP TS 24.08x and 3GPP TS 24.09x. Services shown in dotted lines indicate the trigger provided by the signalling on the radio path, and the signalling triggered on the radio path.
- NOTE 2: For details of the Process Access Request procedure, refer to subclause 25.4 in the present document.
- NOTE 3: Services printed in italics are optional.

Figure 22.3.1/1: Message flow for supplementary service erasure

22.3.2 Procedure in the MSC

The MSC procedure for erasure is identical to that specified for registration in subclause 22.2.2. The text and diagrams in subclause 22.2.2 apply with all references to registration changed to erasure.

22.3.3 Procedure in the VLR

The VLR procedure for erasure is identical to that specified for registration in subclause 22.2.3. The text and diagrams in subclause 22.2.3 apply with all references to registration changed to erasure.

22.3.4 Procedure in the HLR

The HLR procedure for erasure is identical to that specified for registration in subclause 22.2.4. The text and diagrams in subclause 22.2.4 apply with all references to registration changed to erasure.

22.4 Activation procedure

22.4.1 General

The activation procedure is used to activate a supplementary service in the HLR. The activation procedure is a fully transparent communication between the MS and the HLR, except that some services may be invoked as a result of the procedure, as described in the clauses below.


(see clauses 8 and 25);

The activation procedure is shown in figure 22.4.1/1.

MAP_PROCESS_ACCESS_REQUEST

The following services may be used:

	(,
MAP_TRACE_SUBSCRIBER_ACTIVITY	(see clauses 9 and 25);
MAP_PROVIDE_IMSI	(see clauses 8 and 25);
MAP_FORWARD_NEW_TMSI	(see clauses 8 and 25);
MAP_AUTHENTICATE	(see clauses 8 and 25);
MAP_SET_CIPHERING_MODE	(see clauses 8 and 25);
MAP_CHECK_IMEI	(see clauses 8 and 25);
MAP_READY_FOR_SM	(see clauses 12 and 25);
MAP_GET_PASSWORD	(defined in clause 11);
MAP_INSERT_SUBSCRIBER_DATA	(see clauses 8 and 25);
The following service is certainly used:	
MAP_ACTIVATE_SS	(defined in clause 11).



- 1) A_CM_SERV_REQ (Note 1)
- 2) MAP_PROCESS_ACCESS_REQUEST (Note 2)
- 3) A_ACTIVATE_SS (Note 1)
- MAP_ACTIVATE_SS_req/ind MAP_ACTIVATE_SS_req/ind 4)
- 5)
- 6) MAP_GET_PASSWORD_reg/ind (Note 3)
- MAP_GET_PASSWORD_req/ind (Note 3) 7)
- 8) A_GET_PASSWORD (Note 1, Note 3)
- 9) A_GET_PASSWORD ack (Note 1, Note 3)
- 10) MAP_GET_PASSWORD_rsp/cnf (Note 3)
- 11) MAP GET PASSWORD rsp/cnf (Note 3)
- MAP_ACTIVATE_SS_rsp/cnf 12)
- MAP_ACTIVATE_SS_rsp/cnf 13)
- A_ACTIVATE_SS ack (Note 1) 14)
- MAP_INSERT_SUBSCRIBER_DATA_req/ind (Note 3) 15)
- MAP_INSERT_SUBSCRIBER_DATA_rsp/cnf (Note 3) 16)
- NOTE 1: For details of the procedure on the radio path, see 3GPP TS 24.008 [35], 3GPP TS 24.010 [36], 3GPP TS 24.08x and 3GPP TS 24.09x. Services shown in dotted lines indicate the trigger provided by the signalling on the radio path, and the signalling triggered on the radio path.
- NOTE 2: For details of the Process Access Request procedure, refer to subclause 25.4 of this document.
- NOTE 3: Services printed in *italics* are optional.

Figure 22.4.1/1: Message flow for supplementary service activation

22.4.2 Procedure in the MSC

The A_ACTIVATE_SS service indication received by the MAP user in the MSC contains the SS-Code and any parameters related to the supplementary service.

The MSC transfers the received information to the VLR in the MAP ACTIVATE SS request without checking the contents of the service indication. Rules for the mapping are described in 3GPP TS 29.011 [59].

The information in the MAP_ACTIVATE_SS confirm from the VLR is relayed to the MS in the A_ACTIVATE_SS response message, as described in TS 24.08x, 3GPP TS 24.08x and 3GPP TS 29.011.

For call independent SS operations, each message shall contain only a single component. Messages which contain more than one component will be stopped at the air interface (as specified in 3GPP TS 29.011 [59]).

The activation process in the MSC is shown in figure 22.4.2/1.

22.4.3 Procedure in the VLR

The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Ind see subclause 25.1.1;
Receive_Open_Cnf see subclause 25.1.2;
Check_Confirmation see subclause 25.2.2;
Process Access Request VLR see subclause 25.4.2.

The MAP process in the VLR transfers the information received in the MAP_ACTIVATE_SS indication to the HLR in the MAP_ACTIVATE_SS request without checking the contents. The MAP_OPEN request includes the IMSI of the subscriber as the destination reference and the VLR number as the originating reference.

If the MAP_REGISTER_SS confirm is properly formed and contains a result or a user error, the MAP process in the VLR shall transfer the information contained in this primitive to the MSC in the MAP_ACTIVATE_SS response.

For call independent SS operations, each message shall contain only a single component. Messages which contain more than one component will be stopped at the air interface (as specified in 3GPP TS 29.011 [59]).

The activation process in the VLR is shown in figure 22.4.3/1.

22.4.4 Procedure in the HLR

The MAP process invokes a macro and a process not defined in this clause; the definitions of the macro and process can be found as follows:

Check_Indication see subclause 25.2.1;
Insert_Subs_Data_Stand_Alone_HLR see subclause 25.7.3.

The supplementary service request shall be processed according to 3GPP TS 23.011 [22] and the 23.08x and 23.09x-series of technical specifications. This handling may lead to a successful result, a partially successful result or an error being returned.

For call independent SS operations, each message shall contain only a single component. Messages which contain more than one component will be stopped at the air interface (as specified in 3GPP TS 29.011 [59]):

The activation process in the HLR is shown in figure 22.4.4/1.




Figure 22.4.2/1: Process Activate_SS_MSC




Figure 22.4.3/1 (sheet 1 of 2): Process Activate_SS_VLR




Figure 22.4.3/1 (sheet 2 of 2): Process Activate_SS_VLR




Figure 22.4.4/1 (sheet 1 of 2): Process Activate_SS_HLR




Figure 22.4.4/1 (sheet 2 of 2): Process Activate_SS_HLR

22.5 Deactivation procedure

22.5.1 General

The deactivation procedure is used to deactivate a supplementary service in the HLR. The deactivation procedure is a fully transparent communication between the MS and the HLR, except that some services may be invoked as a result of the procedure, as described in the clauses below.


The deactivation procedure is shown in figure 22.5.1/1.

The following services may be used:

MAP_PROCESS_ACCESS_REQUEST (see clauses 8 and 25); MAP_TRACE_SUBSCRIBER_ACTIVITY (see clauses 9 and 25); MAP_PROVIDE_IMSI (see clauses 8 and 25); MAP_FORWARD_NEW_TMSI (see clauses 8 and 25); MAP_AUTHENTICATE (see clauses 8 and 25); MAP_SET_CIPHERING_MODE (see clauses 8 and 25); MAP_CHECK_IMEI (see clauses 8 and 25); (see clauses 12 and 25); MAP_READY_FOR_SM MAP_GET_PASSWORD (defined in clause 11); MAP_INSERT_SUBSCRIBER_DATA (see clauses 8 and 25);

The following service is certainly used:

MAP_DEACTIVATE_SS (defined in clause 11).



1) A_CM_SERV_REQ (Note 1)

- MAP PROCESS ACCESS REQUEST (Note 2) 2) 3) A_DEACTIVATE_SS (Note 1)
- MAP_DEACTIVATE_SS_req/ind 4)
- 5) MAP_DEACTIVATE_SS_req/ind
- 6) MAP_GET_PASSWORD_reg/ind (Note 3)
- 7) MAP_GET_PASSWORD_req/ind (Note 3)
- 8) A GET PASSWORD (Note 1, Note 3)
- 9) A_GET_PASSWORD ack (Note 1, Note 3)
- 10) MAP_GET_PASSWORD_rsp/cnf (Note 3)
- MAP_GET_PASSWORD_rsp/cnf (Note 3) 11)
- MAP_DEACTIVATE_SS_rsp/cnf MAP_DEACTIVATE_SS_rsp/cnf 12)
- 13)
- A_DEACTIVATE_SS ack (Note 1) 14)
- MAP_INSERT_SUBSCRIBER_DATA_reg/ind (Note 3) 15)
- MAP_INSERT_SUBSCRIBER_DATA_rsp/cnf (Note 3) 16)
- NOTE 1: For details of the procedure on the radio path, see 3GPP TS 24.008 [35], 3GPP TS 24.010 [36], 3GPP TS 24.08x and 3GPP TS 24.09x. Services shown in dotted lines indicate the trigger provided by the signalling on the radio path, and the signalling triggered on the radio path.
- NOTE 2: For details of the Process Access Request procedure, refer to subclause 25.4 in the present document.
- NOTE 3: Services printed in *italics* are optional.

Figure 22.5.1/1: Message flow for supplementary service deactivation

22.5.2 Procedure in the MSC

The MSC procedure for deactivation is identical to that specified for activation in subclause 22.4.2. The text and diagrams in subclause 22.4.2 apply with all references to activation changed to deactivation.

22.5.3 Procedures in the VLR

The VLR procedure for deactivation is identical to that specified for activation in subclause 22.4.3. The text and diagrams in subclause 22.4.3 apply with all references to activation changed to deactivation.

22.5.4 Procedures in the HLR

The HLR procedure for deactivation is identical to that specified for activation in subclause 22.4.4. The text and diagrams in subclause 22.4.4 apply with all references to activation changed to deactivation.

22.6 Interrogation procedure

22.6.1 General

The interrogation procedure is used to retrieve information related to a supplementary service from the VLR or the HLR. It is the VLR which decides whether an interrogation request should be forwarded to the HLR or not. Some nonsupplementary service related services may be invoked as a result of the procedure, as described in the clauses below.

The interrogation procedure is shown in figure 22.6.1/1.


The following services may be used:

```
MAP_PROCESS_ACCESS_REQUEST
                                     (see clauses 8 and 25);
MAP_TRACE_SUBSCRIBER_ACTIVITY (see clauses 9 and 25);
MAP_PROVIDE_IMSI
                                     (see clauses 8 and 25);
MAP_FORWARD_NEW_TMSI
                                     (see clauses 8 and 25);
MAP AUTHENTICATE
                                     (see clauses 8 and 25);
MAP_SET_CIPHERING_MODE
                                     (see clauses 8 and 25);
```

MAP_CHECK_IMEI (see clauses 8 and 25); MAP_READY_FOR_SM (see clauses 12 and 25);

The following service is certainly used:

MAP INTERROGATE SS (defined in clause 11).



- 1) A_CM_SERV_REQ (Note 1)
- MAP_PROCESS_ACCESS_REQUEST (Note 2)
- 3) A_INTERROGATE_SS (Note 1)
- 4) MAP_INTERROGATE_SS_req/ind
- 5) MAP_INTERROGATE_SS_reg/ind
- 6) MAP_INTERROGATE_SS_rsp/cnf
- 7) MAP_INTERROGATE_SS_rsp/cnf
- 8) A_INTERROGATE_SS ack (Note 1)
- NOTE 1: For details of the procedure on the radio path, see 3GPP TS 24.008 [35], 3GPP TS 24.010 [36], 3GPP TS 24.08x and 3GPP TS 24.09x. Services shown in dotted lines indicate the trigger provided by the signalling on the radio path, and the signalling triggered on the radio path.
- NOTE 2: For details of the Process Access Request procedure, refer to subclause 25.4 in the present document.
- NOTE 3: Services printed in italics are optional.

Figure 22.6.1/1: Message flow for supplementary service interrogation

22.6.2 Procedure in the MSC

The MSC procedures for interrogation are identical to those specified for registration in subclause 22.2.2. The text and diagrams in subclause 22.2.2 apply with all references to registration changed to interrogation.

22.6.3 Procedures in the VLR

The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Ind see subclause 25.1.1;
Receive_Open_Cnf see subclause 25.1.2;
Check_Confirmation see subclause 25.2.2;
Process_Access_Request_VLR see subclause 25.4.2.

The interrogation is answered either by the VLR or by the HLR, depending on the service interrogated.

1) Interrogation to be handled by the VLR

The supplementary service request shall be processed according to 3GPP TS 23.011 [22] and the 23.08x and 23.09x-series of technical specifications. This handling may lead to a successful result, a partially successful result or an error being returned.

For call independent SS operations, each message shall contain only a single component. Messages which contain more than one component will be stopped at the air interface (as specified in 3GPP TS 29.011 [59]).

2) Interrogation to be handled by the HLR

If the interrogation is to be handled by the HLR, the MAP process in the VLR transfers the information received in the MAP_INTERROGATE_SS indication to the HLR in the MAP_INTERROGATE_SS request without checking the contents of the service indication. The MAP_OPEN request includes the IMSI of the subscriber as the destination reference and the VLR number as the originating reference.

If the MAP_INTERROGATE_SS confirm is properly formed and contains a result or a user error, the MAP process in the VLR shall transfer the information contained in this primitive to the MSC in the MAP_INTERROGATE_SS response.

For call independent SS operations, each message shall contain only a single component. Messages which contain more than one component will be stopped at the air interface (as specified in 3GPP TS 29.011 [59]).

The Interrogation process in the VLR is shown in figure 22.6.3/1.

22.6.4 Procedure in the HLR

The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Check Indication

see subclause 25.2.1.

The HLR acts as follows:

The interrogation is answered either by the VLR or by the HLR, depending on the service interrogated.

1) Interrogation to be handled by the VLR

If the interrogation procedure should have been answered by the VLR, then the HLR assumes that the VLR does not support the interrogated supplementary service, and returns the SS Not Available error to the VLR.

2) Interrogation to be handled by HLR

The supplementary service request shall be processed according to 3GPP TS 23.011 [22] and the 23.08x and 23.09x-series of technical specifications. This handling may lead to either a successful result or an error being returned.

For call independent SS operations, each message shall contain only a single component. Messages which contain more than one component will be stopped at the air interface (as specified in 3GPP TS 29.011 [59]).

The Interrogation process in the HLR is shown in figure 22.6.4/1.




Figure 22.6.3/1 (sheet 1 of 2): Process Interrogate_SS_VLR




Figure 22.6.3/1 (sheet 2 of 2): Process Interrogate_SS_VLR




Figure 22.6.4/1: Process Interrogate_SS_HLR

22.7 Void

Figure 22.7.2/1 void

Figure 22.7.3/1 void

22.8 Password registration procedure

22.8.1 General

The password registration procedure is used to register a password in the HLR. The password registration procedure is a fully transparent communication between the MS and the HLR, except that some services may be invoked as a result of the procedure, as described below.


(defined in clause 11).

The password registration procedure is shown in figure 22.8.1/1.

The following services may be used:

MAP_GET_PASSWORD

MAP_PROCESS_ACCESS_REQUEST	(see clauses 8 and 25);
MAP_TRACE_SUBSCRIBER_ACTIVITY	(see clauses 9 and 25);
MAP_PROVIDE_IMSI	(see clauses 8 and 25);
MAP_FORWARD_NEW_TMSI	(see clauses 8 and 25);
MAP_AUTHENTICATE	(see clauses 8 and 25);
MAP_SET_CIPHERING_MODE	(see clauses 8 and 25);
MAP_CHECK_IMEI	(see clauses 8 and 25);
MAP_READY_FOR_SM	(see clauses 12 and 25);
The following services are certainly used:	
MAP_REGISTER_PASSWORD	(defined in clause 11);



- 1) A_CM_SERV_REQ (Note 1)
- 2) MAP_PROCESS_ACCESS_REQUEST (Note 2)
- 3) A_REGISTER_PASSWORD (Note 1)
- 4) MAP_REGISTER_PASSWORD_req/ind
- 5) MAP_REGISTER_PASSWORD_req/ind
- 6) MAP_GET_PASSWORD_req/ind (Note 3)
- 7) MAP_GET_PASSWORD_req/ind (Note 3)
- 8) A_GET_PASSWORD (Note 1, Note 3)
- 9) A_GET_PASSWORD ack (Note 1, Note 3)
- 10) MAP_GET_PASSWORD_rsp/cnf (Note 3)
- 11) MAP_GET_PASSWORD_rsp/cnf (Note 3)
- 12) MAP_GET_PASSWORD_req/ind (Note 3)
- 13) MAP_GET_PASSWORD_req/ind (Note 3)
- 14) A_GET_PASSWORD (Note 1, Note 3)
- 15) A_GET_PASSWORD ack (Note 1, Note 3)
- 16) MAP_GET_PASSWORD_rsp/cnf (Note 3)
- 17) MAP_GET_PASSWORD_rsp/cnf (Note 3)
- 18) MAP_GET_PASSWORD_req/ind (Note 3)
- 19) MAP_GET_PASSWORD_req/ind (Note 3)
- 20) A_GET_PASSWORD (Note 1, Note 3)
- 21) A_GET_PASSWORD ack (Note 1, Note 3)
- 22) MAP_GET_PASSWORD_rsp/cnf (Note 3)
- 23) MAP_GET_PASSWORD_rsp/cnf (Note 3)
- 24) MAP_REGISTER_PASSWORD_rsp/cnf25) MAP_REGISTER_PASSWORD_rsp/cnf
- 26) A_REGISTER_PASSWORD (Note 1)

- NOTE 1: For details of the procedure on the radio path, see 3GPP TS 24.008 [35], 3GPP TS 24.010 [36], 3GPP TS 24.08x and 3GPP TS 24.09x. Services shown in dotted lines are triggers/ triggered signalling on the radio path.
- NOTE 2: For details of the Process Access Request procedure, refer to subclause 25.4 in the present document.
- NOTE 3: The use of each of the three MAP_GET_PASSWORD operations is described in subclause 22.8.4.

Figure 22.8.1/1: Message flow for supplementary service password registration

22.8.2 Procedure in the MSC

The password registration procedure in the MSC is identical to that for activation specified in subclause 22.4.2. All the text and diagrams in subclause 22.4.2 apply with all references to activation changed to password registration.

22.8.3 Procedure in the VLR

The password registration procedure in the VLR is identical to that for activation specified in subclause 22.4.3. All the text and diagrams in subclause 22.4.3 apply with all references to activation changed to password registration.

22.8.4 Procedure in the HLR

The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Check Indication

see subclause 25.2.1.

The HLR shall process the MAP_REGISTER_PASSWORD indication as specified in 3GPP TS 23.011 [22]. During the handling of password registration, the password procedure is initiated (as specified in 3GPP TS 23.011 [22]) This involves the sending of MAP_GET_PASSWORD requests to the VLR.

The password registration process in the HLR is shown in figure 22.8.4/1.




Figure 22.8.4/1 (sheet 1 of 2): Process Register_PW_HLR




Figure 22.8.4/1 (sheet 2 of 2): Process Register_PW_HLR

22.9 Mobile Initiated USSD procedure

22.9.1 General

The procedure supports supplementary service signalling procedures which allow PLMN specific services to be introduced.

The message flow for the procedure can be found in 3GPP TS 23.090 [34].

The following services may be used:

MAP_PROCESS_ACCESS_REQUEST	(see clauses 8 and 25);
MAP_TRACE_SUBSCRIBER_ACTIVITY	(see clauses 9 and 25);
MAP_PROVIDE_IMSI	(see clauses 8 and 25);
MAP_FORWARD_NEW_TMSI	(see clauses 8 and 25);
MAP_AUTHENTICATE	(see clauses 8 and 25);
MAP_SET_CIPHERING_MODE	(see clauses 8 and 25);
MAP_CHECK_IMEI	(see clauses 8 and 25);
MAP_READY_FOR_SM	(see clauses 12 and 25);
MAP_UNSTRUCTURED_SS_REQUEST	(defined in clause 11);
MAP_UNSTRUCTURED_SS_NOTIFY	(defined in clause 11).

The following service is certainly used:

MAP_PROCESS_UNSTRUCTURED_SS_REQUEST (defined in clause 11).

22.9.2 Procedure in the MSC

The process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Check_Confirmation see subclause 25.2.2.

The A_PROCESS_UNSTRUCTURED_SS_REQUEST from the MS contains information input by the user; the message may be fed to an application contained locally in the MSC or to the VLR. The rules for determining this are specified in 3GPP TS 23.090 [34].

1) Message Destined for the VLR

If the message is destined for the VLR then the MSC shall transfer the message to the VLR using the mapping specified in detail in 3GPP TS 29.011 [59].

2) Message Destined for the Local Application

If the message is destined for the local USSD application then the MSC shall transfer the information contained in the message to the application.

The process in the MSC is shown in figure 22.9.2/1.

22.9.3 Procedure in the VLR

The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2;
Check_Confirmation see subclause 25.2.2;

Process_Access_Request_VLR see subclause 25.4.2.

The MAP_PROCESS_UNSTRUCTURED_SS_REQUEST from the MSC contains information input by the user; the message may be fed to an application contained locally in the VLR or to the HLR. The rules for determining this are specified in 3GPP TS 23.090 [34].

1) Message Destined for the HLR

If the message is destined for the HLR then the VLR shall transfer the message transparently to the HLR.

2) Message Destined for the Local Application

If the message is destined for the local USSD application then the VLR shall transfer the information contained in the message to the application.

The process in the VLR is shown in figure 22.9.3/1.

22.9.4 Procedure in the HLR

The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Ind see subclause 25.1.1;
Receive_Open_Cnf see subclause 25.1.2;
Check_Confirmation see subclause 25.2.2.

The MAP_PROCESS_UNSTRUCTURED_SS_REQUEST from the VLR contains information input by the user. If the alphabet used for the message is understood then the message shall be fed to an application contained locally in the HLR or to the gsmSCF or to a secondary HLR where the USSD application is located.

1) Message Destined for the Local Application

If the message is destined for the local USSD application then the HLR shall transfer the information contained in the message to the local application.

2) Message Destined for the gsmSCF or the secondary HLR

If the message is destined for the gsmSCF or the secondary HLR then the primary HLR shall transfer the message transparently to the next node.

The process in the primary HLR is shown in figure 22.9.4/1.

22.9.5 Procedures in the gsmSCF/secondary HLR

The MAP process invokes a macro not defined in this clause; the definition of this macros can be found as follows:

Receive_Open_Ind see subclause 25.1.1.

The process in the gsmSCF or secondary HLR is shown in figure 22.9.5/1.




Figure 22.9.2/1 (sheet 1 of 3): Process MS_Init_USSD_MSC




Figure 22.9.2/1 (sheet 2 of 3): Process MS_Init_USSD_MSC




Figure 22.9.2/1 (sheet 3 of 3): Process MS_Init_USSD_MSC




Figure 22.9.3/1 (sheet 1 of 4): Process MS_Init_USSD_VLR




Figure 22.9.3/1 (sheet 2 of 4): Process MS_Init_USSD_VLR




Figure 22.9.3/1 (sheet 3 of 4): Process_MS_Init_USSD_VLR




Figure 22.9.3/1 (sheet 4 of 4): Process_MS_Init_USSD_VLR
Figure 22.9.3/2 void




Figure 22.9.4/1 (sheet 1 of 4): Process MS_Init_USSD_HLR




Figure 22.9.4/1 (sheet 2 of 4): Process MS_Init_USSD_HLR




Figure 22.9.4/1 (sheet 3 of 4): Process MS_Init_USSD_HLR




Figure 22.9.4/1 (sheet 4 of 4): Process MS_Init_USSD_HLR




Figure 22.9.5/1 (sheet 1 of 2): Process MS_Init_USSD_gsmSCF_Secondary_HLR




Figure 22.9.5/1 (sheet 2 of 2): Process MS_Init_USSD_gsmSCF_Secondary_HLR

Network initiated USSD procedure 22.10

22.10.1 General

The procedure supports supplementary service signalling procedures which allow PLMN specific services to be introduced.

The message flow for the procedure can be found in 3GPP TS 23.090 [34].

The following services may be used:

```
MAP_PAGE
                                                  (see clauses 8 and 25);
     MAP_SEARCH_FOR_MOBILE_SUBSCRIBER
                                                  (see clauses 8 and 25);
     MAP_PROCESS_ACCESS_REQUEST
                                                  (see clauses 8 and 25);
     MAP_AUTHENTICATE
                                                  (see clauses 8 and 25);
     MAP_SET_CIPHERING_MODE
                                                  (see clauses 8 and 25);
     MAP_FORWARD_NEW_TMSI
                                                  (see clauses 8 and 25);
     MAP_READY_FOR_SM
                                                  (see clauses 12 and 25).
At least one of the following services will certainly be used, and both may be used:
```

MAP_UNSTRUCTURED_SS_REQUEST (defined in clause 11); MAP UNSTRUCTURED SS NOTIFY (defined in clause 11).

22.10.2 Procedure in the MSC

The process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

```
Receive_Open_Ind
                                   see subclause 25.1.1;
Receive_Open_Cnf
                                   see subclause 25.1.2;
Page_MSC
                                   see subclause 25.3.1;
Search_For_MS_MSC
                                   see subclause 25.3.2;
Process_Access_Request_MSC
                                   see subclause 25.4.1.
```

The process in the MSC is shown in figure 22.10.2/1.

22.10.3 Procedure in the VLR

The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

```
Receive_Open_Ind
                                    see subclause 25.1.1;
Receive_Open_Cnf
                                    see subclause 25.1.2;
                                    see subclause 25.2.1;
Check_Indication
Check Confirmation
                                    see subclause 25.2.2.
```

The process in the VLR is shown in figure 22.10.3/1.

MSC Initiated USSD

If a USSD application in the MSC wishes to use the network initiated USSD procedure, and a connection to the MS does not exist then the MSC opens a dialogue with the VLR. This dialogue leads to the VLR performing page or search using the macro Start_USSD_VLR.

Macro Start_USSD_VLR

The macro invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Check_Confirmation see subclause 25.2.1;
Process_Access_Request_VLR see subclause 25.4.2.

The macro is shown in figure 22.10.3/2.

22.10.4 Procedure in the HLR

The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Ind see subclause 25.1.1;
Receive_Open_Cnf see subclause 25.1.2;
Check_Indication see subclause 25.2.1;
Check Confirmation see subclause 25.2.2.

The process in the primary HLR is shown in figures 22.10.4/1 and 22.10.4/2.

22.10.5 Procedure in the gsmSCF or secondary HLR

The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2;
Check_Confirmation see subclause 25.2.2.

The procedure in the gsmSCF or secondary HLR is shown in figure 22.10.5/1.




Figure 22.10.2/1 (sheet 1 of 4): Process NW_Init_USSD_MSC




Figure 22.10.2/1 (sheet 2 of 4): Process NW_Init_USSD_MSC




Figure 22.10.2/1 (sheet 3 of 4): Process NW_Init_USSD_MSC




Figure 22.10.2/1 (sheet 4 of 4): Process NW_Init_USSD_MSC




Figure 22.10.3/1 (sheet 1 of 5): Process NW_Init_USSD_VLR




Figure 22.10.3/1 (sheet 2 of 5): Process NW_Init_USSD_VLR




Figure 22.10.3/1 (sheet 3 of 5): Process NW_Init_USSD_VLR




Figure 22.10.3/1 (sheet 4 of 5): Process NW_Init_USSD_VLR




Figure 22.10.3/1 (sheet 5 of 5): Process NW_Init_USSD_VLR




Figure 22.10.3/2 (sheet 1 of 2): Macro Start_USSD_VLR




Figure 22.10.3/2 (sheet 2 of 2): Macro Start_USSD_VLR




Figure 22.10.4/1 (sheet 1 of 5): Process NW_Init_USSD_HLR




Figure 22.10.4/1 (sheet 2 of 5): Process NW_Init_USSD_HLR




Figure 22.10.4/1 (sheet 3 of 5): Process NW_Init_USSD_HLR




Figure 22.10.4/1 (sheet 4 of 5): Process NW_Init_USSD_HLR




Figure 22.10.4/1 (sheet 5 of 5): Process NW_Init_USSD_HLR




Figure 22.10.4/2: Macro Start_USSD_HLR




Figure 22.10.5/1 (sheet 1 of 2): Process NW_Init_USSD_gsmSCF_secondary_HLR




Figure 22.10.5/1 (sheet 2 of 2): Process NW_Init_USSD_gsmSCF_Secondary_HLR

22.11 Common macros for clause 22

The following macros are used for the description of more than one of the supplementary service processes described in clause 22.

22.11.1 SS Password handling macros

Macro Get_Password_MSC

This macro is used by the MSC to relay a request for password from the VLR to the MS, and to relay a response from the MS back to the VLR. The macro is shown in figure 22.11.1/1.

Macro Get_Password_VLR

This macro is used by the VLR to relay a request for password from the HLR to the MSC, and to relay a response from the MSC back to the HLR. The macro invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Check_Indication

see subclause 25.2.1.

The macro is shown in figure 22.11.1/2.

22.11.2 Void




Figure 22.11.1/1: Macro Get_Password_MSC




Figure 22.11.1/2: Macro Get_Password_VLR

Figure 22.11.2/1 void

Figure 22.11.2/2 void

Figure 22.11.2/3 void

Figure 22.11.2/4 void

Figure 22.11.2/5 void

22.12 Supplementary Service Invocation Notification procedure

22.12.1 General

The Supplementary Service Invocation Notification procedure is used to notify a gsmSCF about the invocation of a GSM Supplementary Service.

(defined in clause 11).

The supplementary service invocation notification procedure is shown in figure 22.12.1/1.

The following service is certainly used:

MAP_SS_INVOCATION_NOTIFY

MSC gsmSCF

- 1) MAP_SS_INVOCATION_NOTIFY_req/ind
- 2) MAP_SS_INVOCATION_NOTIFY_rsp/cnf

Figure 22.12.1/1: Message flow for supplementary service invocation notification

22.12.2 Procedure in the MSC

The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2;
Check Confirmation see subclause 25.2.2.

The supplementary service invocation notification process in the MSC is shown in figure 22.12.2/1.

22.12.3 Procedure in the gsmSCF

The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Receive_Open_Ind see subclause 25.1.1.

The supplementary service invocation notification process in the smSCF is shown in figure 22.12.3/1.




Figure 22.12.2/1: Process Notify_SS_Invocation_MSC




Figure 22.12.3/1: Process Note_SS_Invocation_gsmSCF


22.13 Activation of a CCBS request

22.13.1 General

The message flow to activate a CCBS request is shown in figure 22.13.1/1.

The following service is certainly used:

MAP_REGISTER_CC_ENTRY (defined in clause 11).



- 1) MAP_REGISTER_CC_ENTRY_req/ind
- 2) MAP_REGISTER_CC_ENTRY_rsp/cnf

Figure 22.13.1/1: Message flow to activate a CCBS request

22.13.2 Procedure in the VLR

The MAP process in the VLR to activate a CCBS request is shown in figure 22.13.2/1. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2; Check_Confirmation see subclause 25.2.2.

22.13.3 Procedure in the HLR

The MAP process in the HLR to activate a CCBS request is shown in figure 22.13.2/1.




Figure 22.13.2/1: Process Register_CC_Entry_VLR




Figure 22.13.3/1: Process Register_CC_Entry_HLR


22.14 Deactivation of a CCBS request

22.14.1 General

The message flow to deactivate a CCBS request is shown in figure 22.14.1/1.

The following service is certainly used:

MAP_ERASE_CC_ENTRY (defined in clause 11).



- 1) MAP_ERASE_CC_ENTRY_req/ind
- 2) MAP_ERASE_CC_ENTRY_rsp/cnf

Figure 22.14.1/1: Message flow to deactivate a CCBS request

22.14.2 Procedure in the VLR

The MAP process in the VLR to deactivate a CCBS request is shown in figure 22.14.2/1. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2; Check_Confirmation see subclause 25.2.2.

22.14.3 Procedure in the HLR

The MAP process in the HLR to deactivate a CCBS request is shown in figure 22.14.2/1.




Figure 22.14.2/1: Process Erase_CC_Entry_VLR




Figure 22.14.3/1: Process Erase_CC_Entry_HLR

23 Short message service procedures

23.1 General

The short message service procedures are used to control both mobile originated and mobile terminated short message transfer.

Four procedures exist for short message services:

- mobile originated short message service transfer;
- mobile terminated short message service transfer;
- short message alert procedure;
- short message delivery status report procedure.

The following application context refers to a complex MAP user consisting of several processes:

shortMessageGatewayContext.

This application context needs a co-ordinating process in the HLR. Additionally a co-ordinating process needed for the mobile originated situation in the MSC, because the A_CM_SERV_REQ message does not distinguish between mobile originated short message transfer and the short message alert procedures.

NOTE: the A_CM_SERV_REQ message is not used for SMS over GPRS. The modelling is based on the assumption that the SGSN will trigger the appropriate process, according to whether an RP_MO_DATA or an RP_SM_MEMORY_AVAILABLE is received over the LLC layer.

23.1.1 Mobile originated short message service Co-ordinator for the MSC

The process starts when the MSC receives an A_CM_SERV_REQ message (see 3GPP TS 24.008 [35]), with a CM service type indicating short message service, from the A-interface. The process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Process_Access_Request_MSC see subclause 25.4.1.

If the macro Process_Access_Request_MSC takes the "OK" exit (which means that the MSC has sent an A_CM_SERVICE_ACCEPT to the MS), , the MS initiates mobile originated short message transfer or sends an indication that it has memory available for more short messages.

The SMS Co-ordinator process in the MSC is shown in figure 23.1/1.

23.1.2 Short message Gateway Co-ordinator for the HLR

The process starts when the HLR receives a MAP_OPEN indication using when the application context shortMessageGatewayContext. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Receive_Open_Ind see subclause 25.1.1.

The SM Gateway Co-ordinator process in the HLR is shown in figure 23.1/2.

If the Receive_Open_Ind macro takes the Vr exit then HLR shall perform the MAP dialogue as specified for the appropriate application context version. Depending on the subscriber data, handling at the MAP user application level may be performed as specified in subclauses 23.3.2 and 23.5.2 of the present document:




Figure 23.1/1 (sheet 1 of 2): Process Co_SMS_MSC




Figure 23.1/1 (sheet 2 of 2): Process Co_SMS_MSC





Figure 23.1/2: Process Co_SM_Gateway_HLR

23.2 The mobile originated short message transfer procedure

The mobile originated short message service procedure is used to forward a short message from a mobile subscriber to a Service Centre. The message flow for the mobile originated short message service procedure is shown in figure 23.2/1.



- Short Message (3GPP TS 24.011 [37]). 1)
- 2) MAP_SEND_INFO_FOR_MO_SMS (*).
- 3) MAP_SEND_INFO_FOR_MO_SMS_ACK (*).
- 4) TCAP BEGIN (**)
- 4a) TCAP CONTINUE (**)
- MAP_MO_FORWARD_SHORT_MESSAGE. 4b)
- 5) Short message (3GPP TS 23.040).
- 6) 7) Short message Acknowledgement (3GPP TS 23.040).
- MAP_MO_FÖRWARD_SHÖRT_MESSAGE_ACK.
- 8) Short Message Acknowledgement (3GPP TS 24.011 [37]).
- Messages 2) and 3) are not used by the SGSN.
- lf a)

the capacity of a message signal unit in the lower layers of the protocol is enough to carry the content of the MAP_OPEN request and the content of the MAP_MO_FORWARD_SHORT_MESSAGE request in a single TC message

and

the Interworking MSC operator and the serving node (MSC or SGSN) operator agreed not to use the TCAP handshake countermeasure against SMS fraud for messages exchanged between their networks (see 3GPP TS 33.200 [34a])

the TCAP handshake may be omitted.

Figure 23.2/1: Mobile originated short message transfer

In addition the following MAP services are used:

```
MAP_PROCESS_ACCESS_REQUEST
                                           (see subclause 8.3); (*)
MAP_AUTHENTICATE
                                           (see subclause 8.5); (*)
MAP_SET_CIPHERING_MODE
                                           (see subclause 8.6); (*)
```

MAP_PROVIDE_IMSI (see subclause 8.9); (*)

MAP_CHECK_IMEI (see subclause 8.7);

MAP_FORWARD_NEW_TMSI (see subclause 8.9); (*)

MAP_TRACE_SUBSCRIBER_ACTIVITY (see subclause 9.1); (*)

MAP_READY_FOR_SM (see subclause 12.4).

(*) These services are not used by the SGSN.

23.2.1 Procedure in the serving MSC

Any CAMEL-specific handling defined in this subclause is omitted if the MSC does not support CAMEL control of MO SMS, or if the subscriber does not have a subscription for CAMEL control of MO SMS.

The process starts when the MSC receives a short message from the MS. The process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2;
Check_Indication see subclause 25.2.1;
Check Confirmation see subclause 25.2.2.

Sheet 1: If the MSC is integrated with the SMS-IWMSC, it communicates directly with the Short Message Service Centre (SMSC) using one of the protocols described in 3GPP TS 23.039 [25a]; otherwise it communicates with the SMS-IWMSC using MAP.

Sheet 3: If the capacity of a message signal unit in the lower layers of the protocol is enough to carry the content of the MAP_OPEN request and the content of the MAP_MO_FORWARD_SHORT_MESSAGE request in a single TC message, the test "Message segmentation needed" takes the "No" exit; otherwise the test takes the "Yes" exit.

Sheet 3:The decision box "TCAP Handshake required" takes the "yes" or "no" exit depending on agreements between the serving MSC's operator and the SMS-IWMSC's operator (see 3GPP TS 33.200 [34a]).

The mobile originated short message service process in the MSC is shown in figure 23.2/2.

23.2.2 Procedure in the VLR

Any CAMEL-specific handling defined in this subclause is omitted if the VLR does not support CAMEL control of MO SMS.

The process starts when the VLR receives a dialogue opening request followed by a MAP_PROCESS_ACCESS_REQUEST including a CM service type Short Message Service. The process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Ind see subclause 25.1.1;
Check_Indication see subclause 25.2.1;
Process_Access_Request_VLR see subclause 25.4.2.

The mobile originated short message transfer process in the VLR is shown in figure 23.2/3.

23.2.3 Procedure in the SGSN

Any CAMEL-specific handling defined in this subclause is omitted if the SGSN does not support CAMEL control of MO SMS, or if the subscriber does not have a subscription for CAMEL control of MO SMS.

The process starts when the SGSN receives a short message received from the MS over the Gb interface. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2;

Check_Confirmation see subclause 25.2.2.

Sheet 2: If the capacity of a message signal unit in the lower layers of the protocol is enough to carry the content of the MAP_OPEN request and the content of the MAP_MO_FORWARD_SHORT_MESSAGE request in a single TC message, the test "Message segmentation needed" takes the "No" exit; otherwise the test takes the "Yes" exit.

Sheet 2:The decision box "TCAP Handshake required" takes the "yes" or "no" exit depending on agreements between the serving SGSN's operator and the SMS-IWMSC's operator (see 3GPP TS 33.200 [34a]).

The mobile originated short message service process in the SGSN is shown in figure 23.2/4.

23.2.4 Procedure in the SMS Interworking MSC (SMS-IWMSC)

This procedure applies only when the SMS-IWMSC is not integrated with the serving MSC or SGSN.

The process starts when the SMS-IWMSC receives a dialogue opening request with the application context shortMsgMO-RelayContext. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Ind see subclause 25.1.1;
Check_Indication see subclause 25.2.1.

Sheet 1:The decision box "TCAP Handshake required" takes the "yes" or "no" exit depending on agreements between the SMS-IWMSC's operator and the serving node's operator (see 3GPP TS 33.200 [34a]).

The mobile originated short message service transfer process in the SMS-IWMSC is shown in figure 23.2/5.




Figure 23.2/2 (sheet 1 of 4): Process MO_SM_MSC




Figure 23.2/2 (sheet 2 of 4): Process MO_SM_MSC




Figure 23.2/2 (sheet 3 of 4): Process MO_SM_MSC




Figure 23.2/2 (sheet 4 of 4): Process MO_SM_MSC




Figure 23.2/3 (sheet 1 of 2): Process MOSM_VLR




Figure 23.2/3 (sheet 2 of 2): Process MO_SM_VLR




Figure 23.2/4 (sheet 1 of 3): Process MO_SM_SGSN




Figure 23.2/4 (sheet 2 of 3): Process MO_SM_SGSN




Figure 23.2/4 (sheet 3 of 3): Process MO_SM_SGSN




Figure 23.2/5 (sheet 1 of 2): Process MO_SM_IWMSC




Figure 23.2/5 (sheet 2 of 2): Process MO_SM_IWMSC

23.3 The mobile terminated short message transfer procedure

The mobile terminated short message transfer procedure is used for forwarding a short message or several short messages from a Service Centre to a mobile subscriber. The message flow for the mobile terminated short message procedure for a single short message transfer is shown in figure 23.3/1.




Figure 23.3/1: Mobile terminated short message service procedures

- 1) Short Message (3GPP TS 23.040).
- 2) MAP_SEND_ROUTING_INFO_FOR_SM.
- 3) MAP_SEND_ROUTING_INFO_FOR_SM_ACK.
- 4) TCAP BEGIN (***)
- 4a) TCAP CONTINUE (***)
- 4b) MAP_MT_FORWARD_SHORT_MESSAGE.
- 5) MAP_SEND_INFO_FOR_MT_SMS (*).
- 5a) MAP_CONTINUE_CAMEL_SMS_HANDLING (*)(**)
- 5b) MAP_SEND_INFO_FOR_MT_SMS (*)(**)
- 6) MAP_PAGE/MAP_SEARCH_FOR_MOBILE_SUBSCRIBER (*).
- 7) Page (3GPP TS 24.008 [35]).
- 8) Page response (3GPP TS 24.008 [35]).
- 9) MAP_PROCESS_ACCESS_REQUEST_ACK and
- MAP_SEARCH_FOR_MOBILE_SUBSCRIBER_ACK (*).

 MAP_SEND_INFO_FOR_MT_SMS_ACK (*).
- 11) Short Message (3GPP TS 24.011 [37])
- 12) Short Message Acknowledgement (3GPP TS 24.011 [37]).
- 13) MAP_MT_FORWARD_SHORT_MESSAGE_ACK.
- 14) Short Message Acknowledgement (3GPP TS 23.040).
- (*) Messages 5), 5a), 5b), 6), 9), and 10) are not used by the SGSN.
- (**) These messages are used only for a subscriber provisioned with MT-SMS-CSI in the VLR.
- (***) I1
 - a)
 - the capacity of a message signal unit in the lower layers of the protocol is enough to carry the content of the MAP_OPEN request and the content of the MAP_MT_FORWARD_SHORT_MESSAGE request in a single TC message,
 - and
 - b)

the SMS Gateway MSC operator and the serving node (MSC or SGSN) operator agreed not to use the TCAP handshake countermeasure against SMS fraud for messages exchanged between their networks (see 3GPP TS 33.200 [34a]) then

the TCAP handshake may be omitted.

The message flow for the mobile terminated short message procedure for multiple short message transfer is shown in figure 23.3/2.




Figure 23.3/2: Mobile terminated short message procedure for multiple short message transfer

- 1) Short Message (3GPP TS 23.040).
- 2) MAP_SEND_ROUTING_INFO_FOR_SM.
- 3) MAP_SEND_ROUTING_INFO_FOR_SM_ACK.
- 4)
- TCAP BEGIN (***)
 TCAP CONTINUE (***) 4a
- MAP_MT_FORWARD_SHORT_MESSAGE (note 1). 4b)
- MAP_SEND_INFO_FOR_MT_SMS (*). 5)
- MAP_CONTINUE_CAMEL_SMS_HANDLING (*)(**) 5a)
- 5b) MAP_SEND_INFO_FOR_MT_SMS (*)(**)
- MAP_PAGE/MAP_SEARCH_FOR_MOBILE_SUBSCRIBER (*). 6)
- Page (3GPP TS 48.008 [49]). 7)
- 8) Page response (3GPP TS 24.008 [35]).
- 9) MAP_PROCESS_ACCESS_REQUEST_ACK and
 - MAP_SEARCH_FOR_MOBILE_SUBSCRIBER_ACK (*).
- MAP_SEND_INFO_FOR_MT_SMS_ACK (*). 10)
- Short Message (3GPP TS 24.011 [37]). 11)
- Short Message Acknowledgement (3GPP TS 24.011 [37]). 12)
- MAP_MT_FÖRWARD_SHÖRT_MESSAGE_ACK. 13)
- 14) Short Message Acknowledgement (3GPP TS 23.040).
- 15) Short Message (3GPP TS 23.040).

- 16) MAP_MT_FORWARD_SHORT_MESSAGE (note 2).
- 17) Short Message (3GPP TS 24.011 [37]).
- 18) Short Message Acknowledgement (3GPP TS 24.011 [37]).
- 19) MAP_MT_FORWARD_SHORT_MESSAGE_ACK.
- 20) Short Message Acknowledgement (3GPP TS 23.040).
- (*) Messages 5), 5a), 5b) 6), 9), and 10) are not used by the SGSN.
- (**) These messages are used only for a subscriber provisioned with MT-SMS-CSI in the VLR.

(***) I

- a) the capacity of a message signal unit in the lower layers of the protocol is enough to carry the content of the MAP_OPEN request and the content of the MAP_MT_FORWARD_SHORT_MESSAGE request in a single TC message,
- b) the SMS Gateway MSC operator and the serving node (MSC or SGSN) operator agreed not to use the TCAP handshake countermeasure against SMS fraud for messages exchanged between their networks (see 3GPP TS 33.200 [34a]) then the TCAP handshake may be omitted.

NOTE 1: The 'More Messages To Send' flag is TRUE. NOTE 2: The 'More Messages To Send' flag is FALSE.

In the multiple short message transfer the service MAP_MT_FORWARD_SHORT_MESSAGE can be used several times. However, the short message transfer is always acknowledged to the Service Centre before the next short message is sent.

In addition the following MAP services are used:

MAP PROCESS ACCESS REQUEST (see subclause 8.3); (*) MAP PAGE (see subclause 8.2); (*) MAP_SEARCH_FOR_MS (see subclause 8.2); (*) MAP_AUTHENTICATE (see subclause 8.5); (*) MAP_SET_CIPHERING_MODE (see subclause 8.6); (*) MAP_CHECK_IMEI (see subclause 8.7); MAP_FORWARD_NEW_TMSI (see subclause 8.9); (*) MAP_REPORT_SM_DELIVERY_STATUS (see subclause 12.3); MAP_INFORM_SERVICE_CENTRE (see subclause 12.6); MAP TRACE SUBSCRIBER ACTIVITY (see subclause 9.1); (*) MAP_READY_FOR_SM (see subclause 12.4). (*) These services are not used by the SGSN.

23.3.1 Procedure in the SMS-GMSC

Any CAMEL-specific handling described in this subclause is omitted if the SMS-GMSC does not support CAMEL. CAMEL-specific handling is invoked only if the SMS-GMSC is integrated with the VMSC.

The process starts when the SMS-GMSC receives an SC_RP_MT_DATA indication from a Service Centre. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2;
Check_Confirmation see subclause 25.2.2.

Process MT_SM_GMSC sheet 1: If the MAP_SEND_ROUTING_INFO_FOR_SM confirmation included an LMSI, it may be included in the sm-RP-DA information field of the first MAP_MT_FORWARD_SHORT_MESSAGE request sent to the serving MSC. In this case, the IMSI shall be included in the Destination Reference of the MAP_OPEN request. The SMS-GMSC shall not send an LMSI to an SGSN. If the SMS-GMSC does not send an LMSI to the

serving node, the sm-RP-DA information field in the first MAP_MT_FORWARD_SHORT_MESSAGE request sent to the serving MSC or SGSN shall contain the IMSI, and the Destination Reference in the MAP_OPEN request shall not be present. The parameter SM_RP_OA shall contain the Service Centre address.

Process MT_SM_GMSC sheet 1: The indication of which number belongs to the SGSN and which to the MSC, received from the HLR in the MAP_SEND_ROUTING_INFO_FOR_SM confirm (see subclause 23.3.2) will enable the SMS-GMSC to map the causes received from one or both serving nodes into the appropriate causes for non GPRS, GPRS or both, and send them to the SC and the HLR.

Process MT_SM_GMSC sheet 2: The SMS-GMSC maps "Unexpected data value" and "System failure" MAP errors from the serving node to a "System failure" RP_ERROR error cause. The mapping between other MAP error causes and the RP_ERROR error cause is given in 3GPP TS 23.040 [26] and 3GPP TS 24.011 [37].

Process MT_SM_GMSC sheet 2: If the SMS-GMSC receives both MSC and SGSN numbers from the HLR as routeing information, it may choose which serving node to use for the first delivery attempt.

Process MT_SM_GMSC sheet 2: If the SMS-GMSC makes two delivery attempts, it may report the result of each delivery attempt to the HLR according to the conditions described below.

Procedure MT_SM_Delivery_Attempt_GMSC sheet 1: if the macro MT_SM_Transfer_MSC takes the Error exit, the SMS-GMSC maps the MAP User Error to the corresponding SC_RP error, as defined in 3GPP TS 23.040 [26].

Procedure MT_SM_Delivery_Attempt_GMSC sheet 3: The decision box "TCAP Handshake required" takes the "yes" or "no" exit depending on agreements between the GMSC's operator and the serving node's operator (see 3GPP TS 33.200 [34a]).

Procedure MT_SM_Delivery_Attempt_GMSC sheet 1, sheet 2, sheet 4, sheet 5: The SMS-GMSC invokes the macro Report_SM_Delivery_Stat_GMSC if:

- the reason received from the serving node for failure to deliver the message is absent subscriber_SM, unidentified subscriber or SM delivery failure with error cause "MS memory capacity exceeded", and the SC address is not yet included in the MWD set, or
- the reason received from the serving node for failure to deliver the message is absent subscriber_SM, unidentified subscriber or SM delivery failure with error cause MS memory capacity exceeded, and the corresponding flag in the HLR (as indicated in the information received in the MAP_INFORM_ SERVICE_CENTRE) is not set, or
- the reason received from the serving node (MSC or SGSN) for failure to deliver the message is absent subscriber_SM and the absent subscriber diagnostic is different from the absent subscriber diagnostic received in the MAP_INFORM_ SERVICE_CENTRE.

Procedure MT_SM_Delivery_Attempt_GMSC sheet 1, sheet 2, sheet 4, sheet 5: If absent subscriber diagnostic information (see 3GPP TS 23.040 [26]) is included with the absent subscriber_SM error indication then the SMS-GMSC relays this information to the HLR using the MAP_REPORT_SM_DELIVERY_STATUS service.

Procedure MT_SM_Delivery_Attempt_GMSC sheet 1, sheet 4: The More Messages To Send flag is set to TRUE or FALSE according to the information received from the Service Centre.

Procedure MT_SM_Delivery_Attempt_GMSC sheet 3: If the capacity of a message signal unit in the lower layers of the protocol is enough to carry the content of the MAP_OPEN request and the content of the MAP_MT_FORWARD_SHORT_MESSAGE request in a single TC message, the test "Message segmentation needed" takes the "No" exit; otherwise the test takes the "Yes" exit.

The mobile terminated short message transfer process in the SMS-GMSC is shown in figure 23.3/3. The procedure MT_SM_Delivery_Attempt_GMSC is shown in figure 23.3/4. The macro MT_SM_Transfer_MSC is shown in figure 23.3/7.

23.3.2 Procedure in the HLR

The process starts when the HLR receives a MAP_SEND_ROUTING_INFO_FOR_SM indication from the SMS-GMSC. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Check_Indication see subclause 25.2.1.

Sheet 3: If the SMS-GMSC does not support GPRS functionality, it uses the protocol defined in the Release 96 version of this specification. The parameter "msc-Number" in "RoutingInfoForSM-Res" in the Release 96 version of the protocol definition corresponds to the parameter "networkNode-Number" in "RoutingInfoForSM-Res" in the Release 97 (and later) version of the protocol definition; therefore if the HLR populates the parameter "networkNode-Number" with the SGSN number, the Release 96 SMS-GMSC will interpret the SGSN number as an MSC number. If the HLR populates the "gprsNodeIndicator" parameter in the MAP_SEND_ROUTING_INFO_FOR_SM response, a Release 96 SMS-GMSC will silently discard the parameter.

Sheet 5: If the HLR received a LMSI from the VLR at location updating, it shall include the LMSI in the MAP_SEND_ROUTING_INFO_FOR_SM response only if the MAP_SEND_ROUTING_INFO_FOR_SM response also includes the MSC number.

The mobile terminated short message transfer process in the HLR is shown in figure 23.3/5.

23.3.3 Procedure in the Serving MSC

Any CAMEL-specific handling defined in this subclause is omitted if the MSC does not support CAMEL control of MT SMS, or if the subscriber does not have a subscription for CAMEL control of MT SMS.

The process starts when the MSC receives a dialogue opening request with the application context shortMsgMT-RelayContext. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Ind see subclause 25.1.1;
Check Indication see subclause 25.2.1.

The mobile terminated short message transfer process in the serving MSC is shown in figure 23.3/6

Procedure MT_SM_VMSC sheet 1: The decision box "TCAP Handshake required" takes the "yes" or "no" exit depending on agreements between the Serving MSC's operator and the SMS Gateway MSC's operator (see 3GPP TS 33.200 [34a]).

The macro MT_SM_Transfer_MSC may be invoked either in a stand-alone serving MSC or in a serving MSC which is integrated with the SMS-GMSC. It is used to transfer the first MT short message of a possible sequence of messages. The macro invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Check_Confirmation see subclause 25.2.2.

Page_MSC see subclause 25.3.1;

Search_for_MS_MSC see subclause 25.3.2;

Process_Access_Request_MSC see subclause 25.4.1;

Trace_Subscriber_Activity_MSC see subclause 25.9.1.

The macro MT_SM_Transfer_MSC is shown in figure 23.3/7. The macro Check_Subscr_Identity_For_MT_SMS is shown in figure 23.3/8.

23.3.4 Procedure in the VLR

Any CAMEL-specific handling defined in this subclause is omitted if the VLR does not support CAMEL control of MT SMS.

The process starts when the VLR receives a dialogue opening request from the MSC. The process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Ind see subclause 25.1.1;
Check_Indication see subclause 25.2.1;
Check_Confirmation see subclause 25.2.2;
Process_Access_Request_VLR see subclause 25.4.2.

The mobile terminated short message transfer process in the VLR is shown in figure 23.3/9.

23.3.5 Procedure in the SGSN

Any CAMEL-specific handling defined in this subclause is omitted if the SGSN does not support CAMEL control of MT SMS, or if the subscriber does not have a subscription for CAMEL control of MT SMS.

The process starts when the SGSN receives a dialogue opening request with the application context shortMsgMT-RelayContext. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Ind see subclause 25.1.1;
Check_Indication see subclause 25.2.1.

The mobile terminated short message transfer process in the SGSN is shown in figure 23.3/10.

Procedure MT_SM_SGSN sheet 1: The decision box "TCAP Handshake required" takes the "yes" or "no" exit depending on agreements between the Serving SGSN's operator and the SMS Gateway MSC's operator (see 3GPP TS 33.200 [34a]).

The macro MT_SM_Transfer_SGSN is used to transfer the first MT short message of a possible sequence of messages. It is shown in figure 23.3/11.

The macro Check_Subscr_Identity_For_MT_SMS is shown in figure 23.3/8. The page and search procedures are shown in figures 23.3/12 and 23.3/13.




Figure 23.3/3 (sheet 1 of 2): Process MT_SM_GMSC




Figure 23.3/3 (sheet 2 of 2): Process MT_SM_GMSC




Figure 23.3/4 (sheet 1 of 8): Procedure MT_SM_Delivery_Attempt_GMSC




Figure 23.3/4 (sheet 2 of 8): Procedure MT_SM_Delivery_Attempt_GMSC




Figure 23.3/4 (sheet 3 of 8): Procedure MT_SM_Delivery_Attempt_GMSC




Figure 23.3/4 (sheet 4 of 8): Procedure MT_SM_Delivery_Attempt_GMSC




Figure 23.3/4 (sheet 5 of 8): Procedure MT_SM_Delivery_Attempt_GMSC




Figure 23.3/4 (sheet 6 of 8): Procedure MT_SM_Delivery_Attempt_GMSC




Figure 23.3/4 (sheet 7 of 8): Procedure MT_SM_Delivery_Attempt_GMSC




Figure 23.3/4 (sheet 8 of 8): Procedure MT_SM_Delivery_Attempt_GMSC




Figure 23.3/5 (sheet 1 of 5): Process MT_SM_HLR




Figure 23.3/5 (sheet 2 of 5): Process MT_SM_HLR




Figure 23.3/5 (sheet 3 of 5): Process MT_SM_HLR




Figure 23.3/5 (sheet 4 of 5): Process MT_SM_HLR




Figure 23.3/5 (sheet 5 of 5): Process MT_SM_HLR




Figure 23.3/6 (sheet 1 of 4): Procedure MT_SM_VMSC




Figure 23.3/6 (sheet 2 of 4): Procedure MT_SM_VMSC




Figure 23.3/6 (sheet 3 of 4): Procedure MT_SM_VMSC




Figure 23.3/6 (sheet 4 of 4): Procedure MT_SM_VMSC




Figure 23.3/7 (sheet 1 of 4): Macro MT_SM_Transfer_MSC




Figure 23.3/7 (sheet 2 of 4): Macro MT_SM_Transfer_MSC




Figure 23.3/7 (sheet 3 of 4): Macro MT_SM_Transfer_MSC




Figure 23.3/7 (sheet 4 of 4): Macro MT_SM_Transfer_MSC




Figure 23.3/8: Macro Check_Subscr_Identity_For_MT_SMS




Figure 23.3/9 (sheet 1 of 3): Process MT_SM_VLR




Figure 23.3/9 (sheet 2 of 3): Process MT_SM_VLR




Figure 23.3/9 (sheet 3 of 3): Process MT_SM_VLR




Figure 23.3/10 (sheet 1 of 4): Process MT_SM_SGSN




Figure 23.3/10 (sheet 2 of 4): Process MT_SM_ SGSN




Figure 23.3/10 (sheet 3 of 4): Process MT_SM_ SGSN




Figure 23.3/10 (sheet 4 of 4): Process MT_SM_ SGSN




Figure 23.3/11 (sheet 1 of 3): Macro MT_SM_TRANSFER_SGSN




Figure 23.3/11 (sheet 2 of 3): Macro MT_SM_TRANSFER_SGSN




Figure 23.3/11 (sheet 3 of 3): Macro MT_SM_TRANSFER_SGSN




Figure 23.3/12 (sheet 1 of 1): Procedure Page_SMS_SGSN





Figure 23.3/13 (sheet 1 of 1): Procedure Search_SMS_SGSN

23.4 The Short Message Alert procedure

The Short Message Alert procedure is used to alert the Service Centre when the mobile subscriber is active after a short message transfer has failed because the mobile subscriber is not reachable, or when the MS has indicated that it has memory capacity to accept a short message.


The message flow for the Short Message Alert procedure for the case when the mobile subscriber was not reachable is shown in figure 23.4/1.



- 1) CM Service Request (**), Page response or Location Updating (3GPP TS 24.008 [35]).
- MAP_PROCESS_ACCESS_REQUEST / MAP_UPDATE_LOCATION_AREA (**). 2)
- MAP_READY_FOR_SM (Mobile Present) / MAP_UPDATE_LOCATION / 3) Supplementary Service Control Request (*).
- MAP_READY_FOR_SM_ACK (*). 4)
- MAP_ALERT_SERVICE_CENTRE (notes 1 and 2). 5)
- Alert Service Centre (3GPP TS 23.040). 6)
- MAP_ALERT_SERVICE_CENTRE_ACK. 7)
- NOTE 1: To all Service Centres in the Message Waiting List.
- The HLR initiates the MAP_ALERT_SERVICE_CENTRE service only if the MS Memory Capacity Exceeded flag is clear.
- For GPRS, messages 3) and 4) are sent/received by the SGSN. (*) (**)
- These messages are not used by the SGSN.

Figure 23.4/1: Short message alert procedure (Mobile is present)

The message flow for the Short Message Alert procedure for the case where the MS indicates that it has memory capacity to accept one or more short messages is shown in figure 23.4/2.



- SM memory capacity available (3GPP TS 24.011 [37]). 1)
- 2) MAP_READY_FOR_SM (Memory Available) (*).
- 3) MAP_READY_FOR_SM (Memory Available) (**).
- 4) MAP_READY_FOR_SM_ACK (**).
- 5) MAP_READY_FOR_SM_ACK (*).
- SM memory capacity available (Acknowledge) (3GPP TS 24.011 [37]). 6)
- MAP_ALERT_SERVICE_CENTRE (note). Alert Service Centre (3GPP TS 23.040). 7)
- 8)
- MAP_ALERT_SERVICE_CENTRE_ACK. 9)
- NOTE: To all Service Centres in the Message Waiting List.
- Messages 2) and 5) are not used by the SGSN.
- (*) (**) For GPRS, messages 3) and 4) are sent/received by the SGSN.


Figure 23.4/2: Short message alert procedure (MS memory capacity available)

In addition the following MAP services are used in the MS memory available case:

(see subclause 8.3); (*)
(see subclause 8.5); (*)
(see subclause 8.6); (*)
(see subclause 8.9); (*)
(see subclause 8.7);
(see subclause 8.9); (*)
(see subclause 9.1). (*)

(*) These services are not used by the SGSN.

The Short Message Alert procedure when the MS indicates successful transfer after polling is shown in figure 23.4/3.



- 1) MAP_REPORT_SM_DELIVERY_STATUS (Successful Transfer).
- 2) MAP_REPORT_SM_DELIVERY_STATUS_ACK.
- MAP_ALERT_SERVICE_CENTRE (note).
- 4) Alert Service Centre (3GPP TS 23.040).
- 5) MAP_ALERT_SERVICE_CENTRE_ACK.

NOTE: To all Service Centres in the Message Waiting List.

Figure 23.4/3: Short message alert procedure (Successful transfer after polling)

23.4.1 Procedure in the Serving MSC – the MS has memory available

The process starts when the MSC receives a notification from the MS that it has memory available. The process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Check_Confirmation see subclause 25.2.2.

The short message alert process in the MSC for the MS memory capacity available case is shown in figure 23.4/4.

23.4.2 Procedures in the VLR

23.4.2.1 The Mobile Subscriber is present

If the VLR successfully handles a MAP_PROCESS_ACCESS_REQUEST indication or a MAP_UPDATE_LOCATION_AREA indication while the MS Not Reachable Flag (MNRF) is set, the VLR sends a MAP_READY_FOR_SM request to the HLR. The Alert Reason is set to indicate that the mobile subscriber is present for non GPRS. If authentication fails during the handling of a MAP_PROCESS_ACCESS_REQUEST indication or a MAP_UPDATE_LOCATION_AREA indication, the VLR shall not send a MAP_READY_FOR_SM request to the HLR. The process in the VLR is described in detail in subclause 25.10.1.

23.4.2.2 The MS has memory available

The process starts when the VLR receives dialogue opening request followed by a MAP_PROCESS_ACCESS_REQUEST indication including a CM service type Short Message Service. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Ind see subclause 25.1.1;

Receive_Open_Cnf see subclause 25.1.2;

Check_Indication see subclause 25.2.1;
Check Confirmation see subclause 25.2.2.

The short message alert process in the VLR for the MS memory capacity available case is shown in figure 23.4/5.

23.4.3 Procedures in the SGSN

23.4.3.1 The Mobile Subscriber is present

If the SGSN successfully handles a Page response, Attach request or Routing Area Update request message (3GPP TS 24.008 [35]), while the MS Not Reachable for GPRS (MNRG) flag is set, the SGSN sends a MAP_READY_FOR_SM request to the HLR. The Alert Reason is set to indicate that the mobile subscriber is present for GPRS. If authentication fails during the handling of a Page response, Attach request or Routing Area Update request, the SGSN shall not send a MAP_READY_FOR_SM request to the HLR

The process in the SGSN is described in detail in subclause 25.10.23.

23.4.3.2 The Mobile Equipment has memory available

The process starts when the SGSN receives an RP_SM_MEMORY_AVAILABLE indication from the MS. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2; Check_Confirmation see subclause 25.2.2.

The short message alert procedure in the SGSN for the MS memory capacity available case is shown in figure 23.4/6.

23.4.4 Procedure in the HLR

The process starts when the HLR receives a dialogue opening request using the application context mwdMngtContext. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Ind see subclause 25.1.1;
Check_Indication see subclause 25.2.1;
Alert_Service_Centre_HLR see subclause 25.10.3.

Sheet 1: If the dialogue opening request is from an SGSN, version 2 and version 1 of the application context are not applicable.

The short message alert process in the HLR is shown in figure 23.4/7.

23.4.5 Procedure in the SMS Interworking MSC

The process starts when the SMS-IWMSC receives a dialogue opening request using the application context shortMsgAlertContext. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Ind see subclause 25.1.1;
Check_Indication see subclause 25.2.1.

The short message alert process in the SMS-IWMSC is shown in figure 23.4/8.




Figure 23.4/4: Procedure SM_Alert_MSC




Figure 23.4/5 (sheet 1 of 2): Procedure SM_Alert_VLR




Figure 23.4/5 (sheet 2 of 2): Procedure SM_Alert_VLR




Figure 23.4/6 (sheet 1 of 2): Process SM_Alert_SGSN




Figure 23.4/6 (sheet 2 of 2): Process SM_Alert_SGSN




Figure 23.4/7 (sheet 1 of 2): Process SM_Alert_HLR




Figure 23.4/7 (sheet 2 of 2): Process SM_Alert_HLR





Figure 23.4/8: Process Alert_SC_IWMSC

23.5 The SM delivery status report procedure

The SM delivery status report procedure is used:

- to set the Service Centre address into the message waiting list in the HLR after short message delivery has failed because the subscriber is absent or unidentified or the memory capacity is exceeded. The procedure sets:
 - the Memory Capacity Exceeded Flag (MCEF) in the HLR if the MS memory does not have room for more messages;
 - and/or the MS Not Reachable Flag for non-GPRS if there is no record for the subscriber in the VLR or the subscriber does not respond to paging for delivery via the MSC;
 - and/or the MS Not Reachable for GPRS (MNRG) flag if there is no record for the subscriber in the SGSN unidentified or the subscriber does not respond to paging for delivery via the SGSN.
- to report to the HLRthat delivery has succeeded. The conditions for report of a successful delivery are described in subclause 23.3.1.

The message flow for the SM delivery status report procedure is shown in figure 23.5/1.



- MAP_MT_FORWARD_SHORT_MESSAGE_ACK/_NACK (Absent subscriber_SM, unidentified subscriber or memory capacity exceeded).
- 2) MAP_REPORT_SM_DELIVERY_STATUS.
- 3) MAP_REPORT_SM_DELIVERY_STATUS_ACK.
- 4) Short Message Negative Acknowledgement (3GPP TS 23.040).

Figure 23.5/1: Short message delivery status report procedure

23.5.1 Procedure in the SMS-GMSC

The conditions for the GMSC to invoke the short message delivery status report procedure are specified in subclause 23.3.1.

The short message delivery status report macro in the SMS-GMSC is shown in figure 23.5/2.

23.5.2 Procedure in the HLR

When the HLR receives a MAP_REPORT_SM_DELIVERY_STATUS indication, it acts as described in subclause 23.6, macro Report_SM_Delivery_Stat_HLR.

The short message delivery status report process in the HLR is shown in figure 23.5/3.




Figure 23.5/2: Macro Report_SM_Delivery_Stat_GMSC




Figure 23.5/3: Process SM_Delivery_Status_Report_HLR

23.6 The macro Report_SM_Delivery_Stat_HLR

This macro is invoked when the HLR receives a MAP_REPORT_SM_DELIVERY_STATUS indication from the SMS-GMSC. The macro invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Check_Indication see subclause 25.2.1;
Alert_Service_Centre_HLR see subclause 25.10.3.

Sheet 1: If the MAP_REPORT_SM_DELIVERY_STATUS indication did not include the GPRS support indicator, the HLR deduces the domain for which the delivery report applies as follows:

- if the subscriber is a GPRS-only subscriber, the report applies for GPRS;
- if the subscriber is a non-GPRS-only subscriber, the report applies for non-GPRS;
- if the subscriber is a GPRS and non-GPRS subscriber and the subscription option for MT SMS delivery when the SMS-GMSC does not support GPRS is set to "Delivery via the SGSN", the report applies for GPRS;
- if the subscriber is a GPRS and non-GPRS subscriber and the subscription option for MT SMS delivery when the SMS-GMSC does not support GPRS is set to "Delivery via the MSC", the report applies for non-GPRS;

The short message delivery status report macro in the HLR is shown in figure 23.6/1.




Figure 23.6/1 (sheet 1 of 2): Macro Report_SM_Delivery_Stat_HLR




Figure 23.6/1 (sheet 2 of 2): Macro Report_SM_Delivery_Stat_HLR

24 GPRS process description

The MAP GPRS procedures are used for the Network Requested PDP-Context Activation procedures.

The stage 2 specification for General Packet Radio Service (GPRS) is in 3GPP TS 23.060 [104].

24.1 Procedure for retrieval of routeing information for GPRS

24.1.1 Process in the GGSN

The MAP process in the GGSN to request routeing information for a network requested PDP context activation is shown in figure 24.1/2. The MAP process invokes macros not defined in this clause; the definition of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2; Check_Confirmation see subclause 25.2.2.

24.1.2 Process in the HLR

The MAP process in the HLR to provide routing information for a network-requested PDP context activation is shown in figure 24.1/1. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Ind see subclause 25.1.1;
Check_Indication see subclause 25.2.1.




Figure 24.1/1: Process SRI_GPRS_GGSN




Figure 24.1/2: Process SRI_GPRS_HLR

24.2 Procedure for reporting failure to establish a network requested PDP context

24.2.1 Process in the GGSN

The MAP process in the GGSN to report the failure to establish a network requested PDP context is shown in figure 24.2/2. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2; Check_Confirmation see subclause 25.2.2.

24.2.2 Process in the HLR

The MAP process in the HLR to handle a notification from the GGSN that a network requested PDP context could not be established is shown in figure 24.2/2. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Ind see subclause 25.1.1;

Check Indication see subclause 25.2.1.




Figure 24.2/1: Process Failure_Report_GGSN




Figure 24.2/2: Process Failure_Report_HLR

24.3 Procedure for reporting that an MS has become reachable for GPRS

24.3.1 Process in the HLR

The MAP process in the HLR to report that an MS is reachable for GPRS is shown in figure 24.3/1. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2; Check_Confirmation see subclause 25.2.2.

24.3.2 Process in the GGSN for Note Ms Present For Gprs

The MAP process in the GGSN to handle a notification that the subscriber is present for GPRS again is shown in figure 24.3/2. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Ind see subclause 25.1.1;

Check_Indication see subclause 25.2.1.




Figure 24.3/1: Process Note_MS_Present_For_GPRS_HLR




Figure 24.3/2: Process Note_MS_Present_For_GPRS_GGSN

24A CSE interrogation and control of subscriber data

24A.1 General

The MAP procedures for interrogation and control of subscriber data are used to allow the CSE:

- to retrieve subscriber data from the HLR;
- to modify subscriber data in the HLR;
- to receive notification from the HLR when there is a change in subscriber data;
- to request information about the location of a subscriber from the HLR or the GMLC;
- to request information about the state of a subscriber from the HLR.

The following application context refers to a complex MAP user consisting of several processes:

- anyTimeInfoHandlingContext

This application context needs a co-ordinating process in the HLR.

The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Receive_Open_Ind see subclause 25.1.1;

The Any Time Info Handling Co-ordinator process in the HLR is shown in figure 24A.1/1.




Figure 24A.1/1: Process Co_ATIH_HLR

24A.2 Any Time Subscription Interrogation procedure

24A.2.1 General

The message flow for successful retrieval of subscription information related to an any time subscription interrogation from the CAMEL server are shown in figure 24A.1/1. In an IP Multimedia Core Network, an IM-SSF can take on the role of a gsmSCF for this procedure (see 3GPP TS 23.278 [125]).




Figure 24A.2/1: Message flow for any time subscription interrogation

The following MAP service is used to retrieve requested information:

MAP_ANY_TIME_SUBSCRIPTION_INTERROGATION see subclause 8.11.3.

24A.2.2 Process in the gsmSCF

The MAP process in the gsmSCF to obtain subscription information in response to a request from the application process in the gsmSCF is shown in figure 24A.2/2. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2; Check_Confirmation see subclause 25.2.2

24A.2.3 Process in the HLR

The MAP process in the HLR to provide subscription information in response to an interrogation from the CAMEL server is shown in figure 24A.2/3. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Check_Indication see subclause 25.2.2

If the MAP_ANY_TIME_SUBSCRIPTION_INTERROGATION service response cannot be carried in a single TC-Result component, it is carried in one or more TC-Result-NL components (each sent in a TC-CONTINUE), followed by a TC-Result-L component in a TC-END message.




Figure 24A.2/2: Process ATSI_gsmSCF




Figure 24A.2/3: Process ATSI_HLR

24A.3 Any Time Modification procedure

24A.3.1 General

The message flow for successful modification of subscription information related to an any time modification request from the CAMEL server is shown in figure 24A.3/1




Figure 24A.3/1: Message flow for any time modification

The following MAP service is used to modify subscription information:

MAP_ANY_TIME_MODIFICATION

see subclause 8.11.4.

24A.3.2 Process in the gsmSCF

The MAP process in the gsmSCF to modify subscription information in response to a request from the application process in the gsmSCF is shown in figure 24A.3/2. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2; Check Confirmation see subclause 25.2.2

24A.3.3 Process in the HLR

The MAP process in the HLR to modify subscriber information in response to a modification request from the CAMEL server is shown in figure 24A.3/3. The MAP process invokes a macro and a process not defined in this clause; the definitions of these can be found as follows:

Check_Indication see subclause 25.2.2; Insert_Subs_Data_Stand_Alone_HLR see subclause 25.7.3;

If the macro takes the OK exit, the MAP process waits for a service indication.

If the MAP_ANY_TIME_MODIFICATION service response cannot be carried in a single TC-Result component, it is carried in one or more TC-Result-NL components (each sent in a TC-CONTINUE), followed by a TC-Result-L component in a TC-END message.

If the serving node (VLR or SGSN) is to be updated after the modification, the MAP process creates an instance of the appropriate process (Insert_Subs_Data_Stand_Alone_HLR for VLR update, Insert_GPRS_Subs_Data_Stand_Alone_HLR for SGSN update).




Figure 24A.3/2: Process ATM_gsmSCF




Figure 24A.3/3: Process ATM_HLR

24A.4 Subscriber Data Modification Notification procedure

24A.4.1 General

The Subscriber Data Modification Notification procedure is used to notify a gsmSCF about the modification of subscriber data. In an IP Multimedia Core Network, an IM-SSF can take on the role of a gsmSCF for this procedure.

The stage 2 specification for Subscriber Data Modification Notification is in 3GPP TS 23.078 [98] and 3GPP TS 23.278 [125]. The interworking between the MAP signalling procedures and the Subscriber Data Modification Notification procedures for each entity (HLR, gsmSCF) is shown by the transfer of signals between these processes.

The following services are used:




Figure 24A.4/1: Message flow for subscriber data modification notification

The following MAP service is used to send the notification to the gsmSCF:

MAP_NOTE_SUBSCRIBER_DATA_MODIFIED

see subclause 8.11.5.

24A.4.2 Process in the HLR

The MAP process in the HLR to send modified data to the gsmSCF is shown in figure 24A.4/2. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2; Check_Confirmation see subclause 25.2.2.

If the required information cannot be carried in a single MAP_NOTE_SUBSCRIBER_DATA_MODIFIED service request, the HLR segments the information into two or more requests. The "All Information Sent" parameter is omitted from each request except the last.

Sheet 2: If the MAP_NOTE_SUBSCRIBER_DATA_MODIFIED service request contained the "All Information Sent" parameter, the test "All information sent" takes the "Yes" exit.

24A.4.3 Process in the gsmSCF

The MAP process in the gsmSCF to handle a notification to the gsmSCF of change of subscriber data is shown in figure 24A.4/3. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Ind see subclause 25.1.1; Check_Indication see subclause 25.2.1 If the MAP_NOTE_SUBSCRIBER_DATA_MODIFIED service indication contained the "All Information Sent" parameter, the test "All information sent" takes the "Yes" exit.

If the test "All information sent" takes the "No" exit, the MAP process stores the data received in the MAP_NOTE_SUBSCRIBER_DATA_MODIFIED service indication. If the test "All information sent" takes the "Yes" exit, the MAP process assembles the data received in all the MAP_NOTE_SUBSCRIBER_DATA_MODIFIED service indications received in the dialogue and sends the assembled data to the application process in the gsmSCF.




Figure 24A.4/2 (sheet 1 of 2): Process NSDC_HLR




Figure 24A.4/2 (sheet 2 of 2): Process NSDC_HLR





Figure 24A.4/3: Process NSDC_gsmSCF

24A.5 Any Time Interrogation procedure

24A.5.1 General

The message flows for successful retrieval of subscriber information related to an any time interrogation from the CAMEL server are shown in figure 24A.5/1 for interrogation directed to an HLR and figure 24A.5/2 for interrogation directed to a GMLC.



- 1) MAP_ANY_TIME_INTERROGATION_reg/ind
- 2) MAP_PROVIDE_SUBSCRIBER_INFO_reg/ind
- 3) MAP_PROVIDE_SUBSCRIBER_INFO_rsp/cnf
- 4) MAP_ANY_TIME_INTERROGATION_rsp/cnf


Figure 24A.5/1: Message flow for any time interrogation (gsmSCF to HLR)

The following MAP services are used to retrieve information about the status and/or location of a subscriber:

MAP_ANY_TIME_INTERROGATION see subclause 8.11.1;

MAP_PROVIDE_SUBSCRIBER_INFO see subclause 8.11.2.

The HLR sends the MAP_PROVIDE_SUBSCRIBER_INFO request to the SGSN or the VLR, according to the domain for which the gsmSCF requested the information.



- 1) MAP_ANY_TIME_INTERROGATION_reg/ind
- MAP_ANY_TIME_INTERROGATION_rsp/cnf

Figure 24A.5/2: Message flow for any time interrogation (gsmSCF to GMLC)

The following MAP service is used to retrieve location information from a GMLC:

MAP_ANY_TIME_INTERROGATION see subclause 8.11.1;

In addition, the GMLC may use MAP Services specific to Location Services.

24A.5.2 Procedures in the gsmSCF

The process in the gsmSCF to request information about the location and/or state of a subscriber from the HLR is shown in figure 24A.5/3. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2; Check_Confirmation see subclause 25.2.2.

The process in the gsmSCF to request location information from the GMLC is shown in figure 24A.5/4. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2; Check_Confirmation see subclause 25.2.2.

24A.5.3 Procedure in the HLR

The MAP process in the HLR to provide subscriber information in response to an interrogation from the CAMEL server is shown in figure 24A.5/5. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Ind see subclause 25.1.1;
Receive_Open_Cnf see subclause 25.1.2;
Check_Confirmation see subclause 25.2.2.

24A.5.4 Procedure in the GMLC

The MAP process in the GMLC to provide location information in response to a request from the gsmSCF is shown in figure 24A.5/6. The MAP process invokes a macro not defined in this clause; the definition of this macro can be found as follows:

Receive_Open_Ind see subclause 25.1.1.




Figure 24A.5/3: Process ATI_To_HLR_gsmSCF




Figure 24A.5/4: Process ATI_To_GMLC_gsmSCF




Figure 24A.5/5 (sheet 1 of 2): Process ATI_HLR




Figure 24A.5/5 (sheet 2 of 2): Process ATI_HLR




Figure 24A.5/6: Process ATI_GMLC

24B Location Services process description

24B.1 Routeing information retrieval procedure for LCS

24B.1.1 General

The message flow for successful retrieval of routeing information related to location services is shown in figure 24B.1/1.




Figure 24B.1/1: Message flow for retrieval of routeing information for LCS

The following MAP service is used to retrieve routeing information:

MAP_SEND_ROUTING_INFO_FOR_LCS

see subclause 13A.1.

24B.1.2 Process in the GMLC

The MAP process in the GMLC to request routeing information for LCS is shown in figure 24B.1/2. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2; Check_Confirmation see subclause 25.2.2.

24B.1.3 Process in the HLR

The MAP process in the HLR to handle a request for routeing information for LCS is shown in figure 24B.1/3. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Ind see subclause 25.1.1; Check_Indication see subclause 25.2.1.




Figure 24B.1/2: Process SRI_LCS_GMLC




Figure 24B.1/3: Process SRI_LCS_HLR

24B.2 Provide Subscriber Location procedure

24B.2.1 General

The message flow for successful retrieval of the location information of a target MS related to location services is shown in figure 24B.1/1.



Figure 24B.2/1: Message flow for retrieval of location information

The following MAP service is used to retrieve location information:

MAP_PROVIDE_SUBSCRIBER_LOCATION

see subclause 13A.2.

24B.2.2 Process in the GMLC

The MAP process in the GMLC to request location information from an MSC or an SGSN is shown in figure 24B.2/2. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2; Check Confirmation see subclause 25.2.2.

24B.2.3 Process in the MSC

The MAP process in the MSC to handle a request for location information from a GMLC is shown in figure 24B.2/3. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Ind see subclause 25.1.1; Check_Indication see subclause 25.2.1.

24B.2.4 Process in the SGSN

The MAP process in the SGSN to handle a request for location information from a GMLC is shown in figure 24B.2/4. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Ind see subclause 25.1.1; Check_Indication see subclause 25.2.1.




Figure 24B.2/2: Process PSL_GMLC




Figure 24B.2/3: Process PSL_MSC




Figure 24B.2/4: Process PSL_SGSN

24B.3 Subscriber Location Report procedure

24B.3.1 General

The message flow for successful report of the location information of a target MS related to location services is shown in figure 24B.3/1.




Figure 24B.3/1: Message flow for report of the location information

The following MAP services are used to report location information:

MAP SUBSCRIBER LOCATION REPORT

see subclause 13A.3.

24B.3.2 Process in the MSC

The MAP process in the MSC to send a subscriber location report to the GMLC is shown in figure 24B.3/2. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2; Check Confirmation see subclause 25.2.2.

24B.3.3 Process in the SGSN

The MAP process in the SGSN to send a subscriber location report to the GMLC is shown in figure 24B.3/3. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Cnf see subclause 25.1.2; Check_Confirmation see subclause 25.2.2.

24B.3.4 Process in the GMLC

The MAP process in the GMLC to handle a subscriber location report is shown in figure 24B.3/4. The MAP process invokes macros not defined in this clause; the definitions of these macros can be found as follows:

Receive_Open_Ind see subclause 25.1.1; Check_Indication see subclause 25.2.1.




Figure 24B.3/2: Process SLR_MSC




Figure 24B.3/3: Process SLR_SGSN




Figure 24B.3/4: Process SLR_GMLC

25 General macro description

25.1 MAP_OPEN handling macros

25.1.1 Macro Receive_Open_Ind

This macro is used by a MAP service-user procedure when a peer entity requests opening of a dialogue.

25.1.2 Macro Receive_Open_Cnf

This macro is used by a user procedure after it has requested opening of a dialogue towards a peer entity.




Figure 25.1/1 (sheet 1 of 2): Macro Receive_Open_Ind




Figure 25.1/1 (sheet 2 of 2): Macro Receive_Open_Ind




Figure 25.1/2: Macro Receive_Open_Cnf




Figure 25.1/3: Macro Check_Reference

25.2 Macros to check the content of indication and confirmation primitives

25.2.1 Macro Check_Indication

This macro checks that an indication includes all the parameters required by the application, no more and no less, and that the parameters are all within the correct range. It does not handle syntax checking; that is part of the function of the MAP protocol machine.

25.2.2 Macro Check_Confirmation

This macro checks whether a confirmation contains an error or a result, and if it contains a result whether the result is correctly formed.




Figure 25.2/1: Macro Check_Indication




Figure 25.2/2: Macro Check_Confirmation

25.3 The page and search macros

25.3.1 Macro PAGE_MSC

This macro is called if an unstructured SS notification, a network-initiated unstructured SS request or a mobile terminating short message is to be delivered to the MS and the current location area identity of the MS is known in the VLR.

If an MM-connection over the radio link already exists for the given IMSI, the MSC sets the access connection status according to the characteristics of the existing connection (i.e. RR-connection established, ciphering mode on/off, MM-connection existing and authenticated or not).

If the MSC pages the MS and the VLR provided the TMSI, the MSC uses it to identify the MS at the radio interface; otherwise the MSC uses the IMSI. The MSC also uses the IMSI to determine the page group (see 3GPP TS 24.008 [35]).

If the MS responds with a channel request containing an establishment cause which is not "answer to paging" the MSC sends a MAP_PAGE response primitive with user error Busy Subscriber. This gives priority to the mobile originating request. Alternatively, as an implementation option, the MSC may treat this as a response to paging, which gives priority to the mobile terminating request.

If the paging is for MT SMS delivery and the VLR aborts the transaction before the MSC receives a response from the MS, the MSC aborts the transaction with the SMS-GMSC.

25.3.2 Macro Search_For_MS_MSC

This macro is called if an unstructured SS notification, a network-initiated unstructured SS request or a mobile terminating short message is to be delivered to the MS and the current location area identity of the MS is not known in VLR.

If an MM-connection over the radio link already exists for the given IMSI, the MSC returns a MAP_SEARCH_FOR_MS response containing the IMSI and current location area identification of the called MS to the VLR and sets the access connection status according to the characteristics of the existing connection (i.e. RR-connection established, ciphering mode on/off, MM-connection existing and authenticated or not).

If the MSC pages the MS, the MSC uses the IMSI to identify the subscriber and the page group (see 3GPP TS 24.008 [35]).

If the MS responds with a channel request containing an establishment cause which is not "answer to paging" the MSC sends a MAP_SEARCH_FOR_MS response with user error Busy Subscriber. This gives priority to the mobile originating request. Alternatively, as an implementation option, the MSC may treat this as a response to paging, which gives priority to the mobile terminating request.

If the paging is for MT SMS delivery and the VLR aborts the transaction before the MSC receives a response from the MS, the MSC aborts the transaction with the SMS-GMSC.




Figure 25.3/1: Macro Page_MSC




Figure 25.3/2: Macro Search_for_MS_MSC

25.4 Macros for handling an Access Request

These macros are invoked when a MS accesses the network, e.g. to submit an MO short message or when responding to paging. The macros handle identification and authentication of the mobile subscriber as well as invocation of security related features (see 3GPP TS 42.009 [6]).

25.4.1 Macro Process Access Request MSC

Sheet 1: The MAP_PROCESS_ACCESS_REQUEST request includes the following parameters:

- the received subscriber identification (IMSI, TMSI);
- the CM service type, indicating the type of request;
- the status of the access connection, i.e. whether a connection to this MS already exists and if so, whether it is already authenticated and ciphered;
- the current location area id of the MS: and
- the CKSN received from the MS.

Sheet 2, sheet 3: If the MSC receives an A_SETUP indication while it is waiting for further instructions from the VLR or for the acknowledgment of TMSI reallocation from the MS, the MSC saves the setup request for processing after control has returned from the macro Process_Access_Request_MSC to the calling process.

Sheet 3: When the MSC is waiting for a possible instruction to allocate a new TMSI, a MAP_DELIMITER indication indicates that TMSI reallocation is not required.

Sheet 3: If the MS sends a TMSI reallocation failure in response to the TMSI reallocation command, the MSC takes the OK exit; the VLR treats the lack of response as a provider error (see macro Process_Access_Request_VLR).

25.4.2 Macro Process_Access_Request_VLR

Sheet 3: If the MSC does not send a positive response to the MAP_FORWARD_NEW_TMSI request, this is treated as a MAP_FORWARD_NEW_TMSI confirmation containing a provider error. The Macro takes the Error exit. If TMSI reallocation does not succeed, the old TMSI is frozen, to prevent it from being reallocated. In this case, both old and new TMSIs are regarded as valid.

25.4.3 Macro Obtain_Identity_VLR

This macro is invoked by the macro Process_Access_Request_VLR if the subscriber's identity is not known in the VLR.

It is an operator option to allow or prevent retrieval of the IMSI without encryption.

25.4.4 Process Update_Location_Child_VLR

This process is started when the subscriber successfully accesses the network, e.g. for mobile originated short message submission, response to paging or supplementary services handling.

The procedure Notify_gsmSCF is specified in 3GPP TS 23.078.




Figure 25.4/1 (sheet 1 of 3): Macro Process_Access_Request_MSC




Figure 25.4/1 (sheet 2 of 3): Macro Process_Access_Request_MSC




Figure 25.4/1 (sheet 3 of 3): Macro Process_Access_Request_MSC




Figure 25.4/2 (sheet 1 of 3): Macro Process_Access_Request_VLR




Figure 25.4/2 (sheet 2 of 3): Macro Process_Access_Request_VLR




Figure 25.4/2 (sheet 3 of 3): Macro Process_Access_Request_VLR




Figure 25.4/3: Macro Obtain_Identity_VLR




Figure 25.4/4 (sheet 1 of 2): Process Update_Location_Child_VLR




Figure 25.4/4 (sheet 2 of 2): Process Update_Location_Child_VLR

25.5 Authentication macros and processes

The following macros are used in the network in order to enable authentication of a mobile subscriber.

25.5.1 Macro Authenticate MSC

This macro is used by the MSC to relay a request for authentication transparently from the VLR to the MS, wait for a response from the MS and relay the response from the MS back to the VLR.

25.5.2 Macro Authenticate VLR

This macro is used by the VLR to control the authentication of a subscriber.

Sheet 1: The test "Received SRES=Expected SRES" indicates:

- a comparison of the Signed RESult received from the MS with the Signed RESult received from the HLR, if GSM authentication is used (see 3GPP TS 43.020 [24]), or
- a comparison of the RESult received from the MS with the expected RESult received from the HLR, if UMTS authentication is used (see 3GPP TS 33.102).

25.5.3 Macro Obtain_Authent_Params_VLR

This macro is used by the VLR to request authentication vectors from the HLR.

Sheet 1, sheet 2, sheet 3: It is an operator option whether to allow the re-use of old authentication triplets.

Sheet 2, sheet 3: Old UMTS quintuplets shall not be re-used.

Sheet 2: if the VLR requests more authentication vectors in the same dialogue, the subsequent MAP_SEND_AUTHENTIFICATION_INFO request has no parameters.

25.5.4 Process Obtain_Authentication_Sets_VLR

This process is initiated by the VLR to fetch authentication vectors from a subscriber's HLR independently of any other processing.

25.5.6 Process Obtain_Authent_Sets_SGSN

The procedure for authentication when the serving node is an SGSN is described in 3GPP TS 23.060 [104] and 3GPP TS 24.008 [35].

This Process is used by the SGSN to request authentication vectors from the HLR.

Sheet 1, sheet 2: It is an operator option whether to allow the re-use of old authentication triplets.

Sheet 2: Old UMTS quintuplets shall not be re-used.

25.5.6 Process Obtain_Authent_Sets_HLR

This process is used to provide authentication vectors (triplets or quintuplets) in response to a request from a VLR or an SGSN.

Upon receipt of an authentication information request for a UMTS subscriber, the HLR shall return authentication quintuplets. If the user is a GSM subscriber, the HLR shall return authentication triplets.

25.5.7 Authentication Failure Reporting

25.5.7.1 General

The Authentication Failure Report procedure is used to notify an HLR about the occurrence of an authentication failure in the SGSN or VLR.

The message flows for this procedure are shown in figures 25.5/7& 25.5/8.




Figure 25.5/7: Message Flow for Authentication Failure Report – VLR to HLR




Figure 25.5/8: Message Flow for Authentication Failure Report – SGSN to HLR

- 25.5.7.2 Process in the VLR
- 25.5.7.3 Process in the SGSN
- 25.5.7.4 Process in the HLR




Figure 25.5/1: Macro Authenticate_MSC




Figure 25.5/2 (sheet 1 of 2): Macro Authenticate_VLR




Figure 25.5/2 (sheet 2 of 2): Macro Authenticate_VLR




Figure 25.5/3 (sheet 1 of 3): Macro Obtain_Authent_Params_VLR




Figure 25.5/3 (sheet 2 of 3): Macro Obtain_Authent_Params_VLR




Figure 25.5/3 (sheet 3 of 3): Macro Obtain_Authent_Params_VLR




Figure 25.5/4: Process Obtain_Authent_Sets_VLR




Figure 25.5/5 (sheet 1 of 2): Process Obtain_Authent_Sets_SGSN




Figure 25.5/5 (sheet 2 of 2): Process Obtain_Authent_Sets_SGSN




Figure 25.5/6 (sheet 1 of 2): Process Obtain_Authent_Sets_HLR




Figure 25.5/6 (sheet 2 of 2): Process Obtain_Authent_Sets_HLR




Figure 25.5/7: Procedure Check_Available_Vectors




Figure 25.5/9: Process Report_Authentication_Failure_VLR




Figure 25.5/10: Process Report_Authentication_Failure_SGSN




Figure 25.5/11: Process Note_Authentication_Failure_HLR

25.6 IMEI Handling Macros

The following macros are used in the network in order to enable handling and checking of the mobile equipment identity.

25.6.1 Macro Check_IMEI_MSC

This macro is used by the MSC to receive a request from the VLR, relay it to the EIR, and pass the result from the EIR back to the VLR.

Sheet 1: If the dialogue with the EIR drops back to a previous protocol version and the EIR returned an error, the MSC relays the error to the VLR in the MAP_CHECK_IMEI response. If the dialogue with the EIR failed, or the EIR returned a badly formed result, the MSC sends a System Failure error to the VLR in the MAP_CHECK_IMEI response.

25.6.2 Macro Check IMEI VLR

This macro is used by the VLR to control the check of a mobile equipment's IMEI. It may also be used to request the BMUEF from the EIR.

25.6.3 Process Check_IMEI_SGSN

This process is used by the SGSN to control the check of a mobile equipment's IMEI. It may also be used to request the BMUEF from the EIR.

25.6.4 Process Check_IMEI_EIR

This process is used by the EIR to obtain the status of a mobile equipment, upon request from the MSC or from the SGSN. It may also be used to obtain the BMUEF.

25.6.5 Macro Obtain_IMEI_MSC

This macro is used by the MSC to respond to a request from the VLR to provide the IMEI.

25.6.6 Macro Obtain_IMEI_VLR

This macro is used by the VLR to obtain the IMEI from the MSC.




Figure 25.6/1 (sheet 1 of 2): Macro Check_IMEI_MSC




Figure 25.6/1 (sheet 2 of 2): Macro Check_IMEI_MSC




Figure 25.6/2: Macro Check_IMEI_VLR




Figure 25.6/3 (sheet 1 of 2): Process Check_IMEI_SGSN




Figure 25.6/3 (sheet 2 of 2): Process Check_IMEI_SGSN




Figure 25.6/4: Process Check_IMEI_EIR




Figure 25.6/5: Macro Obtain_IMEI_MSC

833




Figure 25.6/6: Macro Obtain_IMEI_VLR

25.7 Insert Subscriber Data macros and processes

25.7.1 Macro Insert_Subs_Data_VLR

This macro is used by any procedure in the VLR that triggers the reception of subscriber data (e.g. Update Location or Restore Data).

25.7.2 Macro Insert Subs Data SGSN

This macro is used by any procedure that triggers the reception of subscriber data (e.g. Update GPRS Location).

25.7.3 Process Insert_Subs_Data_Stand_Alone_HLR

This process is used by HLR to transfer subscriber data to the VLR in a stand alone mode, i.e. in a separate dialogue. This is done whenever a change of subscriber data is performed either by the operator or by the subscriber and this change has to be reported to the VLR.

Sheet 1: The HLR may wait for each MAP_INSERT_SUBSCRIBER_DATA request to be acknowledged before it sends the next request, or it may handle the requests and the confirmations in parallel.

Sheet 1, sheet 2: If the VLR has indicated that it does not support a service or feature (e.g. Closed User Group or Advice Of Charge Charging Level) which the HLR operator regards as essential for the subscriber, the macro Wait_for_Insert_Subs_Data_Cnf takes the Replace_Service exit; the HLR sets the Roaming Restriction Due To Unsupported Feature flag to roaming restricted and sends Roaming Restriction Due To Unsupported Feature in a subsequent MAP_INSERT_SUBSCRIBER_DATA request.

Sheet 1, sheet 2: If the HLR operator does not regard the unsupported service or feature as essential for the subscriber but the macro Wait_for_Insert_Subs_Data_Cnf takes the Replace_Service exit, the HLR sends the data for a replacement service in a subsequent MAP_INSERT_SUBSCRIBER_DATA request.

Sheet 2: It is an operator option whether to repeat the download of subscriber data if the VLR returns an error response. The number of repeat attempts and the interval between them is also an operator option, depending on the error response from the VLR.

If subscriber data for CAMEL Phase 2 or later services are sent to a VLR which does not support the appropriate phase of CAMEL, the service behaviour may be unpredictable or incorrect. The HLR should therefore ensure that at the conclusion of a stand alone Insert Subscriber data procedure the data in the VLR do not require a capability that the VLR does not have. Possible mechanisms to ensure this are described in 3GPP TS 23.078 [98].

The HLR should send a Forwarded-to number which is not in E.164 international format to the VLR only when the HLR has ascertained that the VLR supports CAMEL Phase 2 or later. Thus, the ISD message containing the Forwarded-to number which is not in E.164 international format shall be sent to the VLR only if the HLR previously received confirmation from the VLR at Location Update that CAMEL Phase 2 or later is supported.

25.7.4 Process Insert GPRS Subs Data Stand Alone HLR

This process is used by the HLR to transfer subscriber data from the HLR to the SGSN in a stand alone mode, i.e. in a separate dialogue. This is done whenever a change of subscriber data is performed either by the operator or by the subscriber and this change has to be reported to the SGSN.

Sheet 1: The HLR may wait for each MAP_INSERT_SUBSCRIBER_DATA request to be acknowledged before it sends the next request, or it may handle the requests and the confirmations in parallel.

Sheet 1, sheet 2: If the SGSN has indicated that it does not support a service or feature which the HLR operator regards as essential for the subscriber, the macro Wait_for_Insert_GPRS_Subs_Data_Cnf takes the Replace_Service exit; the HLR sets the Roaming Restricted In SGSN Due To Unsupported Feature flag to roaming restricted and sends Roaming Restricted In SGSN Due To Unsupported Feature in a subsequent MAP_INSERT_SUBSCRIBER_DATA request.

Sheet 1, sheet 2: If the HLR operator does not regard the unsupported service or feature as essential for the subscriber but the macro Wait_for_Insert_GPRS_Subs_Data_Cnf takes the Replace_Service exit, the HLR sends the data for a replacement service in a subsequent MAP_INSERT_SUBSCRIBER_DATA request.

Sheet 2: It is an operator option whether to repeat the download of subscriber data if the SGSN returns an error response. The number of repeat attempts and the interval between them is also an operator option, depending on the error response from the SGSN.

25.7.5 Macro Wait for Insert Subs Data Cnf

This macro is used by any process or macro that describes the handling in the HLR of the transfer of subscriber data to the VLR (e.g. Update Location or Restore Data).

25.7.6 Macro Wait_for_Insert_GPRS_Subs_Data_Cnf

This macro is used by any process or macro that describes the handling in the HLR of the transfer of subscriber data to the SGSN (e.g. Update GPRS Location).

25.7.7 Process Send_Insert_Subs_Data_HLR

This process is used by any process or macro in the HLR where a MAP_INSERT_SUBSCRIBER_DATA request is sent to the VLR or to the SGSN.




Figure 25.7/1: Macro Insert_Subs_Data_VLR




Figure 25.7/2: Macro Insert_Subs_Data_SGSN




Figure 25.7/3 (sheet 1 of 2): Process Insert_Subs_Data_Stand_Alone_HLR




Figure 25.7/3 (sheet 2 of 2): Process Insert_Subs_Data_Stand_Alone_HLR




Figure 25.7/4 (sheet 1 of 2): Process Insert_GPRS_Subs_Data_Stand_Alone_HLR




Figure 25.7/4 (sheet 2 of 2): Process Insert_GPRS_Subs_Data_Stand_Alone_HLR




Figure 25.7/5: Macro Wait_for_Insert_Subs_Data_Cnf




Figure 25.7/6: Macro Wait_for_Insert_GPRS_Subs_Data_Cnf




Figure 25.7/7: Process Send_Insert_Subs_Data_HLR

25.8 Request IMSI Macros

25.8.1 Macro Obtain_IMSI_MSC

This macro describes the handling of the request received from the VLR to provide the IMSI of a subscriber (e.g. at Location Updating).

25.8.2 Macro Obtain_IMSI_VLR

This macro describes the way VLR requests the MSC the IMSI of a subscriber (e.g. at Location Updating).




Figure 25.8/1: Macro Obtain_IMSI_MSC




Figure 25.8/2: Macro Obtain_IMSI_VLR

25.9 Tracing macros

25.9.1 Macro Trace_Subscriber_Activity_MSC

This macro shows the handling in the MSC for a request from the VLR to trace the activity of a subscriber.

25.9.2 Macro Trace_Subscriber_Activity_VLR

This macro is called during the handling of subscriber activity in the VLR to activate tracing if necessary.

25.9.3 Macro Trace_Subscriber_Activity_SGSN

This macro is called during the handling of subscriber activity in the SGSN to activate tracing if necessary.

25.9.4 Macro Activate_Tracing_VLR

This macro shows the handling in the VLR for a request from the HLR to activate tracing for a subscriber.

25.9.5 Macro Activate_Tracing_SGSN

This macro shows the handling in the SGSN for a request from the HLR to activate tracing for a subscriber.

25.9.6 Macro Control_Tracing_With_VLR_HLR

This macro shows the handling in the HLR to activate tracing in the VLR if it is required during a dialogue between the VLR and the HLR

25.9.7 Macro Control_Tracing_With_SGSN_HLR

This macro shows the handling in the HLR to activate tracing in the SGSN if it is required during a dialogue between the SGSN and the HLR




Figure 25.9/1: Macro Trace_Subscriber_Activity_MSC




Figure 25.9/2: Macro Trace_Subscriber_Activity_VLR




Figure 25.9/3: Macro Trace_Subscriber_Activity_SGSN




Figure 25.9/4: Macro Activate_Tracing_VLR




Figure 25.9/5: Macro Activate_Tracing_SGSN




Figure 25.9/6: Macro Control_Tracing_With_VLR_HLR




Figure 25.9/7: Macro Control_Tracing_With_SGSN_HLR

25.10 Short Message Alert procedures

25.10.1 Process Subscriber_Present_VLR

The VLR invokes the process Subscriber_Present_VLR when the mobile subscriber becomes active. The general description of the short message alert procedures is in subclause 23.4 of the present document.

25.10.2 Process SubscriberPresent_SGSN

The SGSN invokes the process Subscriber_Present_SGSN when it receives a Page response, a GPRS Attach request or a Routing area update request message (3GPP TS 24.008 [35]). The general description of the short message alert procedures is in subclause 23.4 of the present document.

25.10.3 Macro Alert_Service_Centre_HLR

The HLR invokes the macro Alert_Service_Centre_HLR when Service Centre(s) are to be alerted.

25.10.4 Process Alert_SC_HLR

It is an operator option to resend the MAP_ALERT_SERVICE_CENTRE request to the SMS-IWMSC if the alert is unsuccessful. The number of repeat attempts and the interval between them is also an operator option. The service centre address should be purged from the MWD list if the alert is consistently unsuccessful.




Figure 25.10/1: Process Subscriber_Present_VLR




Figure 25.10/2: Process Subscriber_Present_SGSN




Figure 25.10/3: Macro Alert_Service_Centre_HLR




Figure 25.10/4: Process Alert_SC_HLR

252

259

264

267

Annex A (informative): Cross-reference for abstract syntaxes of MAP

Annex A is not part of the standard, it is included for information purposes only.

For every ASN.1 item such as identifier, type-reference or value-reference the cross-reference allows to locate all occurrences by means of module-name and line numbers. For that purpose line numbers are printed at the left margin in front of each ASN.1 source line starting with 1 for every module.

The items are sorted alphabetically in the cross-reference in a case-insensitive manner. Occurrences of an item are its definition and all its usages such as in exports, imports or within a type or value assignment.

For every item additional information is provided such as kind of item (identifier, value reference, type reference), and tag, associated type and value if applicable.

The cross-reference for a root module includes all modules referred to directly or indirectly via imports. The cross-references for the root modules MAP-Protocol/TCAPMessages and MAP-DialoguePDU are included.

12-06	TAG R6.15 Cross Reference Listing for MAP-Protocol 09:33:23 PAGE 1								2006-		
	&alwaysReturnsidentifier of Fieldspec DEFINED in Remote-Operations-Info : 22										
	&ArgumentTypeidentifier of Fieldspec										
	D		in Remote-Operations-Info :		14	105	100	0.00	000		
234	246	261	<pre>in MAP-MobileServiceOpera : 279</pre>		172	185	196	208	220		
231	210	201	213		301	315	328	335	340		
345	359	377	391								
4.60	400	400			404	416	430	438	452		
468	483	496 USED	in MAP-OperationAndMainte :		52	67	81				
			in MAP-CallHandlingOperat :		80	104	119	132	147		
160	174	188	202								
100	105	USED 212	<pre>in MAP-SupplementaryServi : 227</pre>		89	107	125	146	166		
182	195	212	227		245	252	264	282			
		USED	in MAP-ShortMessageServic :		65	81	94	113	126		
136	141										
			<pre>in MAP-Group-Call-Operati : in MAP-LocationServiceOpe :</pre>		45 54	56 69	63 88	68			
		USED	in MAP-Locationserviceope :		54	69	88				
			ypeOptional		dentif 15	ier of	Field	spec			
	&Bothidentifier of Fieldspec DEFINED in Remote-Operations-Info : 56										
	&Consumeridentifier of Fieldspec										
	&errorCodeidentifier of Fieldspec										
	D		in MAP-Errors :		163	170	177	184	190		
196	205	211	214		001		001		0.45		
0.50	0.5.0	0.64	0.67		221	224	231	238	245		

200	214	200	206		273	281	289	296	302
308	314	320	326		332	338	345	352	358
364	373	379	386		393	399	402	405	410
413	416	422	428		436	441	447	453	461
469	475	481	487		493			100	101
					433				
	&Errorsidentifier of Fieldspe							spec	
	Γ		in Remote-Operations-Info		19	100	0.01	010	004
238	250	265	in MAP-MobileServiceOpera 283	:	176	190	201	212	224
					306	319	349	369	382
395	409	421	442		456	473	488	500	
		USED	in MAP-OperationAndMainte	:	57	72	85	300	
			in MAP-CallHandlingOperat		84	108	124	137	152
164	179	193	207						
			O in MAP-SupplementaryServi		94	112	130	151	170
186	200	215	231		257	268	286		
		USED	in MAP-ShortMessageServic	•	257 69	86	99	118	129
146		0022		•	0,5				
			in MAP-Group-Call-Operati		49				
		USED	in MAP-LocationServiceOpe	:	58	73	92		
	Soxt	ongion'	Id		idontif	ior of	Fiold	anog	
			in MAP-ExtensionDataTypes		. raencir. 25	iei oi	rieiu	spec	
			in MAP-ExtensionDataTypes		45				
			Type			ier of	Field	spec	
	L		<pre>in MAP-ExtensionDataTypes in MAP-ExtensionDataTypes</pre>		24 47				
		ОВЦВ	III THE EXCENSION ACCTIVES	•	1,				
	&ididenti				.identif	ier of	spec		
	DEFINED in Remote-Operations-Info : 59								
	&operationCodeidentifier of Fieldspec							snec	
			in Remote-Operations-Info		25	ICI OI	110101	spec	
			in MAP-MobileServiceOpera		182	193	205	215	229
241	256	276	296		210	205	220	225	2.40
354	374	386	399		310	325	332	337	342
334	374	500			413	425	432	435	447
463	478	493	505						
			in MAP-OperationAndMainte		64	78	89		
171	105		in MAP-CallHandlingOperat	:	100	116	129	144	157
171	185	199 USED	210 in MAP-SupplementaryServi		104	122	143	163	179
192	209	224	242	•	101		113	103	1,5
					249	261	279	293	
120	1 - 1	USED	in MAP-ShortMessageServic	:	78	91	110	123	133
138	151	IISED	in MAP-Group-Call-Operati		53	60	65	70	
			in MAP-LocationServiceOpe		66	85	100	. 0	
			_						
			Type			ier of	Field	spec	
	I		<pre>in Remote-Operations-Info in MAP-Errors</pre>	:	43	1.00	173	180	187
					1611				
193	201	208	217	•	160	166	1/3	100	107

3GPP TS 29.002 version 6.17.0 Release 6			863		ETSI TS 129 002 V6.17.0 (2010-07				
					229	234	241	248	255
270	278	286	292		299	305	311	317	323
329	335	342	349		355	361	369	376	382
389	396	408	419		425	433	439	444	450
458	466	472	478		484	490			

12-06	TAG R6.15 Cross Reference Listing for MAP-Protocol 6 09:33:23 PAGE 2											
	¶meterTypeOptionalidentifier of Fieldspec DEFINED in Remote-Operations-Info : 44											
	&ResultTvr	e		identif	ier of	Field	spec					
		o in Remote-Operations-Info			ICI OI	11010	bpcc					
) in MAP-MobileServiceOpera			187	198	210	222				
236	248 263	281		202	217	220	2.45	266				
379	393 406	418		303	317	330	347	366				
3 7 3	333 100	110		440	454	470	485	498				
	USED) in MAP-OperationAndMainte	e :	54	69	83						
		in MAP-CallHandlingOperat		82	106	121	134	149				
162	176 190	204										
104		in MAP-SupplementaryServ	Ŀ:	91	109	127	148	168				
184	197 229	247		254	266	284						
	IICET) in MAP-ShortMessageServic	٠.	254 67	83	26 4 96	115	143				
		in MAP-Group-Call-Operat:		47	58	90	113	143				
) in MAP-LocationServiceOpe		56	71	90						
	OBIL	III MAI LOCACIONDEIVICCOPO	•	50	, _	20						
	&resultTyp	eOptional		.identif	ier of	Field	spec					
		in Remote-Operations-Info		18			-					
		ult		.identif	ier of	Field	spec					
) in Remote-Operations-Info		16								
		in MAP-SupplementaryServ		214								
	USED) in MAP-ShortMessageServi	· :	128								
	. C			: E	:: =	הו בים						
				. rdentrr	ier or	rieia	spec					
	DEFINEL	o in Remote-Operations-Inc		50								
	&synchrono	ous		.identif	ier of	Field	spec					
		in Remote-Operations-Info		21			-					
	a			.identif	ier of	Named	Numbe:	r, 0				
	DEFINED) in MAP-OM-DataTypes	:	96								
	- 1			e			e					
₽DD∩D	Information	scriber		. Intorna	ation of	bject	rerere.	iice				
ERROR,		on object o in MAP-Errors		291								
) in MAP-MobileServiceOpera	•		457							
		o in MAP-CallHandlingOperat			94	114	168					
) in MAP-SupplementaryServ		51	204		100					
		in MAP-LocationServiceOpe			64							
		in MAP-Errors	:	48	0 -	0_						
		scriber			ier of	Named	Numbe:	r, 3				
	DEFINED) in MAP-CH-DataTypes	:	189								
								_				
		scriber			ier of	Named	Numbe:	r, 1				
	DEFINEL	in MAP-SM-DataTypes	:	167								
	ahgent Guha	criberDiagnosticSM		iden+if	ier of	[0]						
Absent		DiagnosticSM		. 10011011	LICI OI	[0]						
		o in MAP-SM-DataTypes	:	146								
			-	~								
		criberDiagnosticSM		.identif	er of							
Absent	SubscriberD)iagnosticSM										
	DEFINED) in MAP-SM-DataTypes	:	185								

 $\verb|absentSubscriberDiagnosticSM.....identifier of$ AbsentSubscriberDiagnosticSM DEFINED in MAP-ER-DataTypes 155 AbsentSubscriberDiagnosticSM.....type reference INTEGER DEFINED in MAP-ER-DataTypes : 165

USED in MAP-SM-DataTypes : 208 1927

USED in MAP-SM-DataTypes : 41 146 159 185 186

USED in MAP-ER-DataTypes : 43 155 160 AbsentSubscriberParam.....type reference SEQUENCE DEFINED in MAP-ER-DataTypes : 244
USED in MAP-Errors : 124
USED in MAP-ER-DataTypes : 34 293 absentSubscriberReason.....identifier of [0] AbsentSubscriberReason DEFINED in MAP-ER-DataTypes AbsentSubscriberReason.....type reference ENUMERATED DEFINED in MAP-ER-DataTypes : 249
USED in MAP-ER-DataTypes : 247 USED in MAP-ER-DataTypes absentSubscriberSM.....information object reference ERROR, Information Object USED in MAP-Errors : 449
USED in MAP-ShortMessageServic : 41 77 109
USED in MAP-Errors DEFINED in MAP-Errors USED in MAP-Errors AbsentSubscriberSM-Param.....type reference SEQUENCE

DEFINED in MAP-ER-DataTypes :

154

TAG R6.15 Cross Reference Listing for MAP-Protocol 2006-12-06 09:33:23 PAGE 3 : 134 451 USED in MAP-Errors USED in MAP-ER-DataTypes : 42 accepted......identifier of Named Number, 0 DEFINED in MAP-CH-DataTypes 396 accessNetworkProtocolId.....identifier of AccessNetworkProtocolId DEFINED in MAP-CommonDataTypes AccessNetworkProtocolId.....type reference ENUMERATED DEFINED in MAP-CommonDataTypes : 262 USED in MAP-CommonDataTypes : 246 AccessNetworkSignalInfo.....type reference SEQUENCE DEFINED in MAP-CommonDataTypes : 245 USED in MAP-MS-DataTypes : 177 177 477 542 603 647 705 655 660 USED in MAP-CommonDataTypes : 23 ${\tt accessOutsideLSAsAllowed......identifier\ of\ Named\ Number,\ 0}$ DEFINED in MAP-MS-DataTypes : 1031 ${\tt accessOutsideLSAsRestricted......identifier\ of\ Named\ Number,\ 1}$ DEFINED in MAP-MS-DataTypes : accessRestrictionData.....identifier of [19] AccessRestrictionData DEFINED in MAP-MS-DataTypes AccessRestrictionData.....type reference BIT STRING DEFINED in MAP-MS-DataTypes : 869 USED in MAP-MS-DataTypes accessType.....identifier of AccessType DEFINED in MAP-MS-DataTypes : 411 AccessType.....type reference ENUMERATED DEFINED in MAP-MS-DataTypes : 416 USED in MAP-MS-DataTypes accuracyFulfilmentIndicator....identifier of [8] AccuracyFulfilmentIndicator DEFINED in MAP-LCS-DataTypes AccuracyFulfilmentIndicator.....type reference ENUMERATED DEFINED in MAP-LCS-DataTypes : 361 USED in MAP-LCS-DataTypes : 347 accuracyFulfilmentIndicator.....identifier of [19] AccuracyFulfilmentIndicator DEFINED in MAP-LCS-DataTypes : 486 activate.....identifier of Named Number, 1 DEFINED in MAP-MS-DataTypes : 2416 activateDeferredLocation.....identifier of Named Number, 3 DEFINED in MAP-LCS-DataTypes : 138

activateSS	.infor	mation	object	reference
OPERATION, Information Object				
DEFINED in MAP-SupplementaryServi	:	124		
USED in MAP-Protocol	:	74	130	
USED in MAP-SupplementaryServi	:	15		
activateTraceMode	.infor	rmation	object	reference
OPERATION, Information Object				
DEFINED in MAP-OperationAndMainte	:	51		
USED in MAP-Protocol			128	
USED in MAP-OperationAndMainte	:	13		
		_		
ActivateTraceModeArg			erence	SEQUENCE
DEFINED in MAP-OM-DataTypes				
USED in MAP-OperationAndMainte			53	
USED in MAP-OM-DataTypes	:	14		
ActivateTraceModeRes	ty	pe ref	erence	SEQUENCE
DEFINED in MAP-OM-DataTypes				
USED in MAP-OperationAndMainte	:	36	55	
USED in MAP-OM-DataTypes				
active	id	lentifi	er of N	amed Number, 2
DEFINED in MAP-SS-DataTypes	:	287		
additionalAbsentSubscriberDiagnosticS	SMid	lentifi	er of [5]
AbsentSubscriberDiagnosticSM				
DEFINED in MAP-SM-DataTypes	:	159		
additional Abgant Cubagribar Diagnostic	ow is	lon+ + f +	ow of [0.1
additionalAbsentSubscriberDiagnosticS AbsentSubscriberDiagnosticSM	oriIO	EHCTII	er or [U J
DEFINED in MAP-SM-DataTypes		106		
DEFINED III MAP-SM-Datalypes	•	100		

2006-

R6.15 Cross Reference Listing for MAP-Protocol

```
12-06 09:33:23 PAGE 4
      additionalAbsentSubscriberDiagnosticSM..identifier of [0]
AbsentSubscriberDiagnosticSM
         DEFINED in MAP-ER-DataTypes :
      AdditionalNetworkResource...........type reference ENUMERATED
DEFINED in MAP-CommonDataTypes : 363
USED in MAP-CommonDataTypes : 39
USED in MAP-ER-DataTypes : 73 179
      additionalNetworkResource.....identifier of [0]
AdditionalNetworkResource
         DEFINED in MAP-ER-DataTypes
additionalRequestedCAMEL-SubscriptionInfidentifier of [7]
AdditionalRequestedCAMEL-SubscriptionInfo
         DEFINED in MAP-MS-DataTypes
      AdditionalRequestedCAMEL-SubscriptionInftype reference ENUMERATED
         DEFINED in MAP-MS-DataTypes :
            USED in MAP-MS-DataTypes
                                              2285 2409
additionalRequestedCAMEL-SubscriptionInfidentifier of [4]
AdditionalRequestedCAMEL-SubscriptionInfo
         DEFINED in MAP-MS-DataTypes
                                       : 2408
      additionalSignalInfo.....identifier of [17] Ext-
ExternalSignalInfo
         DEFINED in MAP-CH-DataTypes
                                       :
                                              110
      additionalSignalInfo.....identifier of [14] Ext-
{\tt ExternalSignalInfo}
         DEFINED in MAP-CH-DataTypes
                                       :
                                               235
      additionalSM-DeliveryOutcome.....identifier of [4] SM-
DeliveryOutcome
         DEFINED in MAP-SM-DataTypes
      additional-LCS-CapabilitySets.....identifier of [5] SupportedLCS-
CapabilitySets
         DEFINED in MAP-LCS-DataTypes
      additional-Number.....identifier of [6] Additional-
         DEFINED in MAP-SM-DataTypes
      Additional-Number.....type reference CHOICE
         DEFINED in MAP-SM-DataTypes : 96
USED in MAP-SM-DataTypes : 28
                                                      92
            USED in MAP-LCS-DataTypes : 67
      additional-Number.....identifier of [3] Additional-
Number
         DEFINED in MAP-LCS-DataTypes
                                      : 98
      \verb|additional-v-gmlc-Address|..... identifier of [6] GSN-Address|
         DEFINED in MAP-LCS-DataTypes
      AddressString.....type reference OCTET STRING
         DEFINED in MAP-CommonDataTypes : 104
```

	USED	in	MAP-MS-DataTypes	:					
			MAP-OM-DataTypes		23	40			
	USED	in	MAP-CommonDataTypes	:		148			
	USED	ın	MAP-SS-DataTypes	:	44	74	300		
	USED	in	MAP-SM-DataTypes	:	32	56	134	139	144
177									
	USED	in	MAP-LCS-DataTypes	:	33	159			
			y			fier of	NULL		
	DEFINED	in	MAP-MS-DataTypes	:	280				
	11 0 1 '					c' c			
			y			iier oi	NULL		
	DELINED	ın	MAP-MS-DataTypes	:	472				
	Add Coogram	ah i	calInformation		+1m0 m	oforona	о ОСШ.	בייי כייים ד	NIC!
			MAP-LCS-DataTypes				e OCI.	EI SIKI	.ING
	LICEL	in	MAP-LCS-DataTypes MAP-LCS-DataTypes	:	25	2/1	176		
	USED	111	MAF-LCS-Datalypes	•	23	241	470		
	add-info				identi	fier of	[13]	ADD-Tn	ıfo
			MAP-MS-DataTypes				[20]		0
			21						
	ADD-Info				type r	eferenc	e SEQ	UENCE	
	DEFINED	in	MAP-MS-DataTypes	:	282				
	USED	in	MAP-MS-DataTypes	:	233	452			
	add-info				identi	fier of	[4]	ADD-Inf	0
	DEFINED	in	MAP-MS-DataTypes	:	452				
			cyExceptionList		identi	fier of	[3]	LCS-	
Privac	yExceptionL:								
	DEFINED	in	MAP-MS-DataTypes	:	887				
						-	5.0.7		
a			stimate		ıdenti	iler of	[2]	Add-	
Geogra	phicalInform				241				
	DELINED	ın	MAP-LCS-DataTypes	:	341				

TAG R6.15 Cross Reference Listing for MAP-Protocol 2006-12-06 09:33:23 PAGE 5 add-LocationEstimate.....identifier of [8] Add-GeographicalInformation DEFINED in MAP-LCS-DataTypes AgeIndicator.....type reference OCTET STRING DEFINED in MAP-MS-DataTypes 250 USED in MAP-MS-DataTypes 859 248 ageOfLocationEstimate.....identifier of [0] AgeOfLocationInformation DEFINED in MAP-LCS-DataTypes ageOfLocationEstimate.....identifier of [6] AgeOfLocationInformation DEFINED in MAP-LCS-DataTypes ageOfLocationInformation.....identifier of AgeOfLocationInformation DEFINED in MAP-MS-DataTypes ageOfLocationInformation.....identifier of [9] AgeOfLocationInformation DEFINED in MAP-MS-DataTypes : 2133 AgeOfLocationInformation.....type reference INTEGER DEFINED in MAP-CommonDataTypes : 603
USED in MAP-MS-DataTypes : 191 2105 2133
USED in MAP-CommonDataTypes : 61
USED in MAP-LCS-DataTypes : 39 338 473 alertingCategory-1......value reference AlertingPattern, '00000100'B DEFINED in MAP-CommonDataTypes : 290 alertingCategory-2......value reference AlertingPattern, '00000101'B DEFINED in MAP-CommonDataTypes 291 : alertingCategory-3......value reference AlertingPattern, '00000110'B DEFINED in MAP-CommonDataTypes : 292 alertingCategory-4.....value reference AlertingPattern, '00000111'B DEFINED in MAP-CommonDataTypes : 293 alertingCategory-5......value reference AlertingPattern, '00001000'B DEFINED in MAP-CommonDataTypes : 294 alertingDP.....identifier of Named Number, 9 DEFINED in MAP-MS-DataTypes : 1748 alertingLevel-0......value reference AlertingPattern, DEFINED in MAP-CommonDataTypes : 284 alertingLevel-1.....value reference AlertingPattern, '0000001'B

DEFINED in MAP-CommonDataTypes : 285 alertingLevel-2......value reference AlertingPattern, '00000010'B DEFINED in MAP-CommonDataTypes AlertingPattern.....type reference OCTET STRING DEFINED in MAP-CommonDataTypes : 271
USED in MAP-CommonDataTypes : 26 26 284 285 286 290 291 292 293 294 USED in MAP-CH-DataTypes : 70 107 232 386 USED in MAP-SS-DataTypes : 50 224 alertingPattern.....identifier of [14] AlertingPattern DEFINED in MAP-CH-DataTypes 107 alertingPattern.....identifier of [12] AlertingPattern DEFINED in MAP-CH-DataTypes 232 alertingPattern.....identifier of [5] AlertingPattern DEFINED in MAP-CH-DataTypes 386 alertingPattern.....identifier of AlertingPattern DEFINED in MAP-SS-DataTypes alertReason.....identifier of AlertReason DEFINED in MAP-SM-DataTypes AlertReason.....type reference ENUMERATED DEFINED in MAP-SM-DataTypes : 213 USED in MAP-SM-DataTypes 27 $\verb|alertReasonIndicator......identifier of NULL|$ DEFINED in MAP-SM-DataTypes :

alertServiceCentre.....information object reference OPERATION, Information Object

TAG 12-06 09:33:	R6.15 Cross Reference Listing for MAP-Protocol 23 PAGE 6	2006-
DEI	INED in MAP-ShortMessageServic : 125 USED in MAP-Protocol : 94 134	
	USED in MAP-ShortMessageServic : 17	
	erviceCentreArgtype reference SEQUENCE INED in MAP-SM-DataTypes : 175	
ם שלו	USED in MAP-ShortMessageServic : 54 127	
	USED in MAP-SM-DataTypes : 22	
allAdo	itionalInfoTransferSSvalue reference SS-Code,	
DEF	INED in MAP-SS-Code : 107	
	ernateSpeech-DataCDAvalue reference	
	INED in MAP-BS-Code : 81	
	ernateSpeech-DataCDSvalue reference	
	INED in MAP-BS-Code : 83	
	nchronousServicesvalue reference	
	Code, '01100000'B INED in MAP-BS-Code : 94	
allBaı	ringSSvalue reference SS-Code,	
'10010000'B DEF	INED in MAP-SS-Code : 117	
allBea	rerServicesvalue reference	
BearerService	Code, '00000000'B INED in MAP-BS-Code : 48	
'01000000'B	lCompletionSSvalue reference SS-Code,	
DEF	INED in MAP-SS-Code : 72	
allCal '00110000'B	lOfferingSSvalue reference SS-Code,	
DEF	INED in MAP-SS-Code : 63	
allCal	lPrioritySSvalue reference SS-Code,	
	INED in MAP-SS-Code : 153	
allCha '01110000'B	rgingSSvalue reference SS-Code,	
	INED in MAP-SS-Code : 99	
	munityOfInterest-SSvalue reference SS-Code,	
'01100000'B DEF	INED in MAP-SS-Code : 93	
allCor	dForwardingSSvalue reference SS-Code,	
	INED in MAP-SS-Code : 52	
+د ۱۱ ا د	aCDA-Servicesvalue reference	
	Code, '00010000'B	

: 50

DEFINED in MAP-BS-Code

allDataCDS- BearerServiceCode,	-Services , '00011000'B	value	reference
DEFINED	in MAP-BS-Code	: 59	
allDataCiro BearerServiceCode,	cuitAsynchronous	value	reference
DEFINED	in MAP-BS-Code	: 91	
BearerServiceCode		value	reference
DEFINED	in MAP-BS-Code	: 97	
allDataPDS- BearerServiceCode,	-Services	value	reference
		: 75	
allDataTele	eservices	value	reference TeleserviceCode,
DEFINED	in MAP-TS-Code	: 54	
	red in MAP-MS-DataTypes		ifier of Named Number, 9
allFacsimil	leTransmissionService	svalue	reference TeleserviceCode,
DEFINED	in MAP-TS-Code	: 47	
allForward	ingSS	value	reference SS-Code,
DEFINED	in MAP-SS-Code	: 48	
	a in MAP-MS-DataTypes	ident : 1466	
	sBarred in MAP-MS-DataTypes		ifier of Named Number, 19
	tionSent in MAP-MS-DataTypes		
allInformat	tionSent	ident	ifier of [11] NULL

TAG R6.15 Cross Reference Listing for MAP-Protocol 2006-12-06 09:33:23 PAGE 7 DEFINED in MAP-CH-DataTypes : 260 allLCSPrivacyException.....value reference SS-Code, '10110000'B DEFINED in MAP-SS-Code 159 allLineIdentificationSS......value reference SS-Code, '00010000'B DEFINED in MAP-SS-Code allLSAData.....identifier of NULL DEFINED in MAP-MS-DataTypes allMOLR-SS.....value reference SS-Code, '11000000'B DEFINED in MAP-SS-Code allMultiPartySS......value reference SS-Code, '01010000'B DEFINED in MAP-SS-Code allNameIdentificationSS.....value reference SS-Code, '00011000'B DEFINED in MAP-SS-Code allog-CallsBarred......identifier of Named Number, 0 $\,$ DEFINED in MAP-MS-DataTypes : 1105 allowedGSM-Algorithms.....identifier of [4] AllowedGSM-Algorithms DEFINED in MAP-MS-DataTypes : AllowedGSM-Algorithms.....type reference OCTET STRING DEFINED in MAP-MS-DataTypes : 497 USED in MAP-MS-DataTypes 548 481 allowedGSM-Algorithms.....identifier of [9] AllowedGSM-Algorithms DEFINED in MAP-MS-DataTypes : allowedIfNoResponse......identifier of Named Number, 2 DEFINED in MAP-LCS-DataTypes : allowedServices.....identifier of [20] AllowedServices : DEFINED in MAP-CH-DataTypes 174 AllowedServices.....type reference BIT STRING DEFINED in MAP-CH-DataTypes : 179
USED in MAP-CH-DataTypes : 174 allowedUMTS-Algorithms.....identifier of [5] AllowedUMTS-Algorithms : 482 DEFINED in MAP-MS-DataTypes AllowedUMTS-Algorithms.....type reference SEQUENCE DEFINED in MAP-MS-DataTypes : 502 USED in MAP-MS-DataTypes : 482 549

allowedUMTS-Algorithmsidentifier of [10] AllowedUMTS-Algorithms
DEFINED in MAP-MS-DataTypes : 549
allowedWithNotificationidentifier of Named Number, 1 DEFINED in MAP-LCS-DataTypes : 275
allowedWithoutNotificationidentifier of Named Number, 0 DEFINED in MAP-LCS-DataTypes : 274
allPacketOrientedServicesBarredidentifier of Named Number, 15 DEFINED in MAP-MS-DataTypes : 1120
allPadAccessCA-Servicesvalue reference BearerServiceCode, '00100000'B
DEFINED in MAP-BS-Code : 66
allPLMN-specificBSvalue reference BearerServiceCode, '11010000'B
DEFINED in MAP-BS-Code : 109
allPLMN-specificSSvalue reference SS-Code,
DEFINED in MAP-SS-Code : 136
allPLMN-specificTSvalue reference TeleserviceCode,
DEFINED in MAP-TS-Code : 70
allShortMessageServicesvalue reference TeleserviceCode,
DEFINED in MAP-TS-Code : 43
allSpeechFollowedByDataCDAvalue reference BearerServiceCode, '01000000'B
DEFINED in MAP-BS-Code : 85
allSpeechFollowedByDataCDSvalue reference BearerServiceCode, '01001000'B
DEFINED in MAP-BS-Code : 87

```
TAG R6.15 Cross Reference Listing for MAP-Protocol
                                                                    2006-
12-06 09:33:23 PAGE 8
      allSpeechTransmissionServices......value reference TeleserviceCode,
'00010000'B
        DEFINED in MAP-TS-Code
      allSS.....value reference SS-Code,
'00000000'B
        DEFINED in MAP-SS-Code
      allSynchronousServices.....value reference
BearerServiceCode, '01101000'B
        DEFINED in MAP-BS-Code
                                            100
      allTeleservices......value reference TeleserviceCode,
'00000000'B
        DEFINED in MAP-TS-Code
      allTeleservices-ExeptSMS......value reference TeleserviceCode,
'10000000'B
         DEFINED in MAP-TS-Code
      allVoiceGroupCallServices......value reference TeleserviceCode,
'10010000'B
        DEFINED in MAP-TS-Code
      alternativeChannelType.....identifier of [15]
RadioResourceInformation
        DEFINED in MAP-MS-DataTypes
      alternativeChannelType.....identifier of [23]
{\tt RadioResourceInformation}
        DEFINED in MAP-MS-DataTypes
                                            564
                                       :
      anonymous
Location......identifier of Named Number, 3
        DEFINED in MAP-CommonDataTypes
                                       :
      anyTimeInterrogation.....information object reference
OPERATION, Information Object
        DEFINED in MAP-MobileServiceOpera : 245
USED in MAP-Protocol : 35
           USED in MAP-MobileServiceOpera :
      AnyTimeInterrogationArg.....type reference SEQUENCE
         DEFINED in MAP-MS-DataTypes : 2242
           USED in MAP-MobileServiceOpera : 150
           USED in MAP-MS-DataTypes :
      AnyTimeInterrogationRes.....type reference SEQUENCE DEFINED in MAP-MS-DataTypes : 2249
           USED in MAP-MobileServiceOpera : 151
           USED in MAP-MS-DataTypes :
      anyTimeModification.....information object reference
OPERATION, Information Object
         DEFINED in MAP-MobileServiceOpera : 278
           USED in MAP-Protocol : 37 126
USED in MAP-MobileServiceOpera : 31
      \verb|AnyTimeModificationArg.....type reference SEQUENCE| \\
         DEFINED in MAP-MS-DataTypes : 2357
```

AccessNetworkSignalInfo

USED in MAP-MobileServiceOpera : 146 280 USED in MAP-MS-DataTypes 122 AnyTimeModificationRes.....type reference SEQUENCE DEFINED in MAP-MS-DataTypes : 2368
USED in MAP-MobileServiceOpera : 147
USED in MAP-MS-DataTypes : 123 282 anyTimeSubscriptionInterrogation....information object reference OPERATION, Information Object DEFINED in MAP-MobileServiceOpera : 260 36 126 30 USED in MAP-Protocol USED in MAP-MobileServiceOpera : AnyTimeSubscriptionInterrogationArg....type reference SEQUENCE DEFINED in MAP-MS-DataTypes : 2256
USED in MAP-MobileServiceOpera : 144
USED in MAP-MS-DataTypes : 120 262 AnyTimeSubscriptionInterrogationRes.....type reference SEQUENCE DEFINED in MAP-MS-DataTypes : 2264 USED in MAP-MobileServiceOpera : 145 USED in MAP-MS-DataTypes an-APDU.....identifier of AccessNetworkSignalInfo DEFINED in MAP-MS-DataTypes an-APDU.....identifier of [2] AccessNetworkSignalInfo DEFINED in MAP-MS-DataTypes

an-APDU.....identifier of [2]

DEFINED in MAP-MS-DataTypes : 603

12-06	TAG R6.1			Reference	Listing	for MAP	-Protoco	ol		2006-
Access	an-APDU NetworkSign DEFINED	alInfo)	 -DataTypes			fier of	[3]		
Access	an-APDU NetworkSign	alInfo)				fier of			
	DEFINED an-APDU			-DataTypes			fier of			
Access	NetworkSign	alInfo)	-DataTypes			1101 01			
N a a o a a	an-APDU					identi	fier of			
Access.	NetworkSign DEFINED			-DataTypes	:	705				
'01110							referenc	ce SS	-Code,	
	DEFINED aoci				:		referenc	re SS	-Code	
'01110					:				code,	
	apn DEFINED			 -DataTypes			fier of	[20]	APN	
	APN			 -DataTypes			eference	e OCT	ET STRING	
	USED	in MA	AP-MS-	-DataTypes S-DataType	:	91		2193	2194	
	apn-InUse. DEFINED			 -DataTypes			fier of	[5] 2	APN	
	apn-Subscr DEFINED	ibed. in M	AP-MS-	 -DataTypes	:	identi 2193	fier of	[4]	APN	
		in MA	AP-LCS	 S-DataType S-DataType	s :	298	eference	e SEQI	UENCE	
	areaDefini DEFINED			 S-DataType			fier of	[0]	AreaDefin	ition
	AreaDefini			 S-DataType			eference	e SEQI	UENCE	
	USED	in MA	AP-LCS	S-DataType	s :	285				
	areaEventI DEFINED			S-DataType			fier of	[14]	AreaEven	tInfo
	AreaEventI: DEFINED USED	in MA	AP-LCS	 S-DataType S-DataType	s :	284		e SEQI	UENCE	
AreaId	areaIdenti entification		ion			identi	fier of	[1]		
	DEFINED	in MA	AP-LCS	S-DataType	s :	300				

DEFINED	Eicationin MAP-LCS-DataTypes in MAP-LCS-DataTypes	:	312	eference	OCTET STRING	
	in MAP-LCS-DataTypes			ier of	[0] AreaList	
DEFINED	in MAP-LCS-DataTypes in MAP-LCS-DataTypes	:	294	eference	SEQUENCE OF	
	in MAP-LCS-DataTypes			ier of	[0] AreaType	
DEFINED	in MAP-LCS-DataTypes in MAP-LCS-DataTypes	:	303	eference	ENUMERATED	
	Eerence		.identif	ier of	[20] ASCI-	
CallReference DEFINED	in MAP-MS-DataTypes	:	557			
asciCallRef	ference		identif	eier of A	ASCI-CallReferenc	е
DEFINED	in MAP-GR-DataTypes	:	50			
	eference			eference	TBCD-STRING	
	in MAP-CommonDataTypes					
	in MAP-MS-DataTypes					
USED	in MAP-CommonDataTypes	:	42			
USED	in MAP-GR-DataTypes	:	26	50		

12-06	TAG R6.15 Cross Reference Listin 09:33:23 PAGE 10	ng	for MAF	P-Protocol	2006-
14	assetAndServiceFinding		.value	reference	LCSServiceTypeID,
	DEFINED in MAP-CommonDataTypes	:	426		
4	assetManagement		.value	reference	LCSServiceTypeID,
	DEFINED in MAP-CommonDataTypes	:	415		
	assumedIdle		.identi	fier of [0] NULL
	DEFINED in MAP-MS-DataTypes				
	ati-NotAllowed		.inform	nation obje	ect reference
ERROR,	Information Object				
	DEFINED in MAP-Errors				
	USED in MAP-MobileServiceOpera			252	
	USED in MAP-Errors	:	55		
	ATI-NotAllowedParam		tyne r	reference (SEOHENCE
	DEFINED in MAP-ER-DataTypes				SEQUENCE
	USED in MAP-Errors	:	131		
	USED in MAP-ER-DataTypes	:	30	343	
	OBED IN MAR-EK-Datalypes	•	37		
	atm-NotAllowed		.inform	nation obje	ect reference
ERROR,	Information Object				
	DEFINED in MAP-Errors	:	354		
	USED in MAP-MobileServiceOpera	:	94	284	
	USED in MAP-Errors	:	59		
	ATM-NotAllowedParam		time r	oforongo (CEOHENCE
				ererence :	SEQUENCE
	DEFINED in MAP-ER-DataTypes USED in MAP-Errors		288 146	256	
	USED IN MAP-Errors USED in MAP-ER-DataTypes			356	
	USED IN MAP-ER-Datalypes	:	33		
	atsi-NotAllowed		.inform	nation obje	ect reference
ERROR,	Information Object			-	
	DEFINED in MAP-Errors	:	348		
	USED in MAP-MobileServiceOpera	:	93	266	
	USED in MAP-Errors	:	58		
				-	
	ATSI-NotAllowedParam			reference S	SEQUENCE
	DEFINED in MAP-ER-DataTypes			0.50	
	USED in MAP-Errors			350	
	USED in MAP-ER-DataTypes	:	54		
	attach		identi	fier of Na	amed Number 1
	DEFINED in MAP-MS-DataTypes			lier or No	amed Number, I
	attachChangeOfPosition		.identi	fier of Na	amed Number, 2
	DEFINED in MAP-MS-DataTypes	:	987		
			2 3 2	6:	J. M E
	auc DEFINED in MAP-CommonDataTypes		.identi	LIET OF N	amed Number, 5
	DITTIND III PAT COMMOIDACATYPES	•	309		
	authenticationFailureReport	.in	ıformati	on object	reference
OPERAT:	ION, Information Object				
	DEFINED in MAP-MobileServiceOpera				
	USED in MAP-Protocol			124	
	USED in MAP-MobileServiceOpera	:	46		

AuthenticationFailureReportArg....type reference SEQUENCE

DEFINED in MAP-MS-DataTypes : 405

USED in MAP-MobileServiceOpera : 131 378

USED in MAP-MS-DataTypes : 45

AuthenticationFailureReportRes.....type reference SEQUENCE

DEFINED in MAP-MS-DataTypes : 432

USED in MAP-MS-DataTypes : 432

USED in MAP-MS-DataTypes : 46

AuthenticationQuintuplet......type reference SEQUENCE

DEFINED in MAP-MS-DataTypes : 360

USED in MAP-MS-DataTypes : 352

authenticationSetList......identifier of

AuthenticationSetList

DEFINED in MAP-MS-DataTypes : 337

AuthenticationSetList.......type reference CHOICE

DEFINED in MAP-MS-DataTypes : 344

USED in MAP-MS-DataTypes : 344

USED in MAP-MS-DataTypes : 344

authenticationSetList........type reference CHOICE

DEFINED in MAP-MS-DataTypes : 344

USED in MAP-MS-DataTypes : 794

AuthenticationTriplet.....type reference SEQUENCE

DEFINED in MAP-MS-DataTypes : 354
USED in MAP-MS-DataTypes : 349

12-06	TAG R6.15 Cross Reference Listing for MAP-Protocol 09:33:23 PAGE 11	2006-
	autnidentifier of AUTN DEFINED in MAP-MS-DataTypes : 365	
	AUTNtype reference OCTET DEFINED in MAP-MS-DataTypes : 395 USED in MAP-MS-DataTypes : 365	'STRING
'01100		eserviceCode,
	DEFINED in MAP-TS-Code : 49 autonomousSelfLocationvalue reference SS-C	lode.
'11000		,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,
	AUTStype reference OCTET DEFINED in MAP-MS-DataTypes : 397	STRING
	USED in MAP-MS-DataTypes : 790 autsidentifier of AUTS	
	DEFINED in MAP-MS-DataTypes : 790	
	a-sideidentifier of Named DEFINED in MAP-CH-DataTypes : 359	Number, 0
'10011		lode,
110010	DEFINED in MAP-SS-Code : 130 DAOCvalue reference SS-C	Code,
'10010	DEFINED in MAP-SS-Code : 121	
'10011	oarringOfIncomingCallsvalue reference SS-C	lode,
	DEFINED in MAP-SS-Code : 128	
'10010	barringOfOutgoingCallsvalue reference SS-C 01'B DEFINED in MAP-SS-Code : 119	lode,
	parringServiceActiveidentifier of Named DEFINED in MAP-ER-DataTypes : 108	Number, 0
	DasicCallidentifier of Named DEFINED in MAP-CH-DataTypes : 125	Number, 0
	pasicISTSupportedidentifier of Named DEFINED in MAP-MS-DataTypes : 254	Number, 0
'11000	basicSelfLocationsalue reference SS-C	lode,
	DEFINED in MAP-SS-Code : 175	
BasicS	pasicServiceidentifier of Ext- rviceCode	
BasicS	DEFINED in MAP-MS-DataTypes : 1171 DasicServiceidentifier of Ext- rviceCode	

DEFINED in MAP-MS-DataTypes

: 1230

basicService.....identifier of Ext-BasicServiceCode DEFINED in MAP-MS-DataTypes basicService.....identifier of [1] Ext-BasicServiceCode DEFINED in MAP-MS-DataTypes basicService.....identifier of [1] Ext-BasicServiceCode DEFINED in MAP-MS-DataTypes basicService.....identifier of [5] Ext-BasicServiceCode DEFINED in MAP-CH-DataTypes $\verb|basicService.....identifier of BasicServiceCode|\\$ DEFINED in MAP-SS-DataTypes basicService.....identifier of BasicServiceCode DEFINED in MAP-SS-DataTypes

basicService.....identifier of BasicServiceCode
 DEFINED in MAP-SS-DataTypes : 156

basicService.....identifier of BasicServiceCode

DEFINED in MAP-SS-DataTypes : 185

 $\verb|basicService.....identifier of BasicServiceCode|\\$

DEFINED in MAP-ER-DataTypes : 130

basicService2......identifier of [19] Ext-

BasicServiceCode

DEFINED in MAP-CH-DataTypes : 173

TAG R6.15 Cross Reference Listing for MAP-Protocol 2006-12-06 09:33:23 PAGE 12 BasicServiceCode.....type reference CHOICE DEFINED in MAP-CommonDataTypes : 538
USED in MAP-CommonDataTypes : 51
USED in MAP-SS-DataTypes : 49 73 99 156 185 209 264 71 130 USED in MAP-ER-DataTypes basicServiceCriteria.....identifier of [1] BasicServiceCriteria DEFINED in MAP-MS-DataTypes basicServiceCriteria.....identifier of [0] BasicServiceCriteria DEFINED in MAP-MS-DataTypes BasicServiceCriteria.....type reference SEQUENCE OF DEFINED in MAP-MS-DataTypes : 1669
USED in MAP-MS-DataTypes : 76 76 1641 1649 basicServiceGroup.....identifier of [9] Ext-BasicServiceCode DEFINED in MAP-CH-DataTypes basicServiceGroup.....identifier of [1] Ext-BasicServiceCode DEFINED in MAP-CH-DataTypes basicServiceGroup.....identifier of [3] BasicServiceCode DEFINED in MAP-SS-DataTypes basicServiceGroup2.....identifier of [25] Ext-BasicServiceCode DEFINED in MAP-CH-DataTypes basicServiceGroup2.....identifier of [14] Ext-BasicServiceCode DEFINED in MAP-CH-DataTypes basicServiceGroupList.....identifier of Ext-BasicServiceGroupList DEFINED in MAP-MS-DataTypes : 1248 basicServiceGroupList.....identifier of Ext-BasicServiceGroupList DEFINED in MAP-MS-DataTypes : 1295 basicServiceGroupList.....identifier of BasicServiceGroupList DEFINED in MAP-SS-DataTypes : 164 basicServiceGroupList.....identifier of [2] ${\tt BasicServiceGroupList}$ DEFINED in MAP-SS-DataTypes : 216 BasicServiceGroupList.....type reference SEQUENCE OF DEFINED in MAP-SS-DataTypes : 263 USED in MAP-SS-DataTypes : 164 216

Basic	basi Servic		ceLis	t		.identi	fier of	[1]				
	D	EFINED	in M	IAP-MS-DataTypes	:	1425						
				t			eferenc	ce SEQ	JENCE	OF		
	D			IAP-MS-DataTypes								
		USED	in M	IAP-MS-DataTypes	:	1425						
Beare	bearerServiceidentifier of [2] BearerServiceCode											
	D	EFINED	in M	IAP-CommonDataTypes	:	539						
BearerServiceCodetype reference OCTET STRING												
	D	EFINED	in M	IAP-BS-Code	:	11						
		USED	in M	IAP-CommonDataTypes	:	74	539					
		USED	in M	IAP-BS-Code			50	51	52	53		
54	55		57									
						59	60	61	62	63		
64	66	67	68					-				
01	00	0 /	00			69	70	71	72	73		
75	76	77	78			0,5	70	, _	72	73		
13	70	1 1	70			79	81	83	85	87		
0.1	0.4	0.77	100			19	81	83	85	8 /		
91	94	97	100									
						109	110	111	112	113		
114	115	116	117									
						118	119	120	121	122		
123	124											
	bear	erServ	iceLi	st		.identi	fier of	[4]				
Beare	rServi	ceList										
	D	EFINED	in M	IAP-MS-DataTypes	:	1066						
	_			iii lie beleel/pes								
	Rear	erServ	iceLi	.st		twne r	eferenc	re SEOI	TENCE	OF		
				IAP-MS-DataTypes			0101011	JC DIQ				
	ט			IAP-MS-DataTypes			1400					
		لظون	111 141	AF-M5-Datalypes	•	1000	1400					
	b	C		.st		4 4 4 4 4 4	£44	[0]				
D				.St		. raentr	rier or	_ [2]				
Beare	rServi											
	D	EFINED	ın M	IAP-MS-DataTypes	:	1408						
	bear	erServ	iceNo	tProvisioned		.inform	ation o	bject	refer	ence		
ERROR	, Info							-				
			_	IAP-Errors	:	247						
				MAP-MobileServiceOper			270	288				
				IAP-CallHandlingOpera			92	200				
		لاقادات	T11 11	carrianaringopera		١ د	22					

12-06					Reference	Listin	ıg :	for MAP	-Prot	occ	ol		2006-
174		USED	in :	MAP-Sur	pplementar	yServi	:	38	98	1	116	134	155
		USED	in	MAP-Eri	rors		:	32					
					isioned -DataTypes				fier	of	Named	Number	c, 1
	Bearer	Servl	NotP	rovPara	am			.type r	efere	nce	e SEQUI	ENCE	
	DEF	INED	in	MAP-ER-	-DataTypes								
					rors			119	249)			
		USED	in	MAP-ER-	-DataTypes		:	30					
	beingT	nside	-Are	a				.identi	fier	of	Named	Number	^. 3
					S-DataType:					-		1.0	-, -
'10011		ım						.value	refer	enc	ce SS-0	Code,	
	DEF	INED	in	MAP-SS-	-Code		:	132					
	hlackī	.ieter	٦					identi	fier	οf	Named	Number	^ 1
					-DataTypes				LICI	OI	Ivallica	Ivanibei	-, +
	DMCC E	'110n+T	· : a+					time r	oforo	nac	, סדים	CTD T MC	
					DataTypes				erere	HICE	S BII '	SIRING	
		USED	ТП.	MAP-OM-	-DataTypes		:	14 /					
	BMSC-T	nterf	face	List				.t.vpe r	efere	nce	BTT 9	STRING	
					-DataTypes								
					-DataTypes								
Interf:	bmsc-I aceList							.identi	fier	of	[5] Bi	MSC-	
IIICCII		-	in :	MAP-OM-	-DataTypes		:	92					
									c '	_	[4] D		
					 -DataTypes				iler	OI	[4] BI	MSC-EVE	entList
			_						fier	of	[5] T:	raceDep	oth
	DEF	INED	in :	MAP-OM-	-DataTypes		:	66					
	hmu o f								fion	٥f	TIECDT	т.,	
					DataTypes				rrer	OL	OESDI.	-ıu	
	DHI	TNDD	111	MAI MO	расатурсь		•	010					
	bmuef.							.identi	fier	of	Named	Number	c, 1
					-DataTypes								,
	bm-sc.							.identi	fier	of	Named	Number	c, 5
	DEF	INED	in	MAP-OM-	-DataTypes		:	83					
							• •	.value	refer	enc	ce SS-0	Code,	
'10010					- 1								
	DEF	INED	ın	MAP-SS-	-Code		:	123					
	hoiata	-HC						סיינובעי	refor	on c	70 CC_/	2507	
'10010							• •	.varue	TOTEL	CIIC	,c bb-(code,	
_0010.		INED	in	MAP-SS-	-Code		:	125					
					DataTypes			.identi 902	fier	of	Named	Number	c, 0

broadcastInitEntitlement DEFINED in MAP-MS-DataTypes	
broadcastService DEFINED in MAP-CommonDataTypes	
bssmap-ServiceHandover	identifier of [9] BSSMAP-
DEFINED in MAP-MS-DataTypes	: 487
bssmap-ServiceHandover ServiceHandover	identifier of [13] BSSMAP-
DEFINED in MAP-MS-DataTypes	: 554
bssmap-ServiceHandover ServiceHandover	identifier of BSSMAP-
DEFINED in MAP-MS-DataTypes	: 571
BSSMAP-ServiceHandover	type reference OCTET STRING
DEFINED in MAP-MS-DataTypes	
USED in MAP-MS-DataTypes	: 487 554 571
BSSMAP-ServiceHandoverInfo	type reference SEQUENCE
DEFINED in MAP-MS-DataTypes	: 570
USED in MAP-MS-DataTypes	: 568
bssmap-ServiceHandoverList ServiceHandoverList	identifier of [10] BSSMAP-
DEFINED in MAP-MS-DataTypes	: 489
bssmap-ServiceHandoverList ServiceHandoverList	identifier of [15] BSSMAP-

12-06	TAG R6.1		Reference	Listing	for	MAP-E	?rotoco	ol		2006-
	DEFINED	in MAP-MS	G-DataTypes	:	5	556				
			verList				erence	e SEQUI	ENCE OF	7
			S-DataTypes							
	USED	in MAP-MS	S-DataTypes	:	4	89،	556			
	busv				ide	entifi	ier of	Named	Number	· 1
			I-DataTypes							,
							er of	Named	Number	î, 2
	DEFINED	in MAP-CH	I-DataTypes	:	3	369				
	busvSubscr	iber			inf	ormat	ion ob	piect :	referer	nce
ERROR,	Information									
		in MAP-Er		:						
			llHandling(95	170		
	USED	in MAP-Er	rors	:		46				
	hugyQuhgar	iher			i de	ntifi	ier of	Named	Number	^ 1
			I-DataTypes				ler or	Nameu	Number	., 4
	DLI INLD	111 1111 011	Datalypes	•	_	.50				
	BusySubscr	iberParam.			typ	oe ref	erence	e SEQUI	ENCE	
	DEFINED	in MAP-ER	R-DataTypes	:	2	262				
			rors				300			
	USED	in MAP-ER	R-DataTypes	:		35				
	h gido				: 40	n+ifi	ior of	Namad	Numbor	^ 1
			I-DataTypes				rer or	Named	Number	., ⊥
	DLI INLD	111 1111 011	Datalypes	•	_	,00				
	b-subscribe	erNumber			ide	entifi	ler of	[1] IS	SDN-	
Addres	sString									
	DEFINED	in MAP-SS	S-DataTypes	:	2	207				
		1			i de	ntifi	ier of	[5] TO	SDM_	
	h-guhaari h	arNiimhar				,110111	ICI OI	נטן דג	אוענ	
Addres	b-subscribe	erNumber								
Addres	sString		G-DataTypes	:	_	280				
Addres	sString DEFINED	in MAP-SS		:	2					
	sString DEFINED b-subscribe	in MAP-SS	S-DataTypes	:	2		ler of	[2] IS	3DN-	
	sString DEFINED b-subscribe ressString	in MAP-SS erSubaddre	ess	:	ide	entifi	ier of	[2] IS	3DN-	
	sString DEFINED b-subscribe ressString	in MAP-SS erSubaddre		:	ide		ier of	[2] IS	SDN-	
	sString DEFINED b-subscriberessString DEFINED	in MAP-SS erSubaddre in MAP-SS	ess G-DataTypes	:	ide	entifi 208				c, 0
	sString DEFINED b-subscriberessString DEFINED call	in MAP-SSerSubaddre in MAP-SS	ess	:	2 ide 2	entifi 208				c, 0
	sString DEFINED b-subscriberessString DEFINED call DEFINED	in MAP-SS erSubaddre in MAP-SS	ess G-DataTypes G-DataTypes	:	2 ide ide	entifi 208 entifi 117	ier of	Named	Number	
Subadd	sString DEFINED b-subscriberessString DEFINED call DEFINED callBarred	in MAP-SS erSubaddre in MAP-SS	ess G-DataTypes	:	2 ide ide	entifi 208 entifi 117	ier of	Named	Number	
Subadd	sString DEFINED b-subscriberessString DEFINED call DEFINED callBarred Information	in MAP-SS erSubaddre in MAP-SS in MAP-MS	S-DataTypes S-DataTypes	:	2ide 2ide 4	entifi 208 entifi 117 Format	ier of	Named	Number	
Subadd	sString DEFINED b-subscriberessString DEFINED call DEFINED callBarred Information DEFINED	in MAP-SS erSubaddre in MAP-SSin MAP-MSn Object in MAP-Er	ess	:	2ide 2ide 4inf	entifi 208 entifi 117 Format	ier of	Named	Number referer	
Subadd	sString DEFINED b-subscriberessString DEFINED call DEFINED callBarred Information DEFINED USED	in MAP-SS erSubaddre in MAP-SS in MAP-MS n Object in MAP-Er in MAP-Mo	ess	: : : :	2ide 2ide 4inf	entifi 208 entifi 117 Format 310 97	ier of tion ok	Named	Number referer	
Subadd	sString DEFINED b-subscriberessString DEFINED call DEFINED callBarred Information DEFINED USED USED	in MAP-SS erSubaddre in MAP-SS in MAP-MS ODJect in MAP-Er in MAP-Mo in MAP-Ca	ess	:: : eOpera :	2ide 2ide 4inf	entifi 208 entifi 117 Format 310 97 43	ier of tion ok 272 97	Named Dject 1	Number referer 462	ace
Subadd ERROR,	sString DEFINED b-subscriberessString DEFINED call DEFINED callBarred Information DEFINED USED USED USED	in MAP-SS erSubaddre in MAP-SS in MAP-MS ODJect in MAP-Er in MAP-Mo in MAP-Ca	ess	:: : eOpera :	2ide 2ide 4inf	entifi 208 entifi 117 Format 310 97 43	ier of tion ok	Named Dject 1	Number referer 462	
Subadd ERROR,	sString DEFINED b-subscriberessString DEFINED call DEFINED callBarred Information DEFINED USED USED USED	in MAP-SS erSubaddre in MAP-SS in MAP-MS Object in MAP-Er in MAP-Mo in MAP-Ca in MAP-Su	ess	:: : eOpera :	2ide 2ide 4inf	entifi 208 entifi 117 Format 310 97 43	ier of tion ok 272 97	Named Dject 1	Number referer 462	ace
Subadd ERROR,	sString DEFINED b-subscriberessString DEFINED call DEFINED callBarred Information DEFINED USED USED USED 191 235	in MAP-SS erSubaddre in MAP-SS in MAP-MS n Object in MAP-Er in MAP-Mo in MAP-Ca in MAP-Su 272	ess	: : : : : : : : : : : : : : : : : : :	2ide 2ide 4inf	entifi 208 entifi 117 Format 310 97 43 40	ier of tion ok 272 97	Named Dject 1	Number referer 462	ace
Subadd ERROR,	sString DEFINED b-subscriberessString DEFINED call DEFINED callBarred Information DEFINED USED USED USED 191 235 USED	in MAP-SS erSubaddre in MAP-SS in MAP-MS n Object in MAP-Er in MAP-Mo in MAP-Ca in MAP-Su 272	ess	: : : : : : : : : : : : : : : : : : :	2ide 2ide 4inf	entifi 208 entifi 117 Format 310 97 43 40	ier of zion ok 272 97 100	Named Dject 1	Number referer 462	ace
Subadd ERROR,	b-subscriberesstring DEFINED call DEFINED call DEFINED callBarred Information DEFINED USED USED USED 191 235 USED USED USED USED	in MAP-SS erSubaddre in MAP-SS in MAP-MS n Object in MAP-Er in MAP-Ca in MAP-Ca in MAP-Su 272 in MAP-Sh in MAP-Er	ess	: : : : : : : : : : : : : : : : : : :	2ide 2ide 4inf	208 entifi 208 entifi 217 cormat 310 97 43 40 290 37 49	ier of cion ok 272 97 100	Named Dject 1 290 118	Number referer 462 136	nce 157
Subadd ERROR,	b-subscriberessString DEFINED call DEFINED callBarred Information DEFINED USED USED USED USED USED USED USED CallBarred CallBarred Companies Companie	in MAP-SS erSubaddre in MAP-SS in MAP-MS in MAP-MS Object in MAP-Er in MAP-Ca in MAP-Su 272 in MAP-Sh in MAP-Er	ess	: eOpera : perat : yServi :	2ide 4inf	entifi 208 entifi 117 Format 310 97 43 40 290 37 49	ier of cion ok 272 97 100	Named Dject 1 290 118	Number referer 462 136	nce 157
Subadd ERROR,	b-subscriberessString DEFINED call DEFINED callBarred Information DEFINED USED USED USED USED USED USED USED CallBarred CallBarred Companies Companie	in MAP-SS erSubaddre in MAP-SS in MAP-MS in MAP-MS Object in MAP-Er in MAP-Ca in MAP-Su 272 in MAP-Sh in MAP-Er	ess	: eOpera : perat : yServi :	2ide 4inf	208 entifi 208 entifi 217 cormat 310 97 43 40 290 37 49	ier of cion ok 272 97 100	Named Dject 1 290 118	Number referer 462 136	nce 157
Subadd ERROR,	b-subscriberessString DEFINED call DEFINED callBarred Information DEFINED USED USED USED USED USED USED CallBarred DEFINED CallBarred USED USED USED CallBarred DEFINED	in MAP-SS erSubaddre in MAP-SS in MAP-MS in MAP-MS Object in MAP-Er in MAP-Ca in MAP-Su 272 in MAP-Sh in MAP-Er	S-DataTypes S-DataTypes S-DataTypes S-DataTypes Strors SallHandling SallHandling Sapplementary Sarrors SallHandling Sapplementary Sarrors SallHandling Sapplementary	: eOpera : perat : yServi : Servic :	2ide 4inf 3	entifi 208 entifi 117 Format 310 97 43 40 290 37 49 entifi	ier of 272 97 100 76	Named 290 118 Named	Number referer 462 136 Number	nce 157
Subadd ERROR,	b-subscriberessString DEFINED call DEFINED callBarred Information DEFINED USED USED USED USED USED CallBarred CallBarred CallBarred CallBarred CallBarred CallBarred CallBarred	in MAP-SS erSubaddre in MAP-SS in MAP-MS in MAP-MS Object in MAP-Er in MAP-Ca in MAP-Su 272 in MAP-Sh in MAP-Er	ess	: eOpera : perat : yServi : Servic :	2ide 4inf 3ide 1typ	entifi 208 entifi 117 Format 310 97 43 40 290 37 49 entifi	ier of 272 97 100 76	Named 290 118 Named	Number referer 462 136 Number	nce 157

USED in MAP-Errors : 127 312 USED in MAP-ER-DataTypes : 15 ${\tt callBarringCause}. {\tt identifier of CallBarringCause}$ DEFINED in MAP-ER-DataTypes 101 CallBarringCause.....type reference ENUMERATED : 107 : 101 DEFINED in MAP-ER-DataTypes USED in MAP-ER-DataTypes 112 ${\tt callBarringCause}. {\tt identifier of CallBarringCause}$ DEFINED in MAP-ER-DataTypes 112 callBarringData.....identifier of [2] CallBarringData DEFINED in MAP-MS-DataTypes : 2266 CallBarringData.....type reference SEQUENCE DEFINED in MAP-MS-DataTypes : 2314
USED in MAP-MS-DataTypes : 2266 USED in MAP-MS-DataTypes CallBarringFeature.....type reference SEQUENCE

callBarringFeatureList.....identifier of Ext-

CallBarFeatureList

DEFINED in MAP-MS-DataTypes

DEFINED in MAP-SS-DataTypes : 155

USED in MAP-SS-DataTypes

callBarringFeatureList.....identifier of Ext-CallBarFeatureList

R6.15 Cross Reference Listing for MAP-Protocol 2006-12-06 09:33:23 PAGE 15 DEFINED in MAP-MS-DataTypes : 2315 callBarringFeatureList.....identifier of [1] Ext-CallBarFeatureList DEFINED in MAP-MS-DataTypes : 2468 callBarringFeatureList.....identifier of CallBarringFeatureList DEFINED in MAP-SS-DataTypes CallBarringFeatureList.....type reference SEQUENCE OF DEFINED in MAP-SS-DataTypes : 152 USED in MAP-SS-DataTypes 149 callBarringInfo.....identifier of [1] Ext-CallBarInfo DEFINED in MAP-MS-DataTypes 1156 ${\tt callBarringInfo}..... {\tt identifier of [1] CallBarringInfo}$ DEFINED in MAP-SS-DataTypes CallBarringInfo.....type reference SEQUENCE DEFINED in MAP-SS-DataTypes : 147 USED in MAP-SS-DataTypes callBarringInfoFor-CSE.....identifier of [1] Ext-CallBarringInfoFor-CSE DEFINED in MAP-MS-DataTypes : 2424 callBarringInfoFor-CSE.....identifier of [1] Ext-CallBarringInfoFor-CSE DEFINED in MAP-MS-DataTypes : 2456 callDiversionTreatmentIndicator.....identifier of [20] ${\tt CallDiversionTreatmentIndicator}$ DEFINED in MAP-CH-DataTypes 113 CallDiversionTreatmentIndicator.....type reference OCTET STRING DEFINED in MAP-CH-DataTypes : 143 USED in MAP-CH-DataTypes calledPartySS-InteractionViolation.....identifier of Named Number, 7 DEFINED in MAP-ER-DataTypes : 126 callForwardingData.....identifier of [1] CallForwardingData DEFINED in MAP-MS-DataTypes CallForwardingData.....type reference SEQUENCE DEFINED in MAP-MS-DataTypes : 2308 USED in MAP-MS-DataTypes : 2265 callInfo.....identifier of [1] ExternalSignalInfo DEFINED in MAP-CH-DataTypes callInfo.....identifier of [3] ExternalSignalInfo DEFINED in MAP-SS-DataTypes : 313 callOriginator.....identifier of [8] NULL

DEFINED in MAP-GR-DataTypes : 126 $\verb|callOutcome| identifier of [1] CallOutcome|$ DEFINED in MAP-CH-DataTypes 354 CallOutcome.....type reference ENUMERATED DEFINED in MAP-CH-DataTypes : 366 USED in MAP-CH-DataTypes : 354 callReferenceNumber.....identifier of [7] CallReferenceNumber DEFINED in MAP-CH-DataTypes : 99 CallReferenceNumber.....type reference OCTET STRING DEFINED in MAP-CH-DataTypes : 130 USED in MAP-CH-DataTypes : 22 99 228 250 callReferenceNumber.....identifier of [9] CallReferenceNumber DEFINED in MAP-CH-DataTypes callReferenceNumber.....identifier of [0] CallReferenceNumber DEFINED in MAP-CH-DataTypes 250 $\verb|callReportdata| identifier of [2] CallReportData|$ DEFINED in MAP-CH-DataTypes : 343 CallReportData.....type reference SEQUENCE DEFINED in MAP-CH-DataTypes : 352 USED in MAP-CH-DataTypes callSessionRelated.....value reference SS-Code, '10110010'B

TAG R6.15 Cross Reference Listing for MAP-Protocol 2006-12-06 09:33:23 PAGE 16 DEFINED in MAP-SS-Code 163 callSessionRelated.....identifier of [1] PrivacyCheckRelatedAction DEFINED in MAP-LCS-DataTypes : 270 callSessionUnrelated.....value reference SS-Code, '10110011'B DEFINED in MAP-SS-Code 166 callSessionUnrelated.....identifier of [0] PrivacyCheckRelatedAction DEFINED in MAP-LCS-DataTypes callTerminationIndicator.....identifier of [2] CallTerminationIndicator DEFINED in MAP-CH-DataTypes CallTerminationIndicator.....type reference ENUMERATED : DEFINED in MAP-CH-DataTypes 432 USED in MAP-CH-DataTypes $\verb|callToClientNotSetup......identifier of Named Number, 2|\\$ DEFINED in MAP-ER-DataTypes : callTypeCriteria.....identifier of [2] CallTypeCriteria DEFINED in MAP-MS-DataTypes : 1642 CallTypeCriteria.....type reference ENUMERATED DEFINED in MAP-MS-DataTypes : 1680 USED in MAP-MS-DataTypes ${\tt camelBusy......identifier\ of\ [1]\ NULL}$ DEFINED in MAP-MS-DataTypes : 2172 camelCapabilityHandling.....identifier of [1] CamelCapabilityHandling DEFINED in MAP-MS-DataTypes : camelCapabilityHandling.....identifier of [1] CamelCapabilityHandling DEFINED in MAP-MS-DataTypes camelCapabilityHandling.....identifier of [0] CamelCapabilityHandling DEFINED in MAP-MS-DataTypes CamelCapabilityHandling.....type reference INTEGER DEFINED in MAP-MS-DataTypes : 1710 USED in MAP-MS-DataTypes : 75 75 951 1534 1593 1765 1881 camelCapabilityHandling.....identifier of [1] CamelCapabilityHandling DEFINED in MAP-MS-DataTypes : 1765 camelCapabilityHandling.....identifier of [0] CamelCapabilityHandling DEFINED in MAP-MS-DataTypes : 1881

camelInfo DEFINED in MAP-CH-DataTypes	
CamelInfo DEFINED in MAP-CH-DataTypes	type reference SEQUENCE : 284
USED in MAP-CH-DataTypes	
<pre>camelRoutingInfo</pre>	identifier of [8]
DEFINED in MAP-CH-DataTypes	: 293
CamelRoutingInfo	
DEFINED in MAP-CH-DataTypes	
USED in MAP-CH-DataTypes	: 293
camelSubscriptionInfoWithdraw	identifier of [9] NULL
DEFINED in MAP-MS-DataTypes	: 1433
camel-invoked	identifier of Named Number, 1
DEFINED in MAP-SS-DataTypes	: 319
camel-SubscriptionInfo	identifier of [4] CAMEL-
SubscriptionInfo	
DEFINED in MAP-MS-DataTypes	: 2268
CAMEL-SubscriptionInfo	
DEFINED in MAP-MS-DataTypes	: 2330
USED in MAP-MS-DataTypes	: 2268 2370 2426
camel-SubscriptionInfo	identifier of [1] CAMEL-
SubscriptionInfo	
DEFINED in MAP-MS-DataTypes	: 2370
camel-SubscriptionInfoSubscriptionInfo	identifier of [3] CAMEL-

12-06	TAG R6.1			Reference	Listing	for	MAP	P-Protocol		2006-
				on G-DataType				fier of Named N	ſumber,	4
				DataTypes			enti 290	fier of Cancell.	ationTy	⁄pe
	Cancellati	onTy	pe			typ	pe r	reference ENUMER	ATED	
	DEFINED	in	MAP-MS-	DataTypes	:	2	294			
	USED	in	MAP-MS-	-DataTypes	:	2	290			
OPERAT	cancelLoca TION, Inform				i	nform	mati	on object refer	ence	
012111				pileServic	eOpera :	-	184			
			MAP-Pro		:		17	121		
	USED	in	MAP-Mob	oileServic						
	G 3.T		7							-
				DataTypes			pe r 288	reference [3] S	EQUENCE	S
	תביבות חפינ דוופר	in	MAP-MS- MAD-Mol	oileServic	: eOnera :	-	200 113	186		
	USED	in	MAP-MS-	DataTypes	eopera . :	-		100		
	0.2.2.2				·					
							pe r	reference SEQUEN	ICE	
				-DataTypes			300			
	USED	in	MAP-Mok	pileServic	eOpera :	-		188		
	USED	in	MAP-MS-	-DataTypes	:		19			
	can					ide	⊃nti	fier of Named N	umber.	7
				-DataTypes			103	Titor of Namea 1	ianizer,	,
	category					ide	enti	fier of [2] Cat	egory	
	DEFINED	in	MAP-MS-	-DataTypes	:	10	064			
	Category					± szr	ne r	reference OCTET	QTD T NIC	
				DataTypes				CICICIO COIDI	DIKING	
	USED	in	MAP-MS-	-DataTypes	:	10				
								reference OCTET	STRING	
				-DataTypes						
	USED	in	MAP-MS-	-DataTypes	:	16	589	1692		
	cchsIdle					ide	⊃nti	fier of Named N	lumber	1
				DataTypes				iller of wanted to	idilibet,	_
				71						
								fier of Named N	umber,	0
	DEFINED	in	MAP-CH-	-DataTypes	:	3	331			
	aabaNo+Doo	ahah	1.0			4 44	-n+ +	fier of Named N	numb o m	2
				DataTypes				liter of Named N	iumber,	2
				Bacarypes	•	_				
	ccbs-A					val	lue	reference SS-Co	ode,	
'01000										
	DEFINED	ın	MAP-SS-	-coae	:		79			
	ccbs-B					val	lue	reference SS-Co	de,	
'01000									•	
	DEFINED	in	MAP-SS-	-Code	:		81			
	arala B							E1 C [4]	т.	
	_			DataTypes			enti 266	fier of [1] NUI	ıLı	
	DELINED	т11 .	MAE-DK-	Datalypes	:	4	200			

ccbs-Call DEFINED in MAP-CH-DataTypes	
ccbs-Call DEFINED in MAP-CH-DataTypes	
ccbs-Data DEFINED in MAP-SS-DataTypes	
CCBS-Data DEFINED in MAP-SS-DataTypes USED in MAP-SS-DataTypes	: 309
ccbs-Feature DEFINED in MAP-CH-DataTypes	
CCBS-Feature	type reference SEQUENCE
DEFINED in MAP-SS-DataTypes	: 205
USED in MAP-CH-DataTypes	
USED in MAP-SS-DataTypes	: 36 201 310 324
ccbs-Feature DEFINED in MAP-SS-DataTypes	

12-06	TAG R6.1 09:33:23			Reference	Listing	fo	r MAP-Pro	tocc	ol	2006-
				 -DataTypes				of	[0]	CCBS-Feature
Featur								of	[2]	CCBS-
	DEFINED	in	MAP-SS-	-DataTypes	:		195			
	CCBS-Featu							ence	e SEÇ	QUENCE OF
				-DataTypes						
	USED	TII	MAP-SS-	-DataTypes	:		195			
	ccbs-Index					i	dentifier	of	[0]	CCBS-Index
				-DataTypes						
	CCBS-Index					t	ype refer	ence	e INT	ΓEGER
	DEFINED	in	MAP-SS-	-DataTypes	:		212			
	USED	in	MAP-SS-	-DataTypes	:		206 32	9		
	aaba Todaa					<u>.</u>	J	۰.	[1]	aana Indon
				DataTypes				OI	[]	CCBS-Index
	DELINED	111	MAP-55	-Datalypes	•		329			
Indica	ccbs-Indic	ator	`S			i	dentifier	of	[11]	CCBS-
		in	MAP-CH-	-DataTypes	:		165			
	CCBS-Indic	ator	·a			+ -	wne refer	ence	\ CE(TIENCE
				DataTypes		-		CIICC	, טביק	SORICE
				-DataTypes						
								of	[2]	ReportingState
	DEFINED	in	MAP-CH-	-DataTypes	:		313			
	ccbs-Possi	hle				i,	dentifier	٥f	[0]	NITIT.T.
				-DataTypes				O1	[0]	NOLL
				71						
	ccbs-Possi					i	dentifier	of	[8]	NULL
	DEFINED	in	MAP-CH-	-DataTypes	:		257			
	asha Dasai'	h 7 a				<u>.</u>	J	۰.	[0]	ATTIT T
	ccbs-Possi			DataTypes				OI	[0]	NOLL
	DELINED	111	IIAI LIK	DataTypes	•		205			
	ccbs-Reque	stSt	ate			i	dentifier	of	[6]	CCBS-
Reques										
	DEFINED	in	MAP-SS-	-DataTypes	:		281			
	CCDC Domio	a+ C+	2+0			+-	mo rofor	ongo	. EMI	IMEDATED
	CCBS-Reque			-DataTypes			ype reter 284	ence	EIN C	JMERAIED
				-DataTypes			281			
	0022			DataTypes	•		201			
	ccbs-Subsc	ribe	rStatus	3		i	dentifier	of	[0]	CCBS-
Subscr	iberStatus									
	DEFINED	in	MAP-CH-	-DataTypes	:		326			
	CCBS-Subsc	riha	rCtatur	3		+-	me rofor	onac	ידאים ב	TMFDNTFD
				-DataTypes		-		GIICE	י היוא (OHERA I ED
				-DataTypes				8		
	0010		011		•			-		
	ccbs-Subsc	ribe	rStatus	3		i	dentifier	of	[0]	CCBS-
Subscr	iberStatus									
	DEFINED	in	MAP-CH-	-DataTypes	:		348			

cd.....value reference SS-Code, '00100100'B DEFINED in MAP-SS-Code 60 cellGlobalId.....identifier of Named Number, 4 DEFINED in MAP-LCS-DataTypes 308 cellGlobalIdOrServiceAreaIdFixedLength..identifier of [0] CellGlobalIdOrServiceAreaIdFixedLength DEFINED in MAP-CommonDataTypes : ${\tt CellGlobalIdOrServiceAreaIdFixedLength..type\ reference\ OCTET\ STRING}$ DEFINED in MAP-CommonDataTypes : 508 USED in MAP-CommonDataTypes : 47 505 cellGlobalIdOrServiceAreaIdOrLAI.....identifier of [3] CellGlobalIdOrServiceAreaIdOrLAI DEFINED in MAP-MS-DataTypes cellGlobalIdOrServiceAreaIdOrLAI.....identifier of [0] CellGlobalIdOrServiceAreaIdOrLAI DEFINED in MAP-MS-DataTypes CellGlobalIdOrServiceAreaIdOrLAI.....type reference CHOICE DEFINED in MAP-CommonDataTypes : 504

USED in MAP-MS-DataTypes : 185 2109 2123

USED in MAP-CommonDataTypes : 46

USED in MAP-LCS-DataTypes : 43 345 481 cellIdOrSai.....identifier of [6] CellGlobalIdOrServiceAreaIdOrLAI

12-06	TAG R6.15 09:33:23 PAGE		sting for MAP-Protocol	2006-
	DEFINED in	MAP-LCS-DataTypes	: 345	
CellGl	obalIdOrService		identifier of [13]	
'00101	001'B		value reference SS-C	ode,
'00101	011'B		value reference SS-C	ode,
'00101	cfnry 010'B		value reference SS-C	ode,
			: 56value reference SS-C	ode.
'00100	001'B		: 50	,
		s MAP-MS-DataTypes	identifier of Named : 1753	Number, 14
		onDP MAP-MS-DataTypes	identifier of Named : 1750	Number, 11
		Barred MAP-MS-DataTypes	identifier of Named : 1115	Number, 10
Chargi	ngCharacteristi		identifier of [18]	
	ChargingCharac	teristics	type reference OCTET	STRING
		MAP-MS-DataTypes MAP-MS-DataTypes	: 1027 : 863 924 2204	
Charqi	chargingCharac ngCharacteristi		identifier of [15]	
		MAP-MS-DataTypes	: 2204	
		teristicsWithdraw. MAP-MS-DataTypes	identifier of [16] N : 1442	ULL
		MAP-MS-DataTypes	identifier of [14] G : 2203	PRSChargingID
		tor MAP-MS-DataTypes	identifier of Named : 1747	Number, 8
18	chatting		value reference LCSS	erviceTypeID,
10	DEFINED in	MAP-CommonDataType:	: 430	
OPERAT	ION, Information DEFINED in	n Object MAP-MobileServiceOp		rence
	USED in	MAP-Protocol	: 28 124	

USED in MAP-MobileServiceOpera : 49	
ol lawar a	CHOLIDNICH
CheckIMEI-Argtype refe	erence SEQUENCE
DEFINED in MAP-MS-DataTypes : 808	
USED in MAP-MobileServiceOpera : 133	392
USED in MAP-MS-DataTypes : 52	
CheckIMEI-Restype refe	erence SEQUENCE
DEFINED in MAP-MS-DataTypes : 814	
USED in MAP-MobileServiceOpera: 134	394
USED in MAP-MS-DataTypes : 53	
COLD III THII THE DACKLYPED	
chosenChannelInfoidentifie	er of [0]
ChosenChannelInfo	
DEFINED in MAP-MS-DataTypes : 632	
Charan Charmal Trafa	omen as OCHER CHRING
ChosenChannelInfotype refe	erence OCIET STRING
DEFINED in MAP-MS-DataTypes : 636	
USED in MAP-MS-DataTypes : 632	
ChosenEncryptionAlgorithmtype refe	erence OCTET STRING
DEFINED in MAP-MS-DataTypes : 625	
USED in MAP-MS-DataTypes : 615	
COLD III THI THE DACKLYPED . 013	
ChosenIntegrityProtectionAlgorithmtype refe	erence OCTET STRING
DEFINED in MAP-MS-DataTypes : 619	
USED in MAP-MS-DataTypes : 614	
chosenRadioResourceInformationidentific	om of [6]
	ST OT [0]
ChosenRadioResourceInformation	
DEFINED in MAP-MS-DataTypes : 607	
ChosenRadioResourceInformationtype refe	erence SEQUENCE

```
TAG R6.15 Cross Reference Listing for MAP-Protocol
                                                            2006-
12-06 09:33:23 PAGE 20
       DEFINED in MAP-MS-DataTypes
                                      631
                                     607 663
          USED in MAP-MS-DataTypes
     chosenRadioResourceInformation.....identifier of [3]
ChosenRadioResourceInformation
       DEFINED in MAP-MS-DataTypes
     chosenSpeechVersion.....identifier of [1]
ChosenSpeechVersion
       DEFINED in MAP-MS-DataTypes
     ChosenSpeechVersion.....type reference OCTET STRING
       DEFINED in MAP-MS-DataTypes
          USED in MAP-MS-DataTypes
     \verb|cipheringAlgorithm|..... identifier of CipheringAlgorithm|
        DEFINED in MAP-GR-DataTypes
     CipheringAlgorithm.....type reference OCTET STRING
        DEFINED in MAP-GR-DataTypes
          USED in MAP-GR-DataTypes
     citySightseeing......value reference LCSServiceTypeID,
       DEFINED in MAP-CommonDataTypes
                                      421
     ck.....identifier of CK
       DEFINED in MAP-MS-DataTypes
     {\tt ck......identifier\ of\ CK}
       DEFINED in MAP-MS-DataTypes
     CK.....type reference OCTET STRING
       DEFINED in MAP-MS-DataTypes : 391
          USED in MAP-MS-DataTypes
                                       363 378
     cksn.....identifier of Cksn
       DEFINED in MAP-MS-DataTypes
                                  :
     Cksn.....type reference OCTET STRING
       DEFINED in MAP-MS-DataTypes : 399
          USED in MAP-MS-DataTypes
     \verb|clientIdentity....| identifier of LCSClientExternalID| \\
       DEFINED in MAP-MS-DataTypes
     clientNotInMSPrivacyExceptionList.....identifier of Named Number, 1
       DEFINED in MAP-ER-DataTypes
                                       348
     clip.....value reference SS-Code,
'00010001'B
       DEFINED in MAP-SS-Code
                                       28
     clir.....value reference SS-Code,
'00010010'B
       DEFINED in MAP-SS-Code
                                       30
     cliRestrictionOption.....identifier of [2]
CliRestrictionOption
       DEFINED in MAP-SS-DataTypes : 171
```

CliRestrictionOption DEFINED in MAP-SS-DataTypes			ferenc	e ENU	MERATED)
USED in MAP-SS-DataTypes	:	29	171	191		
<pre>cliRestrictionOption</pre>	i	dentif	ier of			
DEFINED in MAP-SS-DataTypes	:	191				
clir-invoked DEFINED in MAP-SS-DataTypes			ier of	Name	d Numbe	er, 0
			_			
cnap'00011001'B	v	alue r	eferen	ce SS	-Code,	
DEFINED in MAP-SS-Code	:	42				
Code DEFINED in Remote-Operations-Info			ferenc	e CHC	ICE	
USED in Remote-Operations-Info			46			
Codec			ferenc	e OCT	ET STRI	NG
DEFINED in MAP-MS-DataTypes						
USED in MAP-MS-DataTypes 677 678 679 680	:	490	493	559	610	667
		681	682	683	684	
codec1 DEFINED in MAP-MS-DataTypes			ier of	[1]	Codec	
codec2 DEFINED in MAP-MS-DataTypes			ier of	[2]	Codec	

12-06	TAG R6.15 Cross Reference Listing for MA 09:33:23 PAGE 21	AP-Protocol	2006-
	codec3ident DEFINED in MAP-MS-DataTypes : 679		Codec
	codec4ident DEFINED in MAP-MS-DataTypes : 680		Codec
	codec5ident DEFINED in MAP-MS-DataTypes : 681		Codec
	codec6ident DEFINED in MAP-MS-DataTypes : 682		Codec
	codec7ident DEFINED in MAP-MS-DataTypes : 683		Codec
	codec8ident DEFINED in MAP-MS-DataTypes : 684		Codec
	CodecListtype DEFINED in MAP-MS-DataTypes : 676 USED in MAP-MS-DataTypes : 611	5	
	codec-Infoident DEFINED in MAP-GR-DataTypes : 51	cifier of COI	
	CODEC-Infotype DEFINED in MAP-GR-DataTypes : 103	reference 00	TET STRING
	USED in MAP-GR-DataTypes : 51 collectedInfoident	tifier of Nam	ned Number, 2
	DEFINED in MAP-MS-DataTypes : 1621 colpvalue		SS-Code,
'00010	011'B DEFINED in MAP-SS-Code : 32	2	
'00010	colrvalue 100'B DEFINED in MAP-SS-Code : 34		SS-Code,
	completedident	cifier of Nam	ned Number, 3
	DEFINED in MAP-SS-DataTypes : 288 completeDataListIncludedident	cifier of NUI	ıL
	DEFINED in MAP-MS-DataTypes : 932 completeDataListIncludedident		ıL
	DEFINED in MAP-MS-DataTypes : 1047 congestionident	tifier of Nam	ned Number, 3
	DEFINED in MAP-LCS-DataTypes : 526 congestionident		ned Number, 0
	DEFINED in MAP-ER-DataTypes : 365 contextident	5	
	DEFINED in MAP-OM-DataTypes : 159)	
	ContextIdtype	rererence IN	IIEGEK

	AP-MS-DataTypes AP-MS-DataTypes			1470	2189		
	AP-MS-DataTypes			ier of	Conte	ktIdList	
DEFINED in MA	AP-MS-DataTypes AP-MS-DataTypes	:	1469	ferenc	e SEQUI	ENCE OF	
	AP-MS-DataTypes			ier of	Named	Number,	0
	cion AP-MS-DataTypes			ier of	Named	Number,	0
	ion AP-MS-DataTypes			ier of	Named	Number,	0
	AP-CommonDataTypes			ier of	Named	Number,	4
	AP-LCS-DataTypes			ier of	Named	Number,	0

12-06	TAG R6.15 Cross Reference Listing 09:33:23 PAGE 22	for MAP-Protocol	2006-
	criteriaForChangeOfPositionDP DEFINED in MAP-MS-DataTypes :		17
	csiActive DEFINED in MAP-MS-DataTypes :		
	csi-Active DEFINED in MAP-MS-DataTypes :		
	csi-Active DEFINED in MAP-MS-DataTypes :		
	csi-Active DEFINED in MAP-MS-DataTypes :		
	csi-Active DEFINED in MAP-MS-DataTypes :		
	csi-Active DEFINED in MAP-MS-DataTypes :		
	csi-Active DEFINED in MAP-MS-DataTypes :		
	csi-Active DEFINED in MAP-MS-DataTypes :		
Alloca	cs-AllocationRetentionPriority cionRetentionPriority DEFINED in MAP-MS-DataTypes :		
	CS-AllocationRetentionPriority DEFINED in MAP-MS-DataTypes : USED in MAP-MS-DataTypes :	876	
	cs-Domain DEFINED in MAP-MS-DataTypes :		0
	cs-LCS-NotSupportedByUE DEFINED in MAP-MS-DataTypes :		
'01100	cug	value reference SS-Code,	
01100	DEFINED in MAP-SS-Code :	96	
	<pre>cugIC-CallBarred DEFINED in MAP-MS-DataTypes :</pre>		1
	<pre>cugOG-CallBarred DEFINED in MAP-MS-DataTypes :</pre>		2
	<pre>cugSubscriptionFlag DEFINED in MAP-CH-DataTypes :</pre>		
	CUG-CheckInfo DEFINED in MAP-CH-DataTypes : USED in MAP-CH-DataTypes :	83	
	cug-CheckInfo	identifier of [1] CUG-Check	Info

DEFINED in MAP-CH-DataTypes	: 93
cug-CheckInfo DEFINED in MAP-CH-DataTypes	
cug-CheckInfo DEFINED in MAP-CH-DataTypes	
CUG-Feature DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes	: 1272
cug-FeatureList DEFINED in MAP-MS-DataTypes	
CUG-FeatureList DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes	: 1264
cug-Index DEFINED in MAP-MS-DataTypes	
CUG-Index DEFINED in MAP-MS-DataTypes	

12-06	TAG R6.15 Cross Reference Listi 09:33:23 PAGE 23	.ng	for MAP-Protocol 2006-
	USED in MAP-MS-DataTypes	:	81 1245 1274
	cug-Info DEFINED in MAP-MS-DataTypes		
	CUG-Info DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes	:	1235
	cug-Interlock DEFINED in MAP-MS-DataTypes		
	CUG-Interlock DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes USED in MAP-CH-DataTypes	:	1255 83 1246
	cug-Interlock		identifier of CUG-Interlock
	cug-OutgoingAccess DEFINED in MAP-CH-DataTypes		
ERROR,	cug-Reject Information Object DEFINED in MAP-Errors		
	USED in MAP-CallHandlingOperat	:	
	cug-Reject DEFINED in MAP-CH-DataTypes	:	identifier of Named Number, 6 192
	cug-RejectCause DEFINED in MAP-ER-DataTypes		
	CUG-RejectCause DEFINED in MAP-ER-DataTypes USED in MAP-ER-DataTypes	:	122
	CUG-RejectParam DEFINED in MAP-ER-DataTypes USED in MAP-Errors	:	117 130 330
	USED in MAP-ER-DataTypes		
	CUG-Subscription DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes	:	1244
Subscr	cug-SubscriptionListiptionList DEFINED in MAP-MS-DataTypes		
	CUG-SubscriptionList		
	DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes	:	1241
	currentLocation DEFINED in MAP-MS-DataTypes		
	currentLocation		identifier of Named Number, 0

DEFINED in MAP-SS-Code

DEFINED in MAP-LCS-DataTypes : 134 currentLocationRetrieved.....identifier of [8] NULL DEFINED in MAP-MS-DataTypes : 2115 $\verb|currentLocationRetrieved..... identifier of [8] NULL|$ DEFINED in MAP-MS-DataTypes : 2132 $\verb|currentlyUsedCodec.....identifier of [11] Codec|\\$ 490 DEFINED in MAP-MS-DataTypes $\verb|currentOrLastKnownLocation.....identifier of Named Number, 1|\\$ DEFINED in MAP-LCS-DataTypes : 135 currentSecurityContext.....identifier of [2] CurrentSecurityContext DEFINED in MAP-MS-DataTypes CurrentSecurityContext.....type reference CHOICE DEFINED in MAP-MS-DataTypes : 368
USED in MAP-MS-DataTypes : 338 USED in MAP-MS-DataTypes 338 cw.....value reference SS-Code, '01000001'B

TAG R6.15 Cross Reference Listing for MAP-Protocol 12-06 09:33:23 PAGE 24	2006-
dataCDA-1200bpsvalue reference BearerServiceCode, '00010010'B DEFINED in MAP-BS-Code : 52	
dataCDA-1200-75bpsvalue reference BearerServiceCode, '00010011'B DEFINED in MAP-BS-Code : 53	
dataCDA-2400bpsvalue reference BearerServiceCode, '00010100'B DEFINED in MAP-BS-Code : 54	
dataCDA-300bpsvalue reference BearerServiceCode, '00010001'B DEFINED in MAP-BS-Code : 51	
dataCDA-4800bpsvalue reference BearerServiceCode, '00010101'B DEFINED in MAP-BS-Code : 55	
dataCDA-9600bpsvalue reference BearerServiceCode, '00010110'B	
DEFINED in MAP-BS-Code : 56 dataCDS-1200bpsvalue reference BearerServiceCode, '00011010'B	
DEFINED in MAP-BS-Code : 60 dataCDS-2400bpsvalue reference BearerServiceCode, '00011100'B	
DEFINED in MAP-BS-Code : 61 dataCDS-4800bpsvalue reference	
BearerServiceCode, '00011101'B DEFINED in MAP-BS-Code : 62 dataCDS-9600bpsvalue reference	
BearerServiceCode, '00011110'B DEFINED in MAP-BS-Code : 63	
dataCodingSchemeidentifier of [0] USSD- DataCodingScheme DEFINED in MAP-LCS-DataTypes : 178	
dataCodingSchemeidentifier of [0] USSD-DataCodingScheme DEFINED in MAP-LCS-DataTypes : 193	
dataCodingSchemeidentifier of [0] USSD-DataCodingScheme DEFINED in MAP-LCS-DataTypes : 260	
dataMissinginformation object reference ERROR, Information Object DEFINED in MAP-Errors : 165	Э
USED in MAP-MobileServiceOpera: 81 178 191 202 23 239 253 267 285	13 97
410 422 444 459 475 490 501	- 1

										•	Ī
				MAP-OperationAndMainte		25		74			
156	1.66	USED	ın	MAP-CallHandlingOperat	:	31	86	110	128	141	
156	166	HATE		MAD G		2.5	0.6	114	120	1.50	
170	100			MAP-SupplementaryServi	:	35	96	114	132	153	
172	188	202	21	/		233	258	270	288		
		IICED	in	MAP-ShortMessageServic		233 29	258 71			131	
147		USED	Т11	MAF-SHOT CHESSAGESET VIC	•	49	7 1	101	119	131	
147		IIGED	in	MAP-LocationServiceOpe		25	60	75	94		
				MAP-Errors	:	15	00	7.5	J 1		
		0011			•	13					
	Data	Missin	ηPa:	ram		.tvpe r	eferen	ce SEO	UENCE		
				MAP-ER-DataTypes				~			
				MAP-Errors			167				
						21					
	data	PDS-24	00b	os		.value	refere	nce			
Beare				00101100'B							
	Ι	EFINED	in	MAP-BS-Code	:	76					
				os		.value	refere	nce			
Beare				00101101'B							
	Ι	EFINED	in	MAP-BS-Code	:	77					
				os		.value	refere	nce			
Beare				00101110'B							
	Ι	EFINED	in	MAP-BS-Code	:	78					
						-	_	T 0	a a '		
1 17	dati	.ng			• • •	.value	refere	nce LCS	SServi	cellypell),
17	_	CHINTHH.		MAD CommonDataErmog		400					
	L	PLINED	Т11	MAP-CommonDataTypes	:	429					
	deac	tivata				identi	fier o	F Name	d Numbe	ar O	
				MAP-MS-DataTypes			TIEL O.	L Name	a Numbe	JI, 0	
	_	, 1111111		THE TIB DataTypes	•	2113					
	deac	tivate9	SS.		.in	formati	on obi	ect re	ference	7	
OPERA				on Object	• ====					-	
01 2141				MAP-SupplementaryServi	:	145					
	_			MAP-Protocol	:	75	130				
				MAP-SupplementaryServi	:	16	200				
				7.02.02							
	deac	tivate:	Γra	ceMode	.in:	formati	on obi	ect re:	ference	9	
OPERA				on Object			3				
				MAP-OperationAndMainte	:	66					
				MAP-Protocol	:	51	128				
				MAP-OperationAndMainte	:	14					

```
TAG R6.15 Cross Reference Listing for MAP-Protocol
                                                                      2006-
12-06 09:33:23 PAGE 25
      DeactivateTraceModeArg.....type reference SEQUENCE
         DEFINED in MAP-OM-DataTypes : 200
USED in MAP-OperationAndMainte : 37
USED in MAP-OM-DataTypes : 16
      DeactivateTraceModeRes.....type reference SEQUENCE
         DEFINED in MAP-OM-DataTypes : 208
USED in MAP-OperationAndMainte : 38
                                     inte: 38
: 17
                                                   70
            USED in MAP-OM-DataTypes
      defaultCallHandling.....identifier of DefaultCallHandling
         DEFINED in MAP-MS-DataTypes
                                            1556
      defaultCallHandling.....identifier of [1]
DefaultCallHandling
         DEFINED in MAP-MS-DataTypes
      DefaultCallHandling.....type reference ENUMERATED
         DEFINED in MAP-MS-DataTypes : 1702
USED in MAP-MS-DataTypes : 74
                                              74 1556 1613 1901
      defaultCallHandling.....identifier of [1]
DefaultCallHandling
         DEFINED in MAP-MS-DataTypes
      DefaultGPRS-Handling.....type reference ENUMERATED
         DEFINED in MAP-MS-DataTypes : 977
            USED in MAP-MS-DataTypes
      {\tt defaultPriority}..... {\tt identifier} \ {\tt of} \ {\tt EMLPP-Priority}
         DEFINED in MAP-CommonDataTypes
                                        :
      defaultPriority......identifier of [7] EMLPP-Priority
         DEFINED in MAP-SS-DataTypes
                                        :
      {\tt defaultPriority}..... {\tt identifier of EMLPP-Priority}
         DEFINED in MAP-SS-DataTypes
                                        :
                                             166
      defaultPriority......identifier of [1] EMLPP-Priority
         DEFINED in MAP-SS-DataTypes
                                        :
                                              194
      defaultSessionHandling.....identifier of [3] DefaultGPRS-
Handling
         DEFINED in MAP-MS-DataTypes
                                        :
                                              972
      defaultSMS-Handling.....identifier of [3] DefaultSMS-
Handling
                                     : 1787
         DEFINED in MAP-MS-DataTypes
      DefaultSMS-Handling.....type reference ENUMERATED
         DEFINED in MAP-MS-DataTypes : 1814
USED in MAP-MS-DataTypes : 1787
      deferredLocationEventType.....identifier of [1]
DeferredLocationEventType
         DEFINED in MAP-LCS-DataTypes
                                     : 131
      DeferredLocationEventType.....type reference BIT STRING
         DEFINED in MAP-LCS-DataTypes : 144
USED in MAP-LCS-DataTypes : 18 131 505
```

Deferre	deferredLoc edLocationEv	cationEventType		ider	ntifier	of		
201011		in MAP-LCS-DataType	es :	50)5			
lrData	deferredmt.	-lrData		ider	ntifier	of	[9] Defe	erredmt-
IIData	DEFINED	in MAP-LCS-DataType	es :	47	77			
	DEFINED	-lrDatain MAP-LCS-DataType in MAP-LCS-DataType	es :	50)4	rence	SEQUENO	CE
	deferredmt.	-lrResponsein MAP-LCS-DataType		ider	ntifier	of	Named Ni	umber, 3
	deferredmt-	-lrResponseIndicator in MAP-LCS-DataType		ider	ntifier	of	[3] NULI	
	-	ant in MAP-LCS-DataType				of	Named Nu	ımber, 1
		in MAP-SS-DataTypes				of	Named Nu	ımber, 6
OPERATI	ON, Informa DEFINED	criberData ation Object in MAP-MobileServic in MAP-Protocol	ceOpera :	41	L5		t refere	ence
		in MAP-MobileServic						

2006-

TAG R6.15 Cross Reference Listing for MAP-Protocol

12-06 09:33:23 PAGE 26 DeleteSubscriberDataArg.....type reference SEQUENCE DEFINED in MAP-MS-DataTypes : 1423
USED in MAP-MobileServiceOpera : 137 417
USED in MAP-MS-DataTypes : 59 DeleteSubscriberDataRes.....type reference SEQUENCE DEFINED in MAP-MS-DataTypes : 1484
USED in MAP-MobileServiceOpera : 138 419 USED in MAP-MS-DataTypes : ${\tt deliveryOutcomeIndicator......identifier\ of\ [3]\ NULL}$ DEFINED in MAP-SM-DataTypes destinationNumberCriteria.....identifier of [0] DestinationNumberCriteria DEFINED in MAP-MS-DataTypes DestinationNumberCriteria.....type reference SEQUENCE DEFINED in MAP-MS-DataTypes : 1653 USED in MAP-MS-DataTypes destinationNumberLengthList.....identifier of [2] DestinationNumberLengthList DEFINED in MAP-MS-DataTypes : 1656 ${\tt DestinationNumberLengthList................type\ reference\ {\tt SEQUENCE\ OF}}$ DEFINED in MAP-MS-DataTypes : 1666 USED in MAP-MS-DataTypes destinationNumberList.....identifier of [1] DestinationNumberList DEFINED in MAP-MS-DataTypes : 1655 DestinationNumberList.....type reference SEQUENCE OF DEFINED in MAP-MS-DataTypes : 1661 USED in MAP-MS-DataTypes dfc-WithArgument......identifier of Named Number, 5 DEFINED in MAP-MS-DataTypes : 1744 diagnosticInfo.....identifier of SignalInfo DEFINED in MAP-ER-DataTypes : dialledNumber.....identifier of ISDN-AddressString DEFINED in MAP-MS-DataTypes : 1553 disallowedByLocalRequlatoryRequirements.identifier of Named Number, 4 DEFINED in MAP-ER-DataTypes : 351 disconnectLeg.....identifier of Named Number, 3 DEFINED in MAP-MS-DataTypes : 1742 DomainType.....type reference ENUMERATED DEFINED in MAP-MS-DataTypes : 2097 USED in MAP-MS-DataTypes : 2090 doublyChargeableECT-Barred.....identifier of Named Number, 13 DEFINED in MAP-MS-DataTypes : 1118

downlinkAttached DEFINED in MAP-GR-DataTypes	
<pre>dp-AnalysedInfoCriteriaList AnalysedInfoCriteriaList</pre>	
DP-AnalysedInfoCriteriaList DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes	type reference SEQUENCE OF : 1547
DP-AnalysedInfoCriterium DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes	: 1552
dtmf-MidCall DEFINED in MAP-MS-DataTypes	identifier of Named Number, 7 : 1746
dualCommunication DEFINED in MAP-GR-DataTypes	
d-csi DEFINED in MAP-MS-DataTypes	identifier of Named Number, 3 : 1448
d-CSI DEFINED in MAP-MS-DataTypes	

12-06	TAG R6.15 Cross Reference Listing for MAP-Protocol 09:33:23 PAGE 27	2006-							
	D-CSItype reference SEQUENCE DEFINED in MAP-MS-DataTypes : 1532 USED in MAP-MS-DataTypes : 69 1500 2333 2352 USED in MAP-CH-DataTypes : 44 262 308								
	d-csiidentifier of Named Number, DEFINED in MAP-MS-DataTypes : 1727	1							
	d-csiidentifier of Named Number, DEFINED in MAP-MS-DataTypes : 2297	8							
	d-CSIidentifier of [2] D-CSI DEFINED in MAP-MS-DataTypes : 2333								
	d-csiidentifier of [12] D-CSI DEFINED in MAP-CH-DataTypes : 262								
	d-csiidentifier of [5] D-CSI DEFINED in MAP-CH-DataTypes : 308								
	d-IM-CSIidentifier of Named Number, DEFINED in MAP-MS-DataTypes : 1457	12							
	d-IM-CSIidentifier of Named Number, DEFINED in MAP-MS-DataTypes : 2303	3							
	d-IM-CSIidentifier of [20] D-CSI DEFINED in MAP-MS-DataTypes : 2352								
'00110	ectvalue reference SS-Code,								
	DEFINED in MAP-SS-Code : 66								
	eiridentifier of Named Number, DEFINED in MAP-CommonDataTypes : 360	6							
	ellipsoidArcidentifier of Named Number, DEFINED in MAP-LCS-DataTypes : 253	6							
	ellipsoidPointidentifier of Named Number, DEFINED in MAP-LCS-DataTypes : 247	0							
	ellipsoidPointWithAltitudeidentifier of Named Number, DEFINED in MAP-LCS-DataTypes : 251	4							
	ellipsoidPointWithAltitudeAndUncertaintyidentifier of Named Number, DEFINED in MAP-LCS-DataTypes : 252	5							
	ellipsoidPointWithUncertaintyCircleidentifier of Named Number, DEFINED in MAP-LCS-DataTypes : 248	1							
	ellipsoidPointWithUncertaintyEllipseidentifier of Named Number, DEFINED in MAP-LCS-DataTypes : 249	2							
1	emergencyAlertServicesvalue reference LCSServiceTy	peID,							
1	DEFINED in MAP-CommonDataTypes : 412								
	emergencyCallidentifier of Named Number,	1							

	DEFINED in MAP-MS-DataTypes	:	418
	emergencyCallOrigination DEFINED in MAP-LCS-DataTypes		
	emergencyCallRelease DEFINED in MAP-LCS-DataTypes		
'00010	emergencyCalls	v	ralue reference TeleserviceCode,
.00010		:	41
0	emergencyServices	v	ralue reference LCSServiceTypeID,
O	DEFINED in MAP-CommonDataTypes	:	411
	emergencyServices DEFINED in MAP-LCS-DataTypes		
'10100	emlpp	v	ralue reference SS-Code,
		:	156
	emlpp-Info DEFINED in MAP-MS-DataTypes		
	EMLPP-Info	t	ype reference SEQUENCE

	TAG R6.1		Reference	Listin	g f	or MAP	-Protoc	ol		2006-
	DEEINED	in MAD-Co	mmonDataTy	neg		546				
	IIGED	in MAD-MS	-DataTypes	pes	:	188	1159			
	USED	in MAP Co	-DataTypes mmonDataTy	200	•	100	1133			
	USED	III MAP-CO	IIIIIOIIDataiy	pes	:	53				
	EMLPP-Prio		mmonDataTy				eferenc	e INTE	GER	
			mmonDataTy	_			547	548	558	559
560 5		563	mmonbacary.	рсь	•	51	517	310	330	333
						564				
	USED	in MAP-SS	-DataTypes		:	51	78	166	193	194
	USED	in MAP-GR	-DataTypes		:	25	56			
			21							
	enabling					identi:	fier of	Named	Number	r, 1
			-DataTypes							•
			21							
	encryption ncryptionA					identi:	fier of	[1]		
	DEFINED	in MAP-MS	-DataTypes		:	615				
	encryption					identi	fier of	[1]		
Permitt	edEncryption									
	DEFINED	in MAP-MS	-DataTypes		:	504				
		_								
	encryption:					identi:	fier of	[1]		
Encrypt	ionInformat									
	DEFINED	in MAP-MS	-DataTypes		:	479				
							c			
	encryption		• • • • • • • • • •		• • •	ident:	tier of	[6]		
Encrypt	ionInformat									
	DEFINED	in MAP-MS	-DataTypes		:	546				
	Engarantion	Informatio	~			+	ofomono		т стрт	ATC.
	Encryption:						ererenc	e ocie	I SIRII	NG
			-DataTypes				T 4 C			
	USED	in MAP-MS	-DataTypes		:	4 / 9	546			
	ontoning Tri	- 0 7 20 0				4 don+4.	fion of	: Namad	Mumbos	n 1
	enteringIn						rier or	. Named	ишшрел	г, т
	DEFINED	III MAP-LC	S-DataType	S	:	146				
	enterNewPW					idonti	fior of	Namad	Numboi	n 1
			-DataTypes				rier or	. Nameu	Number	L, _
	DELINED	III MAP-55	-Datalypes		:	249				
	enterNewPW	-Nasin				identi:	fier of	Namad	Numbai	r 2
			-DataTypes				rier or	Named	Number	L, Z
	DEFINED	III MAE -55	-Dacarypes		•	250				
	enterPW					identi:	fior of	Named	Numbai	r O
			-DataTypes				rier or	. Ivallieu	Number	L, U
	DELINED	III MAP-55	-Datalypes		•	240				
	entityRelea	bone				idonti	fior of	FomeN	Numboi	r 1
	DEELMED	in MND-MC	-DataTypes			17/2	rier or	. Ivallieu	Number	L, 4
	DEFINED	III MAF-MS	-Dacarypes		•	1/43				
	equipmentNo	nt SM - Faution	ned			identi.	fier of	Namad	Number	r 2
			-DataTypes				rier or	Namea	Number	L, Z
	DELINED	TII MAP-EK	-pararyhes		•	142				
	equipmentP:	rotocol Err	or			identi.	fier of	Namad	Number	r 1
			-DataTypes				riei OI	. Named	Manmel	-, <u>-</u>
	DELINED	TII MAE-EK	Dacarybes		•	7.4.7				
	equipmentS	atus				idon+:	fior of	Fanis	man+C+	2+110
			-DataTypes				riei Ol	. Бапты	m e nto La	acus
	NELINED	III MAP-MS	-naraiypes		•	0 Τ2				
	equipmentS	- 2 + 11 G				idonti	fior of	Namad	Number	r O
	edarbillette	atus				TOCITOT.	riei Ol	. Named	Marimel	L, U

DEFINED in MAP-MS-DataTypes	:	821	
EquipmentStatus	t	ype re	eference ENUMERATED
DEFINED in MAP-MS-DataTypes			
USED in MAP-MS-DataTypes			
over godd. Entwy	info		un object reference
eraseCC-Entry OPERATION, Information Object	. 11110	Illacic	on object reference
DEFINED in MAP-SupplementaryServi	:	281	
USED in MAP-Protocol			132
USED in MAP-SupplementaryServi	:	25	
EragoCC_EntryArg	+	uno ro	oforongo CEOUENCE
EraseCC-EntryArg DEFINED in MAP-SS-DataTypes			ETETETICE SEQUENCE
USED in MAP-SupplementaryServi			282
USED in MAP-SS-DataTypes			203
OSED III MAR-SS-Datalypes	•	33	
EraseCC-EntryRes	t	ype re	eference SEQUENCE
DEFINED in MAP-SS-DataTypes			
USED in MAP-SupplementaryServi	:	74	285
USED in MAP-SS-DataTypes			
eraseSS	info	rmatic	on object reference
OPERATION, Information Object	. 11110	IMACIC	
DEFINED in MAP-SupplementaryServi	:	106	
USED in MAP-Protocol			130
USED in MAP-SupplementaryServi			
777.07		_	
ERROR	i	niorma	ition object class
reference CLASS			

12-06	TAG 09:3	R6.1 3:23		Cross Reference Li 29	sting	for MAP-	Protoc	ol		2006-
	D	USED	in E	Remote-Operations-I	nfo:	42 19	150	165	170	170
186	192	200	1n r 207	MAP-Errors	:	97	159	165	172	179
240	247	254	263			213	216	223	228	233
298	304	310	316			266	269	277	285	291
354	360	368	375			322	328	334	341	348
407	412	415	418			381 424	388 432	395	401	404
457	465	471	477			424	432	438	443	449
	orro	rundof	inod					Namod	Numbe	n 1
	D	EFINED	in N	MAP-LCS-DataTypes	:	524				
							ier of	Named	Numbe	er, 4
							ier of	Named	Numbe	er, 1
							ier of	[O] M	M-Code	2
				a MAP-CH-DataTypes			ier of	[1] E	ventRe	eportData
		EFINED	in N	a MAP-CH-DataTypes	:	347	eferenc	e SEQU	ENCE	
		USED	in N	MAP-CH-DataTypes	:	342				
Subsc	ext2 ribed	-QoS-S	ubscı	cibed		.identif	ier of	[2] E	xt2-Qo	oS-
	D	EFINED	in N	MAP-MS-DataTypes	:	925				
		EFINED	in N	cibed MAP-MS-DataTypes	:	1022				
		USED	in N	MAP-MS-DataTypes	:	62	925	2208	2210	2212
				gInfo MAP-CH-DataTypes			ier of	Exten	dedRou	ıtingInfo
	Exte	ndedRo	uting	gInfo		.type re	ferenc	e CHOI	CE	
	D	EFINED	in N	MAP-CH-DataTypes	:	291				
				MAP-CH-DataTypes						
Enton		nsible allBar		BarredParam	• • • • • •	.identif	ier of			
Excen					:	103				
	Exte	nsible	CallE	BarredParam		.type re	ferenc	e SEOU	ENCE	
				MAP-ER-DataTypes				20		
				MAP-ER-DataTypes						
Exten				emFailureParam reParam		.identif	ier of			

DEFI	NED in MAP-ER-DataTypes	:	171		
DEFI	bleSystemFailureParam NED in MAP-ER-DataTypes SED in MAP-ER-DataTypes	:	175	ence	e SEQUENCE
	onContainer NED in MAP-MS-DataTypes			of	ExtensionContainer
	onContainer NED in MAP-MS-DataTypes			of	ExtensionContainer
	onContainer NED in MAP-MS-DataTypes			of	ExtensionContainer
	onContainer NED in MAP-MS-DataTypes			of	ExtensionContainer
	onContainer NED in MAP-MS-DataTypes			of	ExtensionContainer
	onContainer NED in MAP-MS-DataTypes			of	ExtensionContainer
	onContainer NED in MAP-MS-DataTypes			of	ExtensionContainer
	onContainer NED in MAP-MS-DataTypes			of	ExtensionContainer
extensi ExtensionConta	onContaineriner		.identifier	of	[3]

	TAG R6.15 09:33:23 PAGE		Reference	Listing	for MAP-Pro	otoco	2006-
	DEFINED in	MAP-MS-	-DataTypes	:	339		
	extensionConta DEFINED in					of	ExtensionContainer
	extensionConta DEFINED in					of	ExtensionContainer
	extensionConta DEFINED in					of	ExtensionContainer
	extensionConta onContainer DEFINED in					of	[1]
							ExtensionContainer
	DEFINED in					COI	ExtensionContainer
	extensionConta	iner			.identifier	of	[3]
	DEFINED in	MAP-MS-	-DataTypes	:	484		
	extensionConta onContainer	iner			.identifier	of	[2]
	DEFINED in	MAP-MS-	-DataTypes	:	505		
	extensionConta onContainer					of	[8]
	DEFINED in						
	extensionConta onContainer DEFINED in					of	[4]
	extensionConta					of	[2]
Extensi	onContainer DEFINED in	MAP-MS-	-DataTypes	:	616		
	extensionConta	iner			.identifier	of	[5]
Extensi	onContainer DEFINED in	MAP-MS-	-DataTypes	:	649		
	extensionConta onContainer	iner	• • • • • • • • • •		.identifier	of	[0]
	DEFINED in	MAP-MS-	-DataTypes	:	656		
	extensionConta onContainer					of	[0]
	DEFINED in						
	extensionConta onContainer DEFINED in					of	[2]
	extensionConta				.identifier	of	[9]
Extensi	onContainer DEFINED in	MAP-MS-	-DataTypes	:	685		
	extensionConta onContainer	iner			.identifier	of	[0]

DEFINED in	MAP-MS-DataTypes	:	706		
extensionConta	ainer		identifier	of	[0]
	MAP-MS-DataTypes	:	710		
extensionConta ExtensionContainer	ainer		identifier	of	[2]
	MAP-MS-DataTypes	:	771		
	ainer MAP-MS-DataTypes			of	ExtensionContainer
		:		of	ExtensionContainer
extensionConta ExtensionContainer	ainer		identifier	of	[0]
	MAP-MS-DataTypes	:	817		
extensionConta ExtensionContainer	ainer		identifier	of	[14]
	MAP-MS-DataTypes	:	847		
extensionConta ExtensionContainer	ainer		identifier	of	[21]
DEFINED in	MAP-MS-DataTypes	:	921		
extensionConta ExtensionContainer	ainer		identifier	of	[2]
DEFINED in	MAP-MS-DataTypes	:	936		
extensionConta ExtensionContainer	ainer		identifier	of	[2]
DEFINED in	MAP-MS-DataTypes	:	942		
extensionConta ExtensionContainer	ainer		identifier	of	[2]
	MAP-MS-DataTypes				
extensionConta ExtensionContainer	ainer		identifier	of	[4]

DEFINED in MAP-MS-DataTypes : 973

TAG R6.15 Cross Reference Listing for MAP-Protocol 2006- 12-06 09:33:23 PAGE 31	-
extensionContaineridentifier of [3] ExtensionContainer DEFINED in MAP-MS-DataTypes : 1043	
extensionContaineridentifier of [3]	
ExtensionContainer DEFINED in MAP-MS-DataTypes : 1053	
extensionContaineridentifier of ExtensionContainer DEFINED in MAP-MS-DataTypes : 1101	
extensionContaineridentifier of [0] ExtensionContainer DEFINED in MAP-MS-DataTypes : 1164	
extensionContaineridentifier of [9]	
ExtensionContainer DEFINED in MAP-MS-DataTypes : 1180	
extensionContaineridentifier of ExtensionContainer DEFINED in MAP-MS-DataTypes : 1223	
extensionContaineridentifier of ExtensionContainer DEFINED in MAP-MS-DataTypes : 1232	
extensionContaineridentifier of [0] ExtensionContainer	
DEFINED in MAP-MS-DataTypes : 1238	
extensionContaineridentifier of [0] ExtensionContainer DEFINED in MAP-MS-DataTypes : 1249	
extensionContaineridentifier of ExtensionContainer DEFINED in MAP-MS-DataTypes : 1276	
extensionContaineridentifier of [5] ExtensionContainer	
DEFINED in MAP-MS-DataTypes : 1296	
extensionContaineridentifier of [3] ExtensionContainer	
DEFINED in MAP-MS-DataTypes : 1319	
extensionContaineridentifier of [2] ExtensionContainer DEFINED in MAP-MS-DataTypes : 1352	
extensionContaineridentifier of [2]	
ExtensionContainer DEFINED in MAP-MS-DataTypes : 1384	
extensionContaineridentifier of [0] ExtensionContainer	
DEFINED in MAP-MS-DataTypes : 1395	
extensionContaineridentifier of [7] ExtensionContainer	
DEFINED in MAP-MS-DataTypes : 1413	

extensionContaineridentifier ExtensionContainer	of	[6]
DEFINED in MAP-MS-DataTypes : 1434		
extensionContaineridentifier DEFINED in MAP-MS-DataTypes : 1486	of	ExtensionContainer
extensionContaineridentifier ExtensionContainer	of	[1]
DEFINED in MAP-MS-DataTypes : 1491		
extensionContaineridentifier ExtensionContainer	of	[2]
DEFINED in MAP-MS-DataTypes : 1535		
extensionContaineridentifier DEFINED in MAP-MS-DataTypes : 1557	of	ExtensionContainer
extensionContaineridentifier DEFINED in MAP-MS-DataTypes : 1562	of	ExtensionContainer
extensionContaineridentifier ExtensionContainer	of	[0]
DEFINED in MAP-MS-DataTypes : 1573		
extensionContaineridentifier DEFINED in MAP-MS-DataTypes : 1591	of	ExtensionContainer
extensionContaineridentifier ExtensionContainer	of	[2]
DEFINED in MAP-MS-DataTypes : 1614		
extensionContaineridentifier ExtensionContainer	of	[4]
DEFINED in MAP-MS-DataTypes : 1645		
extensionContaineridentifier ExtensionContainer	of	[2]
DEFINED in MAP-MS-DataTypes : 1766		

extensionContaineridentifier of [4] ExtensionContainer DEFINED in MAP-MS-DataTypes : 1788
21
extensionContaineridentifier of [1] ExtensionContainer
DEFINED in MAP-MS-DataTypes : 1826
extensionContaineridentifier of [1] ExtensionContainer DEFINED in MAP-MS-DataTypes : 1837
extensionContaineridentifier of ExtensionContainer DEFINED in MAP-MS-DataTypes : 1879
extensionContaineridentifier of [2] ExtensionContainer
DEFINED in MAP-MS-DataTypes : 1902
extensionContaineridentifier of [3] ExtensionContainer DEFINED in MAP-MS-DataTypes : 1921
extensionContaineridentifier of [3] ExtensionContainer
DEFINED in MAP-MS-DataTypes : 1928
extensionContaineridentifier of [3] ExtensionContainer
DEFINED in MAP-MS-DataTypes : 1937 extensionContaineridentifier of [1]
ExtensionContainer DEFINED in MAP-MS-DataTypes : 1942
extensionContaineridentifier of [3] ExtensionContainer
DEFINED in MAP-MS-DataTypes : 1951
extensionContaineridentifier of [0] ExtensionContainer DEFINED in MAP-MS-DataTypes : 1955
extensionContaineridentifier of ExtensionContainer DEFINED in MAP-MS-DataTypes : 1968
extensionContaineridentifier of ExtensionContainer DEFINED in MAP-MS-DataTypes : 1975
extensionContaineridentifier of ExtensionContainer DEFINED in MAP-MS-DataTypes : 1992
extensionContaineridentifier of ExtensionContainer DEFINED in MAP-MS-DataTypes : 1998
extensionContaineridentifier of [3] ExtensionContainer
DEFINED in MAP-MS-DataTypes : 2013 extensionContaineridentifier of ExtensionContainer

DEFINED in MAP-MS-DataTypes	:	2018		
extensionContainer	i	dentifier	of	[2]
DEFINED in MAP-MS-DataTypes	:	2024		
extensionContainer	i	dentifier	of	[4]
DEFINED in MAP-MS-DataTypes	:	2044		
extensionContainer	i	dentifier	of	[2]
DEFINED in MAP-MS-DataTypes	:	2087		
extensionContainer	i	dentifier	of	[4]
DEFINED in MAP-MS-DataTypes	:	2110		
extensionContainer	i	dentifier	of	[5]
DEFINED in MAP-MS-DataTypes	:	2128		
extensionContainer	i	dentifier	of	[17]
DEFINED in MAP-MS-DataTypes	:	2206		
extensionContainer	i	dentifier	of	[2]
DEFINED in MAP-MS-DataTypes	:	2246		
extensionContainer DEFINED in MAP-MS-DataTypes			of	ExtensionContainer
extensionContainer	i	dentifier	of	[3]
ExtensionContainer DEFINED in MAP-MS-DataTypes	:	2260		
extensionContainer	i	ldentifier	of	[7]
DEFINED in MAP-MS-DataTypes	:	2271		
extensionContainer	i	dentifier	of	[6]

12-06 C				Reference	Listing	for MA	AP-Prot	COC	ol 2006-
	DEFI	NED in	MAP-MS	-DataTypes	:	2282	2		
e Extensio	onConta	iner						of	[0]
				-DataTypes					
e				-DataTypes				of	ExtensionContainer
€				 -DataTypes				of	ExtensionContainer
e Extensio	onConta	iner						of	[13]
_								۔ د	[-]
Extensio	onConta	iner						OI	[5]
e Extensio			ainer			.ident	ifier	of	[2]
EXCENSIO			MAP-MS	-DataTypes	:	2371	L		
e Extensic			ainer	• • • • • • • • •		.ident	cifier	of	[7]
	DEFI	NED in	MAP-MS	-DataTypes	:	2383	3		
Extensio	onConta	iner						of	[6]
				-DataTypes					
Extensic	onConta	iner		 -DataTypes				of	[2]
								of	וכן
Extensio	onConta	iner		-DataTypes				OI	[3]
e				 -DataTypes				of	ExtensionContainer
e	extensi	onConta	ainer			.ident	tifier	of	ExtensionContainer
				-DataTypes					
Extensic	onConta	iner		DataTimos				of	[6]
				-DataTypes		2444		_	
€				-DataTypes				of	ExtensionContainer
Extensio	onConta	iner						of	[3]
				-DataTypes					
Extensio	onConta	iner						of	[5]
	DELT!	NED IU	MAP-MS	-DataTypes	:	24/2	4		

extensionContainer			of	[4]
DEFINED in MAP-OM-DataTypes	:	41		
extensionContainer	io	dentifier	of	[0]
DEFINED in MAP-OM-DataTypes	:	195		
extensionContainer ExtensionContainer	io	dentifier	of	[2]
DEFINED in MAP-OM-DataTypes	:	203		
extensionContainer	io	dentifier	of	[0]
DEFINED in MAP-OM-DataTypes	:	209		
extensionContainer DEFINED in MAP-CommonDataTypes			of	ExtensionContainer
extensionContainer DEFINED in MAP-CommonDataTypes			of	ExtensionContainer
extensionContainer DEFINED in MAP-CommonDataTypes			of	ExtensionContainer
extensionContainer	io	dentifier	of	[1]
DEFINED in MAP-CommonDataTypes	:	377		
extensionContainer	io	dentifier	of	[1]
DEFINED in MAP-CommonDataTypes	:	394		
extensionContainer DEFINED in MAP-CommonDataTypes			of	ExtensionContainer
extensionContainer	io	dentifier	of	[4]
DEFINED in MAP-CommonDataTypes	:	571		

TAG R6.15 Cross Reference Listing for MAP-Protocol 20 12-06 09:33:23 PAGE 34	06-
extensionContaineridentifier of ExtensionContain DEFINED in MAP-CH-DataTypes : 86	ıer
extensionContaineridentifier of [13] ExtensionContainer DEFINED in MAP-CH-DataTypes : 105	
extensionContaineridentifier of [0] ExtensionContainer	
DEFINED in MAP-CH-DataTypes : 161	
extensionContaineridentifier of [2] ExtensionContainer DEFINED in MAP-CH-DataTypes : 201	
extensionContaineridentifier of [7]	
ExtensionContainer DEFINED in MAP-CH-DataTypes : 215	
extensionContaineridentifier of [11]	
DEFINED in MAP-CH-DataTypes : 230	
extensionContaineridentifier of ExtensionContain DEFINED in MAP-CH-DataTypes : 245	ıer
extensionContaineridentifier of [7] ExtensionContainer	
DEFINED in MAP-CH-DataTypes : 256	
extensionContaineridentifier of [3] ExtensionContainer DEFINED in MAP-CH-DataTypes : 271	
extensionContaineridentifier of ExtensionContain DEFINED in MAP-CH-DataTypes : 281	ıer
extensionContaineridentifier of ExtensionContain DEFINED in MAP-CH-DataTypes : 287	ıer
extensionContaineridentifier of [1] ExtensionContainer	
DEFINED in MAP-CH-DataTypes : 298	
extensionContaineridentifier of [2] ExtensionContainer	
DEFINED in MAP-CH-DataTypes : 304	
extensionContaineridentifier of [3] ExtensionContainer DEFINED in MAP-CH-DataTypes : 314	
extensionContaineridentifier of [1] ExtensionContainer	
DEFINED in MAP-CH-DataTypes : 327	
extensionContaineridentifier of [3] ExtensionContainer	
DEFINED in MAP-CH-DataTypes : 344	

extensionContaineridentifier ExtensionContainer DEFINED in MAP-CH-DataTypes : 349	of	[1]
extensionContaineridentifier ExtensionContainer DEFINED in MAP-CH-DataTypes : 355	of	[2]
extensionContaineridentifier ExtensionContainer DEFINED in MAP-CH-DataTypes : 377	of	[0]
extensionContaineridentifier ExtensionContainer	of	[6]
DEFINED in MAP-CH-DataTypes : 387 extensionContaineridentifier	of	[1]
ExtensionContainer DEFINED in MAP-CH-DataTypes : 392 extensionContaineridentifier	٥£	[1]
ExtensionContainer DEFINED in MAP-CH-DataTypes : 413	OI	[1]
extensionContaineridentifier ExtensionContainer DEFINED in MAP-CH-DataTypes : 420	of	[3]
extensionContaineridentifier ExtensionContainer DEFINED in MAP-CH-DataTypes : 425	of	[1]
extensionContaineridentifier DEFINED in MAP-CH-DataTypes : 429	of	ExtensionContainer
extensionContaineridentifier DEFINED in MAP-CH-DataTypes : 445	of	ExtensionContainer
extensionContaineridentifier DEFINED in MAP-CH-DataTypes : 449	of	ExtensionContainer

TAG R6.15 Cross Reference Listing for MAP-Protoc 12-06 09:33:23 PAGE 35	ol 2006-
extensionContaineridentifier of ExtensionContainer DEFINED in MAP-SS-DataTypes : 278	[4]
extensionContaineridentifier of DEFINED in MAP-SS-DataTypes : 295	ExtensionContainer
extensionContaineridentifier of ExtensionContainer DEFINED in MAP-SM-DataTypes : 57	[6]
extensionContaineridentifier of ExtensionContainer DEFINED in MAP-SM-DataTypes : 81	[4]
extensionContaineridentifier of DEFINED in MAP-SM-DataTypes : 87	ExtensionContainer
extensionContaineridentifier of DEFINED in MAP-SM-DataTypes : 109	ExtensionContainer
extensionContaineridentifier of DEFINED in MAP-SM-DataTypes : 115	ExtensionContainer
extensionContaineridentifier of DEFINED in MAP-SM-DataTypes : 123	ExtensionContainer
extensionContaineridentifier of DEFINED in MAP-SM-DataTypes : 128	ExtensionContainer
extensionContaineridentifier of ExtensionContainer DEFINED in MAP-SM-DataTypes : 148	[1]
extensionContaineridentifier of DEFINED in MAP-SM-DataTypes : 172	ExtensionContainer
extensionContaineridentifier of DEFINED in MAP-SM-DataTypes : 183	ExtensionContainer
extensionContaineridentifier of DEFINED in MAP-SM-DataTypes : 206	ExtensionContainer
extensionContaineridentifier of DEFINED in MAP-SM-DataTypes : 210	ExtensionContainer
extensionContaineridentifier of ExtensionContainer DEFINED in MAP-GR-DataTypes : 58	[4]
extensionContaineridentifier of DEFINED in MAP-GR-DataTypes : 71	ExtensionContainer
extensionContaineridentifier of DEFINED in MAP-GR-DataTypes : 76	ExtensionContainer
extensionContaineridentifier of DEFINED in MAP-GR-DataTypes : 80	ExtensionContainer
extensionContaineridentifier of	ExtensionContainer

DEFINED in MAP-GR-DataTypes	:	90		
extensionContainer DEFINED in MAP-GR-DataTypes			of	ExtensionContainer
extensionContainer ExtensionContainer DEFINED in MAP-LCS-DataTypes			of	[2]
extensionContainer			of	[2]
DEFINED in MAP-LCS-DataTypes	:	83		
extensionContainer ExtensionContainer			of	[1]
DEFINED in MAP-LCS-DataTypes	:	94		
extensionContainer ExtensionContainer		identifier	of	[8]
DEFINED in MAP-LCS-DataTypes	:	114		
extensionContainer		identifier	of	[4]
DEFINED in MAP-LCS-DataTypes	:	219		
extensionContainer		identifier	of	[1]
DEFINED in MAP-LCS-DataTypes	:	339		
extensionContainer DEFINED in MAP-LCS-DataTypes			of	ExtensionContainer
extensionContainer		identifier	of	ExtensionContainer

12-06	TAG R6.15		Reference	Listing	for MAP-Pro	toco	ol 2006-
	DEFINED	in MAP-ER-	DataTypes	:	93		
			 DataTypes			of	ExtensionContainer
			 DataTypes			of	ExtensionContainer
			 DataTypes			of	ExtensionContainer
			 DataTypes			of	ExtensionContainer
			 DataTypes			of	ExtensionContainer
			 DataTypes			of	ExtensionContainer
			 DataTypes			of	ExtensionContainer
			 DataTypes			of	ExtensionContainer
			 DataTypes			of	ExtensionContainer
			 DataTypes			of	ExtensionContainer
			 DataTypes			of	ExtensionContainer
			 DataTypes			of	ExtensionContainer
			 DataTypes			of	ExtensionContainer
			 DataTypes			of	ExtensionContainer
			 DataTypes			of	ExtensionContainer
			 DataTypes			of	ExtensionContainer
			 DataTypes			of	ExtensionContainer
			 DataTypes			of	ExtensionContainer
			 DataTypes			of	ExtensionContainer
	extensionCo	ntainer			.identifier	of	ExtensionContainer

DEFINED in MAP-ER-DataTypes	: 263
extensionContainer DEFINED in MAP-ER-DataTypes	

12-06			Cross Reference Listing for MAP-Protocol PAGE 37								200	6-		
					 -DataTypes				fier	of	Exte	nsionC	ontaine	er
					 -DataTypes				fier	of	Exte	nsionC	ontaine	er
					 -DataTypes				fier	of	Exte	nsionC	ontaine	er
					 -DataTypes				fier	of	Exte	nsionC	ontaine	er
					 -DataTypes			.identi: 316	fier	of	Exte	nsionC	ontaine	er
					 -DataTypes				fier	of	Exte	nsionC	ontaine	er
					 -DataTypes				fier	of	Exte	nsionC	ontaine	er
					 -DataTypes				fier	of	Exte	nsionC	ontaine	er
					 -DataTypes				fier	of	Exte	nsionC	ontaine	er
Extens	sionCo	ntaine:	r						fier	of	[1]			
extensionContainer ExtensionContainer									fier	of	[1]			
	D	EFINED	in M	IAP-ER	-DataTypes		:	361						
					 -DataTypes				fier	of	Exte	nsionC	ontaine	er
					 -DataTypes				fier	of	Exte	nsionC	ontaine	er
					 -DataTypes				fier	of	Exte	nsionC	ontaine	er
					tensionData				efere	ence	e SEQ	UENCE		
301			in M		-DataTypes				227	7	237	278	291	
	308		324					339	408	3	433	446	456	
470	484	505	551					608	616	5	649	656	665	
673	685	706	710					771	795	5	811	817	847	
921	936	942	952					973	1043	3 :	L053	1101	1164	
1180	1223	1232	1238					1249	1276	5 .	L296	1319	1352	
1384	1395	1413	1434											

					1486	1491	1535	1557	1562	
1573	1591	1614	1645							
1902	1921	1928	1937		1766	1788	1826	1837	1879	
1902	1921	1926	1937		1942	1951	1955	1968	1975	
1992	1998	2013	2018		0004	0044	0005	0110	0100	
2206	2246	2251	2260		2024	2044	2087	2110	2128	
					2271	2282	2311	2319	2327	
2344	2363	2371	2383		2393	2399	2406	2428	2432	
2444	2451	2463	2472		2333	2333	2406	2420	2432	
		USED	in MAP-OM-DataTypes	:	29	41	195	203	209	
			in MAP-CommonDataTypes	:	85	207	233	250	377	
394	549	571	in MAD CH DataTimos	:	76	86	105	161	201	
215	230	245	in MAP-CH-DataTypes 256	:	76	86	105	101	201	
213	230	213	230		271	281	287	298	304	
314	327	344	349							
					355	377	387	392	413	
420	425	429	445		449					
		USED	in MAP-SS-DataTypes	:	59	278	295			
			in MAP-SM-DataTypes	:	46	57	81	87	109	
115	123	128	148							
					172	183	206	210		
0.0	0.0	USED	in MAP-GR-DataTypes	:	41	58	71	76	80	
90	98	IISED	in MAP-LCS-DataTypes	:	48	77	83	94	114	
219	339	540	III THE LOS DACATYPOS	•	10	, ,	03	J 1		
		USED	in MAP-ER-DataTypes	:	85	93	113	119	151	
158	177	182	186							
221	225	229	233		190	196	200	213	217	
221	223	227	233		237	241	245	263	269	
273	277	281	285							
					289	293	297	301	305	
309	316	320	324		328	338	343	361	270	
383	387				3∠8	338	343	201	379	
		USED	in MAP-ExtensionDataTypes	:	16					

ExtensionSet.....information object set reference MAP-EXTENSION, Information Object Set

DEFINED in MAP-ExtensionDataTypes : 52

USED in MAP-ExtensionDataTypes : 46 48

externalAddress......identifier of [0] ISDN-

AddressString

DEFINED in MAP-CommonDataTypes : 393

```
TAG R6.15 Cross Reference Listing for MAP-Protocol
                                                                              2006-
12-06 09:33:23 PAGE 38
       ExternalClient.....type reference SEQUENCE
          DEFINED in MAP-MS-DataTypes : 1346
USED in MAP-MS-DataTypes : 1332 1342
       externalClientList.....identifier of [1]
ExternalClientList
          DEFINED in MAP-MS-DataTypes
                                          : 1312
       ExternalClientList.....type reference SEQUENCE OF
          DEFINED in MAP-MS-DataTypes : 1331
USED in MAP-MS-DataTypes : 1312
       ExternalSignalInfo.......................type reference SEQUENCE

DEFINED in MAP-CommonDataTypes : 202

USED in MAP-CommonDataTypes : 21

USED in MAP-CH-DataTypes : 65 102 119 224 225
382
                                                   54 313 314
             USED in MAP-SS-DataTypes
                                             :
       extId.....identifier of
InformationObjectClassFieldType
          DEFINED in MAP-ExtensionDataTypes :
       extType.....identifier of
InformationObjectClassFieldType
          DEFINED in MAP-ExtensionDataTypes :
       Ext-BasicServiceCode.....type reference CHOICE
          DEFINED in MAP-CommonDataTypes : 542
USED in MAP-MS-DataTypes : 186 1171 1230 1268 1273
1480 1670 2377 2388
            USED in MAP-CommonDataTypes : 52
USED in MAP-CH-DataTypes : 69 101 118 158 173
251
      264
       Ext-BasicServiceGroupList.....type reference SEQUENCE OF
          DEFINED in MAP-MS-DataTypes : 1267
USED in MAP-MS-DataTypes : 1248 1295
       ext-BearerService.....identifier of [2] Ext-
BearerServiceCode
          DEFINED in MAP-CommonDataTypes : 543
       Ext-BearerServiceCode......type reference OCTET STRING
          DEFINED in MAP-BS-Code : 25
USED in MAP-MS-DataTypes : 163 1089
USED in MAP-CommonDataTypes : 75 543
       Ext-CallBarFeatureList.....type reference SEQUENCE OF
          DEFINED in MAP-MS-DataTypes : 1226
USED in MAP-MS-DataTypes : 1222 2315 2468
       Ext-CallBarInfo.....type reference SEQUENCE
          DEFINED in MAP-MS-DataTypes : 1220
USED in MAP-MS-DataTypes : 1156
       Ext-CallBarringFeature.....type reference SEQUENCE
          DEFINED in MAP-MS-DataTypes : 1229
USED in MAP-MS-DataTypes : 1227
```

Ext-CallBarringInfoFor-CSE.....type reference SEQUENCE DEFINED in MAP-MS-DataTypes : 2466
USED in MAP-MS-DataTypes : 2424 2456 ext-externalClientList.....identifier of [4] Ext-ExternalClientList DEFINED in MAP-MS-DataTypes : 1341 : 1321 DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes Ext-ExternalSignalInfo.......type reference SEQUENCE

DEFINED in MAP-CommonDataTypes : 228

USED in MAP-CommonDataTypes : 22

USED in MAP-CH-DataTypes : 66 110 235 ${\tt Ext-ForwardingInfoFor-CSE......type\ reference\ SEQUENCE}$ DEFINED in MAP-MS-DataTypes : 2459 USED in MAP-MS-DataTypes : 2423 2455 Ext-ForwFeature.....type reference SEQUENCE DEFINED in MAP-MS-DataTypes : 1170 USED in MAP-MS-DataTypes Ext-ForwFeatureList......type reference SEQUENCE OF DEFINED in MAP-MS-DataTypes : 1167
USED in MAP-MS-DataTypes : 1163 2309 2461 Ext-ForwInfo.....type reference SEQUENCE

```
TAG R6.15 Cross Reference Listing for MAP-Protocol
                                                                     2006-
12-06 09:33:23 PAGE 39
                                   : 1161
         DEFINED in MAP-MS-DataTypes
                                         : 1155
           USED in MAP-MS-DataTypes
      Ext-ForwOptions.....type reference OCTET STRING
                                   : 1184
: 1178
         DEFINED in MAP-MS-DataTypes
            USED in MAP-MS-DataTypes
      Ext-GeographicalInformation......type reference OCTET STRING DEFINED in MAP-LCS-DataTypes : 366
USED in MAP-LCS-DataTypes : 23 337 472
      Ext-NoRepCondTime.....type reference INTEGER
         DEFINED in MAP-MS-DataTypes : 1213
USED in MAP-MS-DataTypes : 1179 2381
      ext-ProtocolId.....identifier of Ext-ProtocolId
         DEFINED in MAP-CommonDataTypes
      Ext-ProtocolId.....type reference ENUMERATED
         DEFINED in MAP-CommonDataTypes : 236
USED in MAP-CommonDataTypes : 229
      ext-QoS-Subscribed......identifier of [0] Ext-QoS-
Subscribed
        DEFINED in MAP-MS-DataTypes
                                     :
      Ext-QoS-Subscribed.....type reference OCTET STRING
         DEFINED in MAP-MS-DataTypes : 1015
           USED in MAP-MS-DataTypes
                                             61 923 2200 2201 2202
                                        :
      Ext-SS-Data.....type reference SEQUENCE
         DEFINED in MAP-MS-DataTypes : 1291
           USED in MAP-MS-DataTypes
      Ext-SS-Info.....type reference CHOICE
         DEFINED in MAP-MS-DataTypes : 1154
           USED in MAP-MS-DataTypes
      Ext-SS-InfoFor-CSE.....type reference CHOICE
         DEFINED in MAP-MS-DataTypes : 2454
USED in MAP-MS-DataTypes : 2369
      Ext-SS-InfoList.....type reference SEQUENCE OF
         DEFINED in MAP-MS-DataTypes : 1151
           USED in MAP-MS-DataTypes
      Ext-SS-Status.....type reference OCTET STRING
         DEFINED in MAP-CommonDataTypes : 580
USED in MAP-MS-DataTypes : 194 1172 1231 1293 1306
1394 2378 2389
           USED in MAP-CommonDataTypes : 58 568
      ext-Teleservice.....identifier of [3] Ext-
TeleserviceCode
        DEFINED in MAP-CommonDataTypes : 544
      Ext-TeleserviceCode.....type reference OCTET STRING
           FINED in MAP-TS-Code : 20
USED in MAP-MS-DataTypes : 168 1094
USED in MAP-CommonDataTypes : 69 544
         DEFINED in MAP-TS-Code
```

	USED	in	MAP-GR-DataTypes	:	31	49			
	e-mailAddre	ess			.identi	fier c	of Name	d Numbe	er, 1
	DEFINED	in	MAP-LCS-DataTypes	:	204				
	FacilityNot	:Suj	pParam		.type r	eferen	nce SEQ	JENCE	
	DEFINED	in	MAP-ER-DataTypes	:	189				
	USED	in	MAP-Errors	:	112	181			
	USED	in	MAP-ER-DataTypes	:	23				
	facilityNot	:Suj	pported		.inform	ation	object	refere	ence
ERROR,	Information	n Ol	oject						
			MAP-Errors		_				
	USED	in	MAP-OperationAndMainte	:	27	61	76		
	USED	in	MAP-CallHandlingOperat	:	33	88	112	143	184
198									
	USED	in	MAP-SupplementaryServi	:	56	278			
	USED	in	MAP-ShortMessageServic	:	31	73	89	103	149
	USED	in	MAP-LocationServiceOpe	:	27	62	77		
	USED	in	MAP-Errors	:	17				
'01100		rouj	p3AndAlterSpeech		.value	refere	ence Te	leservi	iceCode,
01100		in	MAP-TS-Code	:	48				
'01100		rouj	94		.value	refere	ence Tel	leservi	iceCode,
3==30		in	MAP-TS-Code	:	50				

```
TAG R6.15 Cross Reference Listing for MAP-Protocol
                                                                     2006-
12-06 09:33:23 PAGE 40
      failure.....identifier\ of\ Named\ Number,\ 1
         DEFINED in MAP-CH-DataTypes
      failureCause.....identifier of FailureCause
         DEFINED in MAP-MS-DataTypes
                                             407
      FailureCause.....type reference ENUMERATED
         DEFINED in MAP-MS-DataTypes : 436
USED in MAP-MS-DataTypes : 407
      failureReport.....information object reference
OPERATION, Information Object
         DEFINED in MAP-MobileServiceOpera : 467
           USED in MAP-Protocol : 39
USED in MAP-MobileServiceOpera : 64
                                                 127
      FailureReportArg.....type reference SEQUENCE
         DEFINED in MAP-MS-DataTypes : 1933
USED in MAP-MobileServiceOpera : 154
           USED in MAP-MS-DataTypes
      FailureReportRes.....type reference SEQUENCE
         DEFINED in MAP-MS-DataTypes : 1940
USED in MAP-MobileServiceOpera : 155
                                                  471
           USED in MAP-MS-DataTypes :
      findYourFriend.....value reference LCSServiceTypeID,
16
         DEFINED in MAP-CommonDataTypes
                                            428
                                       :
      firstServiceAllowed.....identifier of Named Number, 0
         DEFINED in MAP-CH-DataTypes
                                             180
                                       :
      fleetManagement.....value reference LCSServiceTypeID,
3
         DEFINED in MAP-CommonDataTypes
                                       :
                                            414
      foreignNumberPortedIn.....identifier of Named Number, 5
        DEFINED in MAP-MS-DataTypes
                                       : 2059
      foreignNumberPortedToForeignNetwork.....identifier of Named Number, 2
         DEFINED in MAP-MS-DataTypes
                                       :
                                            2056
      forwardAccessSignalling.....information object reference
OPERATION, Information Object
         DEFINED in MAP-MobileServiceOpera: 339
           USED in MAP-Protocol :
           USED in MAP-MobileServiceOpera :
                                            41
      ForwardAccessSignalling-Arg.....type reference [3] SEQUENCE
         DEFINED in MAP-MS-DataTypes : 476
USED in MAP-MobileServiceOpera : 123
           USED in MAP-MS-DataTypes :
                                             33
      forwardCheckSS-Indication.....information object reference
OPERATION, Information Object
        DEFINED in MAP-MobileServiceOpera: 434
           USED in MAP-Protocol : 32
USED in MAP-MobileServiceOpera : 57
```

forwardedidentifier of Named Number, 0 DEFINED in MAP-MS-DataTypes : 1681	
forwardedToNumberidentifier of [5] ISDN-	
AddressString DEFINED in MAP-MS-DataTypes : 1173	
forwardedToNumberidentifier of [3] AddressString DEFINED in MAP-MS-DataTypes : 2379	ſ
forwardedToNumberidentifier of [5] ISDN-	
AddressString	
DEFINED in MAP-CH-DataTypes : 209	
forwardedToNumberidentifier of [4] AddressString DEFINED in MAP-SS-DataTypes : 74	Į
forwardedToNumberidentifier of [5] ISDN-AddressString	
DEFINED in MAP-SS-DataTypes : 101	
forwardedToSubaddressidentifier of [8] ISDN-	
SubaddressString DEFINED in MAP-MS-DataTypes : 1177	
forwardedToSubaddressidentifier of [4] ISDN-	
SubaddressString DEFINED in MAP-MS-DataTypes : 2380	
forwardedToSubaddressidentifier of [4] ISDN-	
SubaddressString DEFINED in MAP-CH-DataTypes : 213	

```
TAG R6.15 Cross Reference Listing for MAP-Protocol
                                                                     2006-
12-06 09:33:23 PAGE 41
      forwardedToSubaddress.....identifier of [6] ISDN-
SubaddressString
         DEFINED in MAP-SS-DataTypes
                                            75
      forwardedToSubaddress.....identifier of [8] ISDN-
SubaddressString
         DEFINED in MAP-SS-DataTypes
                                       :
                                            102
      forwardGroupCallSignalling.....information object reference
OPERATION, Information Object
         DEFINED in MAP-Group-Call-Operati : 67
USED in MAP-Protocol : 104
USED in MAP-Group-Call-Operati : 15
                                                  135
      ForwardGroupCallSignallingArg.....type reference SEQUENCE
            FINED in MAP-GR-DataTypes : 83
USED in MAP-Group-Call-Operati : 36
USED in MAP-GR-DataTypes : 18
         DEFINED in MAP-GR-DataTypes
      forwarding......identifier of Named Number, 1
         DEFINED in MAP-CH-DataTypes
      forwarding Data ..... identifier \ of \ Forwarding Data
         DEFINED in MAP-CH-DataTypes
                                        :
      ForwardingData.....type reference SEQUENCE
         DEFINED in MAP-CH-DataTypes : 208
            USED in MAP-CH-DataTypes
                                        :
                                             206
                                                   252 296
      forwardingData.....identifier of [2] ForwardingData
         DEFINED in MAP-CH-DataTypes
                                             252
      forwardingData.....identifier of ForwardingData
         DEFINED in MAP-CH-DataTypes
                                        :
                                             296
      forwardingFailed.....information object reference
ERROR, Information Object
         DEFINED in MAP-Errors
                                        : 322
            USED in MAP-CallHandlingOperat :
            USED in MAP-Errors
      ForwardingFailedParam.....type reference SEQUENCE
         DEFINED in MAP-ER-DataTypes : 276
USED in MAP-Errors : 129
            USED in MAP-ER-DataTypes
      ForwardingFeature.....type reference SEQUENCE
         DEFINED in MAP-SS-DataTypes : USED in MAP-SS-DataTypes :
      for warding Feature List..... identifier \ of \ {\tt Ext-ForwFeature List}
         DEFINED in MAP-MS-DataTypes
                                       : 1163
      forwardingFeatureList.....identifier of Ext-ForwFeatureList
                                     : 2309
         DEFINED in MAP-MS-DataTypes
      forwardingFeatureList.....identifier of [1] Ext-
ForwFeatureList
         DEFINED in MAP-MS-DataTypes : 2461
```

forwardingFeatureList.....identifier of ForwardingFeatureList DEFINED in MAP-SS-DataTypes ForwardingFeatureList.....type reference SEQUENCE OF : 94 : 91 DEFINED in MAP-SS-DataTypes USED in MAP-SS-DataTypes 217 forwardingFeatureList.....identifier of [3] ForwardingFeatureList DEFINED in MAP-SS-DataTypes forwardingInfo......identifier of [0] Ext-ForwInfo DEFINED in MAP-MS-DataTypes 1155 $forwarding Info.....identifier\ of\ [0]\ Forwarding Info$ DEFINED in MAP-SS-DataTypes ForwardingInfo.....type reference SEQUENCE DEFINED in MAP-SS-DataTypes USED in MAP-SS-DataTypes forwardingInfoFor-CSE.....identifier of [0] Ext-ForwardingInfoFor-CSE DEFINED in MAP-MS-DataTypes forwardingInfoFor-CSE.....identifier of [0] Ext-ForwardingInfoFor-CSE DEFINED in MAP-MS-DataTypes : 2455 forwardingInterrogationRequired.....identifier of [4] NULL

```
TAG R6.15 Cross Reference Listing for MAP-Protocol
                                                                      2006-
12-06 09:33:23 PAGE 42
         DEFINED in MAP-CH-DataTypes
                                     :
                                            159
      forwardingOptions.....identifier of [6] Ext-ForwOptions
         DEFINED in MAP-MS-DataTypes
                                           1178
      forwardingOptions.....identifier of [6]
ForwardingOptions
         DEFINED in MAP-CH-DataTypes
      forwardingOptions.....identifier of [6]
ForwardingOptions
         DEFINED in MAP-SS-DataTypes
      ForwardingOptions.....type reference OCTET STRING
         DEFINED in MAP-SS-DataTypes : 123
USED in MAP-CH-DataTypes : 55
USED in MAP-SS-DataTypes : 31
                                            55
31
                                                   214
            USED in MAP-SS-DataTypes
                                        :
      forwardingReason.....identifier of [8]
ForwardingReason
         DEFINED in MAP-CH-DataTypes
      ForwardingReason.....type reference ENUMERATED
         DEFINED in MAP-CH-DataTypes : 132
            USED in MAP-CH-DataTypes
      forwardingViolation.....information object reference
ERROR, Information Object
         DEFINED in MAP-Errors
            USED in MAP-Errors : 316
USED in MAP-CallHandlingOperat : 44
USED in MAP-Errors
                                                   99
            USED in MAP-Errors
                                              50
      {\tt Forwarding Violation Param......type\ reference\ SEQUENCE}
         DEFINED in MAP-ER-DataTypes : 272
USED in MAP-Errors : 128 318
            USED in MAP-ER-DataTypes :
      \texttt{freezeP-TMSI}..... \texttt{identifier of [1] NULL}
         DEFINED in MAP-MS-DataTypes
                                        :
      freezeTMSI.....identifier of [0] NULL
         DEFINED in MAP-MS-DataTypes
                                        :
      frozen.....identifier of Named Number, 5
         DEFINED in MAP-SS-DataTypes
      FTN-AddressString.....type reference AddressString
         DEFINED in MAP-CommonDataTypes : 153

USED in MAP-MS-DataTypes : 176 1182

USED in MAP-CommonDataTypes : 19

USED in MAP-CH-DataTypes : 64 217

USED in MAP-SS-DataTypes : 47 106
      gaming.....value reference LCSServiceTypeID,
15
         DEFINED in MAP-CommonDataTypes : 427
      gb.....identifier of Named Number, 0
         DEFINED in MAP-OM-DataTypes : 115
```

ge DEFINED in MAP-OM-DataTypes	identifier of Named Number, 7 : 122
general-dataCDA BearerServiceCode, '00010111'B	value reference
DEFINED in MAP-BS-Code	: 57
general-dataCDS BearerServiceCode, '00011111'B	value reference
	: 64
general-dataPDS BearerServiceCode, '00101111'B	value reference
	: 79
general-padAccessCA BearerServiceCode, '00100111'B	
DEFINED in MAP-BS-Code	: 73
GenericServiceInfo	type reference SEQUENCE
DEFINED in MAP-SS-DataTypes	: 189
USED in MAP-SS-DataTypes	: 218
genericServiceInfoGenericServiceInfo	identifier of [4]
DEFINED in MAP-SS-DataTypes	
<pre>geodeticInformation</pre> <pre>GeodeticInformation</pre>	
DEFINED in MAP-MS-DataTypes	
geodeticInformationGeodeticInformation	
DEFINED in MAP-MS-DataTypes	: 2131

TAG R6.15 Cross Reference Listin 12-06 09:33:23 PAGE 43	ng for MAP-Protocol 2006-
GeodeticInformation DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes	: 2155
geographicalInformation GeographicalInformation DEFINED in MAP-MS-DataTypes	
geographicalInformationGeographicalInformation DEFINED in MAP-MS-DataTypes	
GeographicalInformation DEFINED in MAP-MS-DataTypes	
USED in MAP-MS-DataTypes	
geranCodecList	
DEFINED in MAP-MS-DataTypes	: 672
geranNotAllowed DEFINED in MAP-MS-DataTypes	
geranPositioningData PositioningDataInformation	identifier of [4]
DEFINED in MAP-LCS-DataTypes	: 343
geranPositioningData PositioningDataInformation	
DEFINED in MAP-LCS-DataTypes	: 479
geran-classmark	identifier of [16] GERAN-
DEFINED in MAP-MS-DataTypes	: 558
geran-classmark DEFINED in MAP-MS-DataTypes	identifier of [6] GERAN-Classmark : 651
GERAN-Classmark	
DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes	
getPassword OPERATION, Information Object	.information object reference
DEFINED in MAP-SupplementaryServi	: 244
USED in MAP-Protocol USED in MAP-SupplementaryServi	
ggsn	
DEFINED in MAP-OM-DataTypes	
ggsn DEFINED in MAP-CommonDataTypes	<pre>identifier of Named Number, 1 : 365</pre>
ggsn-Address DEFINED in MAP-MS-DataTypes	
ggsn-Address DEFINED in MAP-MS-DataTypes	

ggsn-Address DEFINED in MAP-MS-DataTypes :	.identifier of [2] GSN-Address 1936
ggsn-Address DEFINED in MAP-MS-DataTypes :	
ggsn-Address DEFINED in MAP-MS-DataTypes :	
ggsn-Address DEFINED in MAP-MS-DataTypes :	.identifier of [10] GSN-Address 2199
GGSN-EventList	.type reference BIT STRING
DEFINED in MAP-OM-DataTypes :	169
USED in MAP-OM-DataTypes :	146
GGSN-InterfaceList	.type reference BIT STRING
DEFINED in MAP-OM-DataTypes :	125
DEFINED in MAP-OM-DataTypes : USED in MAP-OM-DataTypes :	
	90
USED in MAP-OM-DataTypes : ggsn-List	90identifier of [3] GGSN-
USED in MAP-OM-DataTypes : ggsn-List	90identifier of [3] GGSN- 90identifier of [3] GGSN-EventList
USED in MAP-OM-DataTypes : ggsn-List	90 .identifier of [3] GGSN- 90 .identifier of [3] GGSN-EventList 146

12-06	AG R6.15 Cross Reference Listing for MAP-Protocol 9:33:23 PAGE 44	2006-
Addres	gsn-Numberidentifier of [1] ISDN- tring DEFINED in MAP-MS-DataTypes : 1935	
	gsn-TraceDepthidentifier of [3] TraceDep DEFINED in MAP-OM-DataTypes : 64	th
	iidentifier of Named Number DEFINED in MAP-OM-DataTypes : 127	, 1
	lobalidentifier of OBJECT IDENT DEFINED in Remote-Operations-Info : 115	IFIER
	lobalCellIdtype reference OCTET STRIN DEFINED in MAP-CommonDataTypes : 340 USED in MAP-MS-DataTypes : 184 539 644 USED in MAP-CommonDataTypes : 37	G
	mbidentifier of Named Number DEFINED in MAP-OM-DataTypes : 128	, 2
	mbidentifier of Named Number DEFINED in MAP-OM-DataTypes : 139	, 0
	mlcidentifier of Named Number DEFINED in MAP-CommonDataTypes : 366	, 2
	mlc-Listidentifier of [0] GMLC-Lis DEFINED in MAP-MS-DataTypes : 883	t
	MLC-Listtype reference SEQUENCE OF DEFINED in MAP-MS-DataTypes : 895 USED in MAP-MS-DataTypes : 883	
	mlc-Listidentifier of Named Number DEFINED in MAP-MS-DataTypes : 1356	, 0
	mlc-ListWithdrawidentifier of [13] NULL DEFINED in MAP-MS-DataTypes : 1439	
Restri		
	DEFINED in MAP-MS-DataTypes : 1348	
	MLC-Restriction	
Restri		
	DEFINED in MAP-MS-DataTypes : 1380	
GmscCa	mscCamelSubscriptionInfoidentifier of [0] lSubscriptionInfo DEFINED in MAP-CH-DataTypes : 297	
	mscCamelSubscriptionInfotype reference SEQUENCE DEFINED in MAP-CH-DataTypes : 301 USED in MAP-CH-DataTypes : 297	

Address	gmsc-Addresssstring	identifier of [8] ISDN-
	DEFINED in MAP-CH-DataTypes	: 227
Address	gmsc-OrGsmSCF-AddresssString	identifier of [6] ISDN-
	DEFINED in MAP-CH-DataTypes	: 98
	gn DEFINED in MAP-OM-DataTypes	
	gn DEFINED in MAP-OM-DataTypes	
	gprsAttach DEFINED in MAP-MS-DataTypes	
	GPRSChargingID	type reference OCTET STRING
	DEFINED in MAP-MS-DataTypes	
	USED in MAP-MS-DataTypes	: 111 2203
	gprsConnectionSuspended	identifier of NULL
	DEFINED in MAP-ER-DataTypes	: 311
	GPRSDataList DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes	: 909

12-06	TAG R6.15 Cross Reference Listing 09:33:23 PAGE 45	for MAP-Protocol	2006-
	gprsDataList DEFINED in MAP-MS-DataTypes :		ataList
	<pre>gprsDetach DEFINED in MAP-MS-DataTypes :</pre>	identifier of Named Numb 428	oer, 10
	<pre>gprsEnhancementsSupportIndicator DEFINED in MAP-MS-DataTypes :</pre>	identifier of [3] NULL 459	
	GPRSMSClass	type reference SEQUENCE	
	DEFINED in MAP-MS-DataTypes :	2071	
	USED in MAP-MS-DataTypes :	101 2030	
	<pre>gprsNodeIndicator</pre>	identifier of [5] NULL	
	DEFINED in MAP-SM-DataTypes :	89	
		: 1: E:E [0] NULL	
	<pre>gprsNodeIndicator DEFINED in MAP-LCS-DataTypes :</pre>		
	gprsSubscriptionData	identifier of [16]	
GPRSSul	bscriptionData		
	DEFINED in MAP-MS-DataTypes :	851	
	GPRSSubscriptionData	type reference SEOHENCE	
	DEFINED in MAP-MS-DataTypes :		
		851	
	USED in MAP-MS-DataTypes :	831	
GPRSSul	gprsSubscriptionDataWithdrawbscriptionDataWithdraw		
	DEFINED in MAP-MS-DataTypes :	1436	
	GPRSSubscriptionDataWithdraw	type reference CHOICE	
	DEFINED in MAP-MS-DataTypes :		
	USED in MAP-MS-DataTypes :	1405	
	OSED III MAP-MS-Datalypes :	1430	
	<pre>gprsSubscriptionUnknown DEFINED in MAP-ER-DataTypes :</pre>	identifier of Named Numb	per, 1
	DEFINED IN MAP-EK-Datalypes :	206	
	gprsSupportIndicator	identifier of [7] NULL	
	DEFINED in MAP-SM-DataTypes :		
	gprsSupportIndicator		
	DEFINED in MAP-SM-DataTypes :	150	
	GPRS-CamelTDPData	tyme reference SECTIONCE	
	DEFINED in MAP-MS-DataTypes :		
		964	
	osed in MAF-Ms-Datalypes :	304	
CamelT	gprs-CamelTDPDataList DPDataList	identifier of [0] GPRS-	
	DEFINED in MAP-MS-DataTypes :	950	
	GPRS-CamelTDPDataList	tumo roforenzo CECHENCE	OF
			OF
	DEFINED in MAP-MS-DataTypes :		
	USED in MAP-MS-DataTypes :	950	
	gprs-CSI	identifier of [0] CDDC (~QT
	DEFINED in MAP-MS-DataTypes :		~o⊥

GPRS-CSItype reference SEQUENCE DEFINED in MAP-MS-DataTypes : 949 USED in MAP-MS-DataTypes : 940 2340
gprs-csiidentifier of Named Number, 7 DEFINED in MAP-MS-DataTypes : 1452
gprs-CSIidentifier of Named Number, 4 DEFINED in MAP-MS-DataTypes : 2293
gprs-CSIidentifier of [9] GPRS-CSI DEFINED in MAP-MS-DataTypes : 2340
gprs-MS-Classidentifier of [7] GPRSMSClass DEFINED in MAP-MS-DataTypes : 2030
<pre>gprs-TriggerDetectionPointidentifier of [0] GPRS- TriggerDetectionPoint</pre>
DEFINED in MAP-MS-DataTypes : 969
GPRS-TriggerDetectionPointtype reference ENUMERATED DEFINED in MAP-MS-DataTypes : 985 USED in MAP-MS-DataTypes : 969
greyListedidentifier of Named Number, 2 DEFINED in MAP-MS-DataTypes : 840

12-06	TAG R6.1			Reference	Listin	ng	for	MAP-Pro	toco	ol		2006-
	groupCallN DEFINED			 DataTypes					of	ISDN	N-AddressS	tring
	groupId DEFINED			DataTypes					of	Grou	ıpId	
	groupid DEFINED			DataTypes					of	Grou	ıpId	
		in M	AP-MS-	DataTypes DataTypes		:	20	01		e TBC	CD-STRING	
	groupKey DEFINED			 DataTypes					of	[1]	Kc	
		in M	AP-GR-	DataTypes DataTypes		:	1	01	ence	e INT	reger	
	groupKeyNu DEFINED			 DataTypes				ntifier 53	of	[0]	GroupKeyN	umber
	gs DEFINED			 DataTypes				ntifier 21	of	Name	ed Number,	6
	gsmSCF DEFINED			nmonDataTy					of	Name	ed Number,	3
Address	gsmSCF-Add sString DEFINED			DataTypes					of	[2]	ISDN-	
	gsmSCF-Add DEFINED			 DataTypes					of	ISDN	I-AddressS	tring
	gsmSCF-Add DEFINED			DataTypes					of	ISDN	N-AddressS	tring
Address	_			DataTypes					of	[0]	ISDN-	
Address	gsmSCF-Add sString								of	[2]	ISDN-	
	gsmSCF-Add			·DataTypes					of	[0]	ISDN-	
Address	DEFINED			·DataTypes								
Address				DataTypes					of	[0]	ISDN-	
Address									of	[0]	ISDN-	
	DELINED	ın M	AP-MS-	DataTypes		:	19	00				

gsmSCF-Address	identifier of [3] ISDN-
DEFINED in MAP-MS-DataTypes	: 2245
gsmSCF-Address	identifier of [2] ISDN-
DEFINED in MAP-MS-DataTypes	: 2259
gsmSCF-Address	identifier of [1] ISDN-
DEFINED in MAP-MS-DataTypes	: 2359
gsmSCF-InitiatedCall DEFINED in MAP-CH-DataTypes	
gsm-0408 DEFINED in MAP-CommonDataTypes	
gsm-0806 DEFINED in MAP-CommonDataTypes	
gsm-BearerCapability ExternalSignalInfo	identifier of [5]
DEFINED in MAP-CH-DataTypes	: 224
gsm-BSSMAP DEFINED in MAP-CommonDataTypes	
gsm-SecurityContextData SecurityContextData	identifier of [0] GSM-
DEFINED in MAP-MS-DataTypes	: 369
GSM-SecurityContextData	type reference SEQUENCE

12-06	TAG R6.1		Reference	Listing	for MAP	-Protoc	ol		2006-
	DEFINED USED	in MAP-MS in MAP-MS	-DataTypes -DataTypes	:	372 369				
	GSN-Addres					referenc	e OCT	ET STR	ING
1925		in MAP-MS	-DataTypes -DataTypes			232	445	451	1919
122	USED 482	in MAP-LC	S-DataType:	5 :	1949 61	1950 85	2199 86	2205 87	88
	GuidanceIn	fo			type r	referenc	e ENU	MERATEI)
			-DataTypes						
			pplementary			246			
	USED	in MAP-SS	-DataTypes	:	25				
Addres	handoverNu ssString	mber			identi	fier of	[0]	ISDN-	
ridarei	_	in MAP-MS	-DataTypes	:	601				
	handoverNu					fier of	ISDN	-Addres	ssString
			-DataTypes						
	handovers. DEFINED		-DataTypes			fier of.	Name	d Numbe	er, 3
	hlr				identi	fier of	Name	d Numbe	er, 1
			mmonDataTy						
	HLR-Id					referenc	e IMS	I	
			mmonDataTy						
	USED	in MAP-Co	mmonDataTy	pes :	334				
	hlr-List				identi	fier of	HLR-	List	
			-DataTypes						
	HLR-List					referenc	e SEQ	UENCE (OF
			mmonDataTy			1060			
			-DataTypes mmonDataTy			1962			
	OSED	III MAF-CO	iiiiiOIIDacai y	Jes :	33				
	hlr-Number DEFINED	in MAP-MS	 -DataTypes	:	identi 277	fier of	ISDN	-Addres	ssString
	la la a Nicerala a sa				ل ع م م له ل	e:e	TODM	7 4 4	~ ~ () +
	hlr-Number DEFINED		-DataTypes			lier or	TODN	-Addres	ssscring
	hlr-Number				identi	fier of	ISDN	-Addres	ssString
			-DataTypes						J
	hlr-Number DEFINED		 -DataTypes			fier of	ISDN	-Addres	ssString
101000	hold				value	referen	ce SS	-Code,	
31000		in MAP-SS	-Code	:	77				
	home-Count		 -DataTypes			fier of	Name	d Numbe	er, 1

-	in MAP-MS-DataTypes		.identifier of [1] HopCounter 328
DEFINED	in MAP-MS-DataTypes in MAP-MS-DataTypes	:	330
	-accuracy		.identifier of [0] Horizontal-
Accuracy DEFINED	in MAP-LCS-DataTypes	:	216
DEFINED	-Accuracy in MAP-LCS-DataTypes in MAP-LCS-DataTypes	:	
	otRequired in MAP-MS-DataTypes		
	ress in MAP-LCS-DataTypes		identifier of [4] GSN-Address.
	ress in MAP-LCS-DataTypes		identifier of [15] GSN-Address
-	ress in MAP-LCS-DataTypes		identifier of [14] GSN-Address

```
TAG R6.15 Cross Reference Listing for MAP-Protocol
                                                                            2006-
12-06 09:33:23 PAGE 48
       identity.....identifier of Identity
          DEFINED in MAP-MS-DataTypes
       Identity.....type reference CHOICE
          DEFINED in MAP-CommonDataTypes : 303
USED in MAP-MS-DataTypes : 183
USED in MAP-CommonDataTypes : 32
                                                        289
       ik.....identifier of IK
         DEFINED in MAP-MS-DataTypes
       \verb"ik..... identifier of IK"
         DEFINED in MAP-MS-DataTypes
       IK.....type reference OCTET STRING
          DEFINED in MAP-MS-DataTypes : 393
USED in MAP-MS-DataTypes : 364
       illegalEquipment.....information object reference
ERROR, Information Object
          DEFINED in MAP-Errors
                                            : 240
            USED in MAP-SupplementaryServi: 53 206 221
USED in MAP-ShortMessageServic: 35 106
USED in MAP-LocationServiceOpe: 36 80
             USED in MAP-Errors
       IllegalEquipmentParam.....type reference SEQUENCE
          DEFINED in MAP-ER-DataTypes : 224
USED in MAP-Errors : 118 242
USED in MAP-ER-DataTypes : 29
       illegalSS-Operation.....information object reference
ERROR, Information Object
            USED in MAP-Errors : 368
USED in MAP-MobileServiceOpera : 98 273 291
USED in MAP-SupplementaryServi : 41 101 119 137 158
          DEFINED in MAP-Errors
177 273 291
             USED in MAP-Errors
                                                  63
       IllegalSS-OperationParam.....type reference SEQUENCE
          DEFINED in MAP-ER-DataTypes : 292
USED in MAP-Errors : 147
                                                        370
             USED in MAP-ER-DataTypes
       illegalSubscriber.....information object reference
ERROR, Information Object
          DEFINED in MAP-Errors
             USED in MAP-SupplementaryServi : 52 205 220 USED in MAP-ShortMessageServic : 34 105 USED in MAP-LocationServiceOpe : 37 79
             USED in MAP-Errors
                                                  30
       IllegalSubscriberParam.....type reference SEQUENCE
          DEFINED in MAP-ER-DataTypes : 220
USED in MAP-Errors : 117 235
             USED in MAP-ER-DataTypes :
                                                 28
       \verb"imei..... identifier of IMEI"
          DEFINED in MAP-MS-DataTypes : 809
```

imei DEFINED in MAP-MS-DataTypes	
imei DEFINED in MAP-MS-DataTypes	
IMEI DEFINED in MAP-CommonDataTypes	
USED in MAP-MS-DataTypes USED in MAP-CommonDataTypes	: 179 283 563 809 2028 : 34
USED in MAP-LCS-DataTypes	
imei DEFINED in MAP-LCS-DataTypes	
imei DEFINED in MAP-LCS-DataTypes	
imeisv DEFINED in MAP-MS-DataTypes	
imeisv DEFINED in MAP-MS-DataTypes	
immediateResponsePreferred DEFINED in MAP-MS-DataTypes	

12-06	TAG R6.15 Cross Reference Listing for MAP-Protocol 09:33:23 PAGE 49										
	imsiidentifier of IMSI DEFINED in MAP-MS-DataTypes : 223										
	imsiidentifier of IMSI DEFINED in MAP-MS-DataTypes : 305										
	imsiidentifier of IMSI DEFINED in MAP-MS-DataTypes : 333										
	imsiidentifier of IMSI DEFINED in MAP-MS-DataTypes : 406										
	imsiidentifier of IMSI DEFINED in MAP-MS-DataTypes : 443										
	imsiidentifier of [4] IMSI DEFINED in MAP-MS-DataTypes : 544										
	imsiidentifier of [0] IMSI DEFINED in MAP-MS-DataTypes : 766										
	imsiidentifier of [0] IMSI DEFINED in MAP-MS-DataTypes : 845										
	imsiidentifier of [0] IMSI DEFINED in MAP-MS-DataTypes : 1424										
	imsiidentifier of [0] IMSI DEFINED in MAP-MS-DataTypes : 1918										
	imsiidentifier of [0] IMSI DEFINED in MAP-MS-DataTypes : 1934										
	imsiidentifier of [0] IMSI DEFINED in MAP-MS-DataTypes : 1948										
	imsiidentifier of IMSI DEFINED in MAP-MS-DataTypes : 1966										
	imsiidentifier of [0] IMSI DEFINED in MAP-MS-DataTypes : 2010										
	imsiidentifier of [1] IMSI DEFINED in MAP-MS-DataTypes : 2041										
	imsiidentifier of IMSI DEFINED in MAP-MS-DataTypes : 2421										
	imsiidentifier of [1] IMSI DEFINED in MAP-MS-DataTypes : 2440										
	imsiidentifier of [0] IMSI DEFINED in MAP-OM-DataTypes : 37										
	imsiidentifier of [0] IMSI DEFINED in MAP-OM-DataTypes : 201										
	IMSItype reference TBCD-STRING DEFINED in MAP-CommonDataTypes : 300										

		USED	in MAP-OperationAndMaint	e :	44	84				
		USED	in MAP-MS-DataTypes	:	178	223	305	333	406	
443	544	766	845							
					1424	1918	1934	1948	1966	
2010	2041	2421	*							
			in MAP-OM-DataTypes		24					
		USED	in MAP-CommonDataTypes	:	30	304	308	319	329	
388										
			in MAP-CH-DataTypes	:	67	149	220	253	311	
341	381		== =							
			in MAP-SS-DataTypes		48					
			in MAP-SM-DataTypes		35			132	201	
			in MAP-GR-DataTypes							
		USED	in MAP-LCS-DataTypes	:	36	108	468			
	imai				: don+:	fion o	f TMCT			
			in MAP-CommonDataTypes			rier o	I IMSI			
	ט.	GLINED	III MAP-COMMOIDACATYPES	•	304					
	imai				identi	fier o	f TMCT			
			in MAP-CommonDataTypes			iiei o	I IMOI			
	٠.	DI INDD	III THII COMMONDACATYPES	•	300					
	imsi				identi	fier o	f [0]	IMSI		
			in MAP-CommonDataTypes							
			7 P O O	•						
	imsi				identi	fier o	f [0]	IMSI		
			in MAP-CommonDataTypes							

12-06	TAG R6.15 Cross Reference Listing for MAP-Protocol 09:33:23 PAGE 50										
	imsiidentifier of [9] IMSI DEFINED in MAP-CH-DataTypes : 149										
	imsiidentifier of [0] IMSI DEFINED in MAP-CH-DataTypes : 220										
	imsiidentifier of [3] IMSI DEFINED in MAP-CH-DataTypes : 253										
	imsiidentifier of [0] IMSI DEFINED in MAP-CH-DataTypes : 311										
	imsiidentifier of [0] IMSI DEFINED in MAP-CH-DataTypes : 341										
	imsiidentifier of [0] IMSI DEFINED in MAP-CH-DataTypes : 381										
	imsiidentifier of [0] IMSI DEFINED in MAP-CH-DataTypes : 412										
	imsiidentifier of [0] IMSI DEFINED in MAP-CH-DataTypes : 424										
	imsiidentifier of [0] IMSI DEFINED in MAP-SS-DataTypes : 269										
	imsiidentifier of IMSI DEFINED in MAP-SM-DataTypes : 79										
	imsiidentifier of IMSI DEFINED in MAP-SM-DataTypes : 111										
	imsiidentifier of [0] IMSI DEFINED in MAP-SM-DataTypes : 132										
	imsiidentifier of [0] IMSI DEFINED in MAP-SM-DataTypes : 201										
	imsiidentifier of IMSI DEFINED in MAP-GR-DataTypes : 75										
	imsiidentifier of IMSI DEFINED in MAP-GR-DataTypes : 84										
	imsiidentifier of [2] IMSI DEFINED in MAP-LCS-DataTypes : 108										
	imsiidentifier of [1] IMSI DEFINED in MAP-LCS-DataTypes : 468										
	imsiDetachidentifier of Named Number, DEFINED in MAP-ER-DataTypes : 250										
	imsiDetachedidentifier of Named Number, DEFINED in MAP-MS-DataTypes : 2236										
	imsiUnknownidentifier of Named Number, DEFINED in MAP-ER-DataTypes : 205	0									

	imsi-WithLMSI		.identi	fier of	IMSI-WithL	MSI
	DEFINED in MAP-CommonDataTypes	:	305			
	IMSI-WithLMSI		.type r	eference	SEQUENCE	
	DEFINED in MAP-CommonDataTypes	:	307			
	USED in MAP-CommonDataTypes	:	305			
	incomingCallsBarredWithinCUG		.identi	fier of	Named Numbe	er, 0
	DEFINED in MAP-ER-DataTypes	:	123			
	incompatibleTerminal		.inform	ation ob	ject refer	ence
ERROR,	Information Object					
	DEFINED in MAP-Errors	:	186			
	USED in MAP-CallHandlingOperat	:	48	167		
	USED in MAP-Errors	:	18			
	IncompatibleTerminalParam		.type r	eference	SEQUENCE	
	DEFINED in MAP-ER-DataTypes	:	327			
	USED in MAP-Errors	:	137	188		
	USED in MAP-ER-DataTypes	:	46			
	inconsistentMeasurementData		.identi	fier of	Named Numbe	er, 3

TAG R6.15 Cross Reference Listing for MAP-Protocol 2006-12-06 09:33:23 PAGE 51 DEFINED in MAP-ER-DataTypes informationNotAvailable.....information object reference ERROR, Information Object DEFINED in MAP-Errors 360 USED in MAP-MobileServiceOpera : 103 275 295 USED in MAP-Errors InformationNotAvailableParam.....type reference SEQUENCE DEFINED in MAP-ER-DataTypes : 304
USED in MAP-Errors : 150
USED in MAP-ER-DataTypes : 59 $\verb|informPreviousNetworkEntity.....identifier of [11] NULL|$ DEFINED in MAP-MS-DataTypes informPreviousNetworkEntity.....identifier of [1] NULL DEFINED in MAP-MS-DataTypes informServiceCentre.....information object reference OPERATION, Information Object DEFINED in MAP-ShortMessageServic : 135 USED in MAP-Protocol USED in MAP-ShortMessageServic : 18 ${\tt InformServiceCentreArg......} {\tt type \ reference \ SEQUENCE}$ DEFINED in MAP-SM-DataTypes : 180
USED in MAP-ShortMessageServic : 55 137 USED in MAP-SM-DataTypes inhibiting......dentifier of Named Number, 0 DEFINED in MAP-MS-DataTypes : 1685 DEFINED in MAP-LCS-DataTypes : 136 DEFINED in MAP-MS-DataTypes : 1739 insertSubscriberData.....information object reference OPERATION, Information Object DEFINED in MAP-MobileServiceOpera: 403 USED in MAP-Protocol : USED in MAP-MobileServiceOpera : InsertSubscriberDataArg.....type reference SEQUENCE DEFINED in MAP-MS-DataTypes : 844

USED in MAP-MobileServiceOpera : 135 405 USED in MAP-MS-DataTypes : InsertSubscriberDataRes.....type reference SEQUENCE DEFINED in MAP-MS-DataTypes : 1406 USED in MAP-MobileServiceOpera: 136 USED in MAP-MS-DataTypes : 57 insufficientMeasurementData.....identifier of Named Number, 2 DEFINED in MAP-ER-DataTypes insufficientResources......identifier of Named Number, 1 DEFINED in MAP-ER-DataTypes : 366

integrityProtectionAlgorithm.....identifier of [0] ${\tt ChosenIntegrityProtectionAlgorithm}$ DEFINED in MAP-MS-DataTypes : 614 $integrity \verb|ProtectionAlgorithms.....identifier of [0]|\\$ PermittedIntegrityProtectionAlgorithms DEFINED in MAP-MS-DataTypes 503 integrityProtectionInfo.....identifier of [0] IntegrityProtectionInformation DEFINED in MAP-MS-DataTypes 478 integrityProtectionInfo.....identifier of [5] IntegrityProtectionInformation DEFINED in MAP-MS-DataTypes : 545 IntegrityProtectionInformation.....type reference OCTET STRING DEFINED in MAP-MS-DataTypes : 745 USED in MAP-MS-DataTypes : 478 545 interCUG-Restrictions.....identifier of InterCUG-Restrictions DEFINED in MAP-MS-DataTypes : 1275 InterCUG-Restrictions.....type reference OCTET STRING DEFINED in MAP-MS-DataTypes : 1279 USED in MAP-MS-DataTypes : 84 84 1275 internalTimeout......identifier of Named Number, 2

```
R6.15 Cross Reference Listing for MAP-Protocol
                                                                2006-
12-06 09:33:23 PAGE 52
        DEFINED in MAP-LCS-DataTypes :
                                         525
      internationalECT-Barred......identifier of Named Number, 11
        DEFINED in MAP-MS-DataTypes
                                        1116
      internationalOGCallsBarred......identifier of Named Number, 1
                                        1106
        DEFINED in MAP-MS-DataTypes
      internationalOGCallsNotToHPLMN-CountryBaidentifier of Named Number, 2
        DEFINED in MAP-MS-DataTypes
                                  : 1107
      interrogateSS.....information object reference
OPERATION, Information Object
        DEFINED in MAP-SupplementaryServi : 165
           USED in MAP-Protocol
                                              130
           USED in MAP-SupplementaryServi :
                                          17
      InterrogateSS-Res.....type reference CHOICE
        DEFINED in MAP-SS-DataTypes : 214
           USED in MAP-SupplementaryServi : 64
           USED in MAP-SS-DataTypes
      interrogationType.....identifier of [3]
InterrogationType
        DEFINED in MAP-CH-DataTypes
      InterrogationType.....type reference ENUMERATED
        DEFINED in MAP-CH-DataTypes : 124
           USED in MAP-CH-DataTypes
      interval Time..... identifier \ of \ [2] \ Interval Time
        DEFINED in MAP-LCS-DataTypes
                                     :
                                          287
      IntervalTime.....type reference INTEGER
        DEFINED in MAP-LCS-DataTypes : 333
           USED in MAP-LCS-DataTypes
                                     :
      interzonalECT-Barred......identifier of Named Number, 12
        DEFINED in MAP-MS-DataTypes
                                    : 1117
      interzonalOGCallsAndInternationalOGCallsidentifier of Named Number, 8
        DEFINED in MAP-MS-DataTypes : 1110
      interzonalOGCallsBarred.....identifier of Named Number, 6
        DEFINED in MAP-MS-DataTypes
                                   : 1108
      interzonalOGCallsNotToHPLMN-CountryBarreidentifier of Named Number, 7
                                  : 1109
        DEFINED in MAP-MS-DataTypes
      \verb|intraCUG-Options|..... identifier of IntraCUG-Options|
        DEFINED in MAP-MS-DataTypes
      IntraCUG-Options.....type reference ENUMERATED
        DEFINED in MAP-MS-DataTypes : 1257
USED in MAP-MS-DataTypes : 85
                                         85 1247
      invalidFormat......identifier of Named Number, 1
        DEFINED in MAP-ER-DataTypes
      invalidSME-Address.....identifier of Named Number, 5
```

	D	EFINED	in MAP-ER-DataTypes	:	145				
		EFINED	ssStringin MAP-CommonDataTypes	:		eferen	.ce Add	ressSt	ring
			<pre>in MAP-OperationAndMaint in MAP-MS-DataTypes</pre>	ce :	43 174	82 224	225	277	306
307	326	413	414		444	469	601	645	731
896	971	1063	1173		444	469	601	645	/31
					1553	1555	1572	1612	1662
1786	1825	1836	1900		1920	1935	1961	1973	2042
2107	2113	2126	2245		1020	1000	1001	1973	2042
					2259	2359	2422	2441	
		USED	in MAP-CommonDataTypes	:	17	389	393		
205	209	USED 221	in MAP-CH-DataTypes 222	:	62	92	98	160	166
					227	244	258	384	444
		USED	in MAP-SS-DataTypes	:	45	101	207	225	270
280	311								
120	1 4 2		in MAP-SM-DataTypes	:	33	54	85	97	98
138	143	171	176		181				
		HOED	in MAP-GR-DataTypes	:	23	70			
			in MAP-LCS-DataTypes	:	34	75	91	105	109
467	470	471	542	•	34	75	21	105	100
					543				
			_			_			
			dressString			eferen	ce OCT	ET STR	ING
	ט		in MAP-CommonDataTypes	:		1177	2200		
			<pre>in MAP-MS-DataTypes in MAP-CommonDataTypes</pre>		175 20	1177	∠38U		
		لاندن	III MAE - COMMOTIDACAT YPES	•	20				

```
TAG R6.15 Cross Reference Listing for MAP-Protocol
                                                                      2006-
12-06 09:33:23 PAGE 53
            USED in MAP-CH-DataTypes : 63 213
USED in MAP-SS-DataTypes : 46 75 102 208
            USED in MAP-CH-DataTypes
      istAlertTimer.....identifier of [26] IST-
AlertTimerValue
         DEFINED in MAP-MS-DataTypes
      istAlertTimer.....identifier of [14] IST-
AlertTimerValue
        DEFINED in MAP-CH-DataTypes
      istAlertTimer.....identifier of [0] IST-
AlertTimerValue
         DEFINED in MAP-CH-DataTypes
      \verb|istCommandSupported..... identifier of Named Number, 1|\\
         DEFINED in MAP-MS-DataTypes
      istInformationWithdraw.....identifier of [14] NULL
         DEFINED in MAP-MS-DataTypes
      \verb|istInformationWithdraw|..... identifier of [1] NULL \\
         DEFINED in MAP-CH-DataTypes
      istSupportIndicator.....identifier of [1] IST-
SupportIndicator
         DEFINED in MAP-MS-DataTypes
      istSupportIndicator.....identifier of [18] IST-
SupportIndicator
         DEFINED in MAP-CH-DataTypes
                                        :
      ist-Alert.....information object reference
OPERATION, Information Object
         DEFINED in MAP-CallHandlingOperat: 173
USED in MAP-Protocol: 64 129
            USED in MAP-CallHandlingOperat :
                                              19
      IST-AlertArg.....type reference SEQUENCE
         DEFINED in MAP-CH-DataTypes : 411
USED in MAP-CallHandlingOperat : 66 175
            USED in MAP-CH-DataTypes :
                                              29
      IST-AlertRes......type reference SEQUENCE
DEFINED in MAP-CH-DataTypes : 416
USED in MAP-CallHandlingOperat : 67 177
            USED in MAP-CH-DataTypes
      IST-AlertTimerValue.....type reference INTEGER
         DEFINED in MAP-MS-DataTypes : 880
USED in MAP-MS-DataTypes : 88
USED in MAP-CH-DataTypes : 48
                                             88 858
48 168 417
      ist-Command.....information object reference
OPERATION, Information Object
         DEFINED in MAP-CallHandlingOperat : 187
           USED in MAP-Protocol :
                                                    130
            USED in MAP-CallHandlingOperat : 20
      IST-CommandArg.....type reference SEQUENCE
```

חבבואבט	in	MAP-CH-DataTypes		122				
		4 +			100			
		MAP-CallHandlingOperat			189			
USED	ın	MAP-CH-DataTypes	:	31				
	_			_				
		S			erence	e SEQU	IENCE	
DEFINED	in	MAP-CH-DataTypes	:	428				
USED	in	MAP-CallHandlingOperat	:	69	191			
USED	in	MAP-CH-DataTypes	:	32				
	_							
		dicator			erence	e ENUM	IERATED	
		MAP-MS-DataTypes						
		MAP-MS-DataTypes						
USED	in	MAP-CH-DataTypes	:	47	111			
iu				.identifi	er of	Named	l Number,	1
DEFINED	in	MAP-OM-DataTypes	:	97				
4						NT		-
					er or	Nameo	number,	Т
DELINED	ın	MAP-OM-DataTypes	:	116				
i 11				identifi	er of	Named	Number.	0
		MAP-OM-DataTypes			.01 01	11011100	rameer,	Ŭ
iuAvailable	eCo	decsList		.identifi	er of	[8] C	odecList	
DEFINED	in	MAP-MS-DataTypes	:	611				
		decsList			er of	[6] C	odecList	
DEFINED	in	MAP-MS-DataTypes	:	668				

12-06	TAG R6.1			Reference	Listing	for MAP-Pr	otoco	ol		2006-
				 -DataTypes		.identifie 134	er of	Named	Number,	2
				 -DataTypes		.identifie 559	er of	[17]	Codec	
	iur DEFINED	in N	 MAP-OM-	 -DataTypes	· · · · · · · · · · · · · · · · · · ·	.identifie 133	er of	Named	Number,	1
				 -DataTypes		.identifie 493	er of	[14]	Codec	
				 -DataTypes		.identifie 610	er of	[7] C	odec	
				 -DataTypes		.identifie 667	er of	[5] C	odec	
Support	tedCodecsLi	.st				.identifie	er of	[12]		
				-DataTypes			. of	[10]		
Support	iusupporte tedCodecsLi		ecsList	<u>-</u>		.identifie	er oi	[18]		
			MAP-MS-	-DataTypes	:	560				
				 -DataTypes		.identifie 111	er of	Named	Number,	2
				 -DataTypes		.identifie 357	er of	Kc		
				 -DataTypes		.identifie 373	er of	Kc		
	Kc					.type refe	rence	e OCTE	T STRING	
	DEFINE) in N	MAP-MS-	-DataTypes	:	387				
				-DataTypes -DataTypes		49 3 36		3./3		
				or -DataTypes		.identifie 200	er of	[1] N	ULL	
	keyStatus. DEFINED	in N	MAP-MS-	 -DataTypes		.identifie 480	er of	[2] K	eyStatus	
	KeyStatus.					.type refe	rence	e ENUM	ERATED	
				-DataTypes						
	USEI) in N	MAP-MS-	-DataTypes	:	480				
	ksi					.identifie	r of	KSI		
	DEFINEL) in N	MAP-MS-	-DataTypes	:	380				
						.type refe	rence	e OCTE	T STRING	
				-DataTypes						
	USEI) in N	MAP-MS-	-DataTypes	:	380				
				nmonDataTyp		.identifie 506	er of	[1] L	AIFixedLe	ength

LAIFixedLength	type reference OCTET STRING
DEFINED in MAP-CommonDataTypes	
USED in MAP-MS-DataTypes	
USED in MAP-CommonDataTypes	: 48 506
lawfulInterceptServices	identifier of Named Number, 3
DEFINED in MAP-LCS-DataTypes	: 170
lcsAPN	identifier of [5] APN
DEFINED in MAP-LCS-DataTypes	: 163
lcsCapabilitySet1	identifier of Named Number, 0
DEFINED in MAP-MS-DataTypes	: 261
lcsCapabilitySet2	identifier of Named Number, 1
DEFINED in MAP-MS-DataTypes	: 262
lcsCapabilitySet3	identifier of Named Number, 2
DEFINED in MAP-MS-DataTypes	: 263
lcsCapabilitySet4	identifier of Named Number, 3
DEFINED in MAP-MS-DataTypes	: 264
lcsClientDialedByMS	identifier of [2] AddressString

```
TAG R6.15 Cross Reference Listing for MAP-Protocol
                                                                        2006-
12-06 09:33:23 PAGE 55
         DEFINED in MAP-LCS-DataTypes : 159
      LCSClientExternalID.....type reference SEQUENCE
         DEFINED in MAP-CommonDataTypes : 392
USED in MAP-MS-DataTypes : 192 1347
USED in MAP-CommonDataTypes : 62
USED in MAP-LCS-DataTypes : 40 158
      lcsClientExternalID.....identifier of [1]
LCSClientExternalID
         DEFINED in MAP-LCS-DataTypes
      LCSClientInternalID.....type reference ENUMERATED
         DEFINED in MAP-CommonDataTypes : 397

USED in MAP-MS-DataTypes : 193 1337

USED in MAP-CommonDataTypes : 63

USED in MAP-LCS-DataTypes : 41 160
      lcsClientInternalID.....identifier of [3]
LCSClientInternalID
         DEFINED in MAP-LCS-DataTypes
      lcsClientName.....identifier of [4] LCSClientName
         DEFINED in MAP-LCS-DataTypes
                                         :
      LCSClientName.....type reference SEQUENCE
         DEFINED in MAP-LCS-DataTypes : 177
            USED in MAP-LCS-DataTypes
                                         :
                                               19
      lcsClientType......identifier of [0] LCSClientType
         DEFINED in MAP-LCS-DataTypes
                                         :
      LCSClientType.....type reference ENUMERATED
         DEFINED in MAP-LCS-DataTypes : 166
            USED in MAP-LCS-DataTypes
      {\tt lcsCodeword}..... {\tt identifier of [12] LCSCodeword}
         DEFINED in MAP-LCS-DataTypes
                                         :
                                               119
      LCSCodeword.....type reference SEQUENCE
         DEFINED in MAP-LCS-DataTypes : 259
USED in MAP-LCS-DataTypes : 28
      lcsCodewordString.....identifier of [1]
LCSCodewordString
         DEFINED in MAP-LCS-DataTypes
      LCSCodewordString.....type reference USSD-String
         DEFINED in MAP-LCS-DataTypes : 264
USED in MAP-LCS-DataTypes : 261
      {\tt lcsInformation.....identifier\ of\ [22]\ LCSInformation}
         DEFINED in MAP-MS-DataTypes
      LCSInformation.....type reference SEQUENCE
         DEFINED in MAP-MS-DataTypes : 882
USED in MAP-MS-DataTypes : 857
      {\tt lcsLocationInfo}..... {\tt identifier of [1] LCSLocationInfo}
```

DEFINED in MAP-LCS-DataTypes :

	LCSI	Location	nInfo		.tvpe r	eferenc	e SEO	UENCE		
			in MAP-LCS-DataTypes				~			
			in MAP-LCS-DataTypes			466	507			
	lcsI	Cocation	nInfo		.identi	fier of	LCSL	ocation	nTnfo	
			in MAP-LCS-DataTypes					0000101		
	lcal	ocatio	nInfo		identi	fier of	[1]	LCSLoca	ationInfo	,
			in MAP-LCS-DataTypes			TICE OF		перпосс	20101111110	
	lagi	Pemiest	orID		identi	fier of	: [6] :	T.CSPect	16gtorID	
			in MAP-LCS-DataTypes			rier or	[0]	псыкед	rescolid	
	t CCI	Poguogt	orID		tumo n	oforono	10 CEO	IIENICE		
		_	in MAP-LCS-DataTypes			ererenc	e seQ	OENCE		
	1		in MAP-LCS-DataTypes			164				
		USED	in MAF-LCS-Datalypes	•	20	104				
	LCSS	Service'	TypeID		.type r	eferenc	e INT	EGER		
	I	DEFINED	in MAP-CommonDataTypes	s :	406					
		USED	in MAP-MS-DataTypes	:	195	1379				
		USED	in MAP-CommonDataTypes	s :	64	411	412	413	414	
415	416	417	418							
					419	421	422	423	424	
425	426	427	428							
					429	430	431	432	437	
438	439	440	441							
					442	443	444	445	446	
447	448	449	450							

12-06		R6.1 3:23		Cross Reference Li	sting fo	or MAP-	Protoc	ol		2006-
456	457	458	459)		451	452	453	454	455
465	466	467	468			460	461	462	463	464
474	475	476	477			469	470	471	472	473
483	484	485	486			478	479	480	481	482
						487	488	489	490	491
492	493		495			496	_		499	500
				MAP-LCS-DataTypes						
LCSSe	rviceT	ypeID		eID			ier of	[11]		
				MAP-LCS-DataTypes						
LCSSe	lcsS rviceT		Турє	eID		identif	ier of	[15]		
	D	EFINED	in	MAP-LCS-DataTypes	:	483				
				MAP-LCS-DataTypes			ier of	[0] L	cs-cli	entID
				MAD I GG Datamana			ferenc	e SEQU	ENCE	
	ט	USED	in	MAP-LCS-DataTypes MAP-LCS-DataTypes	:	156 106	465			
				 MAP-LCS-DataTypes			ier of	LCS-C	:lientI	D
				MAP-LCS-DataTypes			ier of	LCS-E	vent	
		EFINED	in	MAP-LCS-DataTypes MAP-LCS-DataTypes	:	512	ferenc	e ENUM	ERATED)
Forma	lcs- tIndic		Indi	.cator	:	identif	ier of	[3] L	CS-	
	D	EFINED	in	MAP-LCS-DataTypes	:	181				
Forma	tIndic	ator		cator			ier of	[2] L	iCS-	
				MAP-LCS-DataTypes						
				.cator			ferenc	e ENUM	ERATED)
	D			MAP-LCS-DataTypes			196			
	lcs- D	Priori EFINED	ty in	MAP-LCS-DataTypes	:	identif 112	ier of	[6] L	CS-Pri	ority
				MAP-LCS-DataTypes			ferenc	e OCTE	T STRI	NG
		USED	in	MAP-LCS-DataTypes	:	112				
Priva	lcs- cyChec		yChe	eck		identif	ier of	[13]	LCS-	
	-		in	MAP-LCS-DataTypes	:	120				

LCS-PrivacyCheck.....type reference SEQUENCE DEFINED in MAP-LCS-DataTypes : 268
USED in MAP-LCS-DataTypes : 120 LCS-PrivacyClass.....type reference SEQUENCE DEFINED in MAP-MS-DataTypes : 1304
USED in MAP-MS-DataTypes : 1300 lcs-PrivacyExceptionList.....identifier of [1] LCS-PrivacyExceptionList DEFINED in MAP-MS-DataTypes : 884 LCS-PrivacyExceptionList.....type reference SEQUENCE OF DEFINED in MAP-MS-DataTypes : 1299 USED in MAP-MS-DataTypes : 884 lcs-QoS.....identifier of [7] LCS-QoS DEFINED in MAP-LCS-DataTypes 113 LCS-QoS.....type reference SEQUENCE DEFINED in MAP-LCS-DataTypes : 215 USED in MAP-LCS-DataTypes lcs-ReferenceNumber......identifier of [10] LCS-ReferenceNumber DEFINED in MAP-LCS-DataTypes : LCS-ReferenceNumber.....type reference OCTET STRING DEFINED in MAP-LCS-DataTypes : 257 USED in MAP-LCS-DataTypes 27 117 478 : lcs-ReferenceNumber.....identifier of [10] LCS-ReferenceNumber DEFINED in MAP-LCS-DataTypes : 478

12-06	TAG R6.	15 Cross Reference Lis PAGE 57	ting	for MAP	-Protoco	ol		2006-
		comArea D in MAP-LCS-DataTypes			fier of	Name	d Number	, 2
		D in MAP-MS-DataTypes			fier of	[10]	LMSI	
		D in MAP-MS-DataTypes			fier of	LMSI		
		D in MAP-MS-DataTypes			fier of	[1]	LMSI	
	lmsi			identi	fier of	TMST		
		D in MAP-CommonDataTypes			rici or	ширт		
	LMSI			.type r	eference	e OCT	ET STRIN	G
	DEFINE	D in MAP-CommonDataTypes	•	338				
	TICE	TD in MAD MC DataTimes		100	226 1	067	2011	
	USE	CD in MAP-MS-DataTypes CD in MAP-CommonDataTypes CD in MAP-CH-DataTypes	•	102	220	1967	2011	
	USE	D in MAP-CommonDataTypes	:	36	309			
	USE	D in MAP-CH-DataTypes	:	68	223	312		
	USE	D in MAP-SM-DataTypes	:	36	86	133		
	USE	D in MAP-LCS-DataTypes	:	37	93	110		
		D in MAP-CH-DataTypes		.identi 223	fier of	[4]	LMSI	
		 D in MAP-CH-DataTypes			fier of	[1]	LMSI	
	DELINE	III MAP-Ch-Datalypes	•	312				
	1mai			1 don+1	fion of	TMCT		
					iler oi	LMSI	•	
	DELINE	D in MAP-SM-DataTypes	:	86				
	1 mai			1 don+1	fion of	[1]	TMCT	
		D in MAP-SM-DataTypes			lier or	[1]	TIMOT	
	lmsi			.identi	fier of	[0]	LMSI	
	DEFINE	D in MAP-LCS-DataTypes	:	93				
	lmsi			.identi	fier of	[4]	LMSI	
	DEFINE	D in MAP-LCS-DataTypes	:	110				
	lmu-Indic	ator		.identi	fier of	[21]	NULL	
			:					
	10001			idonti	fior of	TNTTE	CED	
		D in Remote-Operations-In			TIET OT	TINTE	<u> ۱۷</u> ۱۲۲۷	
		-		114				
		D in MAP-MobileServiceOpe	ra :	182	193	205	215	229
241	256 276	296						
				310	325	332	337	342
354	374 386	399						
				413	425	432	435	447
463	478 493	505						
		ID in MAP-OperationAndMain	to .	64	78	89		
							1 4 4	1
		D in MAP-CallHandlingOper	at:	100	116	129	144	157
171	185 199	210						
	USE	D in MAP-SupplementarySer	vi :	104	122	143	163	179
192	209 224	242						
				249	261	279	293	

3GPP TS 29.002 version 6.17.0 Release 6 975 ETSI TS 129 002 V6.17.0 (2010-0)										7.0 (2010-07)	
138	151	USED	in MAP-ShortMessageS	ervic	:	78	91	110	123	133	
150	131		in MAP-Group-Call-Op in MAP-LocationServi			53 66	60 85	65 100	70		
196	205		in MAP-Errors 214		:	163	170	177	184	190	
252	259	264	267			221	224	231	238	245	
308	314	320	326			273	281	289	296	302	
364	373	379	386			332	338	345	352	358	
						393	399	402	405	410	
413	416	422	428			436	441	447	453	461	
469	475	481	487			493					
	localizedAdvertisingvalue reference LCSServiceTypeID,										
10	DEFINED in MAP-CommonDataTypes : 422										
			eaId in MAP-LCS-DataTypes				ier of	Named	l Numbe	er, 2	
			Alerting in MAP-MS-DataTypes				ier of	Named	l Numbe	er, 10	
G			timate			identif	ier of	Ext-			
Geogr	GeographicalInformation DEFINED in MAP-LCS-DataTypes : 337										
locationEstimateidentifier of [5] Ext-											
Geogr	GeographicalInformation DEFINED in MAP-LCS-DataTypes : 472										
						identif	ier of	[0]			
Locat	locationEstimateTypeidentifier of [0] LocationEstimateType DEFINED in MAP-LCS-DataTypes : 129										

2006-

12-06	TAG R6.1			Reference	Listing	g for MA	P-Protoco	1	2006-
	DEFINED	in	MAP-LCS	 G-DataType: G-DataType:	S :	133		ENUMERATED	
Locati	locationIn onInformati		ation.			ident	ifier of	[0]	
	DEFINED	in	MAP-MS-	-DataTypes	:	2022			
	locationIn DEFINED			 -DataTypes				[0] NULL	
		in	MAP-MS-	-DataTypes	;	2104			
	USED	in	MAP-MS-	-DataTypes	:	107	2022 2	442	
Locati	locationIn onInformati	on						[3]	
	DEFINED	ın	MAP-MS-	-DataTypes	:	2442			
Locati	locationIn onInformati	onGP	RS					[3]	
	DEFINED	in	MAP-MS-	-DataTypes	:	2026			
	LocationIn	form	ationGI	PRS -DataTypes		type	reference	SEQUENCE	
	USED	in	MAP-MS-	-DataTypes	:	108	2026 2	446	
Locati	locationIn onInformati			PRS		ident	ifier of	[7]	
	DEFINED	in	MAP-MS-	-DataTypes	:	2446			
Locati	locationIn onInfoWithL	MSI					ifier of	[0]	
	DEFINED	in	MAP-SM-	-DataTypes	:	80			
	LocationIn			 DataTypes				SEQUENCE	
				-DataTypes					
								Named Number,	3
	DEFINED	in	MAP-MS-	-DataTypes	;	1368			
				 -DataTypes				[2] LocationN	umber
								OCTET STRING	Ţ
				-DataTypes -DataTypes					
				CompletedDataTypes				Named Number,	4
				SupportedBy -DataTypes				Named Number,	5
				 S-DataType:				LocationType	
	LocationTy	pe				type	reference	SEQUENCE	

DEFINED in MAP-LCS-DataTypes USED in MAP-LCS-DataTypes			4	
locationUpdating DEFINED in MAP-MS-DataTypes	· · · · · · · · · · · · · · · · · · ·	identifier 419	of	Named Number, 2
logicalName DEFINED in MAP-LCS-DataTypes			of	Named Number, 0
longForwardedToNumberAddressString		identifier	of	[10] FTN-
DEFINED in MAP-MS-DataTypes	:	1182		
longForwardedToNumber		identifier	of	[8] FTN-
DEFINED in MAP-CH-DataTypes	:	217		
longForwardedToNumberAddressString		identifier	of	[9] FTN-
DEFINED in MAP-SS-DataTypes	:	106		
longFTN-Supported DEFINED in MAP-MS-DataTypes			of	[4] NULL
longFTN-Supported DEFINED in MAP-MS-DataTypes			of	[4] NULL
longFTN-Supported DEFINED in MAP-MS-DataTypes			of	[6] NULL

12-06	TAG R6.15 Cross Reference Listin 09:33:23 PAGE 59	ng for MAP-Protocol 20	006-
	longFTN-Supported DEFINED in MAP-CH-DataTypes		
	longFTN-Supported		
	longFTN-Supported		
	longFTN-Supported DEFINED in MAP-SS-DataTypes		
	LongSignalInfo DEFINED in MAP-CommonDataTypes USED in MAP-CommonDataTypes	: 253	
ERROR,	<pre>longTermDenial</pre>	-	
	USED in MAP-SupplementaryServi		
	LongTermDenialParam DEFINED in MAP-ER-DataTypes USED in MAP-Errors USED in MAP-ER-DataTypes	: 334 : 139 426	
	lowdelay DEFINED in MAP-LCS-DataTypes		
	lsaActiveModeIndicator DEFINED in MAP-MS-DataTypes		
	lsaAttributes DEFINED in MAP-MS-DataTypes		es
	LSAAttributes DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes	: 1059	
	LSAData DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes	: 1039	
	LSADataList DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes	: 1034	
	lsaDataList DEFINED in MAP-MS-DataTypes		
	lsaIdentity DEFINED in MAP-MS-DataTypes		
	LSAIdentity DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes		
	lsaIdentityList DEFINED in MAP-MS-DataTypes	identifier of LSAIdentityList : 1474	

LSAIdentityList.....type reference SEQUENCE OF DEFINED in MAP-MS-DataTypes : 1476 USED in MAP-MS-DataTypes : 1474 $lsaInformation.....identifier\ of\ [25]\ LSAInformation$ DEFINED in MAP-MS-DataTypes 855 LSAInformation.....type reference SEQUENCE DEFINED in MAP-MS-DataTypes : 1046
USED in MAP-MS-DataTypes : 855 lsaInformationWithdraw.....identifier of [12] LSAInformationWithdraw DEFINED in MAP-MS-DataTypes DEFINED in MAP-MS-DataTypes : 1472 USED in MAP-MS-DataTypes : 1438 DEFINED in MAP-MS-DataTypes : 1030 USED in MAP-MS-DataTypes : 1051

```
TAG R6.15 Cross Reference Listing for MAP-Protocol
                                                                       2006-
12-06 09:33:23 PAGE 60
      lsaOnlyAccessIndicator.....identifier of [1]
LSAOnlyAccessIndicator
                                     : 1051
         DEFINED in MAP-MS-DataTypes
      lu-imsiAttach-imsiDetach.....identifier of Named Number, 2
         DEFINED in MAP-OM-DataTypes
                                             153
      mah.....value reference SS-Code,
'00110010'B
         DEFINED in MAP-SS-Code
      map-b.....identifier of Named Number, 4
         DEFINED in MAP-OM-DataTypes
      MAP-BS-Code......module reference
            FINED in MAP-BS-Code : USED in MAP-MS-DataTypes : USED in MAP-CommonDataTypes :
         DEFINED in MAP-BS-Code
      map-c....identifier of Named Number, 9
         DEFINED in MAP-OM-DataTypes
      MAP-CallHandlingOperations.....module reference
         DEFINED in MAP-CallHandlingOperat : 1
            USED in MAP-Protocol
      MAP-CH-DataTypes.....module reference
         DEFINED in MAP-CH-DataTypes : 1
            USED in MAP-CallHandlingOperat :
      MAP-CommonDataTypes.....module reference
         DEFINED in MAP-CommonDataTypes : 1
            USED in MAP-OperationAndMainte :
            USED in MAP-MS-DataTypes : 199
            USED in MAP-OM-DataTypes :
USED in MAP-CH-DataTypes :
USED in MAP-SS-DataTypes :
USED in MAP-SM-DataTypes :
USED in MAP-GR-DataTypes :
USED in MAP-LCS-DataTypes :
USED in MAP-LCS-DataTypes :
            USED in MAP-ER-DataTypes
                                              74
      map-d.....identifier of Named Number, 8
         DEFINED in MAP-OM-DataTypes
      map-e.....identifier of Named Number, 5
         DEFINED in MAP-OM-DataTypes
      MAP-Errors.....module reference
         DEFINED in MAP-Errors
            USED in MAP-MobileServiceOpera :
            USED in MAP-OperationAndMainte : 31
USED in MAP-CallHandlingOperat : 51
            USED in MAP-SupplementaryServi : 57
USED in MAP-ShortMessageServic : 42
            USED in MAP-Group-Call-Operati :
            USED in MAP-LocationServiceOpe : 38
      MAP-ER-DataTypes.....module reference
```

DEFINED in MAP-ER-DataTypes

USED	in	MAP-Errors MAP-MS-DataTypes MAP-SM-DataTypes	:	209				
MAP-EXTENSI	ON	• • • • • • • • • • • • • • • • • • • •		.informa	ation	object	class	
reference CLASS								
DEFINED	in	MAP-ExtensionDataTypes	:	23				
USED	in	MAP-ExtensionDataTypes	:	45	47	52		
MAD Errt ong;	on!	Dot office a		modulo	mo for	020		
		DataTypes			rerer	ence		
		MAP-ExtensionDataTypes						
		MAP-MS-DataTypes						
		MAP-OM-DataTypes						
USED	in	MAP-CommonDataTypes	:	86				
		MAP-CH-DataTypes						
		MAP-SS-DataTypes						
		MAP-SM-DataTypes						
USED	in	MAP-GR-DataTypes	:	42				
USED	in	MAP-LCS-DataTypes	:	50				
USED	in	MAP-ER-DataTypes	:	86				
		MAP-OM-DataTypes			ier o	f Named	l Number,	6
map-g				.identif	eier o	f Named	l Number,	3

12-06	TAG R6.15 09:33:23 PA		eference	Listing	for MAP-	-Protocol	-		2006-
	DEFINED i	n MAP-OM-D	ataTypes	:	99				
	map-gd DEFINED i	n MAP-OM-D	ataTypes	:	.identif	eier of N	Jamed	Number,	4
	map-gf DEFINED i	n MAP-OM-D				ier of N	Jamed	Number,	5
	map-gr DEFINED i	n MAP-OM-D				ier of N	Jamed	Number,	3
		ll-Operati n MAP-Grou n MAP-Prot	p-Call-Op	perati :	1	referenc	ce		
		ypes n MAP-GR-D n MAP-Grou	ataTypes	:	1	referenc	ce		
	MAP-LCS-Data DEFINED i USED i	Types n MAP-LCS- n MAP-Loca	DataTypes	· :	1	referenc	ce		
		ServiceOpe n MAP-Loca n MAP-Prot	tionServ		1	referenc	ce		
		rviceOpera n MAP-Mobi n MAP-Prot	leService		1	referenc	ce		
	USED i USED i USED i	ypes n MAP-MS-D n MAP-Mobi n MAP-CH-D n MAP-GR-D n MAP-LCS-	ataTypes leService ataTypes ataTypes	: eOpera : :	1 162 51 37	referenc	ce		
	USED i	ypes n MAP-OM-D n MAP-Oper n MAP-MS-D	ataTypes ationAndN	: Mainte :	1 39	referenc	ce		
		nAndMainte n MAP-Oper n MAP-Prot	ationAndN		.module 1 53	referenc	ce		
	MAP-Protocol DEFINED i	n MAP-Prot				referenc	ce		
		sageServic n MAP-Shor n MAP-Prot	tMessageS		1	referenc	ce		
	USED i	ypes n MAP-SM-D n MAP-Shor n MAP-LCS-	ataTypes tMessages	: Servic :	1 58	referenc	ce		
	MAP-SS-Code.					referenc	ce		

DEFINED	in	MAP-SS-Code	:	1	
USED	in	MAP-SupplementaryServi	:	80	
USED	in	MAP-MS-DataTypes	:	159	
USED	in	MAP-CommonDataTypes	:	81	
USED	in	MAP-SS-DataTypes	:	65	
USED	in	MAP-ER-DataTypes	:	81	
MAP-SS-Data	аТур	pes		.module	reference
		MAP-SS-DataTypes	:	1	
USED	in	MAP-SupplementaryServi	:	75	
USED	in	MAP-Errors	:	102	
USED	in	MAP-MS-DataTypes	:	154	
USED	in	MAP-CH-DataTypes	:	58	
USED	in	MAP-LCS-DataTypes	:	56	
USED	in	MAP-ER-DataTypes	:	66	
MAP-Suppler	nent	taryServiceOperations		.module	reference
DEFINED	in	MAP-SupplementaryServi	:	1	
USED	in	MAP-Protocol	:	85	
MAP-TS-Code	∋			.module	reference
DEFINED	in	MAP-TS-Code	:	1	

DEFINED in MAP-SS-DataTypes : 193 maxISDN-AddressLength	USED in MAP-GermonDataTypes : 70 USED in MAP-GR-DataTypes : 1624 matchType	12-06	TAG R6.15		Reference	Listing	for MA	P-Protocol		2006-
USED in MAP-CommonDataTypes : 70 USED in MAP-GR-DataTypes : 32 matchType	USED in MAP-CommonDataTypes : 70 USED in MAP-GR-DataTypes : 32 matchType		USED	in MAP-MS	-DataTypes	:	169			
matchType	matchType		USED	in MAP-Co	mmonDataTyr	oes :	70			
matchType	matchType		USED	in MAP-GR	-DataTypes	:	32			
DEFINED in MAP-MS-DataTypes : 1654 MatchType	DEFINED in MAP-MS-DataTypes : 1654 MatchType				21					
DEFINED in MAP-MS-DataTypes : 1654 MatchType	DEFINED in MAP-MS-DataTypes : 1654 MatchType		matchType				.ident:	ifier of [(] MatchTy	ре
MatchType	MatchType								-	-
DEFINED in MAP-MS-DataTypes : 1684 USED in MAP-MS-DataTypes : 1654 maxAddressLength	DEFINED in MAP-MS-DataTypes : 1684 USED in MAP-MS-DataTypes : 1654 maxAddressLength				11					
DEFINED in MAP-MS-DataTypes : 1684 USED in MAP-MS-DataTypes : 1654 maxAddressLength	DEFINED in MAP-MS-DataTypes : 1684 USED in MAP-MS-DataTypes : 1654 maxAddressLength		MatchType				.type :	reference I	ENUMERATED	
maxAddressLength	maxAddressLength									
DEFINED in MAP-CommonDataTypes : 145 USED in MAP-CommonDataTypes : 104 maxAdd-GeographicalInformationvalue reference INTEGER, 91 DEFINED in MAP-LCS-DataTypes : 460 USED in MAP-LCS-DataTypes : 442 maxEventSpecificationvalue reference INTEGER, 2 DEFINED in MAP-SS-DataTypes : 302 USED in MAP-SS-DataTypes : 299 maxExt-GeographicalInformationvalue reference INTEGER, 20 DEFINED in MAP-LCS-DataTypes : 422 USED in MAP-LCS-DataTypes : 366 maxFTN-AddressLengthvalue reference INTEGER, 15 DEFINED in MAP-CommonDataTypes : 160 USED in MAP-CommonDataTypes : 154 maximum	DEFINED in MAP-CommonDataTypes : 145 USED in MAP-CommonDataTypes : 104 maxAdd-GeographicalInformation		USED	in MAP-MS	-DataTypes	:	1654			
DEFINED in MAP-CommonDataTypes : 145 USED in MAP-CommonDataTypes : 104 maxAdd-GeographicalInformationvalue reference INTEGER, 91 DEFINED in MAP-LCS-DataTypes : 460 USED in MAP-LCS-DataTypes : 442 maxEventSpecificationvalue reference INTEGER, 2 DEFINED in MAP-SS-DataTypes : 302 USED in MAP-SS-DataTypes : 299 maxExt-GeographicalInformationvalue reference INTEGER, 20 DEFINED in MAP-LCS-DataTypes : 422 USED in MAP-LCS-DataTypes : 366 maxFTN-AddressLengthvalue reference INTEGER, 15 DEFINED in MAP-CommonDataTypes : 160 USED in MAP-CommonDataTypes : 154 maximum	DEFINED in MAP-CommonDataTypes : 145 USED in MAP-CommonDataTypes : 104 maxAdd-GeographicalInformation									
maxAdd-GeographicalInformationvalue reference INTEGER, 91 DEFINED in MAP-LCS-DataTypes : 460 USED in MAP-LCS-DataTypes : 442 maxEventSpecificationvalue reference INTEGER, 2 DEFINED in MAP-SS-DataTypes : 302 USED in MAP-SS-DataTypes : 299 maxExt-GeographicalInformationvalue reference INTEGER, 20 DEFINED in MAP-LCS-DataTypes : 422 USED in MAP-LCS-DataTypes : 366 maxFTN-AddressLengthvalue reference INTEGER, 15 DEFINED in MAP-CommonDataTypes : 160 USED in MAP-CommonDataTypes : 154 maximum	maxAdd-GeographicalInformation							reference	INTEGER,	20
maxAdd-GeographicalInformationvalue reference INTEGER, 91 DEFINED in MAP-LCS-DataTypes : 460 USED in MAP-LCS-DataTypes : 442 maxEventSpecification	maxAdd-GeographicalInformation		DEFINED	in MAP-Co	mmonDataTyr	pes :	145			
DEFINED in MAP-LCS-DataTypes : 460 USED in MAP-LCS-DataTypes : 442 maxEventSpecification	DEFINED in MAP-LCS-DataTypes : 460 USED in MAP-LCS-DataTypes : 442 maxEventSpecification		USED	in MAP-Co	mmonDataTyp	pes :	104			
DEFINED in MAP-LCS-DataTypes : 460 USED in MAP-LCS-DataTypes : 442 maxEventSpecification	DEFINED in MAP-LCS-DataTypes : 460 USED in MAP-LCS-DataTypes : 442 maxEventSpecification									
USED in MAP-LCS-DataTypes : 442 maxEventSpecification	maxEventSpecification							reference	INTEGER,	91
maxEventSpecification	maxEventSpecification		DEFINED	in MAP-LC	S-DataTypes	:	460			
DEFINED in MAP-SS-DataTypes : 302 USED in MAP-SS-DataTypes : 299 maxExt-GeographicalInformationvalue reference INTEGER, 20 DEFINED in MAP-LCS-DataTypes : 422 USED in MAP-LCS-DataTypes : 366 maxFTN-AddressLengthvalue reference INTEGER, 15 DEFINED in MAP-CommonDataTypes : 160 USED in MAP-CommonDataTypes : 154 maximum	DEFINED in MAP-SS-DataTypes : 302 USED in MAP-SS-DataTypes : 299 maxExt-GeographicalInformationvalue reference INTEGER, 20 DEFINED in MAP-LCS-DataTypes : 422 USED in MAP-LCS-DataTypes : 366 maxFTN-AddressLengthvalue reference INTEGER, 15 DEFINED in MAP-CommonDataTypes : 160 USED in MAP-CommonDataTypes : 154 maximum		USED	in MAP-LC	S-DataTypes	:	442			
DEFINED in MAP-SS-DataTypes : 302 USED in MAP-SS-DataTypes : 299 maxExt-GeographicalInformationvalue reference INTEGER, 20 DEFINED in MAP-LCS-DataTypes : 422 USED in MAP-LCS-DataTypes : 366 maxFTN-AddressLengthvalue reference INTEGER, 15 DEFINED in MAP-CommonDataTypes : 160 USED in MAP-CommonDataTypes : 154 maximum	DEFINED in MAP-SS-DataTypes : 302 USED in MAP-SS-DataTypes : 299 maxExt-GeographicalInformationvalue reference INTEGER, 20 DEFINED in MAP-LCS-DataTypes : 422 USED in MAP-LCS-DataTypes : 366 maxFTN-AddressLengthvalue reference INTEGER, 15 DEFINED in MAP-CommonDataTypes : 160 USED in MAP-CommonDataTypes : 154 maximum									
MAP-SS-DataTypes : 299 maxExt-GeographicalInformationvalue reference INTEGER, 20 DEFINED in MAP-LCS-DataTypes : 422 USED in MAP-LCS-DataTypes : 366 maxFTN-AddressLengthvalue reference INTEGER, 15 DEFINED in MAP-CommonDataTypes : 160 USED in MAP-CommonDataTypes : 154 maximum	maxExt-GeographicalInformation		maxEventSpe	ecificatio	n		.value	reference	INTEGER,	2
maxExt-GeographicalInformationvalue reference INTEGER, 20DEFINED in MAP-LCS-DataTypes: 422USED in MAP-LCS-DataTypes: 366maxFTN-AddressLengthvalue reference INTEGER, 15DEFINED in MAP-CommonDataTypes: 160USED in MAP-CommonDataTypes: 154maximumidentifier of Named Number, 2DEFINED in MAP-OM-DataTypes: 72maximumentitledPriorityidentifier of EMLPP-PriorityDEFINED in MAP-CommonDataTypes: 547maximumentitledPriorityidentifier of [0] EMLPP-PriorityDEFINED in MAP-SS-DataTypes: 193maxISDN-AddressLengthvalue reference INTEGER, 9DEFINED in MAP-CommonDataTypes: 151USED in MAP-CommonDataTypes: 18148maxISDN-SubaddressLengthvalue reference INTEGER, 21DEFINED in MAP-CommonDataTypes: 200USED in MAP-CommonDataTypes: 200USED in MAP-CommonDataTypes: 163maxLCSCodewordStringLengthvalue reference INTEGER, 20DEFINED in MAP-LCS-DataTypes: 266	maxExt-GeographicalInformation		DEFINED	in MAP-SS	-DataTypes	:	302			
DEFINED in MAP-LCS-DataTypes : 422 USED in MAP-LCS-DataTypes : 366 maxFTN-AddressLength	DEFINED in MAP-LCS-DataTypes : 422 USED in MAP-LCS-DataTypes : 366 maxFTN-AddressLength		USED	in MAP-SS	-DataTypes	:	299			
DEFINED in MAP-LCS-DataTypes : 422 USED in MAP-LCS-DataTypes : 366 maxFTN-AddressLength	DEFINED in MAP-LCS-DataTypes : 422 USED in MAP-LCS-DataTypes : 366 maxFTN-AddressLength									
USED in MAP-LCS-DataTypes : 366 maxFTN-AddressLength	USED in MAP-LCS-DataTypes : 366 maxFTN-AddressLength							reference	INTEGER,	20
maxFTN-AddressLength	maxFTN-AddressLength									
DEFINED in MAP-CommonDataTypes : 160 USED in MAP-CommonDataTypes : 154 maximum	DEFINED in MAP-CommonDataTypes : 160 USED in MAP-CommonDataTypes : 154 maximum		USED	in MAP-LC	S-DataTypes	:	366			
DEFINED in MAP-CommonDataTypes : 160 USED in MAP-CommonDataTypes : 154 maximum	DEFINED in MAP-CommonDataTypes : 160 USED in MAP-CommonDataTypes : 154 maximum		TITES 7 1 1 1	.			7	_	TIMECED	1 -
maximum	maximum								INTEGER,	15
maximum	maximum		DELINED	in MAP-Co	mmonDataTyr	pes :	160			
maximumentitledPriority	maximumentitledPriority		USED	in MAP-Co	mmonDataTy	pes :	154			
DEFINED in MAP-CommonDataTypes : 547 maximumEntitledPriority	DEFINED in MAP-CommonDataTypes : 547 maximumEntitledPriority							ifier of Na	amed Numbe	r, 2
DEFINED in MAP-CommonDataTypes : 547 maximumEntitledPriority	DEFINED in MAP-CommonDataTypes : 547 maximumEntitledPriority		massi mumont i	i+lodDrior	i +		idont	ifion of EN	MIDD Drion	i +
maximumEntitledPriorityidentifier of [0] EMLPP-Priority DEFINED in MAP-SS-DataTypes : 193 maxISDN-AddressLength	maximumEntitledPriorityidentifier of [0] EMLPP-PriorityDEFINED in MAP-SS-DataTypes: 193maxISDN-AddressLengthvalue reference INTEGER, 9DEFINED in MAP-CommonDataTypes: 151USED in MAP-CommonDataTypes: 18 148maxISDN-SubaddressLengthvalue reference INTEGER, 21DEFINED in MAP-CommonDataTypes: 200USED in MAP-CommonDataTypes: 163maxLCSCodewordStringLengthvalue reference INTEGER, 20DEFINED in MAP-LCS-DataTypes: 266USED in MAP-LCS-DataTypes: 264maxLongSignalInfoLengthvalue reference INTEGER, 2560DEFINED in MAP-CommonDataTypes: 255USED in MAP-CommonDataTypes: 253MaxMC-Bearerstype reference INTEGER							iller or er	MUDD-BIIOI	тсу
DEFINED in MAP-SS-DataTypes : 193 maxISDN-AddressLength	DEFINED in MAP-SS-DataTypes : 193 maxISDN-AddressLength		DELINED	III MAF-CO	IIIIIOIIDacai y	jes .	347			
DEFINED in MAP-SS-DataTypes : 193 maxISDN-AddressLength	DEFINED in MAP-SS-DataTypes : 193 maxISDN-AddressLength		maximumEnti	itledPrior	itv		ident	ifier of [(11 FMI.DD-D	riority
maxISDN-AddressLength	maxISDN-AddressLength							IIICI OI (), <u> </u>	rioricy
DEFINED in MAP-CommonDataTypes : 151 USED in MAP-CommonDataTypes : 18 148 maxISDN-SubaddressLengthvalue reference INTEGER, 21 DEFINED in MAP-CommonDataTypes : 200 USED in MAP-CommonDataTypes : 163 maxLCSCodewordStringLengthvalue reference INTEGER, 20 DEFINED in MAP-LCS-DataTypes : 266	DEFINED in MAP-CommonDataTypes : 151 USED in MAP-CommonDataTypes : 18 148 maxISDN-SubaddressLengthvalue reference INTEGER, 21 DEFINED in MAP-CommonDataTypes : 200 USED in MAP-CommonDataTypes : 163 maxLCSCodewordStringLengthvalue reference INTEGER, 20 DEFINED in MAP-LCS-DataTypes : 266 USED in MAP-LCS-DataTypes : 264 maxLongSignalInfoLengthvalue reference INTEGER, 2560 DEFINED in MAP-CommonDataTypes : 255 USED in MAP-CommonDataTypes : 255 USED in MAP-CommonDataTypes : 253 MaxMC-Bearerstype reference INTEGER			111 1111 00	Dacarypes	•	100			
DEFINED in MAP-CommonDataTypes : 151 USED in MAP-CommonDataTypes : 18 148 maxISDN-SubaddressLengthvalue reference INTEGER, 21 DEFINED in MAP-CommonDataTypes : 200 USED in MAP-CommonDataTypes : 163 maxLCSCodewordStringLengthvalue reference INTEGER, 20 DEFINED in MAP-LCS-DataTypes : 266	DEFINED in MAP-CommonDataTypes : 151 USED in MAP-CommonDataTypes : 18 148 maxISDN-SubaddressLengthvalue reference INTEGER, 21 DEFINED in MAP-CommonDataTypes : 200 USED in MAP-CommonDataTypes : 163 maxLCSCodewordStringLengthvalue reference INTEGER, 20 DEFINED in MAP-LCS-DataTypes : 266 USED in MAP-LCS-DataTypes : 264 maxLongSignalInfoLengthvalue reference INTEGER, 2560 DEFINED in MAP-CommonDataTypes : 255 USED in MAP-CommonDataTypes : 255 USED in MAP-CommonDataTypes : 253 MaxMC-Bearerstype reference INTEGER		maxISDN-Ado	dressLengt	h		.value	reference	INTEGER.	9
USED in MAP-CommonDataTypes : 18 148 maxISDN-SubaddressLengthvalue reference INTEGER, 21 DEFINED in MAP-CommonDataTypes : 200 USED in MAP-CommonDataTypes : 163 maxLCSCodewordStringLengthvalue reference INTEGER, 20 DEFINED in MAP-LCS-DataTypes : 266	USED in MAP-CommonDataTypes : 18 148 maxISDN-SubaddressLength									-
maxISDN-SubaddressLengthvalue reference INTEGER, 21 DEFINED in MAP-CommonDataTypes : 200 USED in MAP-CommonDataTypes : 163 maxLCSCodewordStringLengthvalue reference INTEGER, 20 DEFINED in MAP-LCS-DataTypes : 266	maxISDN-SubaddressLength									
DEFINED in MAP-CommonDataTypes : 200 USED in MAP-CommonDataTypes : 163 maxLCSCodewordStringLengthvalue reference INTEGER, 20 DEFINED in MAP-LCS-DataTypes : 266	DEFINED in MAP-CommonDataTypes : 200 USED in MAP-CommonDataTypes : 163 maxLCSCodewordStringLengthvalue reference INTEGER, 20 DEFINED in MAP-LCS-DataTypes : 266 USED in MAP-LCS-DataTypes : 264 maxLongSignalInfoLengthvalue reference INTEGER, 2560 DEFINED in MAP-CommonDataTypes : 255 USED in MAP-CommonDataTypes : 253 MaxMC-Bearerstype reference INTEGER				21					
DEFINED in MAP-CommonDataTypes : 200 USED in MAP-CommonDataTypes : 163 maxLCSCodewordStringLengthvalue reference INTEGER, 20 DEFINED in MAP-LCS-DataTypes : 266	DEFINED in MAP-CommonDataTypes : 200 USED in MAP-CommonDataTypes : 163 maxLCSCodewordStringLengthvalue reference INTEGER, 20 DEFINED in MAP-LCS-DataTypes : 266 USED in MAP-LCS-DataTypes : 264 maxLongSignalInfoLengthvalue reference INTEGER, 2560 DEFINED in MAP-CommonDataTypes : 255 USED in MAP-CommonDataTypes : 253 MaxMC-Bearerstype reference INTEGER		maxISDN-Sub	oaddressLe	ngth		.value	reference	INTEGER,	21
maxLCSCodewordStringLengthvalue reference INTEGER, 20 DEFINED in MAP-LCS-DataTypes : 266	maxLCSCodewordStringLengthvalue reference INTEGER, 20 DEFINED in MAP-LCS-DataTypes : 266 USED in MAP-LCS-DataTypes : 264 maxLongSignalInfoLengthvalue reference INTEGER, 2560 DEFINED in MAP-CommonDataTypes : 255 USED in MAP-CommonDataTypes : 253 MaxMC-Bearerstype reference INTEGER		DEFINED	in MAP-Co	mmonDataTy	oes :	200		•	
maxLCSCodewordStringLengthvalue reference INTEGER, 20 DEFINED in MAP-LCS-DataTypes : 266	maxLCSCodewordStringLengthvalue reference INTEGER, 20 DEFINED in MAP-LCS-DataTypes : 266 USED in MAP-LCS-DataTypes : 264 maxLongSignalInfoLengthvalue reference INTEGER, 2560 DEFINED in MAP-CommonDataTypes : 255 USED in MAP-CommonDataTypes : 253 MaxMC-Bearerstype reference INTEGER		USED	in MAP-Co	mmonDataTy	oes :	163			
DEFINED in MAP-LCS-DataTypes : 266	DEFINED in MAP-LCS-DataTypes : 266 USED in MAP-LCS-DataTypes : 264 maxLongSignalInfoLengthvalue reference INTEGER, 2560 DEFINED in MAP-CommonDataTypes : 255 USED in MAP-CommonDataTypes : 253 MaxMC-Bearerstype reference INTEGER									
	USED in MAP-LCS-DataTypes : 264 maxLongSignalInfoLengthvalue reference INTEGER, 2560 DEFINED in MAP-CommonDataTypes : 255 USED in MAP-CommonDataTypes : 253 MaxMC-Bearerstype reference INTEGER		maxLCSCodev	wordString	Length		.value	reference	INTEGER,	20
ICED in MAD-ICC-DataTypes . 264	maxLongSignalInfoLengthvalue reference INTEGER, 2560 DEFINED in MAP-CommonDataTypes : 255 USED in MAP-CommonDataTypes : 253 MaxMC-Bearerstype reference INTEGER		DEFINED	in MAP-LC	S-DataTypes	:	266			
USED IN MAR-LCS-Datalypes . 204	DEFINED in MAP-CommonDataTypes : 255 USED in MAP-CommonDataTypes : 253 MaxMC-Bearerstype reference INTEGER		USED	in MAP-LC	S-DataTypes	:	264			
	DEFINED in MAP-CommonDataTypes : 255 USED in MAP-CommonDataTypes : 253 MaxMC-Bearerstype reference INTEGER									
maxLongSignalInfoLengthvalue reference INTEGER, 2560	DEFINED in MAP-CommonDataTypes : 255 USED in MAP-CommonDataTypes : 253 MaxMC-Bearerstype reference INTEGER		maxLongSigr	nalInfoLen	gth		value	reference	INTEGER,	2560
DEFINED in MAP-CommonDataTypes : 255	USED in MAP-CommonDataTypes : 253 MaxMC-Bearerstype reference INTEGER		DEFINED	in MAP-Co	mmonDataTyp	pes :	255			
USED in MAP-CommonDataTypes : 253			USED	in MAP-Co	mmonDataTyp	pes :	253			
	DESCRIPTION 1 1/10 0 D 1 - 1								INTEGER	
DEFINED in MAP-CommonDataTypes : 574										
	HCFD in MAD-CommonDataTimos . EC ECO									
USED in MAP-CommonDataTypes : 56 569			USED	ın MAP-SS	-nata'l'ypes	:	52	Т96		
			USED	in MAP-SS	-DataTypes	:	52	196		

maxNameStringLength DEFINED in MAP-LCS-DataTypes USED in MAP-LCS-DataTypes	: 190)	INTEGER,	63
maxNrOfRABs DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes	: 738	}	INTEGER,	255
maxNumOfAreas DEFINED in MAP-LCS-DataTypes USED in MAP-LCS-DataTypes	: 296	;	INTEGER,	10
maxNumOfBasicServiceGroups DEFINED in MAP-SS-DataTypes USED in MAP-SS-DataTypes	: 266	;)		13
maxNumOfBasicServices DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes	: 1482		INTEGER,	70
maxNumOfBearerServices	value	reference	INTEGER,	50

12-06	TAG R6.1		s Reference	Listing	for MAI	P-Protocol		2006-
	DEFINED USED	in MAP-MS	S-DataTypes S-DataTypes	:	1091 1088			
			erviceCrite			reference	INTEGER,	5
	DEFINED	in MAP-M	S-DataTypes	:	1678			
	USED	in MAP-M	S-DataTypes	:	1669			
			ationNumber			reference	INTEGER,	3
	DEFINED	in MAP-MS	S-DataTypes	:	1676			
			S-DataTypes					
			ationNumbers			reference	INTEGER,	10
	DEFINED	in MAP-MS	S-DataTypes	:	1674			
			S-DataTypes					
			S			reference	INTEGER,	10
			S-DataTypes					
			S-DataTypes					
			ā				INTEGER,	10
	DEFINED	in MAP-M	S-DataTypes	:	1607			
		in MAP-MS	S-DataTypes	:	80	963 150	05 1600	1632
1635	1778 1889							
			seValueCrite			reference	INTEGER,	5
			S-DataTypes					
	USED	in MAP-M	S-DataTypes	:	1688			
			seValueCrite			reference	INTEGER,	5
	DEFINED	in MAP-MS	S-DataTypes S-DataTypes	:	1696			
	USED	in MAP-M	S-DataTypes	:	1691			
	maxNumOfCC	BS-Request			value	reference	INTEGER,	5
	DEFINED	in MAP-S	S-DataTypes	:	203			
	USED	in MAP-S	S-DataTypes	:	200	212		
	maxNumOfCU(G			value	reference	INTEGER,	10
	DEFINED	in MAP-M	S-DataTypes	:	1262			
	USED	in MAP-M	S-DataTypes	:	1241			
			InfoCriteria			reference	INTEGER,	10
			S-DataTypes		1550			
	USED	in MAP-M	S-DataTypes	:	1547			
	maxNumOfEn	cryptionI	nfo		value	reference	INTEGER,	100
			S-DataTypes					
			S-DataTypes					
	maxNumOfEx	ternalCli	ent		value	reference	INTEGER.	5
			S-DataTypes				,	
			S-DataTypes					
	maxNumOfExt	t-BasicSe	rviceGroups		value	reference	INTEGER	32
			S-DataTypes					
	USED	in MAP-M	S-DataTypes	:	1167	1226 126	64 1267	
								2-
			lClient			reterence	INTEGER,	35
			S-DataTypes					
	USED	in MAP-MS	S-DataTypes	:	1341			

maxNumOfGMLC DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes	: 899	5
maxNumOfHLR-Id DEFINED in MAP-CommonDataTypes USED in MAP-CommonDataTypes	: 336	50
maxNumOfIntegrityInfo DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes	: 752	100
maxNumOfISDN-AddressDigits DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes	: 1672	15
maxNumOfLSAs DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes	: 1037	20
maxNumOfMC-Bearers DEFINED in MAP-CommonDataTypes USED in MAP-CommonDataTypes	: 578	7

12-06	TAG R6.1		Reference	Listing	for MAI	P-Protocol		2006-
		in MAP-MS	gers -DataTypes -DataTypes	:	1847	reference	INTEGER,	10
		in MAP-MS	 -DataTypes -DataTypes	:	1390	reference	INTEGER,	3
	maxNumOfPD DEFINED USED	in MAP-MS	 -DataTypes -DataTypes	:	912			50
		in MAP-MS	 -DataTypes -DataTypes	:	1339	reference	INTEGER,	5
	maxNumOfPr DEFINED USED	in MAP-MS	 -DataTypes -DataTypes	:	1302	reference	INTEGER,	4
		in MAP-Ex	sions tensionData tensionData	aTypes :	50	reference	INTEGER,	10
	maxNumOfRa DEFINED USED	in MAP-MS	es -DataTypes -DataTypes	:	598	reference	INTEGER,	7
		in MAP-MS	mber -DataTypes -DataTypes	:	740		INTEGER,	7
		in MAP-MS	vers -DataTypes -DataTypes	:	576	reference	INTEGER,	7
		in MAP-MS	 -DataTypes -DataTypes	:	1376	reference	INTEGER,	32
	USED	in MAP-SS in MAP-MS	-DataTypes -DataTypes -DataTypes	:	258 149	1151		30
	maxNumOfTe DEFINED	leservices in MAP-MS			value 1096			20
		in MAP-MS	 -DataTypes -DataTypes	:	1517	reference	INTEGER,	5
	maxNumOfVB DEFINED USED	in MAP-MS	 -DataTypes -DataTypes	:	1986	reference	INTEGER,	50
	maxNumOfVG DEFINED		 -DataTypes			reference	INTEGER,	50

USED	in	MAP-MS-DataTypes	:	1983			
		odes			reference	INTEGER,	10
		MAP-MS-DataTypes MAP-MS-DataTypes		67	1398		
			-				
maxPermitte	edEi	${\tt ncryptionAlgorithmsLength}$	th.	.value	reference	INTEGER,	9
DEFINED	in	MAP-MS-DataTypes	:	528			
USED	in	MAP-MS-DataTypes	:	520			
		ntegrityProtectionAlgor			reference	INTEGER,	9
		MAP-MS-DataTypes					
USED	ın	MAP-MS-DataTypes	:	509			
maxPosition	ning	gDataInformation		.value	reference	INTEGER,	10
DEFINED	in	MAP-LCS-DataTypes	:	431			
USED	in	MAP-LCS-DataTypes	:	426			
_		OStringLength			reference	INTEGER,	63
		MAP-LCS-DataTypes					
USED	in	MAP-LCS-DataTypes	:	198			

12-06	TAG R6.15			Reference	Listing	for MA	P-Protoco	ol		2006-
	maxSignalIn DEFINED USED	in N	MAP-Con	 nmonDataTy nmonDataTy	pes :	213		ce INT	EGER, 2	200
	maxUSSD-Sti	ringI in M	Length. MAP-SS-			value	referen	ce INT	EGER, 1	160
	maxUtranPos DEFINED USED	in N	MAP-LCS	ataInfo G-DataType G-DataType	s :	439		ce INT	EGER, 1	11
	mbmsContext DEFINED			 -DataTypes				Named	Numbe	r, 3
	mbmsContext DEFINED			 -DataTypes				Named	Numbe	r, 1
	mbmsMultica DEFINED			Activation -DataTypes		ident 175		Named	Numbe	r, 0
	mc DEFINED			 -DataTypes				Named	Numbe	r, 2
	mc DEFINED			 -DataTypes		ident 109		Named	Numbe:	r, 0
'010001	mc L01'B DEFINED							ce SS-	Code,	
	mcef-Set DEFINED			 -DataTypes				Named	Numbe	r, 2
'000101							referen	ce SS-	Code,	
	DEFINED MC-Bearers			-Code					CED	
	DEFINED USED	in M	MAP-Con MAP-Con	nmonDataTy nmonDataTy -DataTypes	pes :	576 57				198
	mc-SS-Info DEFINED			 -DataTypes				[28] 1	MC-SS-	Info
	USED	in M	MAP-Con MAP-MS-	nmonDataTy -DataTypes nmonDataTy	rpes :	566 189	860	e SEQU	ENCE	
	medium DEFINED			 -DataTypes		ident		Named	Numbe	r, 1
	memoryAvail DEFINED			 -DataTypes				Named	Numbe	r, 1
	memoryCapac DEFINED			ed -DataTypes				Named	Number	r, 0

	memoryCapacityExceeded DEFINED in MAP-ER-DataTypes			fier of	Name	d Number, 0	
	messageWaitingListFull		.informa	ation ob	oject	reference	
ERROR,	Information Object						
	DEFINED in MAP-Errors						
	USED in MAP-ShortMessageServic			122			
	USED in MAP-Errors	:	79				
	MessageWaitListFullParam		.type re	eference	e SEQU	UENCE	
	DEFINED in MAP-ER-DataTypes						
	USED in MAP-Errors			445			
	USED in MAP-ER-DataTypes						
				c		1 - 1 - 4	
	$mgw.\dots$			fier of	Name	d Number, 1	
	DEFINED in MAP-OM-DataTypes	:	79				
	MGW-EventList		.type re	eference	BIT	STRING	
	DEFINED in MAP-OM-DataTypes	:	158				
	USED in MAP-OM-DataTypes						
	man. Dramblish			e:e	[11]	MCH December	عہ د
	mgw-EventList			rier or	[T T]	MGW-EVench.	ISC
	DEFINED in MAP-OM-DataTypes	:	191				
	MGW-InterfaceList		.type re	eference	e BIT	STRING	

12-06	TAG R6.15		Reference	Listing	for MAP	-Protoco	ol		2006-
	DEFINED USED	in MAP-OM in MAP-OM	-DataTypes -DataTypes	:	108 88	190			
Interf	mgw-Interfa aceList		 -DataTypes			fier of	[10]	MGW-	
Interf	mgw-List					fier of	[1]	MGW-	
	DEFINED mgw-List		-DataTypes			fier of	[1]	MGW-EventI	List
	mgw-TraceDe	pth			identi	fier of	[1]	TraceDeptl	1
	mgw-TraceDe	pth			identi	fier of	[9]	TraceDepth	ı
	mg-csi				identi	fier of	[5]	MG-CSI	
	mg-csi				identi	fier of	Name	d Number,	10
	mg-csi				identi	fier of	Name	d Number,	5
	MG-CSI				type r	eference	e SEQ	UENCE	
	USED	in MAP-MS	-DataTypes -DataTypes	:	946				
		in MAP-MS	-DataTypes	:	2301				1
		in MAP-MS	-DataTypes	:	2349				0
		in MAP-OM	-DataTypes	:	70				0
Addres	mlcNumber sString DEFINED		S-DataType			iler oi	[0]	ISDN-	
	mlc-Number. DEFINED		 S-DataType:			fier of	ISDN	-AddressSt	ring
		in MAP-MS	 -DataTypes -DataTypes	:	1849		e OCT	ET STRING	
ERROR,	mm-EventNot Information DEFINED			:		ation ol	oject	reference	9
	USED		bileServic		92	504			
	MM-EventNot	Supported	-Param		type r	eference	e SEQ	UENCE	

DEFINED in MAP-ER-DataTypes : 382 USED in MAP-Errors 144 491 USED in MAP-ER-DataTypes 53 mnpInfoRes.....identifier of [8] MNPInfoRes DEFINED in MAP-MS-DataTypes 2031 MNPInfoRes.....type reference SEQUENCE DEFINED in MAP-MS-DataTypes : 2039 USED in MAP-MS-DataTypes : 112 112 2031 mnpRequestedInfo.....identifier of [7] NULL : 2093 DEFINED in MAP-MS-DataTypes mnrf-Set.....identifier of Named Number, 1 DEFINED in MAP-SM-DataTypes 194 mnrg-Set.....identifier of Named Number, 3 DEFINED in MAP-SM-DataTypes 196 mobileNotReachableReason.....identifier of [2] AbsentSubscriberDiagnosticSM DEFINED in MAP-MS-DataTypes : 1927 mobileYellowPages.....value reference LCSServiceTypeID, 11 DEFINED in MAP-CommonDataTypes : 423

TAG R6.15 Cross Reference Listing for MAP-Protocol 2006-12-06 09:33:23 PAGE 67 mobilityTriggers.....identifier of MobilityTriggers DEFINED in MAP-MS-DataTypes 1823 mobilityTriggers.....identifier of MobilityTriggers DEFINED in MAP-MS-DataTypes 1834 MobilityTriggers.....type reference SEQUENCE OF DEFINED in MAP-MS-DataTypes : 1844

USED in MAP-MS-DataTypes : 1823 1834 ModificationInstruction.....type reference ENUMERATED DEFINED in MAP-MS-DataTypes : 2414 USED in MAP-MS-DataTypes : 2382 2392 2398 2404 2405 modificationRequestFor-CB-Info.....identifier of [3] ModificationRequestFor-CB-Info DEFINED in MAP-MS-DataTypes 2361 ModificationRequestFor-CB-Info.....type reference SEQUENCE DEFINED in MAP-MS-DataTypes : 2386 USED in MAP-MS-DataTypes modificationRequestFor-CF-Info.....identifier of [2] ModificationRequestFor-CF-Info DEFINED in MAP-MS-DataTypes : 2360 ModificationRequestFor-CF-Info.....type reference SEQUENCE DEFINED in MAP-MS-DataTypes : 2375 USED in MAP-MS-DataTypes modificationRequestFor-CSI.....identifier of [4] ModificationRequestFor-CSI DEFINED in MAP-MS-DataTypes : 2362 ModificationRequestFor-CSI.....type reference SEQUENCE DEFINED in MAP-MS-DataTypes : 2402 USED in MAP-MS-DataTypes modificationRequestFor-ODB-data.....identifier of [7] ModificationRequestFor-ODB-data DEFINED in MAP-MS-DataTypes ModificationRequestFor-ODB-data.....type reference SEQUENCE DEFINED in MAP-MS-DataTypes : 2396 USED in MAP-MS-DataTypes : 2366 modifyCSI-State.....identifier of [2] ModificationInstruction DEFINED in MAP-MS-DataTypes : 2405 modifyNotificationToCSE.....identifier of [6] ModificationInstruction DEFINED in MAP-MS-DataTypes : 2382 modifyNotificationToCSE.....identifier of [5] ModificationInstruction DEFINED in MAP-MS-DataTypes : 2392 modifyNotificationToCSE.....identifier of [1] ModificationInstruction

DEFINED in MAP-MS-DataTypes	: 2398
<pre>modifyNotificationToCSE</pre> ModificationInstruction	identifier of [1]
DEFINED in MAP-MS-DataTypes	: 2404
MOLR-Class	type reference SEQUENCE
DEFINED in MAP-MS-DataTypes	: 1392
USED in MAP-MS-DataTypes	: 1388
molr-List	identifier of [2] MOLR-List
DEFINED in MAP-MS-DataTypes	: 885
MOLR-List	type reference SEQUENCE OF
DEFINED in MAP-MS-DataTypes	: 1387
USED in MAP-MS-DataTypes	: 885
monitoringMode	identifier of [0] MonitoringMode
DEFINED in MAP-CH-DataTypes	: 353
MonitoringMode	
DEFINED in MAP-CH-DataTypes	
USED in MAP-CH-DataTypes	: 353
moreMessagesToSend	
DEFINED in MAP-SM-DataTypes	: 122
moveLeg	identifier of Named Number, 2
DEFINED in MAP-MS-DataTypes	: 1741
mo-ForwardSM	information object reference
OPERATION, Information Object	

12-06	TAG R6.15		Reference	Listing	for MAI	P-Protoc	ol		2006-
	USED	in MAP-Pr	ortMessageS otocol ortMessageS	:	91	133			
	MO-Forwards	SM-Arg			type		e SEQUE	NCE	
	USED	in MAP-Sh	ortMessages -DataTypes	Servic :	48	82			
	USED	in MAP-SM in MAP-Sh		: Servic :	113 49	84	e SEQUE	NCE	
	mo-lr DEFINED		S-DataTypes			ifier of	Named	Number,	2
	mo-mtCall DEFINED		 -DataTypes			ifier of	Named	Number,	0
	mo-mt-sms		 -DataTypes			ifier of	Named	Number,	1
	mo-mt-sms		 -DataTypes			ifier of	Named	Number,	1
	mo-sms-CSI. DEFINED		 -DataTypes			ifier of	[1] SM	S-CSI	
	mo-sms-csi. DEFINED		 -DataTypes			ifier of	Named	Number,	5
	mo-sms-CSI. DEFINED		 -DataTypes			ifier of	[6] SM	S-CSI	
	mo-sms-CSI. DEFINED	in MAP-MS	 -DataTypes	:	ident: 2294	ifier of	Named	Number,	5
	mo-sms-CSI. DEFINED		 -DataTypes			ifier of	[10] S	MS-CSI	
	msAvailable DEFINED		S-DataTypes			ifier of	Named	Number,	0
Addres	msc-Number. sString					ifier of	[1] IS	DN-	
	msc-Number.				ident:	ifier of	ISDN-A	ddressSt	ring
Addres	msc-Number. sString					ifier of	[6] IS	DN-	
	DEFINED msc-Number.		-DataTypes			ifier of	[1] IS	DN-	
Addres	sString DEFINED	in MAP-CH	-DataTypes	:	221				

msc-Number AddressString			.identif	ier of	[0]	ISDN-
2	in MAP-SM-DataTypes	:	97			
	in MAP-OM-DataTypes			ier of	Name	ed Number, 0
DEFINED	tList in MAP-OM-DataTypes in MAP-OM-DataTypes	:	150		e BI	I STRING
	tList			ier of	[8]	MSC-S-EventList
DEFINED	in MAP-OM-DataTypes	:	188			
MSC-S-Inter	rfaceList		.type re	ference	BI'	r string
DEFINED	in MAP-OM-DataTypes	:	95			
USED	in MAP-OM-DataTypes	:	87	187		
msc-s-Inter	rfaceList		.identif	ier of	[7]	MSC-S-
DEFINED	in MAP-OM-DataTypes	:	187			
msc-s-List InterfaceList			.identif	ier of	[0]	MSC-S-
DEFINED	in MAP-OM-DataTypes	:	87			
	in MAP-OM-DataTypes			ier of	[0]	MSC-S-EventList

12-06	TAG R6.3			Reference	Listing	for MA	AP-Pro	toco	ol	2	006-
				DataTypes				of	[0]	TraceDepth	
				DataTypes				of	[6]	TraceDepth	
Addres	msisdn sString					ident	cifier	of	[1]	ISDN-	
	DEFINE) in N	MAP-MS-	-DataTypes	:	1063	3				
Addres	msisdn sString							of	[2]	ISDN-	
	DEFINEI) in N	MAP-MS-	-DataTypes	:	2042	2				
				DataTypes				of	ISDI	N-AddressStr	ing
	msisdn					ident	cifier	of	[2]	ISDN-	
Addres	sString DEFINEI) in N	MAP-MS-	-DataTypes	:	2441	L				
7 ddrog	msisdn					ident	cifier	of	[1]	ISDN-	
Addres	sString DEFINEI) in N	MAP-Con	nmonDataTy	pes :	389	9				
Addross	msisdn sString					ident	cifier	of	[0]	ISDN-	
Addies		o in N	MAP-CH-	-DataTypes	:	92	2				
Addres	msisdn sString					ident	ifier	of	[12]	ISDN-	
	_	o in N	MAP-CH-	-DataTypes	:	166	5				
Addres	msisdn sString					ident	ifier	of	[2]	ISDN-	
	DEFINE) in N	MAP-CH-	-DataTypes	:	222	2				
Addres	msisdn sString							of	[9]	ISDN-	
	DEFINE) in N	MAP-CH-	-DataTypes	:	258	3				
Addres	msisdn sString							of	[0]	ISDN-	
	DEFINE) in N	MAP-SS-	-DataTypes	:	225	5				
Addres	msisdn sString							of	[1]	ISDN-	
	DEFINE) in N	MAP-SS-	-DataTypes	:	270)				
Addres	msisdn sString							of	[0]	ISDN-	
	DEFINE) in N	MAP-SM-	-DataTypes	:	54	1				
Addres	msisdn sString							of	[2]	ISDN-	
	DEFINE) in N	MAP-SM-	-DataTypes	:	138	3				
				 DataTypes				of	ISDI	N-AddressStr	ing

	msisdn DEFINED in MAP-SM-DataTypes			f ISD1	N-AddressString
Addres	msisdnssString	id	entifier o	f [3]	ISDN-
Addica	DEFINED in MAP-LCS-DataTypes	:	109		
	msisdn DEFINED in MAP-LCS-DataTypes		entifier o 205	f Name	ed Number, 2
Addres	msisdnssString	id	entifier o	f [0]	ISDN-
	DEFINED in MAP-LCS-DataTypes	:	467		
MSNetw	mSNetworkCapabilityvorkCapability	id	entifier o	f [0]	
	DEFINED in MAP-MS-DataTypes	: 2	072		
	MSNetworkCapability DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes	: 2	076	ce OC'	TET STRING
	msNotReachable DEFINED in MAP-MS-DataTypes			f NULI	Ĺ
	msPurged			f Name	ed Number, 0
	DEFINED in MAP-MS-DataTypes	: 2	235		
MSRadi	mSRadioAccessCapability	id	entifier o	f [1]	
	DEFINED in MAP-MS-DataTypes	: 2	073		
	MSRadioAccessCapability DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes	: 2	080	ce OC	TET STRING
	msrn DEFINED in MAP-CH-DataTypes			f ISDì	N-AddressString

12.06	TAG R6.1			Reference	Listir	ıg	for	MAP-	-Prot	oco	1		2006-
12-06	09:33:23	PAGI	년 /U										
	ms-classma:								fier	of	[5]	NULL	
	DEFINED	in	MAP-MS	-DataTypes		:	20	92					
	ms-Classma:	rl- O					i do	n+i1	Fior	of	[6]	MC_Clago	mark?
				 -DataTypes					гтет	OI	[0]	MS-CIASS	SIIIalkz
	221 11122		1111 110	Bacarypes		•	20	, _ ,					
	MS-Classma								efere	ence	OCT	ET STRIN	IG
				-DataTypes									
	USED	in	MAP-MS	-DataTypes		:	1	.00	2029)			
	ms-Present						ide	ntii	fier	of	Name	d Number	· 0
				-DataTypes						O.L	1101110	a maniber	., •
	mt-Forward					.in	form	natio	on ok	ojec	t re	ference	
OPERAT	ION, Inform				a '			0.0					
				ortMessage otocol				93	133	,			
				ortMessage				92 15	133)			
	0020		1111 011	or chessage		•							
	MT-Forward							e re	efere	ence	SEQ	UENCE	
				-DataTypes			1	.18					
				ortMessage				50	95	5			
	USED	in	MAP-SM	-DataTypes		:		18					
	MT-Forward	CM_I	Pag				tvr	ne re	sfore	nce	SEC	TIENCE	
				-DataTypes						.1100	рцо	OLIVEL	
				ortMessage					97	7			
				-DataTypes									
	mt-lrResta:								fier	of	Name	d Number	c, 4
	DELINED	ın	MAP-LC:	S-DataType	S	:	5	527					
	MT-smsCAME	LTD:	P-Crite:	ria			.tvp	e re	efere	ence	SEC	UENCE	
	DEFINED	in	MAP-MS	-DataTypes		:	15	808					
	USED	in	MAP-MS	-DataTypes		:	15	06					
	CAND		D				2.3.		c	۔ د	[4]	MIII C7	MUI III D
Criter	mt-smsCAME	וחדח	P-Crice.	гташтят			. rae	SIICTI	Lier	OL	[4]	MT-SIISCA	MELIDP-
CIICCI		in	MAP-MS	-DataTypes		:	9	945					
	mt-smsCAME			riaList			.ide	entif	fier	of	[11]	MT-	
smsCAM	ELTDP-Crite			Do +			1 -						
	DELINED	ın	MAP-MS	-DataTypes		:	15	02					
	MT-smsCAME	LTDI	P-Crite:	riaList			.tvp	e re	efere	ence	SEC	UENCE OF	י
				-DataTypes							~ - 2		
				-DataTypes					1502	2	348		
~~.	mt-smsCAME			riaList			.ide	entif	fier	of	[16]	MT-	
SMSCAM	ELTDP-Crite			DataTroog			2.2	10					
	NELINED	Т11	MAP-MS	-DataTypes		:	∠3	40					
	mt-sms-CSI						.ide	entif	fier	of	[3]	SMS-CSI	
				-DataTypes				44					
												_	
	mt-sms-csi								tier	of	Name	d Number	î , 9
	DEFINED	ın	MAP-MS	-DataTypes		:	14	54					
	mt-sms-CSI						.ide	ntii	fier	οf	[10]	SMS-CST	
	55 CD1									-	[_ 0]	2.10 001	-

DEFINED in MAP-MS-DataTypes	: 1501
mt-sms-csi	
mt-sms-CSI	
mt-sms-CSI	
MT-SMS-TPDU-Type DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes	: 1519
<pre>multicallBearerInfo MulticallBearerInfo</pre>	
MulticallBearerInfo DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes	: 728
multipleBearerNotSupported DEFINED in MAP-MS-DataTypes	
multipleBearerRequested	identifier of [3] NULL

12-06	TAG R6.15		Reference	Listing	for MAP	-Protoco	1		2006-
	DEFINED	in MAP-MS	-DataTypes	:	543				
	multipleEC' DEFINED		 -DataTypes			fier of	Named	Number,	14
	multipleTin DEFINED		 S-DataType:			fier of	Named	Number,	1
'01010	multiPTY				value	referenc	e SS-C	ode,	
.01010		in MAP-SS	-Code	:	90				
	mw-Status. DEFINED		 -DataTypes			fier of	MW-Sta	tus	
	MW-Status. DEFINED USED	in MAP-SM	 -DataTypes -DataTypes	:	192	eference	BIT S	TRING	
	m-csi				identi	fier of	Named	Number	6
			-DataTypes			1101 01	210111100	1102027	· ·
	m-CSI DEFINED		 -DataTypes			fier of	[5] M-	CSI	
	M-CSI		 -DataTypes			eference	SEQUE	NCE	
	USED	in MAP-MS	-DataTypes	:	1496	2343			
	m-CSI DEFINED		 -DataTypes			fier of	Named	Number,	7
	m-CSI DEFINED		 -DataTypes			fier of	[12] M	-CSI	
	NAEA-CIC DEFINED	in MAP-Co	mmonDataTy	oes :	380		OCTET	STRING	
	USED	in MAP-Co	mmonDataTy	pes :	41	376			
Prefer	naea-Prefe: redCI	rredCI			identi	fier of	[15] N	AEA-	
	DEFINED	in MAP-MS	-DataTypes	:	849				
	NAEA-Prefe					eference	SEQUE	NCE	
			mmonDataTy	pes :	375 107	0.4.0			
	LIGED	in MAP-MS	-DataTypes mmonDataTy _l	:	187	849			
			-DataTypes		71	163			
Prefer	naea-Prefe: redCI	rredCI			identi	fier of	[10] N	AEA-	
	DEFINED	in MAP-CH	-DataTypes	:	163				
	naea-Prefe DEFINED		 mmonDataTyp			fier of	[0] NA	EA-CIC	
	nameString DEFINED		 S-DataType:			fier of	[2] Na	meString	3
	NameString				type r	eference	USSD-	String	

	in MAP-LCS-DataTypes in MAP-LCS-DataTypes					
_		v	alue refer	cenc	e Lo	CSServiceTypeID,
8 DEFINED :	in MAP-CommonDataTypes	:	419			
na-ESRD AddressString		i	dentifier	of	[3]	ISDN-
-	in MAP-LCS-DataTypes	:	470			
na-ESRD AddressString		i	dentifier	of	[1]	ISDN-
J	in MAP-LCS-DataTypes	:	543			
na-ESRK AddressString		i	dentifier	of	[4]	ISDN-
	in MAP-LCS-DataTypes	:	471			
na-ESRK AddressString		i	dentifier	of	[0]	ISDN-
-	in MAP-LCS-DataTypes	:	542			
-	ıest in MAP-ExtensionDataType			of	[0]	NULL
	in MAP-CommonDataTypes			of	[2]	MaxMC-Bearers
nbrSB		i	dentifier	of	[3]	MaxMC-Bearers

12-06	TAG R6.1			Reference	e Listi	ing f	or MAP-	-Proto	col	2006
	DEFINED	in I	MAP-SS-	-DataTypes	5	:	196			
				 -DataTypes				fier o	£ [5]	MC-Bearers
				mmonDataTy				fier o	E [3]	MC-Bearers
				 -DataTypes				fier o	E [8]	MC-Bearers
				DataTypes				fier o	E [5]	MC-Bearers
				-DataTypes				fier o	f [4]	MC-Bearers
				-DataTypes				fier o	f Nam	ed Number, 1
	neededLcsCo DEFINED			otSupporte -DataTypes				fier o	f [1]	NULL
ERROR,	negativePW Information DEFINED	n Ob	ject			 :		ation (objec	t reference
	USED	in I	MAP-Sur MAP-Eri	pplementar	ryServi	i :	47	141	161	238
				 -DataTypes				fier o	f Not	ReachableReason
				 -DataTypes				fier o	f Not	ReachableReason
Networ	networkAcc kAccessMode	essMo	ode				identii	Eier o	E [24]
	DEFINED	in I	MAP-MS-	-DataTypes	5	:	854			
		in I	MAP-MS-	DataTypes DataTypes	5	:	901	eferen	ce EN	UMERATED
				ricted -DataTypes				fier o	f Nam	ed Number, 0
Addres	networkNod sString							fier o	f [1]	ISDN-
				-DataTypes			85			
				S-DataType				fier o	E ISD	N-AddressString
	NetworkRes			 mmonDataTy				eferen	ce EN	UMERATED
	USED	in I	MAP-Cor	mmonDataTy -DataTypes	pes	:	38	169	176	
	networkRes	ourc	e				identii			workResource

networkResourceidentifier DEFINED in MAP-ER-DataTypes : 176	of	NetworkResource
networkSignalInfoidentifier ExternalSignalInfo	of	[10]
DEFINED in MAP-CH-DataTypes : 102		
networkSignalInfoidentifierExternalSignalInfo	of	[6]
DEFINED in MAP-CH-DataTypes : 225		
networkSignalInfoidentifierExternalSignalInfo	of	[4]
DEFINED in MAP-SS-DataTypes : 314		
networkSignalInfo2identifier ExternalSignalInfo	of	[26]
DEFINED in MAP-CH-DataTypes : 119		
newidentifier DEFINED in MAP-MS-DataTypes : 532	of	Named Number, 1
newPasswordsMismatchidentifier DEFINED in MAP-ER-DataTypes : 137	of	Named Number, 2
noAdditionalInformationidentifier DEFINED in MAP-ER-DataTypes : 347	of	Named Number, 0

12-06	TAG R6.15 Cross Reference Listi 09:33:23 PAGE 73	ng	for MAP-1	Protoco	ol		2006-
	noCUG-Restrictions			ier of	Named N	umber,	0
	NoGroupCallNbParam			ference	e SEQUEN	CE	
	DEFINED in MAP-ER-DataTypes						
	USED in MAP-Errors			459			
	USED in MAP-ER-DataTypes	:	45				
ERROR,	noGroupCallNumberAvailable Information Object		.informat	tion ob	oject re	ference	2
	DEFINED in MAP-Errors	:	457				
	USED in MAP-Group-Call-Operati			51			
	USED in MAP-Errors	:	83	31			
		•	03				
ERROR,	noHandoverNumberAvailable Information Object		.informat	tion ol	oject re	ference	2
	DEFINED in MAP-Errors	:	263				
	USED in MAP-MobileServiceOpera	•	89	323			
	USED in MAP-Errors	:	36	323			
		•	30				
	noPageResponse DEFINED in MAP-ER-DataTypes	· · ·	.identif: 252	ier of	Named Nu	umber,	2
	noReply		idontif	ior of	Named Na	ımhor	2
				Ter Or	Named N	unber,	4
	DEFINED in MAP-CH-DataTypes	:	135				
NoRepC	noReplyConditionTime		.identif:	ier of	[7] Ext	_	
	DEFINED in MAP-MS-DataTypes	:	1179				
NoRepC	noReplyConditionTime		.identif:	ier of	[5] Ext	_	
-	DEFINED in MAP-MS-DataTypes	:	2381				
N - D 1	noReplyConditionTime		.identif:	ier of	[5]		
иокерт	yConditionTime DEFINED in MAP-SS-DataTypes	:	76				
	NoReplyConditionTime		.type re:	ference	e INTEGE	R	
	DEFINED in MAP-SS-DataTypes	:	82				
	USED in MAP-SS-DataTypes	:	30	76	104		
	no Don Jugon di bi on Mino		1 a	e	[-]		
N - D 1	noReplyConditionTime		.ldentii	ier oi	[/]		
иокерт	yConditionTime		104				
	DEFINED in MAP-SS-DataTypes	:	104				
	n a D a gra ara g a Haram Da ga a M C				Named N.		2
	noResponseFromBusyMS			ier oi	Named Ni	umber,	3
	DEFINED in MAP-CH-DataTypes	:	399				
	noResponseFromFreeMS DEFINED in MAP-CH-DataTypes			ier of	Named Nu	umber,	2
	n o zemo l		4 4	ion -f	Named 3	ımb əss	0
	normal DEFINED in MAP-LCS-DataTypes			ler oi	Named Ni	umber,	0
	No Do om in ortio Do		.	E		an.	
	NoRoamingNbParam			Lerence	SEQUENO	СĽ	
	DEFINED in MAP-ER-DataTypes						
	USED in MAP-Errors			287			
	USED in MAP-ER-DataTypes	:	33				

	noRoamingNumberAvailable		.informat	ion	object	refer	rence
ERROR,	Information Object						
	DEFINED in MAP-Errors	:	285				
	USED in MAP-CallHandlingOperat			115			
	USED in MAP-Errors	:	45				
	noSM-RP-DA		idontifi	or c	ر ا ا ا	NITIT T	
	DEFINED in MAP-SM-DataTypes			.er c)T [3]	ИОПП	
	noSM-RP-OA		.identifi	er c	f [5]	NULL	
	DEFINED in MAP-SM-DataTypes	:	140				
	noSubscriberReply		informat	ion	object	refer	rence
ERROR	Information Object	• • •	· IIII OI ma			. 10101	. 01100
шиноп,	DEFINED in MAP-Errors		3.04				
	USED in MAP-CallHandlingOperat			96			
	USED in MAP-Errors			50			
		•	1,				
	NoSubscriberReplyParam		.type ref	eren	ce SEQ	UENCE	
	DEFINED in MAP-ER-DataTypes						
	USED in MAP-Errors			306			
	USED in MAP-ER-DataTypes	:	36				
	notAllowed		idontifi	0.70	f Nome	d Numb	
				er c) I Name	a Nullib	ber, 4
	DEFINED in MAP-LCS-DataTypes	:	278				
	noteMM-Event	.in	formation	ı obj	ect re	eferenc	ce
OPERAT	ION, Information Object						
	DEFINED in MAP-MobileServiceOpera						
	USED in MAP-Protocol	:	41	127			
	USED in MAP-MobileServiceOpera	:	70				

2006-

TAG R6.15 Cross Reference Listing for MAP-Protocol

```
12-06 09:33:23 PAGE 74
      NoteMM-EventArg.....type reference SEQUENCE
        DEFINED in MAP-MS-DataTypes : 2437
           USED in MAP-MobileServiceOpera : 158 497
USED in MAP-MS-DataTypes : 142
      NoteMM-EventRes.....type reference SEQUENCE
        DEFINED in MAP-MS-DataTypes : 2450

USED in MAP-MS-DataTypes : 159 499

USED in MAP-MS-DataTypes : 143
      noteMsPresentForGprs.....information object reference
OPERATION, Information Object
        DEFINED in MAP-MobileServiceOpera: 482
           USED in MAP-MobileServiceOpera : 40 127
      NoteMsPresentForGprsArg.....type reference SEQUENCE
        DEFINED in MAP-MS-DataTypes : 1947
USED in MAP-MobileServiceOpera : 156
           USED in MAP-MS-DataTypes
      NoteMsPresentForGprsRes.....type reference SEQUENCE
         DEFINED in MAP-MS-DataTypes : 1954
           USED in MAP-MobileServiceOpera : 157
           USED in MAP-MS-DataTypes :
      noteSubscriberDataModified.....information object reference
OPERATION, Information Object
        DEFINED in MAP-MobileServiceOpera : 300
           USED in MAP-Protocol : 42 128 USED in MAP-MobileServiceOpera : 34
      {\tt NoteSubscriberDataModifiedArg.....type\ reference\ SEQUENCE}
        DEFINED in MAP-MS-DataTypes : 2420
           USED in MAP-MobileServiceOpera : 148
           USED in MAP-MS-DataTypes
                                       :
      NoteSubscriberDataModifiedRes.....type reference SEQUENCE
         DEFINED in MAP-MS-DataTypes : 2431
           USED in MAP-MobileServiceOpera : 149 304
           USED in MAP-MS-DataTypes :
                                           127
      notForwarded......identifier of Named Number, 1
        DEFINED in MAP-MS-DataTypes
      notificationToCSE......identifier of [3] NULL
        DEFINED in MAP-MS-DataTypes
                                           953
      notificationToCSE.....identifier of [3] NULL
        DEFINED in MAP-MS-DataTypes
      notificationToCSE.....identifier of [0] NULL
         DEFINED in MAP-MS-DataTypes
                                     : 1564
      notificationToCSE.....identifier of [1] NULL
        DEFINED in MAP-MS-DataTypes
      notificationToCSE.....identifier of [3] NULL
         DEFINED in MAP-MS-DataTypes : 1767
```

notificationToCSEidentifier DEFINED in MAP-MS-DataTypes : 1827	of	[2] NULL
notificationToCSEidentifier DEFINED in MAP-MS-DataTypes : 1838	of	[2] NULL
notificationToCSEidentifier DEFINED in MAP-MS-DataTypes : 1882	of	[1] NULL
notificationToCSEidentifier DEFINED in MAP-MS-DataTypes : 2310	of	NULL
notificationToCSEidentifier DEFINED in MAP-MS-DataTypes : 2318	of	NULL
notificationToCSEidentifier DEFINED in MAP-MS-DataTypes : 2326	of	NULL
notificationToCSEidentifier DEFINED in MAP-MS-DataTypes : 2462	of	[2] NULL
notificationToCSEidentifier DEFINED in MAP-MS-DataTypes : 2471	of	[4] NULL

12-06	TAG R6.15 09:33:23 PAGE		e Listing	for MAP-Protocol	2006-
Notific	cationToMSUser	MSUser		identifier of [0]	
Notific	cationToMSUser	MAP-MS-DataTypes		identifier of [1]	
				type reference ENUMERATED	
	DEFINED in	MAP-MS-DataTypes	:	1363	
	USED in	MAP-MS-DataTypes	:	86 1307 1349 1381	
Notific	cationToMSUser			identifier of [1]	
	DEFINED in	MAP-MS-DataTypes	·	1381	
		Ty-LocationAllower MAP-MS-DataTypes		poidentifier of Named Number, 1365	1
		Ty-LocationNotAl MAP-MS-DataType:		Reidentifier of Named Number, 1366	2
		nAllowed MAP-MS-DataType:		identifier of Named Number, 1364	0
	notKnownToBePc DEFINED in	orted MAP-MS-DataType:		identifier of Named Number, 2054	0
		omSGSN MAP-MS-DataTypes		identifier of [0] NULL 2177	
		omVLR MAP-MS-DataTypes		identifier of [2] NULL 2174	
	notReachable DEFINED in	MAP-CH-DataTypes		identifier of Named Number, 133	0
				type reference ENUMERATED	
		MAP-MS-DataTypes MAP-MS-DataTypes			
				identifier of Named Number,	2
		MAP-MS-DataTypes			3
	npdbMismatch DEFINED in	MAP-ER-DataTypes		identifier of Named Number, 208	2
	nplr	MAP-CommonDataTy		identifier of Named Number,	4
	nsapi			identifier of [6] NSAPI	
	DEFINED in	MAP-MS-DataTypes	:	type reference INTEGER 2216 2195	
ERROR,	numberChanged. Information Ob			information object reference	Э

DEFINED in MAP-Errors : 207 USED in MAP-CallHandlingOperat: 36 91
USED in MAP-Errors: 23 NumberChangedParam.....type reference SEQUENCE DEFINED in MAP-ER-DataTypes : 212
USED in MAP-Errors : 114
USED in MAP-ER-DataTypes : 26 209 NumberOfForwarding.....type reference INTEGER DEFINED in MAP-CH-DataTypes : 89
USED in MAP-CH-DataTypes : 20 numberOfForwarding.....identifier of [2] NumberOfForwarding DEFINED in MAP-CH-DataTypes numberOfPW-AttemptsViolation.....information object reference

ERROR, Information Object : 415 DEFINED in MAP-Errors

USED in MAP-SupplementaryServi : 48 142 162 239

USED in MAP-Errors 72

numberOfRequestedVectors.....identifier of

NumberOfRequestedVectors

DEFINED in MAP-MS-DataTypes

numberOfRequestedVectors.....identifier of

NumberOfRequestedVectors

DEFINED in MAP-MS-DataTypes : 767

12-06	TAG R6.			Reference	Listing	for MAI	P-Protocol	2006-
	DEFINE	Din	MAP-MS	tors -DataTypes -DataTypes	:	786		INTEGER
Number	numberPor Portabilit			tus		identi	ifier of	[3]
TVallib CT				-DataTypes	:	2043		
	DEFINE	D in	MAP-MS	tus -DataTypes -DataTypes	:	2053		ENUMERATED
	USE	D in	MAP-CH-	-DataTypes	:	50	167	
Number	Portabilit	yStat	us	us			ifier of	[13]
							ifier of	[1] OccurrenceInfo
	DEFINE	D in	MAP-LCS	S-DataType:	s :	286		
							reference	ENUMERATED
				S-DataType:				
				S-DataType:				
				D-+			ifier of	[2] NULL
	DELINE	D in	MAP-MS-	-DataTypes	:	2278		
				 -DataTypes			ifier of	[8] ODB-Data
				 -DataTypes				SEQUENCE
				-DataTypes				325 2397
				 -DataTypes			ifier of (DDB-Data
	odb-data.					identi	ifier of	[0] ODB-Data
	DEFINE	Din	MAP-MS-	-DataTypes	:	2397		
				 -DataTypes			ifier of (ODB-GeneralData
			1111 110	DataTypes	•	1000		
	ODB-Gener	alDat	a			type n	reference	BIT STRING
	DEFINE	Din	MAP-MS-	-DataTypes	•	1104		
	USE	D in	MAP-MS	-DataTypes	:	1099	1410	
	odb-Gener	alDat	а			identi	ifier of	[4] ODB-GeneralData
				-DataTypes				[1] 022 001101012000
							ifier of (ODB-HPLMN-Data
	DEFINE	D in	MAP-MS	-DataTypes	:	1100		
	ODB-HPLMN	-Data				type 1	reference	BIT STRING
	DEFINE	D in	MAP-MS-	-DataTypes	:	1140		
	USE	D in	MAP-MS	-DataTypes	:	1100		
				 -DataTypes			ifier of	[3] ODB-Info

ODB-Info.....type reference SEQUENCE DEFINED in MAP-MS-DataTypes : 2324
USED in MAP-MS-DataTypes : 2267 2373 2425 odb-Info.....identifier of [3] ODB-Info DEFINED in MAP-MS-DataTypes 2373 odb-Info.....identifier of [2] ODB-Info 2425 DEFINED in MAP-MS-DataTypes offeredCamel4CSIs.....identifier of [6] OfferedCamel4CSIs DEFINED in MAP-MS-DataTypes offeredCamel4CSIs.....identifier of [6] OfferedCamel4CSIs DEFINED in MAP-MS-DataTypes offeredCamel4CSIs.....identifier of [8] OfferedCamel4CSIs DEFINED in MAP-MS-DataTypes OfferedCamel4CSIs.....type reference BIT STRING DEFINED in MAP-MS-DataTypes : 1725 USED in MAP-MS-DataTypes : 78 78 244 462 1415 2273 2274 USED in MAP-CH-DataTypes : 41 170 240 289

12-06		R6.1			Reference	Listin	ng f	or MAF	-Prot	cocc	ol.		2006-
Offere	dCame	14CSIs							fier	of	[0]		
					-DataTypes								
Offere	dCame	14CSIs			nterrogati				fier	of	[20]		
	D	EFINED	in 1	MAP-CH	-DataTypes		:	240					
Offere		redCam	el4C	SIsInS(GSN			identi	fier	of	[9]		
			in 1	MAP-MS	-DataTypes		:	2274					
			el4C	SIsInVl	LR			identi	fier	of	[8]		
Offere		14CSIs EFINED	in 1	MAP-MS	-DataTypes		:	2273					
			el4C	SIsInV	MSC			identi	fier	of	[16]		
Offere		14CSIs EFINED	in 1	MAP-CH-	-DataTypes		:	170					
	Offe	redCam	el4Fi	unction	nalities			type r	refere	ence	BTT :	STRING	1
					-DataTypes				CICIC	21100		JIMI	•
					-DataTypes				2447	7			
					nalities			identi	fier	of	[8]		
Offere		14Func			s -DataTypes			2447					
					 -DataTypes				fier.	of	Named	Numbe	er, 0
									fier	of	[3] A	ddress	String
	D	EFINED	in 1	MAP-OM-	-DataTypes		:	40					
					 S-DataType			identi 329	fier	of	Named	Numbe	er, 0
					 -DataTypes			identi 903	fier	of	Named	Numbe	er, 1
					 -DataTypes				fier	of	Named	Numbe	er, 2
refere								inform	natior	ı ok	oject (class	
			in 1	Remote	-Operation	s-Info	:	13					
		USED	in 1	MAP-Pro	otocol		:	12	121	L			
					-Operation			56	57		58		0.05
219	233	USED 245	in 1 260		bileServic	eOpera	:	75	171	L	184	195	207
339	344	358	376					278	300)	314	327	334
								390	403	3	415	429	434
437	451	467	482					495					
		USED	in 1	MAP-Ope	erationAnd	Mainte	:	19	51	L	66	80	
					llHandling			25	78		102	118	131
146	159	173	187					201					

201

													-	
165	181	USED	in 213	MAP-Su	ppleme	ntarys	Servi	:	29	88	106	124	145	
		-71		_					226	244	251	263	281	
125	135	USED 140	in	MAP-Sh	ortMes	sageSe	ervic	:	23	64	80	93	112	
				MAP-Gr	-	_			20			62	67	
		USED	in	MAP-Lo	cation	Servi	ce0pe	:	19	53	68	87		
refere		RATION-I	PACI	KAGE					informa	tion c	bject	class		
101010		DEFINED	in	Remote	-Opera	tions-	-Info	:	55					
	_	ratorBaı DEFINED		_						ier of	Name	d Numbe	er, 1	
	_	ratorDet DEFINED			_					ier of	Name	d Numbe	er, 1	
		ratorDet DEFINED								ier of	Name	d Numbe	er, 3	
		otSuppoi DEFINED								ier of	[16]	NULL		
		Capabil: DEFINED								ier of	[5]	OR-Phas	se	
		Interact DEFINED								ier of	Name	d Numbe	er, 12	
		Interroo								ier of	[4]]	NULL		
		Interroo DEFINED								ier of	[10]	NULL		

12-06	TAG R6.15 Cross Reference List 09:33:23 PAGE 78	ing	for MAP-Protocol 2006-
ERROR,	or-NotAllowed		-
			334
	USED in MAP-CallHandlingOpera	it:	34 89 113 126
	USED in MAP-Errors	:	44
	OR-NotAllowedParam		
	DEFINED in MAP-ER-DataTypes	:	195
	USED in MAP-Errors	:	123 336
	USED in MAP-ER-DataTypes	:	24
	OP Phago		type reference INTECED
	OR-Phase DEFINED in MAP-CH-DataTypes		
	USED in MAP-CH-DataTypes		
	USED III MAP-CH-Datalypes	:	91
Overri	overrideCategorydeCategory		identifier of [1]
	DEFINED in MAP-SS-DataTypes	:	172
	OverrideCategory		
	DEFINED in MAP-SS-DataTypes	:	179
	USED in MAP-SS-DataTypes	:	28 172
	overrideDisabled		
	DEFINED in MAP-SS-DataTypes	:	181
	overrideEnabled		
	DEFINED in MAP-SS-DataTypes	:	180
			12 .151
	ownNumberNotPortedOut		
	DEFINED in MAP-MS-DataTypes	:	2058
	ownNumberPortedOut		identifies of Named Number 1
	DEFINED in MAP-MS-DataTypes	:	2055
	o-andM-HDI MN		identifier of Named Number 1
	o-andM-HPLMNDEFINED in MAP-CommonDataTypes		
	DEFINED IN MAP-COMMONDACATYPES	•	399
	o-andM-VPLMN		identifier of Named Number 2
	DEFINED in MAP-CommonDataTypes		
	DHI INID III MAI COMMONDACATYPES	•	400
	O-BcsmCamelTDPCriteriaList		type reference SEQUENCE OF
	DEFINED in MAP-MS-DataTypes		
	USED in MAP-MS-DataTypes		
	USED in MAP-CH-DataTypes		
	7.		
	o-BcsmCamelTDPCriteriaList		identifier of [13] O-
BcsmCa	melTDPCriteriaList		
	DEFINED in MAP-CH-DataTypes	:	263
	O-BcsmCamelTDPData		
	DEFINED in MAP-MS-DataTypes		
	USED in MAP-MS-DataTypes	:	1601
	o-BcsmCamelTDPDataList		identifier of O-
BcsmCa	melTDPDataList		
	DEFINED in MAP-MS-DataTypes	:	1590
	O-BcsmCamelTDPDataList		
	DEFINED in MAP-MS-DataTypes	:	1600

USED in MAP-MS-DataTypes	: 1590
O-BcsmCamelTDP-Criteria DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes	: 1638
o-BcsmCamelTDP-CriteriaList BcsmCamelTDPCriteriaList	identifier of [4] O-
DEFINED in MAP-MS-DataTypes	: 1494
o-BcsmCamelTDP-CriteriaList BcsmCamelTDPCriteriaList	identifier of [1] O-
DEFINED in MAP-MS-DataTypes	: 2332
o-BcsmCamelTDP-CriteriaList BcsmCamelTDPCriteriaList	identifier of [3] O-
DEFINED in MAP-CH-DataTypes	: 306
o-BcsmTriggerDetectionPoint BcsmTriggerDetectionPoint	identifier of O-
DEFINED in MAP-MS-DataTypes	: 1610
O-BcsmTriggerDetectionPoint DEFINED in MAP-MS-DataTypes	type reference ENUMERATED : 1620
USED in MAP-MS-DataTypes	: 1610 1639
o-BcsmTriggerDetectionPoint BcsmTriggerDetectionPoint	identifier of O-
DEFINED in MAP-MS-DataTypes	: 1639
o-CauseValueCriteria CauseValueCriteria	identifier of [3] O-

12-06	TAG R6.15		Reference	Listing	for MAI	P-Protoco	1	2006-
	DEFINED	in MAP-MS	-DataTypes	:	1644			
	DEFINED	in MAP-MS	-DataTypes -DataTypes	:	1688	reference	SEQUENCE OF	
			 -DataTypes			ifier of	Named Number,	0
	o-CSI DEFINED		 -DataTypes			ifier of	[0] O-CSI	
	USED	in MAP-MS	-DataTypes -DataTypes -DataTypes	:	1589 68	1490 2	331 2350	
			 -DataTypes			ifier of	Named Number,	0
			 -DataTypes			ifier of	Named Number,	0
	o-CSI DEFINED		 -DataTypes			ifier of	[0] O-CSI	
	o-CSI DEFINED		 -DataTypes			ifier of	[5] O-CSI	
	o-CSI DEFINED		 -DataTypes			ifier of	[1] O-CSI	
BcsmCa	o-IM-BcsmCa melTDPCriter	riaList	iteriaList. -DataTypes			ifier of	[19] 0-	
	o-IM-CSI				identi	ifier of	Named Number,	11
			 -DataTypes			ifier of	Named Number,	2
	o-IM-CSI DEFINED		 -DataTypes			ifier of	[18] O-CSI	
Bearer	padAccessCA ServiceCode, DEFINED)'B		value	referenc	e	
Bearer	padAccessCA ServiceCode, DEFINED		1'B		value	referenc	ee	
Bearer	padAccessCA ServiceCode, DEFINED		О'В	:		referenc	e	
Bearer	padAccessCF ServiceCode, DEFINED		1'B	:		referenc	e	

<pre>padAccessCA-4800bps BearerServiceCode, '00100101'B</pre>		value	refere	nce	
DEFINED in MAP-BS-Code	:	71			
<pre>padAccessCA-9600bps BearerServiceCode, '00100110'B</pre>		value	refere	nce	
DEFINED in MAP-BS-Code	:	72			
password DEFINED in MAP-MS-DataTypes			lfier o	f Pass	sword
			e:	£ [2]	Daggerand
password DEFINED in MAP-MS-DataTypes			liler o	I [3]	Password
password			lfier o	f [2]	Password
DEFINED in MAP-MS-DataTypes	:	2469			
Password		type r	referen	.ce Nur	mericString
DEFINED in MAP-SS-DataTypes	:	243			
USED in MAP-SupplementaryServi	:	67	230	248	
USED in MAP-MS-DataTypes	:	153	2316	2390	2469
USED in MAP-SS-DataTypes	:	24			
pcs-Extensions			fier o	f [1]	PCS-Extensions
DEFINED in MAP-ExtensionDataTypes	:	33			
PCS-Extensions		type r	referen	.ce SE(QUENCE
DEFINED in MAP-ExtensionDataTypes	:	58			

12-06	TAG R6.15 Cross Reference Listing for MAP-Protocol 209:33:23 PAGE 80	2006-
	USED in MAP-ExtensionDataTypes : 33	
	pdpContextidentifier of Named Number, (DEFINED in MAP-OM-DataTypes : 163	0
	pdpContextidentifier of Named Number, (DEFINED in MAP-OM-DataTypes : 170	0
	pdpContextActivationidentifier of Named Number, 8 DEFINED in MAP-MS-DataTypes : 425	3
	pdpContextDeactivationidentifier of Named Number, 9 DEFINED in MAP-MS-DataTypes : 426	9
	pdp-Addressidentifier of [17] PDP-Addres DEFINED in MAP-MS-DataTypes : 917	ss
	PDP-Addresstype reference OCTET STRING	
	DEFINED in MAP-MS-DataTypes : 1003	
	USED in MAP-MS-DataTypes : 917 2192	
	pdp-Addressidentifier of [3] PDP-Address	-
	DEFINED in MAP-MS-DataTypes : 2192	5
Chargi	pdp-ChargingCharacteristicsidentifier of [1]	
	gCharacteristics DEFINED in MAP-MS-DataTypes : 924	
	PDP-Contexttype reference SEQUENCE	
	DEFINED in MAP-MS-DataTypes : 914	
	USED in MAP-MS-DataTypes : 910	
	pdp-ContextActiveidentifier of [1] NULL	
	DEFINED in MAP-MS-DataTypes : 2190	
	DEFINED III MAP-MS-Datalypes : 2190	
	pdp-ContextChangeOfPositionidentifier of Named Number, 1	1 /
	DEFINED in MAP-MS-DataTypes : 990	LT
	nde GententBeteblishment identifier of Newed Member 1	
	pdp-ContextEstablishmentidentifier of Named Number, 3 DEFINED in MAP-MS-DataTypes : 988	LΤ
	DEFINED in MAP-MS-DataTypes : 988	
	pdp-ContextEstablishmentAcknowledgement.identifier of Named Number, 3	12
	DEFINED in MAP-MS-DataTypes : 989	
	pdp-ContextIdidentifier of ContextId	
	DEFINED in MAP-MS-DataTypes : 915	
	pdp-ContextIdentifieridentifier of [0] ContextId	
	DEFINED in MAP-MS-DataTypes : 2189	
	PDP-ContextInfotype reference SEQUENCE	
	DEFINED in MAP-MS-DataTypes : 2188 USED in MAP-MS-DataTypes : 2186	
	PDP-ContextInfoListtype reference SEQUENCE OF	
	DEFINED in MAP-MS-DataTypes : 2185	
	USED in MAP-MS-DataTypes : 2181 2182	
	ndn Timo	
	pdp-Typeidentifier of [16] PDP-Type DEFINED in MAP-MS-DataTypes : 916	

	PDP-Type	type reference OCTET STRING
	DEFINED in MAP-MS-DataTypes	: 1000
	USED in MAP-MS-DataTypes	: 916 2191
	pdp-Type	
	DEFINED in MAP-MS-DataTypes	: 2191
	permanent	
	DEFINED in MAP-SS-DataTypes	: 175
	PermittedEncryptionAlgorithms	
	DEFINED in MAP-MS-DataTypes	
	USED in MAP-MS-DataTypes	: 504
	PermittedIntegrityProtectionAlgorith	
	DEFINED in MAP-MS-DataTypes	
	USED in MAP-MS-DataTypes	: 503
2	personTracking	value reference LCSServiceTypeID
	DEFINED in MAP-CommonDataTypes	: 413
	phase1	identifier of Named Number, 0

12-06	TAG R6.15		Reference	Listing	for MAP-Pr	rotocol		2006-
	DEFINED	in MAP-MS	-DataTypes	:	1718			
	phase2 DEFINED		 -DataTypes			er of Nam	ed Number,	1
	phase3 DEFINED		 -DataTypes			er of Nam	ed Number,	2
	phase4 DEFINED		 -DataTypes			er of Nam	ed Number,	3
	playTone DEFINED		 -DataTypes			er of Nam	ed Number,	6
	plmn DEFINED		 mmonDataTyr			er of Nam	ed Number,	0
	plmnClientl DEFINED	List in MAP-MS	 -DataTypes	:	identifie 1317	er of [2]	PLMNClien	tList
		in MAP-MS	 -DataTypes -DataTypes	:	1336	erence SE	QUENCE OF	
	plmnId DEFINED		 S-DataTypes			er of Nam	ed Number,	1
'10110:	plmnoperato	or			value ref	erence S	S-Code,	
	DEFINED	in MAP-SS	-Code	:	168			
	plmnOperato DEFINED		 S-DataTypes			er of Nam	ed Number,	2
	plmnRoaming DEFINED		d -DataTypes			er of Nam	ed Number,	0
	PLMN-Id					erence OC	TET STRING	
			-DataTypes -DataTypes					
	plmn-Specia DEFINED		Гуре1 -DataTypes			er of Nam	ed Number,	0
	plmn-Specif DEFINED		Type2 -DataTypes			er of Nam	ed Number,	1
	plmn-Specia DEFINED		Гуре3 -DataTypes			er of Nam	ed Number,	2
	plmn-Specia DEFINED		Гуре4 -DataTypes			er of Nam	ed Number,	3
Bearer	plmn-specit ServiceCode DEFINED		l'B			erence		
	plmn-specia					erence		
Bearer	ServiceCode, DEFINED	, '11010010 in MAP-BS		:	111			

plmn-specificBS-3 BearerServiceCode, '11010011'B	value reference
	: 112
plmn-specificBS-4	value reference
	: 113
plmn-specificBS-5 BearerServiceCode, '11010101'B	value reference
	: 114
plmn-specificBS-6 BearerServiceCode, '11010110'B	value reference
	: 115
plmn-specificBS-7	value reference
plmn-specificBS-7 BearerServiceCode, '11010111'B DEFINED in MAP-BS-Code	value reference
BearerServiceCode, '11010111'B DEFINED in MAP-BS-Code plmn-specificBS-8	: 116
BearerServiceCode, '11010111'B DEFINED in MAP-BS-Code	: 116
BearerServiceCode, '11010111'B	: 116value reference : 117
BearerServiceCode, '11010111'B DEFINED in MAP-BS-Code plmn-specificBS-8 BearerServiceCode, '11011000'B DEFINED in MAP-BS-Code	: 116value reference : 117
BearerServiceCode, '11010111'B DEFINED in MAP-BS-Code plmn-specificBS-8 BearerServiceCode, '11011000'B DEFINED in MAP-BS-Code plmn-specificBS-9 BearerServiceCode, '11011001'B	: 116value reference : 117value reference : 118

12-06	TAG R6.1			Reference	Listing	for MAI	P-Protocol		2006-
Bearer	plmn-speci ServiceCode DEFINED	, '11	01101	l'B	:		reference		
Bearer	plmn-speci ServiceCode DEFINED	, '11	011100	0'B			reference		
Bearer	plmn-speci ServiceCode DEFINED	, '11	011101				reference		
Bearer	plmn-speci ServiceCode DEFINED	ficBS	S-E	 D'B		.value	reference		
Bearer	plmn-speci ServiceCode	ficBS	5-F	 l'B		.value	reference		
'11110	plmn-speci 001'B	ficSS	3-1			.value	reference	SS-Code,	
'11110	DEFINED plmn-speci 010'B				:		reference	SS-Code,	
'11110	DEFINED plmn-speci						reference	SS-Code,	
'11110	plmn-speci			-Code			reference	SS-Code,	
'11110	DEFINED				:		reference	SS-Code,	
	DEFINED				:		reference	SS-Code,	
'11110	110'B DEFINED plmn-speci				:		reference	SS-Code,	
'11110	111'B DEFINED plmn-speci				:		reference	SS-Code.	
'11111	000'B DEFINED	in M	IAP-SS-	-Code	:	144			
'11111	DEFINED	in M	IAP-SS-	-Code	:	145			
'11111	plmn-speci 010'B DEFINED				:		reference	SS-Code,	

plmn-speci:	ficSS-B		.value	reference	SS-Code,
	in MAP-SS-Code	:	147		
plmn-speci:	ficSS-C		.value	reference	SS-Code,
DEFINED	in MAP-SS-Code	:	148		
plmn-speci:	ficSS-D		.value	reference	SS-Code,
		:			
'11111110'B	ficSS-E		.value	reference	SS-Code,
	in MAP-SS-Code				
'11111111'B	ficSS-F			reference	SS-Code,
	in MAP-SS-Code				
'11010001'B				reference	TeleserviceCode,
	in MAP-TS-Code			-	
'11010010'B				reference	TeleserviceCode,
		:		roforongo	TeleserviceCode,
'11010011'B	in MAP-TS-Code			rererence	releservicecode,
				reference	TeleserviceCode,
'11010100'B	in MAP-TS-Code	:		rererence	refeservicecode,
				reference	TeleserviceCode,
'11010101'B	in MAP-TS-Code	:			1010001.1000040,
				reference	TeleserviceCode,
'11010110'B DEFINED	in MAP-TS-Code	:	76		
plmn-speci:	ficTS-7		.value	reference	TeleserviceCode,
'11010111'B DEFINED	in MAP-TS-Code	:	77		
plmn-speci:	FicTS-8		.value	reference	TeleserviceCode,

12-06	TAG R6.1		Reference	Listing	for MA	.P-Protocol	2006-
	DEFINED	in MAP-TS	S-Code	:	78		
'11011		ficTS-9			value	reference	TeleserviceCode,
	DEFINED	in MAP-TS	S-Code	:	79		
'11011		ficTS-A	• • • • • • • • • • • • • • • • • • • •		value	reference	TeleserviceCode,
	DEFINED	in MAP-TS	S-Code	:	80		
'11011		ficTS-B			value	reference	TeleserviceCode,
		in MAP-TS		:			
'11011	100'B						TeleserviceCode,
		in MAP-TS		:			
'11011	101'B			• • • • • • • •	value	reference	TeleserviceCode,
		in MAP-TS		:			
'11011		ficTS-E	• • • • • • • • • • • • • • • • • • • •	• • • • • • • •	value	reference	TeleserviceCode,
		in MAP-TS		:			
'11011	111'B			• • • • • • • •	value	reference	TeleserviceCode,
		in MAP-TS		:			
			CS-DataType				amed Number, 3
							OCTET STRING
			CS-DataType CS-DataType				
ERROR,	positionMe		`e		infor	mation obj	ect reference
,	DEFINED	in MAP-Er		:			
		in MAP-Lo in MAP-Er	cationServ crors	iceOpe :	32 88		
	positionMe			ic	ident	ifier of [0]
Positi	onMethodFai DEFINED		ostic R-DataTypes	:	360		
			re-Diagnost	ic	type	reference	ENUMERATED
			R-DataTypes R-DataTypes	:	364 360		
			re-Param				SEQUENCE
			2-DataTypes		359 142		
			rors 2-DataTypes				
			ilableInLo R-DataTypes				amed Number, 8
	positionMe	thodNotAva	uilableInNe	twork	ident	ifier of N	amed Number, 7

DEFINED in MAP-ER-DataTypes	:	372
ppr-Address		.identifier of [5] GSN-Address
DEFINED in MAP-LCS-DataTypes	:	87
preferentialCUG-Indicator		
DEFINED in MAP-MS-DataTypes	:	1274
premiumRateEntertainementOGCallsBarre		
DEFINED in MAP-MS-DataTypes	:	1112
premiumRateInformationOGCallsBarred		
DEFINED in MAP-MS-DataTypes	:	1111
prepareGroupCall	in:	formation object reference
OPERATION, Information Object		
DEFINED in MAP-Group-Call-Operati		
USED in MAP-Protocol	:	102 134
USED in MAP-Group-Call-Operati	:	13
PrepareGroupCallArg		.type reference SEQUENCE
DEFINED in MAP-GR-DataTypes	:	48
USED in MAP-Group-Call-Operati		
USED in MAP-GR-DataTypes	:	14
PrepareGroupCallRes		.type reference SEQUENCE
DEFINED in MAP-GR-DataTypes	:	69
USED in MAP-Group-Call-Operati	:	33 48
USED in MAP-GR-DataTypes	:	15
prepareHandover	.in:	formation object reference
OPERATION, Information Object		
DEFINED in MAP-MobileServiceOpera	:	314

12-06	TAG R6.15 Cross Reference Listing for MAP-Protoco 09:33:23 PAGE 84	2006-
	USED in MAP-Protocol : 21 122 USED in MAP-MobileServiceOpera : 38	
	PrepareHO-Argtype reference DEFINED in MAP-MS-DataTypes : 538	[3] SEQUENCE
	USED in MAP-MobileServiceOpera : 121 316 USED in MAP-MS-DataTypes : 34	
	PrepareHO-Restype reference DEFINED in MAP-MS-DataTypes : 600	[3] SEQUENCE
	USED in MAP-MobileServiceOpera : 122 318 USED in MAP-MS-DataTypes : 35	
OPERAT	<pre>prepareSubsequentHandoverinformation objec ION, Information Object</pre>	t reference
	DEFINED in MAP-MobileServiceOpera : 344	
	USED in MAP-Protocol : 25 123	
	USED in MAP-MobileServiceOpera : 42	
	PrepareSubsequentHO-Argtype reference	[3] CEOHENCE
	DEFINED in MAP-MS-DataTypes : 643	[3] PEOGRACE
	USED in MAP-MobileServiceOpera: 128 346	
	USED in MAP-MS-DataTypes : 36	
	OSED III MAF-MS-Datalypes : 30	
	PrepareSubsequentHO-Restype reference	[3] SEQUENCE
	DEFINED in MAP-MS-DataTypes • 654	
	USED in MAP-MobileServiceOpera: 127 348	
	USED in MAP-MS-DataTypes : 37	
	previous-LAIidentifier of DEFINED in MAP-MS-DataTypes : 327	[0] LAIFixedLength
	pre-pagingSupportedidentifier of DEFINED in MAP-CH-DataTypes : 112	[19] NULL
	pre-pagingSupportedidentifier of DEFINED in MAP-CH-DataTypes : 237	[17] NULL
	Prioritytype reference DEFINED in Remote-Operations-Info: 118	INTEGER
	<pre>priorityidentifier of DEFINED in MAP-GR-DataTypes : 56</pre>	[2] EMLPP-Priority
	priorityLevel0value reference DEFINED in MAP-CommonDataTypes : 560	e EMLPP-Priority, 0
	priorityLevel1value reference DEFINED in MAP-CommonDataTypes : 561	e EMLPP-Priority, 1
	priorityLevel2value reference DEFINED in MAP-CommonDataTypes : 562	e EMLPP-Priority, 2
	priorityLevel3value reference DEFINED in MAP-CommonDataTypes : 563	e EMLPP-Priority, 3
	priorityLevel4value reference DEFINED in MAP-CommonDataTypes : 564	e EMLPP-Priority, 4
	priorityLevelAvalue referenc	e EMLPP-Priority, 6

DEFINED in MAP-CommonDataTypes : 558
<pre>priorityLevelBvalue reference EMLPP-Priority, 5 DEFINED in MAP-CommonDataTypes : 559</pre>
PrivacyCheckRelatedActiontype reference ENUMERATED DEFINED in MAP-LCS-DataTypes : 273 USED in MAP-LCS-DataTypes : 269 270
privacyOverrideidentifier of [1] NULL DEFINED in MAP-LCS-DataTypes : 107
<pre>privacyOverrideNotApplicableidentifier of Named Number, 3 DEFINED in MAP-ER-DataTypes : 350</pre>
privacyViolationidentifier of Named Number, 5 DEFINED in MAP-LCS-DataTypes : 528
PrivateExtensiontype reference SEQUENCE DEFINED in MAP-ExtensionDataTypes: 44 USED in MAP-ExtensionDataTypes: 15 42
<pre>privateExtensionListidentifier of [0] PrivateExtensionList</pre>

```
TAG R6.15 Cross Reference Listing for MAP-Protocol
                                                                               2006-
12-06 09:33:23 PAGE 85
          DEFINED in MAP-ExtensionDataTypes :
       privateExtensionList.....identifier of [0]
PrivateExtensionList
          DEFINED in MAP-ExtensionDataTypes :
       PrivateExtensionList.....type reference SEQUENCE OF
          DEFINED in MAP-ExtensionDataTypes : 41
USED in MAP-ExtensionDataTypes : 32
       processAccessSignalling.....information object reference
OPERATION, Information Object
          DEFINED in MAP-MobileServiceOpera : 334
             USED in MAP-Protocol : 23
USED in MAP-MobileServiceOpera : 40
                                                         123
       ProcessAccessSignalling-Arg.....type reference [3] SEQUENCE
          DEFINED in MAP-MS-DataTypes : 659
USED in MAP-MobileServiceOpera : 124
             USED in MAP-MS-DataTypes :
       \verb|processGroupCallSignalling..... information object reference|
OPERATION, Information Object
          DEFINED in MAP-Group-Call-Operati :
             USED in MAP-Protocol : 103 135
             USED in MAP-Group-Call-Operati: 16
       {\tt ProcessGroupCallSignallingArg..........type\ reference\ {\tt SEQUENCE}}
          DEFINED in MAP-GR-DataTypes : 94
USED in MAP-Group-Call-Operati : 37
             USED in MAP-GR-DataTypes
                                                    19
       processUnstructuredSS-Request.....information object reference
OPERATION, Information Object
          , Information Object

DEFINED in MAP-SupplementaryServi : 181

USED in MAP-Protocol : 77 131

TORRE in MAR-SupplementaryServi : 18
       protocolId.....identifier of ProtocolId
          DEFINED in MAP-CommonDataTypes :
       ProtocolId.....type reference ENUMERATED
          DEFINED in MAP-CommonDataTypes : 221
USED in MAP-CommonDataTypes : 203
       provideRoamingNumber.....information object reference
OPERATION, Information Object
          DEFINED in MAP-CallHandlingOperat : 102
             USED in MAP-Protocol :
             USED in MAP-CallHandlingOperat: 14
       ProvideRoamingNumberArg.....type reference SEQUENCE
          DEFINED in MAP-CH-DataTypes : 219
USED in MAP-CallHandlingOperat : 56
USED in MAP-CH-DataTypes : 16
             USED in MAP-CH-DataTypes :
       ProvideRoamingNumberRes.....type reference SEQUENCE
          DEFINED in MAP-CH-DataTypes : 243

USED in MAP-CallHandlingOperat : 57 107

USED in MAP-CH-DataTypes : 17
```

provideSubscriberInfoinformation object refer OPERATION, Information Object	ence
DEFINED in MAP-MobileServiceOpera : 233	
USED in MAP-Protocol : 34 125	
USED in MAP-MobileServiceOpera : 24	
ProvideSubscriberInfoArgtype reference SEQUEN	ICE
DEFINED in MAP-MS-DataTypes : 2009	
USED in MAP-MobileServiceOpera : 142 235	
USED in MAP-MS-DataTypes : 104	
ProvideSubscriberInfoRestype reference SEQUEN	ICE
DEFINED in MAP-MS-DataTypes : 2016	
USED in MAP-MobileServiceOpera: 143 237	
USED in MAP-MS-DataTypes : 105	
provideSubscriberLocationinformation object refer OPERATION, Information Object	ence
DEFINED in MAP-LocationServiceOpe : 68	
USED in MAP-Protocol : 111 136	
USED in MAP-LocationServiceOpe : 13	
ProvideSubscriberLocation-Argtype reference SEQUEN	ICE
DEFINED in MAP-LCS-DataTypes : 103	ICE
USED in MAP-LocationServiceOpe : 44 70	
USED in MAP-LCS-DataTypes : 13	
osed in MAR-Des-Dacatypes : 13	
ProvideSubscriberLocation-Restype reference SEQUEN	ICE

12-06	TAG R6.15 Cross Reference Listi 09:33:23 PAGE 86	ng	for MAP-Pr	otoc	ol 2006-
	DEFINED in MAP-LCS-DataTypes USED in MAP-LocationServiceOpe USED in MAP-LCS-DataTypes	:	45	72	
	provisionedSS			r of	[7] Ext-SS-InfoList
	pseudonymIndicator			r of	[18] NULL
	psi-enhancements DEFINED in MAP-MS-DataTypes			r of	Named Number, 6
	ps-AttachedNotReachableForPaging DEFINED in MAP-MS-DataTypes			r of	[2] NULL
	ps-AttachedReachableForPaging DEFINED in MAP-MS-DataTypes		identifie 2180	r of	[3] NULL
	ps-DetachedDEFINED in MAP-MS-DataTypes			r of	[1] NULL
	ps-Domain DEFINED in MAP-MS-DataTypes			r of	Named Number, 1
	ps-LCS-NotSupportedByUE DEFINED in MAP-MS-DataTypes			r of	[2] NULL
Context	ps-PDP-ActiveNotReachableForPaging tInfoList DEFINED in MAP-MS-DataTypes			r of	[4] PDP-
a	ps-PDP-ActiveReachableForPaging			r of	[5] PDP-
Context	tInfoList DEFINED in MAP-MS-DataTypes				
Subscr	ps-SubscriberStateiberState DEFINED in MAP-MS-DataTypes		identifie 2027	r of	[4] PS-
	PS-SubscriberState DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes	:	type refe 2176 2027	renc	e CHOICE
	purgedMS DEFINED in MAP-ER-DataTypes			r of	Named Number, 3
OPERAT	purgeMS	i :	195 18 1	obje 21	ct reference
	PurgeMS-Arg DEFINED in MAP-MS-DataTypes USED in MAP-MobileServiceOpera USED in MAP-MS-DataTypes	: a :	304 115 1	rence 97	e [3] SEQUENCE
	PurgeMS-Res DEFINED in MAP-MS-DataTypes	:	type refe 311	rence	e SEQUENCE

	n MAP-MobileServiceOpera n MAP-MS-DataTypes		
	n MAP-CommonDataTypes		identifier of Named Number, 3 357
pw-Registrat ERROR, Information			information object reference
DEFINED i USED i	n MAP-Errors n MAP-SupplementaryServi n MAP-Errors	:	46 237
DEFINED i USED i	ionFailureCause n MAP-ER-DataTypes n MAP-Errors n MAP-ER-DataTypes	:	107 409
Subscribed	ted n MAP-MS-DataTypes		identifier of [20] Ext2-QoS-
			identifier of [19] Ext2-QoS-
DEFINED i	n MAP-MS-DataTypes	:	2210
qos2-Subscri Subscribed	bed		identifier of [18] Ext2-QoS-
	n MAP-MS-DataTypes	:	2208
qoSNotAttair	able		identifier of Named Number, 6

12-06	TAG R6.15 Cross Reference Listin 09:33:23 PAGE 87	g for MAP-Protocol 2006-
	DEFINED in MAP-ER-DataTypes	: 371
Subscr	qos-Negotiatedibed	identifier of [13] Ext-QoS-
		: 2202
Subscr		
	DEFINED in MAP-MS-DataTypes	
	qos-Subscribed DEFINED in MAP-MS-DataTypes	
	QoS-Subscribed	
	DEFINED in MAP-MS-DataTypes	
	USED in MAP-MS-DataTypes	
Subscr	qos-Subscribedibed	identifier of [11] Ext-QoS-
	DEFINED in MAP-MS-DataTypes	: 2200
	quintupletList	identifier of [1] QuintupletList
	DEFINED in MAP-MS-DataTypes	: 346
	QuintupletList	
	DEFINED in MAP-MS-DataTypes	
	USED in MAP-MS-DataTypes	: 346
	rab-ConfigurationIndicator	identifier of [13] NULL
	DEFINED in MAP-MS-DataTypes	
	rab-ConfigurationIndicator	identifier of [19] NULL
	DEFINED in MAP-MS-DataTypes	: 561
	rab-ConfigurationIndicator	identifier of [7] NULL
	DEFINED in MAP-MS-DataTypes	: 652
	rab-Id	identifier of [12] RAB-Id
	DEFINED in MAP-MS-DataTypes	: 553
	rab-Id	identifier of RAB-Id
	DEFINED in MAP-MS-DataTypes	
	rab-Id	identifier of RAR-Id
	DEFINED in MAP-MS-DataTypes	
	rab-Id	identifier of RAB-Id
	DEFINED in MAP-MS-DataTypes	
	RAB-Id	type reference INTEGER
	DEFINED in MAP-MS-DataTypes	
	_ 	: 553 572 594 648 664
732		
	RadioResource	
	DEFINED in MAP-MS-DataTypes	: 592
	USED in MAP-MS-DataTypes	: 590
D = 31 D	radioResourceInformation	identifier of [6]
касіоК	esourceInformation	

DEFINED in MAP-MS-DataTypes : 483

radioResourceInformation.....identifier of [7]

RadioResourceInformation

DEFINED in MAP-MS-DataTypes

radioResourceInformation.....identifier of

RadioResourceInformation

DEFINED in MAP-MS-DataTypes

RadioResourceInformation.....type reference OCTET STRING

DEFINED in MAP-MS-DataTypes : 742
USED in MAP-MS-DataTypes : 483 494 547 564 593

radioResourceList.....identifier of [7]

RadioResourceList

DEFINED in MAP-MS-DataTypes

radioResourceList.....identifier of [11]

RadioResourceList

DEFINED in MAP-MS-DataTypes

DEFINED in MAP-MS-DataTypes : 589 USED in MAP-MS-DataTypes : 486

486

RAIdentity.....type reference OCTET STRING

DEFINED in MAP-MS-DataTypes : 2139
USED in MAP-MS-DataTypes : 109 2124

ranap-ServiceHandover.....identifier of [8] RANAP-

ServiceHandover

12-06	TAG R6.1			Reference	Listing	for MA	P-Protoco	ol		2006-
	DEFINED	in	MAP-MS-	-DataTypes	:	488				
Servic	ranap-Serv	iceH	Iandoveı	· · · · · · · · · · · · · · · · · · ·		ident:	ifier of	[14]	RANAP-	
Bervie		in	MAP-MS-	-DataTypes	:	555				
	RANAP-Serv	iceE in	Handovei MAP-MS-	DataTypes		type : 582		e OCTE	T STRING	
	USED	in	MAP-MS-	-DataTypes	:	488	555			
	rand DEFINED			DataTypes			ifier of	RAND		
	rand DEFINED			DataTypes			ifier of	RAND		
	RAND DEFINED			DataTypes DataTypes						
	USED	in	MAP-MS-	-DataTypes	:	355	361	412	789	
	rand DEFINED			DataTypes			ifier of	RAND		
	rand			DataTypes			ifier of	RAND		
	rau-gprsAt						ifier of	Named	Number	2
				-DataTypes			IIICI OI	Ivallica	r rumber,	2
OPERAT	readyForSM	atic	on Objec	ct			ion obje	ct ref	erence	
OPERAT	CION, Inform DEFINED	atic in	on Objec MAP-Sho	ct ortMessageS	Servic :	140		ct ref	erence	
OPERAT	CION, Inform DEFINED USED	atic in in	on Objec MAP-Sho MAP-Pro	ct	Servic :	140 96	134	ct ref	erence	
OPERAT	CION, Inform DEFINED USED	atic in in in	on Object MAP-Sho MAP-Pro MAP-Sho	ct ortMessage otocol ortMessage	Servic : : Servic :	140 96 19	134			
OPERAT	TION, Inform DEFINED USED USED ReadyForSM DEFINED	ation in in in -Arg	on Object MAP-Shot MAP-Shot MAP-Shot MAP-Shot MAP-SM-	ortMessagesotocol ortMessagesortMessages	Servic : Servic :	140 96 19 type	134 reference			
OPERAT	CION, Inform DEFINED USED USED ReadyForSM DEFINED USED	ation in in -Arg in in	on Object MAP-Shot MAP-Shot MAP-Shot MAP-Shot MAP-SM-	ct ortMessages otocol ortMessages	Servic : Servic :	140 96 19 type : 200 56	134 reference			
OPERAT	CION, Inform DEFINED USED USED ReadyForSM DEFINED USED	atic in in in -Arg in in	on Object MAP-Sho MAP-Sho MAP-Sho MAP-Sho MAP-SM- MAP-Sho MAP-Sho	ortMessages otocol ortMessages DataTypes ortMessages	Servic : Servic : : Servic :	140 96 19 type 200 56 24	134 reference 142	e SEQU	ENCE	
OPERAT	CION, Inform DEFINED USED USED ReadyForSM DEFINED USED USED ReadyForSM	atic in in in -Arg in in in	on Object MAP-Sho MAP-Sho MAP-Sho MAP-Sho MAP-SM- MAP-Sho MAP-SM- MAP-SM-	ortMessages otocol ortMessages DataTypes ortMessages DataTypes	Servic : Servic : Servic : Servic :	140 96 19 type 2 200 56 24 type 2	134 reference 142 reference	e SEQU	ENCE	
OPERAT	CION, Inform DEFINED USED ReadyForSM DEFINED USED USED ReadyForSM DEFINED USED USED USED	atic in in in -Arg in in in in in in in	on Object MAP-Shot MAP-Pro MAP-Shot MAP-SM- MAP-SM- MAP-SM- MAP-SM- MAP-SM- MAP-SM- MAP-SM-	ortMessages ortMessages ortMessages ortMessages ortMessages ortMessages ortMessages ortMessages ortMessages	Servic : Servic : Servic : Servic : Servic :	140 96 19 type : 200 56 24 type : 209 57	134 reference 142 reference	e SEQU	ENCE	
OPERAT	CION, Inform DEFINED USED ReadyForSM DEFINED USED USED ReadyForSM DEFINED USED USED USED	atic in in in -Arg in in in in in in in	on Object MAP-Shot MAP-Pro MAP-Shot MAP-SM- MAP-SM- MAP-SM- MAP-SM- MAP-SM- MAP-SM- MAP-SM-	ortMessages otocol ortMessages DataTypes ortMessages DataTypes	Servic : Servic : Servic : Servic : Servic :	140 96 19 type : 200 56 24 type : 209 57	134 reference 142 reference	e SEQU	ENCE	
OPERAT	TION, Inform DEFINED USED ReadyForSM DEFINED USED ReadyForSM DEFINED USED ReadyForSM DEFINED USED TECALL TECALL TECALL TOTAL T	atic in in -Arg in in in -Arg in in in -Res in in in	on Object MAP-Shot MAP-Pro MAP-Shot MAP-SM- MAP-SM- MAP-SM- MAP-SM- MAP-SM- MAP-SM- MAP-SM- MAP-SM- MAP-SM-	ortMessages otocol ortMessages	Servic : Servic : Servic : Servic : Servic :	140 96 19 type : 200 56 24 type : 209 57 25	134 reference 142 reference	e SEQU e SEQU	ENCE	1
OPERAT	ReadyForsM DEFINED USED ReadyForSM DEFINED USED USED ReadyForSM DEFINED USED ReadyForSM DEFINED USED Tecall DEFINED regionalSul	atic in in in -Arc in in in in in cres in in in in bscN	on Object MAP-Sho MAP-Pro MAP-Sho MAP-Sho MAP-SM- MAP-SM- MAP-SM- MAP-SM- MAP-SM- MAP-Sho	ortMessages otocol ortMessages -DataTypes -DataTypes -DataTypes -DataTypes -DataTypes -DataTypes -DataTypes -DataTypes	Servic : Servic : Servic : Servic : : Servic :	140 96 19 type : 200 56 24 type : 209 57 25 ident: 286	134 reference 142 reference 144 ifier of	e SEQU e SEQU Named	ENCE ENCE Number,	
OPERAT	ReadyForsM DEFINED USED ReadyForSM DEFINED USED ReadyForSM DEFINED USED ReadyForsM DEFINED USED recall DEFINED regionalSul	atic in in in -Arg in in in in cres in in in bscn in bscr	on Object MAP-Sho MAP-Sho MAP-Sho MAP-Sho MAP-Sho MAP-Sho MAP-Sho MAP-SM- MAP-	ortMessages otocol ortMessages DataTypes ortMessages DataTypes DataTypes ortMessages DataTypes ortMessages DataTypes ortMessages DataTypes ortMessages DataTypes	Servic : Servic : Servic : Servic : : Servic :	140 96 19 type : 200 56 24 type : 209 57 25 ident: 1421 ident:	134 reference 142 reference 144 ifier of	e SEQU Named	ENCE Number,	3
OPERAT	ReadyForsM DEFINED USED USED USED ReadyForsM DEFINED USED USED ReadyForsM DEFINED USED Tecall DEFINED regionalSub DEFINED regionalSub DEFINED	atic in in in -Arg in in in -Res in in in in bscN in bscr	on Object MAP-Sho MAP-Pro MAP-Sho MAP-MS-	ortMessages otocol ortMessages DataTypes ortMessages DataTypes DataTypes DataTypes DataTypes ortMessages DataTypes DataTypes DataTypes OataTypes	Servic : Servic : Servic : Servic : : Servic : : : : : : : : : : : : : : : : : : :	140 96 19 type: 200 56 24 type: 209 57 25 ident: 1421 ident: 1075	134 reference 142 reference 144 ifier of	e SEQU Named Named	ENCE Number, Number,	3
	ReadyForsM DEFINED USED USED USED USED USED USED USED US	atic in in in -Arc in in in -Res in in in bscN in bscr in bscr in bscr in	on Object MAP-Sho MAP-Pro MAP-Sho MAP-MS- CiptionI	ct prtMessages ptocol prtMessages ctocol prtMessages continues pataTypes pataTypes pataTypes pataTypes pataTypes pataTypes conted pataTypes	Servic : Servic : Servic : Servic : : Servic : : : : : : : : : : : : : : : : : : :	140 96 19 type : 200 56 24 type : 209 57 25 ident: 1421 ident: 1075 ident:	134 reference 142 reference 144 ifier of ifier of	e SEQU Named Named [10]	ENCE Number, Number,	3

 ${\tt Regional Subscription Response.............type\ reference\ {\tt ENUMERATED}}$ DEFINED in MAP-MS-DataTypes : 1417
USED in MAP-MS-DataTypes : 1411 1485 regionalSubscriptionResponse.....identifier of [0] RegionalSubscriptionResponse DEFINED in MAP-MS-DataTypes : 1485 registerCC-Entry.....information object reference OPERATION, Information Object DEFINED in MAP-SupplementaryServi : 263 USED in MAP-Protocol : 83 132 USED in MAP-SupplementaryServi : 24 RegisterCC-EntryArg.....type reference SEQUENCE DEFINED in MAP-SS-DataTypes : 304
USED in MAP-SupplementaryServi : 71
USED in MAP-SS-DataTypes : 37 265 RegisterCC-EntryRes.....type reference SEQUENCE DEFINED in MAP-SS-DataTypes : 323 USED in MAP-SupplementaryServi : 72 USED in MAP-SS-DataTypes : 38 267 $\verb"registerPassword...... information object reference"$ OPERATION, Information Object DEFINED in MAP-SupplementaryServi : 226

12-06	TAG R6.15			Reference	Listi	ng	for MA	AP-Pro	toc	ol		2006-
	נופעה	in N	M7 D - D20	otocol			0.0) 13	2			
				plementar					2			
	USED	T11 1	MAF-SUL	premencar	Aper AT	•	2.1	_				
OPERAT	registerSS ION, Informa					.in	format	cion o	bje	ct ref	erence	
	DEFINED	in N	MAP-Sup	plementar	yServi	:	88	3				
	USED	in N	MAP-Pro	otocol	_	:	72	2 13	0			
	USED	in N	MAP-Sup	plementar				3				
	RegisterSS	-Arg					.type	refer	ence	e SEQU	ENCE	
	DEFINED	in N	MAP-SS-	DataTypes		:	71					
	USED	in N	MAP-Sup	plementar	yServi	:	61	_ 9	0			
				·DataTypes								
				71								
	registration	onAl]	lCF-Bar	red			.ident	ifier	of	Named	Number,	24
				DataTypes							,	
	בבו דוים		111	Dacarypes		•		•				
	registratio	onCFI	Not ToHE	PLMN-Barre	4		ident	ifier	of	Named	Number	25
				DataTypes					OL	Ivamea	Number,	25
	DHI INDD	111 1	AL NO	Datalypes		•	115	,				
	registration	on Tnt	-ornati	onalCE_Pa	rrod		idont	ifior	٥f	Namad	Numbor	20
	_								OI	Named	Number,	∠8
	DELINED	T11 I	MAP-MS-	DataTypes		:	1133	3				
				7 0					_			0.7
	registration								Οİ	Named	Number,	27
	DEFINED	in N	MAP-MS-	DataTypes		:	1132	2				
	registration	onInt	terzona	alCF-Barre	d		.ident	ifier	of	Named	Number,	26
	DEFINED	in N	MAP-MS-	DataTypes		:	1131	L				
	rejected						.ident	ifier	of	Named	Number,	1
	DEFINED	in N	MAP-CH-	DataTypes		:	397	7				
	releaseCal:	1					.ident	ifier	of	Named	Number,	1
	DEFINED	in N	MAP-MS-	DataTypes		:	1704	<u> </u>				
	releaseGro	upCa]	11				.ident	ifier	of	[2] N	ULL	
	DEFINED	in N	MAP-GR-	DataTypes		:	97	7				
	releaseRes	ource	es			.in	format	cion o	bje	ct ref	erence	
OPERAT	ION, Informa	ation	n Objec	ct								
	DEFINED	in N	MAP-Cal	lHandling	Operat	:	201	L				
	USED	in N	MAP-Pro	otocol	_	:	66	13	7			
	USED	in N	MAP-Cal	lHandling	Operat	:	21	L				
				5	-							
	ReleaseRes	ource	esAra.				.tvne	refer	ence	e SEOU	ENCE	
				-DataTypes					0110	S DIQU		
				lHandling					2			
				·DataTypes		•	34		5			
	עשפט	T11 I	MAP-CH-	Datalypes		•	34	Ė				
	Dologgana	01170~	ogBos				+	rofor-	0r ~	י זייטיני	EMCE.	
	ReleaseReso								euce	= DEQU	DINCE	
				DataTypes					_			
				lHandling					5			
	USED	ın N	MAP-CH-	DataTypes		:	35					
	_			_								
	releaseResourcesSupportedidentifier of [22] NULL								NULL			
	DEFINED	in N	MAP-CH-	DataTypes		:	176	5				
	releaseRes	ource	esSuppo	orted			.ident	ifier	of	NULL		
	DEFINED	in N	MAP-CH-	DataTypes		:	247	7				

releaseTransaction DEFINED in MAP-MS-DataTypes									
releaseTransaction DEFINED in MAP-MS-DataTypes									
RelocationNumber DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes	: 730								
relocationNumberListidentifier of [1] RelocationNumberList									
DEFINED in MAP-MS-DataTypes	: 602								
RelocationNumberList									
DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes									
remoteUserFreeinformation object reference OPERATION, Information Object									
DEFINED in MAP-CallHandlingOperat USED in MAP-Protocol									
USED in MAP-CallHandlingOperat									
RemoteUserFreeArg DEFINED in MAP-CH-DataTypes									

```
TAG R6.15 Cross Reference Listing for MAP-Protocol
                                                                            2006-
12-06 09:33:23 PAGE 90
            USED in MAP-CallHandlingOperat : 64 161
             USED in MAP-CH-DataTypes
       RemoteUserFreeRes.....type reference SEQUENCE
          DEFINED in MAP-CH-DataTypes : 390
             USED in MAP-CallHandlingOperat : 65
USED in MAP-CH-DataTypes : 28
                                                        163
       Remote-Operations-Information-Objects...module reference
          DEFINED in Remote-Operations-Info: 3
             USED in MAP-Protocol
             USED in MAP-MobileServiceOpera: 76
USED in MAP-OperationAndMainte: 20
USED in MAP-Collumnation 2
             USED in MAP-CallHandlingOperat :
            USED in MAP-SupplementaryServi : 30
USED in MAP-ShortMessageServic : 24
USED in MAP-Group-Call-Operati : 21
USED in MAP-LocationServiceOpe : 20
             USED in MAP-Errors
       replaceB-Number.....identifier of [4] NULL
          DEFINED in MAP-CH-DataTypes
       ReportingState.....type reference ENUMERATED
          DEFINED in MAP-CH-DataTypes : 317
             USED in MAP-CH-DataTypes
                                            :
       \verb"reportSM-DeliveryStatus..... information object reference"
OPERATION, Information Object
         DEFINED in MAP-ShortMessageServic : 112
            USED in MAP-ShortMessageServic : 93 133
       ReportSM-DeliveryStatusArg.....type reference SEQUENCE
          DEFINED in MAP-SM-DataTypes : 142
USED in MAP-ShortMessageServic : 52
                                                        114
             USED in MAP-SM-DataTypes
       ReportSM-DeliveryStatusRes.....type reference SEQUENCE
          DEFINED in MAP-SM-DataTypes : 170
USED in MAP-ShortMessageServic : 53
            USED in MAP-SM-DataTypes :
                                                  21
       request......identifier\ of\ Named\ Number,\ 0
          DEFINED in MAP-SS-DataTypes
       requestedAccuracyFulfilled.....identifier of Named Number, 0
          DEFINED in MAP-LCS-DataTypes
                                                 362
       requestedAccuracyNotFulfilled.....identifier of Named Number, 1
          DEFINED in MAP-LCS-DataTypes
                                                 363
       requestedBasicServiceViolatesCUG-Constraidentifier of Named Number, 5
          DEFINED in MAP-ER-DataTypes
                                         :
                                                  125
       requestedCAMEL-SubscriptionInfo.....identifier of [3] RequestedCAMEL-
SubscriptionInfo
          DEFINED in MAP-MS-DataTypes
                                        : 2279
       {\tt RequestedCAMEL-SubscriptionInfo......type\ reference\ ENUMERATED}
```

DEFINED in MAP-MS-DataTypes : 2288 USED in MAP-MS-DataTypes : 2279 : 2279 2403 requestedCamel-SubscriptionInfo.....identifier of [0] RequestedCAMEL-SubscriptionInfo DEFINED in MAP-MS-DataTypes : 2403 requestedDomain.....identifier of [4] DomainType DEFINED in MAP-MS-DataTypes 2090 requestedEquipmentInfo.....identifier of RequestedEquipmentInfo DEFINED in MAP-MS-DataTypes RequestedEquipmentInfo.....type reference BIT STRING DEFINED in MAP-MS-DataTypes 820 USED in MAP-MS-DataTypes 810 requestedInfo.....identifier of [2] RequestedInfo DEFINED in MAP-MS-DataTypes 2012

RequestedInfo.....type reference SEQUENCE

DEFINED in MAP-MS-DataTypes : 2084
USED in MAP-MS-DataTypes : 2012 2244

```
TAG R6.15 Cross Reference Listing for MAP-Protocol
                                                                2006-
12-06 09:33:23 PAGE 91
        DEFINED in MAP-MS-DataTypes : 2244
      requestedSS-Info.....identifier of [1] SS-ForBS-Code
        DEFINED in MAP-MS-DataTypes
                                        2277
      requestedSubscriptionInfo.....identifier of [1]
RequestedSubscriptionInfo
        DEFINED in MAP-MS-DataTypes
      RequestedSubscriptionInfo.....type reference SEQUENCE
                                 : 2276
        DEFINED in MAP-MS-DataTypes
           USED in MAP-MS-DataTypes
      requestingNodeType.....identifier of [3]
RequestingNodeType
        DEFINED in MAP-MS-DataTypes
      RequestingNodeType.....type reference ENUMERATED
        DEFINED in MAP-MS-DataTypes :
USED in MAP-MS-DataTypes :
           USED in MAP-MS-DataTypes
      \verb|requestingPLMN-Id......identifier of [4] PLMN-Id|\\
        DEFINED in MAP-MS-DataTypes
      requestorIDString.....identifier of [1]
RequestorIDString
        DEFINED in MAP-LCS-DataTypes
                                     :
      RequestorIDString.....type reference USSD-String
        DEFINED in MAP-LCS-DataTypes : 198
           USED in MAP-LCS-DataTypes
      reset.....information object reference
OPERATION, Information Object
        DEFINED in MAP-MobileServiceOpera : 429
           USED in MAP-Protocol : 31 125
           USED in MAP-MobileServiceOpera :
                                          56
      ResetArg.....type reference SEQUENCE DEFINED in MAP-MS-DataTypes : 1960
           USED in MAP-MobileServiceOpera : 139 431
           USED in MAP-MS-DataTypes :
     resourceLimitation.....information object reference
ERROR, Information Object
           FINED in MAP-Errors : 192
USED in MAP-CallHandlingOperat : 47 142 181 195
USED in MAP-LocationServiceOpe : 33 95
        DEFINED in MAP-Errors
           USED in MAP-Errors
      DEFINED in MAP-ER-DataTypes : 319
USED in MAP-Errors : 135 194
           USED in MAP-ER-DataTypes :
                                          44
      \verb|responseTime..... identifier of [3] ResponseTime|\\
        DEFINED in MAP-LCS-DataTypes :
      ResponseTime.....type reference SEQUENCE
        DEFINED in MAP-LCS-DataTypes :
```

USED in MAP-LCS-DataTypes : 22 218 responseTimeCategory.....identifier of ResponseTimeCategory DEFINED in MAP-LCS-DataTypes ResponseTimeCategory.....type reference ENUMERATED DEFINED in MAP-LCS-DataTypes : 239 235 restoreData.....information object reference OPERATION, Information Object DEFINED in MAP-MobileServiceOpera : 437 USED in MAP-Protocol : 33 USED in MAP-MobileServiceOpera : 58 125 RestoreDataArg.....type reference SEQUENCE DEFINED in MAP-MS-DataTypes : 1965
USED in MAP-MobileServiceOpera : 140 439 USED in MAP-MS-DataTypes 95 RestoreDataRes.....type reference SEQUENCE FINED in MAP-MS-DataTypes : 1972
USED in MAP-MobileServiceOpera : 141 DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes : $\tt restricted Area...... identifier of Named Number, 2$

: 2237

DEFINED in MAP-MS-DataTypes

```
TAG R6.15 Cross Reference Listing for MAP-Protocol
                                                                2006-
12-06 09:33:23 PAGE 92
      \tt restricted Area...... identifier of Named Number, 1
        DEFINED in MAP-ER-DataTypes
      \tt restrictedIfNoResponse...... identifier of Named Number, 3
        DEFINED in MAP-LCS-DataTypes
      resumeCallHandling.....information object reference
OPERATION, Information Object
        DEFINED in MAP-CallHandlingOperat : 118
          USED in MAP-Protocol : 60 129
USED in MAP-CallHandlingOperat : 15
      ResumeCallHandlingArg.....type reference SEQUENCE
        DEFINED in MAP-CH-DataTypes : 249
USED in MAP-CallHandlingOperat : 58
USED in MAP-CH-DataTypes : 18
                                              120
      ResumeCallHandlingRes.....type reference SEQUENCE
        DEFINED in MAP-CH-DataTypes : 280
           USED in MAP-CallHandlingOperat: 59
USED in MAP-CH-DataTypes: 19
      \verb|re-attempt.....identifier| of BOOLEAN|
        DEFINED in MAP-MS-DataTypes
      re-synchronisationInfo.....identifier of Re-
synchronisationInfo
        DEFINED in MAP-MS-DataTypes
                                   :
      Re-synchronisationInfo.....type reference SEQUENCE
        DEFINED in MAP-MS-DataTypes :
           USED in MAP-MS-DataTypes
      rnc.....identifier of Named Number, 4
        DEFINED in MAP-OM-DataTypes
        DEFINED in MAP-MS-DataTypes : 713
      RNCId.....type reference OCTET STRING
      rnc-Address.....identifier of [16] GSN-Address
        DEFINED in MAP-MS-DataTypes
                                     : 2205
      RNC-InterfaceList.....type reference BIT STRING
        DEFINED in MAP-OM-DataTypes : 131
           USED in MAP-OM-DataTypes
                                          91
      rnc-InterfaceList.....identifier of [5] RNC-
InterfaceList
        DEFINED in MAP-OM-DataTypes
                                   : 185
     rnc-List.....identifier of [4] RNC-
InterfaceList
                                  : 91
        DEFINED in MAP-OM-DataTypes
      rnc-TraceDepth.....identifier of [4] TraceDepth
        DEFINED in MAP-OM-DataTypes
      rnc-TraceDepth.....identifier of [4] TraceDepth
        DEFINED in MAP-OM-DataTypes
```

6	roadsideAssistance		value referen	ce LCSServiceTypeID,
	DEFINED in MAP-CommonDataTypes	:	417	
	roamerAccessToHPLMN-AP-Barred DEFINED in MAP-MS-DataTypes			Named Number, 16
	roamerAccessToVPLMN-AP-Barred DEFINED in MAP-MS-DataTypes			Named Number, 17
ERROR,	roamingNotAllowed		information ol	bject reference
	DEFINED in MAP-Errors	:	228	
	USED in MAP-MobileServiceOpera	:	87 181	228
	USED in MAP-Errors			
Roamin	roamingNotAllowedCauseqNotAllowedCause		identifier of	
	DEFINED in MAP-ER-DataTypes	:	92	
	RoamingNotAllowedCause		type reference	e ENUMERATED
	DEFINED in MAP-ER-DataTypes	:	96	
	USED in MAP-ER-DataTypes	:	92	
	RoamingNotAllowedParam			e SEQUENCE
	DEFINED in MAP-ER-DataTypes	:	91	
	USED in MAP-Errors	:	116 230	
	USED in MAP-ER-DataTypes	:	14	

12-06	TAG R6.15 Cross Reference Listing 09:33:23 PAGE 93	for MAP-Protocol	2006-
	roamingNumberDEFINED in MAP-CH-DataTypes :		tring
	roamingNumber DEFINED in MAP-CH-DataTypes :		tring
	roamingOutsidePLMNICountryIC-CallsBarr DEFINED in MAP-MS-DataTypes :	redidentifier of Named Number, 1126	21
	roamingOutsidePLMNIC-CallsBarred DEFINED in MAP-MS-DataTypes :	identifier of Named Number, 1125	20
	roamingOutsidePLMNOG-CallsBarred DEFINED in MAP-MS-DataTypes :		18
	roamingOutsidePLMN-Barred DEFINED in MAP-MS-DataTypes :		22
	roamingOutsidePLMN-CountryBarred DEFINED in MAP-MS-DataTypes :		23
	roamingRestrictedInSgsnDueToUnsupporte DEFINED in MAP-MS-DataTypes :		
	roamingRestrictedInSgsnDueToUnsuppport DEFINED in MAP-MS-DataTypes :		
	roamingRestrictionDueToUnsupportedFeat DEFINED in MAP-MS-DataTypes :		
	roamingRestrictionDueToUnsupportedFeat DEFINED in MAP-MS-DataTypes :	uridentifier of [4] NULL 1429	
19	routeFinding	value reference LCSServiceTy	ypeID,
	DEFINED in MAP-CommonDataTypes :	431	
	routeingAreaIdentity DEFINED in MAP-MS-DataTypes :		У
	routeingNumber		umber
	RouteingNumber	type reference TBCD-STRING	
	DEFINED in MAP-MS-DataTypes : USED in MAP-MS-DataTypes :	113 2040	
	routeSelectFailure	identifier of Named Number,	4
	DEFINED in MAP-MS-DataTypes :		
	routingAreaId DEFINED in MAP-LCS-DataTypes :		3
	routingAreaUpdating DEFINED in MAP-MS-DataTypes :		6
	RoutingInfo		
	DEFINED in MAP-CH-DataTypes : USED in MAP-CH-DataTypes :		

routingInfo DEFINED in MAP-CH-DataTypes	
routingInfo2	
DEFINED in MAP-CH-DataTypes	: 171
RoutingInfoForLCS-Arg	type reference SEQUENCE
DEFINED in MAP-LCS-DataTypes	: 74
USED in MAP-LocationServiceOpe	e: 42 55
USED in MAP-LCS-DataTypes	
RoutingInfoForLCS-Res	type reference SEQUENCE
DEFINED in MAP-LCS-DataTypes	
USED in MAP-LocationServiceOpe	ne: 43 57
USED in MAP-LCS-DataTypes	: 12
RoutingInfoForSM-Arg	type reference SEQUENCE
DEFINED in MAP-SM-DataTypes	
USED in MAP-ShortMessageServio	c: 46 66
USED in MAP-SM-DataTypes	: 14
RoutingInfoForSM-Res	type reference SEQUENCE

12-06	TAG R6.15 Cross Reference Listing for MAP-Protocol 2006- 09:33:23 PAGE 94
	DEFINED in MAP-SM-DataTypes : 78 USED in MAP-ShortMessageServic : 47 68 USED in MAP-SM-DataTypes : 15
7	routingToNearestCommercialEnterprisevalue reference LCSServiceTypeID,
,	DEFINED in MAP-CommonDataTypes : 418
	rssidentifier of Named Number, 7 DEFINED in MAP-CommonDataTypes : 361
	ruf-Outcomeidentifier of [0] RUF-Outcome DEFINED in MAP-CH-DataTypes : 391
	RUF-Outcometype reference ENUMERATED DEFINED in MAP-CH-DataTypes : 395 USED in MAP-CH-DataTypes : 391
	sai-Presentidentifier of [9] NULL DEFINED in MAP-MS-DataTypes : 2116
	sai-Presentidentifier of [6] NULL DEFINED in MAP-MS-DataTypes : 2130
	sai-Presentidentifier of [7] NULL DEFINED in MAP-LCS-DataTypes : 346
	sai-Presentidentifier of [17] NULL DEFINED in MAP-LCS-DataTypes : 484
	sc-AddressNotIncludedidentifier of Named Number, 0 DEFINED in MAP-SM-DataTypes : 193
	sc-Congestionidentifier of Named Number, 4 DEFINED in MAP-ER-DataTypes : 144
	secondServiceAllowedidentifier of Named Number, 1 DEFINED in MAP-CH-DataTypes : 181
	segmentationProhibitedidentifier of NULL DEFINED in MAP-MS-DataTypes : 323
	segmentationProhibitedidentifier of NULL DEFINED in MAP-MS-DataTypes : 768
Algori	selectedGSM-Algorithmidentifier of [2] SelectedGSM-
J -	DEFINED in MAP-MS-DataTypes : 662
	SelectedGSM-Algorithmtype reference OCTET STRING DEFINED in MAP-MS-DataTypes : 699 USED in MAP-MS-DataTypes : 662
	selectedLSAIdentityidentifier of [4] LSAIdentity DEFINED in MAP-MS-DataTypes : 2127
	selectedLSA-Ididentifier of [5] LSAIdentity DEFINED in MAP-MS-DataTypes : 2112
	selectedRab-Ididentifier of [4] RAB-Id

DEFINED in MAP-MS-DataTypes : 648

selectedRab-Id.....identifier of [4] RAB-Id

DEFINED in MAP-MS-DataTypes 664

selectedUMTS-Algorithms.....identifier of [5] SelectedUMTS-

Algorithms

: DEFINED in MAP-MS-DataTypes 606

SelectedUMTS-Algorithms.....type reference SEQUENCE

DEFINED in MAP-MS-DataTypes : 613
USED in MAP-MS-DataTypes : 606

661

selectedUMTS-Algorithms.....identifier of [1] SelectedUMTS-

Algorithms

DEFINED in MAP-MS-DataTypes : 661

 $\verb|sendAuthenticationInfo.....information| object reference|$

OPERATION, Information Object

DEFINED in MAP-MobileServiceOpera : 358

USED in MAP-Protocol : 26 USED in MAP-MobileServiceOpera : 45

SendAuthenticationInfoArg.....type reference SEQUENCE

DEFINED in MAP-MS-DataTypes : 765
USED in MAP-MobileServiceOpera : 129 360
USED in MAP-MS-DataTypes : 43

```
TAG R6.15 Cross Reference Listing for MAP-Protocol
                                                                                      2006-
12-06 09:33:23 PAGE 95
        SendAuthenticationInfoRes.....type reference [3] SEQUENCE
           DEFINED in MAP-MS-DataTypes : 793
USED in MAP-MobileServiceOpera : 130 367
USED in MAP-MS-DataTypes : 44
        sendEndSignal.....information object reference
OPERATION, Information Object
           DEFINED in MAP-MobileServiceOpera : 327
              USED in MAP-Protocol : 22 122
USED in MAP-MobileServiceOpera : 39
        SendEndSignal-Arg.....type reference [3] SEQUENCE
           DEFINED in MAP-MS-DataTypes : 704
USED in MAP-MobileServiceOpera : 125
USED in MAP-MS-DataTypes : 39
        sendGroupCallEndSignal.....information object reference
OPERATION, Information Object
           DEFINED in MAP-Group-Call-Operati : 55
USED in MAP-Protocol : 105 135
USED in MAP-Group-Call-Operati : 14
        SendGroupCallEndSignalArg.....type reference SEQUENCE
           DEFINED in MAP-GR-DataTypes : 74
USED in MAP-Group-Call-Operati : 34 57
USED in MAP-GR-DataTypes : 16
        SendGroupCallEndSignalRes.....type reference SEQUENCE
           DEFINED in MAP-GR-DataTypes : 79
USED in MAP-Group-Call-Operati : 35 59
               USED in MAP-GR-DataTypes
                                                         17
       sendIdentification.....information object reference
OPERATION, Information Object
           DEFINED in MAP-MobileServiceOpera : 207
USED in MAP-Protocol : 19 122
               USED in MAP-MobileServiceOpera :
                                                        18
        SendIdentificationArg.....type reference SEQUENCE DEFINED in MAP-MS-DataTypes : 317
USED in MAP-MobileServiceOpera : 117 209
              USED in MAP-MS-DataTypes :
                                                        22
        SendIdentificationRes.....type reference [3] SEQUENCE DEFINED in MAP-MS-DataTypes : 332
USED in MAP-MobileServiceOpera : 118 211
               USED in MAP-MS-DataTypes :
        sendIMSI.....information object reference
OPERATION, Information Object
           DEFINED in MAP-OperationAndMainte : 80
USED in MAP-Protocol : 52 128
USED in MAP-OperationAndMainte : 15
```

sendRoutingInfoinformation ob OPERATION, Information Object	ject reference
DEFINED in MAP-CallHandlingOperat : 78	
USED in MAP-Protocol : 58 129	
USED in MAP-CallHandlingOperat : 13	
5 1	
SendRoutingInfoArgtype refere	nce SEQUENCE
DEFINED in MAP-CH-DataTypes : 91	
USED in MAP-CallHandlingOperat : 54 81	
USED in MAP-CH-DataTypes : 14	
72	
sendRoutingInfoForGprsinformation ob	ject reference
OPERATION, Information Object	5
DEFINED in MAP-MobileServiceOpera : 451	
USED in MAP-Protocol : 38 127	
USED in MAP-MobileServiceOpera : 61	
oblb in hin hobiteberviceopera .	
SendRoutingInfoForGprsArgtype refere	nce SEQUENCE
DEFINED in MAP-MS-DataTypes : 1917	
USED in MAP-MobileServiceOpera : 152 453	
USED in MAP-MS-DataTypes : 130	
SendRoutingInfoForGprsRestype refere	nce SEQUENCE
DEFINED in MAP-MS-DataTypes : 1924	
USED in MAP-MobileServiceOpera : 153 455	
USED in MAP-MS-DataTypes : 131	
sendRoutingInfoForLCSinformation ob	iect reference
OPERATION, Information Object	, 555 151515166
or Entiron, information object	

12-06	TAG R6.15		Reference	Listing	for MA	P-Protocol	2006-
	USED i	n MAP-Pro	cationServi otocol cationServi	:	112	136	
OPERAT	sendRoutingl	ion Objec	ct				reference
	USED i	n MAP-Pro	ortMessageS otocol ortMessageS	:		133	
	DEFINED i USED i	n MAP-CH- n MAP-Cal	DataTypes llHandling(DataTypes	: Operat :	148 55		[3] SEQUENCE
	sendSubscrik DEFINED i		DataTypes			ifier of [(O] NULL
100						reference	LCSServiceTypeID,
101			nmonDataTyr			reference	LCSServiceTypeID,
101			nmonDataTyr				
102			nmonDataTyr			reference	LCSServiceTypeID,
103	serv103				value	reference	LCSServiceTypeID,
			nmonDataTyr			reference	LCSServiceTypeID,
104	DEFINED i	.n MAP-Cor	nmonDataTyr	pes :	477		
105			nmonDataTyr			reference	LCSServiceTypeID,
106	serv106				value	reference	LCSServiceTypeID,
			nmonDataTyr			reference	LCSServiceTypeID,
107			nmonDataTyr				
108			nmonDataTyr			reference	LCSServiceTypeID,
109						reference	LCSServiceTypeID,
			nmonDataTyr			reference	LCSServiceTypeID,
110	DETATIO	•••••	· • • • • • • • • • • • • • • • • • • •	• • • • • • •	varue	rererence	repretates Arcetabeth,

	DEFINED in MAP-CommonDataTypes	:	483		
111	serv111		.value	reference	LCSServiceTypeID,
111	DEFINED in MAP-CommonDataTypes	:	484		
112	serv112		.value	reference	LCSServiceTypeID,
112	DEFINED in MAP-CommonDataTypes	:	485		
113	serv113		.value	reference	LCSServiceTypeID,
113	DEFINED in MAP-CommonDataTypes	:	486		
114	serv114		.value	reference	LCSServiceTypeID,
114	DEFINED in MAP-CommonDataTypes	:	487		
115	serv115		.value	reference	LCSServiceTypeID,
113	DEFINED in MAP-CommonDataTypes	:	488		
116	serv116		.value	reference	LCSServiceTypeID,
110	DEFINED in MAP-CommonDataTypes	:	489		
117	serv117		.value	reference	LCSServiceTypeID,
117	DEFINED in MAP-CommonDataTypes	:	490		
118	serv118		.value	reference	LCSServiceTypeID,
110	DEFINED in MAP-CommonDataTypes	:	491		
119	serv119		.value	reference	LCSServiceTypeID,
117	DEFINED in MAP-CommonDataTypes	:	492		
120	serv120		.value	reference	LCSServiceTypeID,
120	DEFINED in MAP-CommonDataTypes	:	493		
121	serv121		.value	reference	LCSServiceTypeID,
141	DEFINED in MAP-CommonDataTypes	:	494		

12-06	TAG R6.15 Cross Reference Listing for MAP-Protocol 2006- 09:33:23 PAGE 97
122	serv122value reference LCSServiceTypeID,
	DEFINED in MAP-CommonDataTypes : 495
123	serv123value reference LCSServiceTypeID,
123	DEFINED in MAP-CommonDataTypes : 496
104	serv124value reference LCSServiceTypeID,
124	DEFINED in MAP-CommonDataTypes : 497
125	serv125value reference LCSServiceTypeID,
123	DEFINED in MAP-CommonDataTypes : 498
126	serv126value reference LCSServiceTypeID,
120	DEFINED in MAP-CommonDataTypes : 499
127	serv127value reference LCSServiceTypeID,
127	DEFINED in MAP-CommonDataTypes : 500
64	serv64value reference LCSServiceTypeID,
04	DEFINED in MAP-CommonDataTypes : 437
65	serv65value reference LCSServiceTypeID,
65	DEFINED in MAP-CommonDataTypes : 438
66	serv66value reference LCSServiceTypeID,
00	DEFINED in MAP-CommonDataTypes : 439
<i>C</i> 7	serv67value reference LCSServiceTypeID,
67	DEFINED in MAP-CommonDataTypes : 440
68	serv68value reference LCSServiceTypeID,
00	DEFINED in MAP-CommonDataTypes : 441
69	serv69value reference LCSServiceTypeID,
0,5	DEFINED in MAP-CommonDataTypes : 442
70	serv70value reference LCSServiceTypeID,
70	DEFINED in MAP-CommonDataTypes : 443
71	serv71value reference LCSServiceTypeID,
/ ±	DEFINED in MAP-CommonDataTypes : 444
72	serv72value reference LCSServiceTypeID,
72	DEFINED in MAP-CommonDataTypes : 445

73	serv73value	reference LCSServiceTypeID,
	DEFINED in MAP-CommonDataTypes : 446	
74	serv74value	reference LCSServiceTypeID,
74	DEFINED in MAP-CommonDataTypes : 447	,
75	serv75value	reference LCSServiceTypeID,
73	DEFINED in MAP-CommonDataTypes : 448	
76	serv76value	reference LCSServiceTypeID,
70	DEFINED in MAP-CommonDataTypes : 449	
77	serv77value	reference LCSServiceTypeID,
, ,	DEFINED in MAP-CommonDataTypes : 450	
78	serv78value	e reference LCSServiceTypeID,
, 0	DEFINED in MAP-CommonDataTypes : 451	
79	serv79value	e reference LCSServiceTypeID,
	DEFINED in MAP-CommonDataTypes : 452	
80	serv80value	e reference LCSServiceTypeID,
	DEFINED in MAP-CommonDataTypes : 453	
81	serv81value	e reference LCSServiceTypeID,
	DEFINED in MAP-CommonDataTypes : 454	
82	serv82value	e reference LCSServiceTypeID,
	DEFINED in MAP-CommonDataTypes : 455	
83	serv83value	e reference LCSServiceTypeID,
	DEFINED in MAP-CommonDataTypes : 456	
84	serv84value	e reference LCSServiceTypeID,
J 1	DEFINED in MAP-CommonDataTypes : 457	

12-06	TAG R6.15 Cross Reference Listing for MAP-Protocol 09:33:23 PAGE 98	2006-
	serv85value reference	LCSServiceTypeID,
85	DEFINED in MAP-CommonDataTypes : 458	
0.5	serv86value reference	LCSServiceTypeID,
86	DEFINED in MAP-CommonDataTypes : 459	
87	serv87value reference	LCSServiceTypeID,
87	DEFINED in MAP-CommonDataTypes : 460	
0.0	serv88value reference	LCSServiceTypeID,
88	DEFINED in MAP-CommonDataTypes : 461	
89	serv89value reference	LCSServiceTypeID,
09	DEFINED in MAP-CommonDataTypes : 462	
90	serv90value reference	LCSServiceTypeID,
90	DEFINED in MAP-CommonDataTypes : 463	
91	serv91value reference	LCSServiceTypeID,
91	DEFINED in MAP-CommonDataTypes : 464	
92	serv92value reference	LCSServiceTypeID,
92	DEFINED in MAP-CommonDataTypes : 465	
93	serv93value reference	LCSServiceTypeID,
<i>)</i>	DEFINED in MAP-CommonDataTypes : 466	
94	serv94value reference	LCSServiceTypeID,
J 1	DEFINED in MAP-CommonDataTypes : 467	
95	serv95value reference	LCSServiceTypeID,
	DEFINED in MAP-CommonDataTypes : 468	
96	serv96value reference	LCSServiceTypeID,
	DEFINED in MAP-CommonDataTypes : 469	
97	serv97value reference	LCSServiceTypeID,
<i>.</i>	DEFINED in MAP-CommonDataTypes : 470	
98	serv98value reference	LCSServiceTypeID,
20	DEFINED in MAP-CommonDataTypes : 471	
99	serv99value reference	LCSServiceTypeID,
פע	DEFINED in MAP-CommonDataTypes : 472	

	treAddress in MAP-SM-DataTypes			of	[2] AddressString
	treAddress in MAP-SM-DataTypes			of	AddressString
	treAddressin MAP-SM-DataTypes			of	AddressString
	treAddressDA in MAP-SM-DataTypes			of	[4] AddressString
	treAddressOA in MAP-SM-DataTypes			of	[4] AddressString
	ngeDP in MAP-MS-DataTypes			of	Named Number, 18
	nted in MAP-MS-DataTypes			of	Named Number, 0
ServiceIndicator	icator			of	[2]
	in MAP-SS-DataTypes			ance	A RIT STRING
DEFINED	in MAP-SS-DataTypes in MAP-SS-DataTypes	:	317	51100	S BIT SIKING
	in MAP-MS-DataTypes			of	[1] ServiceKey
	in MAP-MS-DataTypes			of	ServiceKey
-	in MAP-MS-DataTypes			of	ServiceKey

12-06	TAG R6.	15 Cross PAGE 99	Reference	Listing	for MAP	Protoco	1	2006-
	DEFINE	y D in MAP-MS D in MAP-MS	-DataTypes	:	1618			1705
1824	1835 1899		-Dacalypes	•	73	970 1:	334 1611	1/65
	serviceKe DEFINE	y O in MAP-MS	-DataTypes		identi 1785	fier of	[1] Service	еКеу
		y D in MAP-MS				fier of a	ServiceKey	
	serviceKe DEFINE	y D in MAP-MS	-DataTypes	:	identi 1835	fier of :	ServiceKey	
		y D in MAP-MS				fier of :	ServiceKey	
		y O in MAP-MS				fier of	ServiceKey	
		quest D in MAP-MS				fier of D	Named Numb	er, 7
	DEFINE	pe D in MAP-MS D in MAP-MS	-DataTypes	:	1378	reference	SEQUENCE	
'10110		pe		 .	value	reference	e SS-Code,	
		o in MAP-SS		:				
	serviceTy DEFINE	peIdentity. D in MAP-MS	-DataTypes	:	identi 1379	fier of I	LCSService'	TypeID
	serviceTy	peList			identi	fier of	[5] Service	eTypeList
		o in MAP-MS						
		peList				eference	SEQUENCE (OF
		o in MAP-MS						
	USE	o in MAP-MS	-DataTypes	:	1324			
		tworkEnhanc D in MAP-MS				fier of D	Named Numb	er, 16
\cap D \Box D Λ Π	setReport	ingState		ir	nformati	on object	t reference	е
OPERAI		nacion obje D in MAP-Ca		Operat :	131			
		D in MAP-Pr				129		
		o in MAP-Ca						
		ingStateArg				reference	SEQUENCE	
	DEFINE	o in MAP-CH	-DataTypes		310	122		
		O in MAP-Ca O in MAP-CH				133		
	USE.	TIL MAP-CH	-naraiyhes	:	∠3			
	SetReport	ingStateRes			type r	eference	SEQUENCE	
	DEFINE	o in MAP-CH	-DataTypes	:	325			
		o in MAP-Ca				135		
	USE	O in MAP-CH	-DataTypes	:	24			

	sgsn DEFINED in MAP-MS-DataTypes			of	Named Number, 1
	sgsn DEFINED in MAP-OM-DataTypes			of	Named Number, 2
	sgsn DEFINED in MAP-CommonDataTypes			of	Named Number, 0
	sgsn-Address DEFINED in MAP-MS-DataTypes			of	GSN-Address
	sgsn-Address DEFINED in MAP-MS-DataTypes			of	[0] GSN-Address
	sgsn-Address DEFINED in MAP-MS-DataTypes			of	[1] GSN-Address
Subscri	sgsn-CAMEL-SubscriptionInfo iptionInfo DEFINED in MAP-MS-DataTypes			of	[17] SGSN-CAMEL-
	SGSN-CAMEL-SubscriptionInfo DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes	:	939	enc	e SEQUENCE

12-06	TAG R6.1 09:33:23		Reference	Listing	for MAP	-Protoco	ol	2006-
			 -DataTypes			fier of	[0]	SGSN-Capability
		in MAP-MS	 -DataTypes -DataTypes	:	454	eference	e SE(QUENCE
	SGSN-Event DEFINED USED	in MAP-OM	 -DataTypes -DataTypes	:	162	eference	e BI'	I STRING
		in MAP-OM	 -DataTypes -DataTypes	:	114	eference	e BI'	I STRING
Interf	sgsn-List. aceList DEFINED					fier of	[2]	SGSN-
	DEFINED	in MAP-OM	-DataTypes	:	145			SGSN-EventList
Addres	sgsn-Numbe sString DEFINED		-DataTypes			fier of	[1]	ISDN-
Addres	sgsn-Numbe sString DEFINED		-DataTypes			fier of	[1]	ISDN-
	_		 -DataTypes			fier of	ISDI	N-AddressString
Addres	sgsn-Numbe sString DEFINED		-DataTypes			fier of	[3]	ISDN-
Addres	sgsn-Numbe sString DEFINED		-DataTypes			fier of	[1]	ISDN-
			 -DataTypes			fier of	[2]	TraceDepth
	DEFINED	in MAP-LC	S-DataType:	s :	530			ed Number, 6
		in MAP-ER	-DataTypes	:	192			
	DEFINED	in MAP-MS	-DataTypes	:	421			ed Number, 4 eleserviceCode,
'00100	010'B DEFINED	in MAP-TS	-Code	:	45			
'00100	001'B	geMT-PP in MAP-TS		:		referend	ce Te	eleserviceCode,

	shortTermDe	enial.				inform	ation	ol	oject	refere	nce
ERROR,	Information										
	DEFINED	in MA	P-Errors		:	418					
	USED	in MA	P-Supplemer	taryServ	i :	54	276				
	USED	in MA	P-Errors		:	73					
	ShortTermDe	enialP	aram			tvpe r	efere	ence	e SEOU	ENCE	
			P-ER-DataTy						~		
			P-Errors				420)			
			P-ER-DataTy								
	signalInfo					identi	fier	of	Signa	lInfo	
	_		P-CommonDat						· J		
	SignalInfo					tvpe r	efere	ence	e OCTE	T STRI	NG
			P-CommonDat								
			P-CommonDat					:	230		
			P-SM-DataTy							121	127
			P-ER-DataTy								
	signalInfo					identi	fier	of	Signa	lInfo	
			P-CommonDat						· J		
	signalInfo					identi	fier	of	LongS	ignalI	nfo
			P-CommonDat						3	3	
	sipUrl					identi	fier	of	Named	Numbe	r, 4
			P-LCS-Data1								

```
TAG R6.15 Cross Reference Listing for MAP-Protocol
                                                                   2006-
12-06 09:33:23 PAGE 101
      {\tt skipSubscriberDataUpdate.....} identifier of {\tt [1] NULL}
        DEFINED in MAP-MS-DataTypes
      slr-ArgExtensionContainer.....identifier of [7] SLR-
ArgExtensionContainer
        DEFINED in MAP-LCS-DataTypes
      SLR-ArgExtensionContainer.....type reference SEQUENCE
        DEFINED in MAP-ExtensionDataTypes : 36
USED in MAP-LCS-DataTypes : 49
                                                 474
           USED in MAP-ExtensionDataTypes : 17
      slr-Arg-PCS-Extensions.....identifier of [1] SLR-Arg-PCS-
Extensions
        DEFINED in MAP-ExtensionDataTypes :
      SLR-Arg-PCS-Extensions.....type reference SEQUENCE
        DEFINED in MAP-ExtensionDataTypes : 61
           USED in MAP-ExtensionDataTypes :
      smsCallBarringSupportIndicator.....identifier of [7] NULL
        DEFINED in MAP-MS-DataTypes
      SMS-CAMEL-TDP-Data.....type reference SEQUENCE
        DEFINED in MAP-MS-DataTypes : 1783
           USED in MAP-MS-DataTypes
                                           1779
      sms-CAMEL-TDP-DataList.....identifier of [0] SMS-CAMEL-TDP-
DataList
        DEFINED in MAP-MS-DataTypes
                                     : 1764
      SMS-CAMEL-TDP-DataList.....type reference SEQUENCE OF
        DEFINED in MAP-MS-DataTypes : 1778
           USED in MAP-MS-DataTypes
                                      : 1764
      \verb|sms-CollectedInfo..... identifier of Named Number, 1|\\
        DEFINED in MAP-MS-DataTypes
                                      : 1793
      SMS-CSI.....type reference SEQUENCE
        DEFINED in MAP-MS-DataTypes : 1763
USED in MAP-MS-DataTypes : 941
                                           941 944 1497 1501 2341
2347
      \verb|sms-DELIVER|..... identifier of Named Number, 0|
        DEFINED in MAP-MS-DataTypes
      {\tt sms-DeliveryRequest......identifier of Named Number, 2}
        DEFINED in MAP-MS-DataTypes
                                      : 1795
      \verb|sms-STATUS-REPORT..... identifier of Named Number, 2|
        DEFINED in MAP-MS-DataTypes
      sms-SUBMIT-REPORT.....identifier of Named Number, 1
         DEFINED in MAP-MS-DataTypes
      sms-TriggerDetectionPoint.....identifier of SMS-
TriggerDetectionPoint
        DEFINED in MAP-MS-DataTypes : 1509
```

sms-TriggerDetectionPoint.....identifier of [0] SMS-TriggerDetectionPoint DEFINED in MAP-MS-DataTypes : 1784 SMS-TriggerDetectionPoint.....type reference ENUMERATED DEFINED in MAP-MS-DataTypes : 1792 USED in MAP-MS-DataTypes : 1509 1784 sm-DeliveryFailure.....information object reference ERROR, Information Object FINED in MAP-Errors : 438
USED in MAP-ShortMessageServic : 39 90 108
USED in MAP-Errors : 78 DEFINED in MAP-Errors SM-DeliveryFailureCause.....type reference SEQUENCE DEFINED in MAP-ER-DataTypes : 148
USED in MAP-Errors : 108
USED in MAP-ER-DataTypes : 19 440 sm-DeliveryOutcome.....identifier of SM-DeliveryOutcome DEFINED in MAP-SM-DataTypes : SM-DeliveryOutcome.....type reference ENUMERATED DEFINED in MAP-SM-DataTypes : 165 USED in MAP-SM-DataTypes : 26 26 145 156 ${\tt SM-EnumeratedDeliveryFailureCause......type\ reference\ {\tt ENUMERATED}}$ DEFINED in MAP-ER-DataTypes : 139
USED in MAP-ER-DataTypes : 149

12-06	TAG R6.15 Cross Reference Listing 09:33:23 PAGE 102	for MAP-Pr	rotocol	2006-
Enumera	sm-EnumeratedDeliveryFailureCause		r of SM-	
	DEFINED in MAP-ER-DataTypes :	149		
	sm-RP-DA DEFINED in MAP-SM-DataTypes :		r of SM-R	P-DA
	sm-RP-DA DEFINED in MAP-SM-DataTypes :		r of SM-R	P-DA
	SM-RP-DA	type refe	rence CHO	ICE
	DEFINED in MAP-SM-DataTypes :	131		
	USED in MAP-SM-DataTypes :	106 1	.19	
	sm-RP-MTI DEFINED in MAP-SM-DataTypes :		r of [8]	SM-RP-MTI
	SM-RP-MTI	type refe	rence INT	EGER
	DEFINED in MAP-SM-DataTypes :	65		
	USED in MAP-SM-DataTypes :	62		
	sm-RP-OA	identifie	r of SM-R	P-OA
	DEFINED in MAP-SM-DataTypes :	107		
	sm-RP-OA	identifie	r of SM-R	P-OA
	DEFINED in MAP-SM-DataTypes :			
	SM-RP-OA	tvpe refe	rence CHO	TCE
	DEFINED in MAP-SM-DataTypes :		201100 0110	
	USED in MAP-SM-DataTypes :	107 1	20	
	sm-RP-PRI	identifie	r of [1]	BOOLEAN
	DEFINED in MAP-SM-DataTypes :			
	sm-RP-SMEA	identifie	r of [9]	SM-RP-SMEA
	DEFINED in MAP-SM-DataTypes :			
	SM-RP-SMEA	type refe	rence OCT	ET STRING
	DEFINED in MAP-SM-DataTypes :			
	USED in MAP-SM-DataTypes :	63		
	sm-RP-UI	identifie	r of Sign	alInfo
	DEFINED in MAP-SM-DataTypes :	108		
	sm-RP-UI	identifie	r of Sign	alInfo
	DEFINED in MAP-SM-DataTypes :			
	sm-RP-UI	identifie	r of Sign	alInfo
	DEFINED in MAP-SM-DataTypes :			
	sm-RP-UI	identifie	r of Sian	alInfo
	DEFINED in MAP-SM-DataTypes :		i or bryn	W
	solsaSupportIndicator	identific	r of [3]	NITIT.T.
	DEFINED in MAP-MS-DataTypes :		.1 (1 [2] .	иолп
	solsaSupportIndicator		r of NULL	
	DEFINED in MAP-MS-DataTypes :	455		

Withdra	specificCSIDeletedList	identifier of [14] SpecificCSI-
WICHGE	DEFINED in MAP-MS-DataTypes	: 2346
Withdra	specificCSI-Withdraw	identifier of [15] SpecificCSI-
Wight	DEFINED in MAP-MS-DataTypes	: 1441
	SpecificCSI-Withdraw	
	DEFINED in MAP-MS-DataTypes	: 1444
	USED in MAP-MS-DataTypes	: 1441 2346
	splitLeg	identifier of Named Number, 1
	DEFINED in MAP-MS-DataTypes	: 1740
	sres	identifier of SRES
	DEFINED in MAP-MS-DataTypes	: 356
	SRES	type reference OCTET STRING
	DEFINED in MAP-MS-DataTypes	: 385
	USED in MAP-MS-DataTypes	: 356
	ss	identifier of Named Number, 4
	DEFINED in MAP-OM-DataTypes	: 155
	ss-AccessBarred	identifier of Named Number, 5

12-06	TAG R6.15 Cross Reference Listing for MAP-Protocol 09:33:23 PAGE 103	2006-
	DEFINED in MAP-MS-DataTypes : 1113	
	ss-CamelDataidentifier of SS-Came DEFINED in MAP-MS-DataTypes : 1561	elData
	SS-CamelDatatype reference SEQUEN DEFINED in MAP-MS-DataTypes : 1570 USED in MAP-MS-DataTypes : 1561	1CE
	ss-Codeidentifier of SS-Code DEFINED in MAP-MS-DataTypes : 1162	<u> </u>
	ss-Codeidentifier of SS-Code DEFINED in MAP-MS-DataTypes : 1221	<u> </u>
	ss-Codeidentifier of SS-Code DEFINED in MAP-MS-DataTypes : 1292	3
	ss-Codeidentifier of SS-Code DEFINED in MAP-MS-DataTypes : 1305	3
	ss-Codeidentifier of SS-Code DEFINED in MAP-MS-DataTypes : 1393	3
	ss-Codeidentifier of [0] SS- DEFINED in MAP-MS-DataTypes : 2376	-Code
	ss-Codeidentifier of [0] SS- DEFINED in MAP-MS-DataTypes : 2387	-Code
	ss-Codeidentifier of [0] SS- DEFINED in MAP-MS-DataTypes : 2460	-Code
	ss-Codeidentifier of [0] SS- DEFINED in MAP-MS-DataTypes : 2467	-Code
	ss-Codeidentifier of [0] SS-DEFINED in MAP-CommonDataTypes : 567	-Code
	ss-Codeidentifier of SS-Code DEFINED in MAP-SS-DataTypes : 72)
	ss-Codeidentifier of SS-Code DEFINED in MAP-SS-DataTypes : 90	3
	ss-Codeidentifier of SS-Code DEFINED in MAP-SS-DataTypes : 148	3
	ss-Codeidentifier of SS-Code DEFINED in MAP-SS-DataTypes : 161)
	ss-Codeidentifier of SS-Code DEFINED in MAP-SS-DataTypes : 184	>
	ss-Codeidentifier of [0] SS-DEFINED in MAP-SS-DataTypes : 305	-Code
	ss-Codeidentifier of [0] SS- DEFINED in MAP-SS-DataTypes : 328	-Code

			in MAP-SS-DataTypes			fier of	[0]	SS-Cod	9
	SS-Co	ode			.type r	eferenc	e OCT	ET STR	ING
			in MAP-SS-Code						
			in MAP-SupplementaryServi	:	79	228			
		USED	in MAP-MS-DataTypes	:	158	1162	1221	1292	1305
1393	1576	2376	2387						
					2460	2467			
		USED	in MAP-CommonDataTypes	:	80	567			
		USED	in MAP-SS-DataTypes	:	64	72	90	148	161
184	256	271	305						
					328	333			
		USED	in MAP-SS-Code	:	21	25	28	30	32
34	36	40	42						
					48	50	52	54	56
58	60	63	66						
					68	72	75	77	79
81	84	87	90						
					93	96	99	102	104
107	110	112	114						
					117	119	121	123	125
128	130	132	136						
					137	138	139	140	141
142	143	144	145						
					146	147	148	149	150
151	153	156	159						
					161	163	166	168	170
173	175	177							
		USED	in MAP-ER-DataTypes	:	80	129			
	ss-Co	ode		• • •	.ıdenti	iler of	[1]	SS-Cod	9

12-06	TAG R6.15 Cross Reference Listin 09:33:23 PAGE 104	ng for MAP-Protocol 2006-
	DEFINED in MAP-ER-DataTypes	: 129
	ss-csi DEFINED in MAP-MS-DataTypes	
	ss-CSI DEFINED in MAP-MS-DataTypes	identifier of [2] SS-CSI : 1493
	SS-CSI DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes	: 1560
	ss-CSI DEFINED in MAP-MS-DataTypes	identifier of Named Number, 6
	ss-CSI	
	ss-Data DEFINED in MAP-MS-DataTypes	
	ss-Data DEFINED in MAP-SS-DataTypes	
	SS-Data DEFINED in MAP-SS-DataTypes USED in MAP-SS-DataTypes	: 160
ERROR,	ss-ErrorStatus	-
274	USED in MAP-MobileServiceOpera USED in MAP-SupplementaryServi	
274 2	USED in MAP-Errors	: 64
	ss-Event DEFINED in MAP-SS-DataTypes	
	ss-EventList DEFINED in MAP-MS-DataTypes	
	SS-EventList DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes	
EventSp	ss-EventSpecificationpecification	identifier of [3] SS-
		: 277
	SS-EventSpecification DEFINED in MAP-SS-DataTypes USED in MAP-SS-DataTypes	
	SS-ForBS-Code DEFINED in MAP-SS-DataTypes USED in MAP-SupplementaryServi USED in MAP-MS-DataTypes USED in MAP-SS-DataTypes	: 183 : 63 108 126 147 167

	ss-Incompat	ibility			informa	tion	object	refere	nce
ERROR,	Information	Object							
	DEFINED	in MAP-Errors		:	395				
	USED	in MAP-MobileSe	erviceOpera	:	101	294			
	USED	in MAP-Suppleme	entaryServi	:	45	103	140	275	
	USED	in MAP-Errors		:	67				
	CC Incompat	ibilituCauga			+	foren	ac CEO	TENCE	
		ibilityCause				reren	ce seq	OENCE	
	DELINED	in MAP-ER-Data	rypes	:	128	207			
	USED	in MAP-Errors	-	:	106	397			
	USED	in MAP-ER-Data	rypes	:	17				
	SS-Info				type re	feren	ce CHO	ICE	
		in MAP-SS-Data							
	USED	in MAP-Suppleme	entaryServi	:	62	92	110	128	149
		in MAP-SS-Data							
	gg-InfoFor-	CSE			identif	ier o	f [0]	Fv+-SS-	InfoFor-
CSE	55 11110101	СБШ		• • • •	Ideliell	ICI O	_ [O] .	DAC DD	IIIIOIOI
002	DEFINED	in MAP-MS-Data	Гуреѕ	:	2369				
						_			
						feren	ce SEQ	UENCE O	F
		in MAP-SS-Data							
	USED	in MAP-SS-Data	Types	:	27				
	gg-Invocati	onNotification		inf	ormatio	n ohi	ect re	ference	
OPERAT	ION, Informa			. 1111	OTMACIO	11 00)	CCC IC.	LCLCIICC	
		in MAP-Suppleme	entaryServi	:	251				

12-06	TAG R6.15 Cross Reference Listin 09:33:23 PAGE 105	ng f	for MAP-Pr	otoco:	1	2006-
	USED in MAP-Protocol USED in MAP-SupplementaryServi			32		
	SS-InvocationNotificationArg DEFINED in MAP-SS-DataTypes USED in MAP-SupplementaryServi	:	268	rence 53	SEQUE	ENCE
	USED in MAP-SS-DataTypes	:	34			
	SS-InvocationNotificationRes DEFINED in MAP-SS-DataTypes	:	294		SEQUE	ENCE
	USED in MAP-SupplementaryServi USED in MAP-SS-DataTypes	:	70 2 35	55		
	ss-List DEFINED in MAP-MS-DataTypes			r of	[3] SS	S-List
	ss-List DEFINED in MAP-MS-DataTypes			r of	[2] SS	S-List
	ss-List DEFINED in MAP-CH-DataTypes			r of	[1] SS	S-List
	SS-List			rence	SEQUE	ENCE OF
	DEFINED in MAP-SS-DataTypes			00 1.	400	
	USED in MAP-MS-DataTypes USED in MAP-CH-DataTypes	:	151 14 56 1	57 ·	±⊿8 172	
	USED in MAP-SS-DataTypes	:	26	57 .	1/2	
				_		
	ss-List2 DEFINED in MAP-CH-DataTypes			r of	[18] 8	SS-List
ERROR,	ss-NotAvailable		.informati	on ob	ject 1	reference
,	DEFINED in MAP-Errors	:	381			
	USED in MAP-MobileServiceOpera			74		
	USED in MAP-SupplementaryServi	:		78		
			65			
	SS-NotAvailableParam		type refe	rence	SEOUE	ENCE
	DEFINED in MAP-ER-DataTypes			101100	рпбог	11.01
				83		
	USED in MAP-ER-DataTypes					
	an Obstant				[4] ==	-t
	ss-Status DEFINED in MAP-MS-DataTypes	:	1172	r oi	[4] E2	Kt-SS-Status
	ss-Status DEFINED in MAP-MS-DataTypes			r of	[4] Ex	kt-SS-Status
	ss-Status DEFINED in MAP-MS-DataTypes			r of	[4] Ex	kt-SS-Status
	ss-Status DEFINED in MAP-MS-DataTypes			r of 1	Ext-SS	G-Status
	ss-Status DEFINED in MAP-MS-DataTypes			r of 1	Ext-SS	G-Status
	ss-Status DEFINED in MAP-MS-DataTypes		identifie 2378	r of	[2] Ex	kt-SS-Status

	ss-Statusidentifier of [2] Ext-SS-Status DEFINED in MAP-MS-DataTypes : 2389
	ss-Statusidentifier of [1] Ext-SS-Status DEFINED in MAP-CommonDataTypes : 568
	ss-Statusidentifier of [4] SS-Status DEFINED in MAP-SS-DataTypes : 100
	SS-Statustype reference OCTET STRING
	DEFINED in MAP-SS-DataTypes : 108
	USED in MAP-Errors : 101 377
	USED in MAP-SS-DataTypes : 16 100 157 162 190
215	334
	USED in MAP-ER-DataTypes : 65 131
	ss-Statusidentifier of [4] SS-Status
	DEFINED in MAP-SS-DataTypes : 157
	ss-Statusidentifier of [4] SS-Status DEFINED in MAP-SS-DataTypes : 162
	ss-Statusidentifier of SS-Status

```
TAG R6.15 Cross Reference Listing for MAP-Protocol
                                                                         2006-
12-06 09:33:23 PAGE 106
                                       :
         DEFINED in MAP-SS-DataTypes
                                              190
      {\tt ss-Status}..... {\tt identifier of [0] SS-Status}
         DEFINED in MAP-SS-DataTypes
                                               215
      ss-Status.....identifier of [1] SS-Status
         DEFINED in MAP-SS-DataTypes
                                               334
      ss-Status.....identifier of [4] SS-Status
         DEFINED in MAP-ER-DataTypes
                                               131
      ss-SubscriptionOption.....identifier of SS-
SubscriptionOption
         DEFINED in MAP-MS-DataTypes
      ss-SubscriptionOption.....identifier of SS-
SubscriptionOption
         DEFINED in MAP-SS-DataTypes
      SS-SubscriptionOption.....type reference CHOICE
         DEFINED in MAP-SS-DataTypes : 170
USED in MAP-MS-DataTypes : 150 1294
USED in MAP-SS-DataTypes : 17 163
            USED in MAP-SS-DataTypes
                                          :
                                                17
      ss-SubscriptionViolation.....information object reference
ERROR, Information Object
            FINED in MAP-Errors : 388
USED in MAP-MobileServiceOpera : 102 292
USED in MAP-SupplementaryServi : 44 139 160 236
USED in MAP-Errors : 66
         DEFINED in MAP-Errors
            USED in MAP-Errors
      SS-SubscriptionViolationParam.....type reference SEQUENCE
         DEFINED in MAP-ER-DataTypes : 300
USED in MAP-Errors : 149
                                                    390
            USED in MAP-ER-DataTypes
                                                58
      \verb|startMonitoring..... identifier of Named Number, 1|\\
         DEFINED in MAP-CH-DataTypes
                                         :
                                               319
      stateAttributes.....identifier of [5] StateAttributes
         DEFINED in MAP-GR-DataTypes
                                          :
      StateAttributes.....type reference SEQUENCE
         DEFINED in MAP-GR-DataTypes : 122
            USED in MAP-GR-DataTypes
      statusReport.....information object reference
OPERATION, Information Object
         DEFINED in MAP-CallHandlingOperat : 146
            USED in MAP-Protocol
            USED in MAP-CallHandlingOperat: 17
      StatusReportArg.....type reference SEQUENCE
         DEFINED in MAP-CH-DataTypes : 340
USED in MAP-CallHandlingOperat : 62
            USED in MAP-CH-DataTypes
      StatusReportRes.....type reference SEQUENCE DEFINED in MAP-CH-DataTypes : 376
USED in MAP-CallHandlingOperat : 63 150
```

	USED in MAP-CH-DataTypes	:	26
	stopMonitoring DEFINED in MAP-CH-DataTypes		
	storedMSISDN DEFINED in MAP-SM-DataTypes		
	storedMSISDN DEFINED in MAP-SM-DataTypes		-
	SubBusyForMT-SMS-Param DEFINED in MAP-ER-DataTypes USED in MAP-Errors USED in MAP-ER-DataTypes	:	308 132 434
	subscribedEnhancedDialledServices DEFINED in MAP-MS-DataTypes		
ERROR,	subscriberBusyForMT-SMS Information Object DEFINED in MAP-Errors USED in MAP-ShortMessageServic USED in MAP-Errors	:	432 38 107
	SubscriberData DEFINED in MAP-MS-DataTypes		

```
TAG R6.15 Cross Reference Listing for MAP-Protocol
                                                                          2006-
12-06 09:33:23 PAGE 107
                                        : 63 846
            USED in MAP-MS-DataTypes
      subscriberDataStored......identifier of [1] AgeIndicator
         DEFINED in MAP-MS-DataTypes
                                                 248
      SubscriberId.....type reference CHOICE
         DEFINED in MAP-CommonDataTypes : 318
USED in MAP-CommonDataTypes : 33
       subscriberIdentity.....identifier of [0]
SubscriberIdentity
         DEFINED in MAP-MS-DataTypes
       subscriberIdentity.....identifier of [0]
SubscriberIdentity
         DEFINED in MAP-MS-DataTypes
       subscriberIdentity.....identifier of [0]
SubscriberIdentity
         DEFINED in MAP-MS-DataTypes
      {\tt SubscriberIdentity......type\ reference\ CHOICE}
         DEFINED in MAP-CommonDataTypes : 387

USED in MAP-MS-DataTypes : 190 2243 2257 2358

USED in MAP-CommonDataTypes : 43

USED in MAP-LCS-DataTypes : 38 76 81
      \verb|subscriberInfo| .... identifier of SubscriberInfo|
         DEFINED in MAP-MS-DataTypes
                                          : 2017
      SubscriberInfo.....type reference SEQUENCE
         DEFINED in MAP-MS-DataTypes : 2021
USED in MAP-MS-DataTypes : 106 2017 2250
USED in MAP-CH-DataTypes : 39 156
      \verb|subscriberInfo| .... identifier of SubscriberInfo|
         DEFINED in MAP-MS-DataTypes
                                         : 2250
       subscriberInfo......identifier of [7] SubscriberInfo
         DEFINED in MAP-CH-DataTypes
                                           :
                                                 156
      subscriberLocationReport.....information object reference
OPERATION, Information Object
         DEFINED in MAP-LocationServiceOpe :
            USED in MAP-Protocol :
            USED in MAP-LocationServiceOpe : 15
       SubscriberLocationReport-Arg.....type reference SEQUENCE
         DEFINED in MAP-LCS-DataTypes : 463
USED in MAP-LocationServiceOpe : 46
USED in MAP-LCS-DataTypes : 15
      SubscriberLocationReport-Res.....type reference SEQUENCE
         DEFINED in MAP-LCS-DataTypes : 539
USED in MAP-LocationServiceOpe : 47
                                               47
16
            USED in MAP-LCS-DataTypes :
       subscriberNotMemberOfCUG.....identifier of Named Number, 1
         DEFINED in MAP-ER-DataTypes : 124
```

subscriberNotSC-Subscriber.....identifier of Named Number, 6 DEFINED in MAP-ER-DataTypes : 146 subscriberState......identifier of [1] SubscriberState DEFINED in MAP-MS-DataTypes 2023 subscriberState.....identifier of [1] NULL DEFINED in MAP-MS-DataTypes 2086 SubscriberState.....type reference CHOICE DEFINED in MAP-MS-DataTypes : 2170

USED in MAP-MS-DataTypes : 110 2023 subscriberStatus.....identifier of [3] SubscriberStatus DEFINED in MAP-MS-DataTypes : 1065 SubscriberStatus.....type reference ENUMERATED DEFINED in MAP-MS-DataTypes : 1084
USED in MAP-MS-DataTypes : 65 65 1065 $\verb|subscriptionWithdraw|...... identifier of Named Number, 1|$ DEFINED in MAP-MS-DataTypes 296 subsequentHandoverFailure.....information object reference ERROR, Information Object FINED in MAP-Errors : 266
USED in MAP-MobileServiceOpera : 90 353 DEFINED in MAP-Errors

12-06	TAG R6.15 Cross Reference Listing for MAP-Protocol 09:33:23 PAGE 108								
	USED in M	AP-Errors	:	37					
					of Name	ed Numbe	er, 0		
		fer AP-SM-DataTypes			of Name	ed Numbe	er, 2		
	SuperChargerInfotype reference CHOICE DEFINED in MAP-MS-DataTypes : 246								
		AP-MS-DataTypes			3				
	superChargerSup DEFINED in M	portedInHLR AP-MS-DataTypes	:	.identifier 859	of [27]	AgeInd	licator		
<pre>superChargerSupportedInServingNetworkEntidentifier of [3] SuperChargerInfo</pre>									
		AP-MS-DataTypes	:	241					
<pre>superChargerSupportedInServingNetworkEntidentifier of [2] SuperChargerInfo</pre>									
-	2	AP-MS-DataTypes	:	458					
		rvice AP-MS-DataTypes			of Name	ed Numbe	er, 3		
Suppor	tedCamelPhases	hases			of [0]				
		AP-MS-DataTypes							
Suppor	tedCamelPhases	hases AP-MS-DataTypes			oi [4]				
		hases			of [6]				
Suppor	tedCamelPhases	AP-MS-DataTypes			OI [6]				
		hases			nce RTT	י פייס דאמ	<u>.</u>		
		AP-MS-DataTypes			ince bil	. SIRING	ī		
2270	USED in M. 2443	AP-MS-DataTypes	:	77 236	460	1412	2269		
2270		AP-CH-DataTypes	:	40 169	234	285			
Suppor	tedCamelPhases	hases			of [5]				
	DEFINED in M	AP-MS-DataTypes	:	2443					
Suppor	tedCamelPhases	hases			of				
		11	:						
Suppor	tedCamelPhases	hasesInInterroga AP-CH-DataTypes			of [15]				
		hasesInVMSC			Of [15]				
Suppor	tedCamelPhases	AP-CH-DataTypes			Or [10]				
		1 F	-						

supportedCCBS-Phase.....identifier of [16] SupportedCCBS-Phase DEFINED in MAP-CH-DataTypes SupportedCCBS-Phase.....type reference INTEGER DEFINED in MAP-CH-DataTypes 137 USED in MAP-CH-DataTypes 109 SupportedCodecsList......type reference SEQUENCE DEFINED in MAP-MS-DataTypes : 670
USED in MAP-MS-DataTypes : 491 560 supportedGADShapes.....identifier of [9] SupportedGADShapes DEFINED in MAP-LCS-DataTypes DEFINED in MAP-LCS-DataTypes : 246 USED in MAP-LCS-DataTypes 24 116 supportedLCS-CapabilitySets.....identifier of [5] SupportedLCS-CapabilitySets DEFINED in MAP-MS-DataTypes SupportedLCS-CapabilitySets.....type reference BIT STRING DEFINED in MAP-MS-DataTypes : 260
USED in MAP-MS-DataTypes : 27 243 461
USED in MAP-LCS-DataTypes : 62 99 100 supportedLCS-CapabilitySets.....identifier of [5] SupportedLCS-CapabilitySets DEFINED in MAP-MS-DataTypes 461 : supportedLCS-CapabilitySets.....identifier of [4] SupportedLCS-CapabilitySets DEFINED in MAP-LCS-DataTypes : 99

12-06	TAG 09:33				Reference	e Listi	ng i	for MAP-	-Protoc	ol		2006-
Suppor	tedCam	elPha	ses		Phases -DataType:				fier of	[6]		
	suppo	rtedS	GSN-	-CAMEL-	Phases -DataType:			.identif	fier of	[5] I	NULL	
Suppor	tedCam	elPha	ses		hases				fier of	[5]		
	suppo	rtedV	LR-C	CAMEL-P	hases -DataType:			.identif	fier of	[4] I	NULL	
Supported-MAP-Operationsinformation object set reference OPERATION, Information Object Set												
	DE	FINED	ın	MAP-Pr	otocol		:	121				
					Barring -DataType:				fier of	[23]	NULL	
Suppre	essionO	fAnno	unce	ement	ement				fier of	[12]		
	DE	FINED	in	MAP-CH	-DataType:	S	:	104				
					ement -DataType:				eferenc	e NUL	<u></u>	
		USED	in	MAP-CH	-DataType:	S	:	21	104	226		
suppressionOfAnnouncementidentifier of [7] SuppressionOfAnnouncement DEFINED in MAP-CH-DataTypes : 226												
	DE	FLINED	ın	MAP-CH	-DataTypes	5	:	226				
									fier of	NULL		
	DE	FINED	in	MAP-CH	-DataType:	S	:	286				
					 -DataType:				fier of	[22]	NULL	
					 -DataType:				fier of	[19]	NULL	
					 -DataType:				fier of	Name	d Numbe	er, 4
ERROR,	syste Infor							.informa	ation o	bject	refere	ence
,		FINED	in	MAP-Er			:	159				
370	383	USED 396	in 443		bileServi	ceOpera	:	80	177	225	251	320
570	505	J J U	-1-13	•				458	474	489		
				_	erationAnd			24	58	73		
160	102		in 209		llHandling	g0perat	:	30	85	109	138	154
169	183	197 USED			pplementa	ryServi	:	34	95	113	131	152
171	187	201	216	5				00-	0.55	00=		
		וומבט	in	MAD-Ch	ortMessage	-Servia		232 28	269 70	287 87	100	130
					oup-Call-(25	50	5 /	100	100
					cationSer			24	59	74	93	

AddressString

DEFINED in MAP-MS-DataTypes

USED in MAP-Errors : 14 SystemFailureParam.....type reference CHOICE DEFINED in MAP-ER-DataTypes : 168
USED in MAP-Errors : 109
USED in MAP-ER-DataTypes : 20 161 targetCellId...... identifier of [0] GlobalCellIdDEFINED in MAP-MS-DataTypes 539 ${\tt targetCellId}...... {\tt identifier of [0] GlobalCellId}$ DEFINED in MAP-MS-DataTypes 644 TargetCellOutsideGCA-Param.....type reference SEQUENCE DEFINED in MAP-ER-DataTypes : 386
USED in MAP-Errors : 151
USED in MAP-ER-DataTypes : 60 271 targetCellOutsideGroupCallArea.....information object reference ERROR, Information Object DEFINED in MAP-Errors USED in MAP-MobileServiceOpera: 104 USED in MAP-Errors targetMS.....identifier of [1] SubscriberIdentity DEFINED in MAP-LCS-DataTypes targetMS.....identifier of [0] SubscriberIdentity DEFINED in MAP-LCS-DataTypes : targetMSC-Number.....identifier of [1] ISDN-

: 645

12-06	TAG 09:33				Referen	ce Listi	ing	for MAF	-Protoc	ol		2006-
					rvice mmonData				fier of	Name	ed Numbe	r, 4
	_				 -DataTyp				fier of	[1]	RNCId	
					 -DataTyp				fier of	[2]	RNCId	
					mmonData							NG
		משפוו	in	MAD-MG.	mmonData -DataTyp	- A DCD	:	197	2001	2050		
		IIGED	in	MAD-Cor	nmonData'	Types		27	300	213	322	
									fier of	Name	ed Numbe	r, 13
	DE	FINED	in	MAP-MS-	-DataTyp	es	:	1908				
	TEID.							.type r	referenc	e OCT	TET STRI	NG
					-DataTyp							
		USED	in	MAP-MS-	-DataTyp	es	:	2197	2198			
	teid-	ForGn	∆ndG	n				identi	fier of	[8]	TEID	
				_	-DataTyp				TICE OF	[0]		
	teid-	ForIu						.identi	fier of	[9]	TEID	
					-DataTyp							
'00010	telep	hony.						.value	referen	ce Te	eleservi	ceCode,
0001		FINED	in	MAP-TS-	-Code		:	40				
	+0100	omi a	_					idonti	fior of	[2]	Tologor	viceCode
					nmonData				iller or	[3]	rereser	vicecode
									۲ ,		m 1	· a 1
					······· -DataTyp		· · · · ·	.1dent1	lier or	EXT-	-Teleser	viceCode
	Teles	ervice	eCod	e				.tvpe r	eferenc	e OCT	TET STRI	NG
				MAP-TS-			:					
		USED	in	MAP-Cor	mmonData	Types	•		540			
				MAP-TS-		- 7 F - 1	:	37		40	41	43
44	45	47	48					49	50	54	57	66
67	68	70	71					70			7.5	7.6
77	78	79	80					72	73	74	75	76
								81	82	83	84	85
					 -DataTyp			.identi 1069	fier of	[6]	Teleser	viceList
	Teles	ervic	eLis	t				.type r	eferenc	e SEÇ	QUENCE O	F
	DE				-DataTyp							
		USED	in	MAP-MS-	-DataTyp	es	:	1069	1407			
					 -DataTyp				fier of	[1]	Teleser	viceList

			tProvisioned		.inform	ation	ok	ject 1	referen	ce
ERROR,	Information		3		0.5.4					
			MAP-Errors							
			MAP-MobileServiceOpera					289		
			MAP-CallHandlingOperat							
	USED	in	MAP-SupplementaryServi	:	39	99		117	135	156
175										
			MAP-ShortMessageServic			75				
	USED	in	MAP-Errors	:	33					
	teleservice	Not	tProvisioned		.identi	fier	of	Named	Number	, 2
	DEFINED	in	MAP-CH-DataTypes	:	188					
	TeleservNot	Pro	ovParam		.tvpe r	efere	nce	SEOUE	ENCE	
								~		
	USED	in	MAP-ER-DataTypes MAP-Errors		120	256				
	IISED	in	MAP-ER-DataTypes	:	31	250				
	ОВЦЬ	T11	HAI ER Datalypes	•	31					
	temporaryDe	ıfaı	ultAllowed		identi	fier	∩f	Named	Number	. 2
			MAP-SS-DataTypes			IICI .		Ivanica	Number	, 4
	DELINED	T11	MAI -55-Datalypes	•	111					
	tomporaryDo	s f a i	ultRestricted		idonti	fior	o.f	Namad	Numbor	. 1
						TIEL	ΟL	Nameu	Number	, _
	DELINED	ТП	MAP-SS-DataTypes	:	1/6					
	t 7 t t t	- 70	-1		2.32	e:	۔ ۔	NT	NT1	. 10
			thorized			ller (OT	Named	Number	, 12
	DELINED	ın	MAP-MS-DataTypes	:	1906					
								_		
			allActivities			tier (of	Named	Number	, 1
	DEFINED	in	MAP-CH-DataTypes	:	434					

12-06	TAG R6.15 Cross Reference Listing for MAP-Protocol 2 09:33:23 PAGE 111	006-
	terminateCallActivityReferredidentifier of Named Number, 0 DEFINED in MAP-CH-DataTypes : 433	
Termin	terminationCauseidentifier of [0]	
	DEFINED in MAP-LCS-DataTypes : 506	
	TerminationCausetype reference ENUMERATED	
	DEFINED in MAP-LCS-DataTypes : 522 USED in MAP-LCS-DataTypes : 506	
	tif-csiidentifier of Named Number, 2 DEFINED in MAP-MS-DataTypes : 1447	
	tif-CSIidentifier of [3] NULL	
	DEFINED in MAP-MS-DataTypes : 1495	
	tif-CSIidentifier of Named Number, 3	
	DEFINED in MAP-MS-DataTypes : 2292	
	tif-CSIidentifier of [7] NULL	
	DEFINED in MAP-MS-DataTypes : 2338	
	tif-CSI-NotificationToCSEidentifier of [8] NULL	
	DEFINED in MAP-MS-DataTypes : 2339	
	tmsiidentifier of TMSI	
	DEFINED in MAP-MS-DataTypes : 318	
	TMSItype reference OCTET STRING	
	DEFINED in MAP MC PataTypes : 316	
	USED in MAP-MS-DataTypes : 180 318 USED in MAP-CommonDataTypes : 31 320	
	tmsiidentifier of [1] TMSI DEFINED in MAP-CommonDataTypes : 320	
	tNoAnsweridentifier of Named Number, 1	4
	DEFINED in MAP-MS-DataTypes : 1909	
	tooManyZoneCodesidentifier of Named Number, 1	
	DEFINED in MAP-MS-DataTypes : 1419	
	tpdu-TypeCriterionidentifier of [0] TPDU-	
TypeCr	iterion	
	DEFINED in MAP-MS-DataTypes : 1510	
	TPDU-TypeCriteriontype reference SEQUENCE OF	
	DEFINED in MAP-MS-DataTypes : 1513 USED in MAP-MS-DataTypes : 1510	
	OSED III MAF-MS-Datatypes . 1310	
	TraceDepthtype reference ENUMERATED	
	DEFINED in MAP-OM-DataTypes : 69 USED in MAP-OM-DataTypes : 61 62 63 64 65	
66 1	34 186 189	
	traceDepthListidentifier of [6] TraceDepthL	ic+
	DEFINED in MAP-OM-DataTypes : 44	1106

TraceDepthList	: 60
traceEventList DEFINED in MAP-OM-DataTypes	<pre>identifier of [9] TraceEventList : 47</pre>
TraceEventList	: 142
traceInterfaceList TraceInterfaceList DEFINED in MAP-OM-DataTypes	
TraceInterfaceList DEFINED in MAP-OM-DataTypes USED in MAP-OM-DataTypes	: 86
traceNE-TypeList	
TraceNE-TypeList DEFINED in MAP-OM-DataTypes USED in MAP-OM-DataTypes	: 77

12-06	TAG R6.15			Reference	e Listi	ng i	for MAP-	-Prot	coco	ol	2006-
TraceP	tracePropagropagropagationL	ist		······································				fier	of	[17]	l
TraceP	tracePropagropagropagropagropagropagropagropag	gatio						fier	of	[25]	I
			AP-MS-	-DataTypes	5	:	565				
	TracePropag DEFINED			DataTypes				efere	ence	e SE(QUENCE
	USED USED	in M	AP-MS- AP-OM-	DataTypes DataTypes	5	:	213 18	495	5	565	
	TraceRecor	dingS	essior	nReference	·		.type re	efere	ence	e OCT	TET STRING
				DataTypes DataTypes							
Two go D	traceRecor	_			e		.identii	Eier	of	[3]	
Tracek	ecordingSes: DEFINED			ice ·DataTypes	3	:	183				
				DataTypes				fier	of	[1]	TraceReference
	TraceRefere	ence.					type re	efere	ence	e OCT	TET STRING
				DataTypes DataTypes				180)	202	
				DataTypes				fier	of	[0]	TraceReference
				DataTypes				Eier	of	[1]	TraceReference
				DataTypes		:		fier	of	[5]	TraceReference2
	TraceRefere			DataTypes				efere	ence	e OCT	TET STRING
	USED	in M	AP-OM-	-DataTypes	3	:	43	182	2	205	
				DataTypes				fier	of	[2]	TraceReference2
	traceRefero DEFINED	ence2 in M	AP-OM-	DataTypes	3	:	identii 205	fier	of	[3]	TraceReference2
	traceSuppo: DEFINED			DataTypes				fier	of	[1]	NULL
	traceType. DEFINED			DataTypes				fier	of	[2]	TraceType
	TraceType. DEFINED	in M	AP-OM-	DataTypes	3	:	56			e INT	ΓEGER
	USED traceType.			-DataTypes				181 Eier		[1]	TraceTvpe
				-DataTypes							<u>- 2 F</u> -

ERROR,	tracingBuff Information	ferFull n Object		.inform	nation obje	ect reference	3			
	DEFINED	in MAP-Errors	:	277						
		in MAP-OperationAndMai								
		in MAP-Errors								
	0022		•							
	TracingBuff	ferFullParam		.type r	reference S	SEQUENCE				
	DEFINED	in MAP-ER-DataTypes	:	236						
	USED	in MAP-Errors	:	121	279					
		in MAP-ER-DataTypes								
		71								
12	trafficAnd	PublicTransportationInf	ō	.value	reference	LCSServiceTy	peID,			
	DEFINED	in MAP-CommonDataTypes	:	424						
5	trafficCongestionReportingvalue reference LCSServiceTypeID									
5	DEFINED	in MAP-CommonDataTypes	:	416						
	transaction	nId		.identi	fier of [7	7] Transactio	onId			
	DEFINED	in MAP-MS-DataTypes	:	2196						
	Transaction	nId		.tvpe r	reference (OCTET STRING				
		in MAP-MS-DataTypes								
		in MAP-MS-DataTypes								
	ODED	III IIII III Dacarypes	•	2170						
	transferToT	ThirdParty		.value	reference	SS-Code,				
111000	011'B									
	DEFINED	in MAP-SS-Code	:	180						

12-06	TAG R6.1 09:33:23			Reference	Listing	for	MAP-Protocol		2006-
Addres	translated SString	B-Nu	ımber			id	entifier of [3]	ISDN-	
	DEFINED	in	MAP-CH-	-DataTypes	:		384		
Addres	translated SString	B-Nu	ımber			id	entifier of [1]	ISDN-	
	_	in	MAP-SS	-DataTypes	:		311		
	tripletLis	t				id	entifier of [0]	TripletLi	st
	DEFINED	in	MAP-MS	-DataTypes	:		345		
							pe reference SE	EQUENCE OF	
				-DataTypes					
	USED	in	MAP-MS	-DataTypes	:		345		
	ts3G-25413					id	entifier of Nam	med Number.	2
				mmonDataTy				,	_
	ts3G-48006					id	entifier of Nam	ned Number,	1
				mmonDataTy				,	
	T-RosmCame	ם חיים ב	Data			± 3.7	pe reference SE	COHENCE	
				 -DataTypes			_	дописп	
				-DataTypes					
			DataLi	st		id	entifier of T-		
BcsmCar	melTDPDataL								
	DEFINED	in	MAP-MS-	-DataTypes	:	1	878		
	T-BcsmCame	1TDE	DataLi	st		tv	pe reference SE	EOUENCE OF	
				-DataTypes				~	
				-DataTypes					
		_							
D = ==================================				onPoint		1d	entifier of T-		
BCSIIIT.	iggerDetect DEFINED			-DataTypes		1	898		
	DELINED	111	TIAI TIO	Dacatypes	•		0,50		
	T-BcsmTrig	gerI	etectio	onPoint		ty	pe reference EN	NUMERATED	
				-DataTypes					
	USED	in	MAP-MS	-DataTypes	:		90 1648 1898	3	
	T-RCSM-CAM	ET7	יחם_כ~; +	teria		+ 17	pe reference SE	COHENCE	
				-DataTypes				SQUENCE	
				-DataTypes					
				21					
		EL-I	DP-Crit	teriaList.		id	entifier of [8]	T-BCSM-CA	MEL-
TDP-Cr	iteriaList								
	DEFINED	in	MAP-MS	-DataTypes	:	1	499		
	T-BCSM-CAM	EI,-T	'DP-Crit	teriaList		+ 37	pe reference SE	COUENCE OF	
				-DataTypes				-ZOLINOL OI	
							71 1499 2335	5 2337 23	54
	USED	in	MAP-CH-	-DataTypes	:		46 307		
				- 1 - 1 F 30	•				
TDP-Cr	t-BCSM-CAM iteriaList	EL-I	DP-Crit	teriaList.		id	entifier of [4]	T-BCSM-CA	MEL-
01.		in	MAP-MS	-DataTypes	:	2	335		

t-BCSM-CAMEL-TDP-CriteriaList TDP-CriteriaList	identifier of [4] T-BCSM-CAMEL-
DEFINED in MAP-CH-DataTypes	: 307
t-BCSM-TriggerDetectionPoint BcsmTriggerDetectionPoint	identifier of T-
DEFINED in MAP-MS-DataTypes	: 1648
t-CauseValueCriteria	identifier of [1] T-
DEFINED in MAP-MS-DataTypes	: 1650
T-CauseValueCriteria	type reference SEQUENCE OF
DEFINED in MAP-MS-DataTypes	: 1691
USED in MAP-MS-DataTypes	
t-csi	identifier of Named Number, 8
DEFINED in MAP-MS-DataTypes	
t-csi	identifier of Named Number, 3
DEFINED in MAP-MS-DataTypes	
T-CSI	type reference SEQUENCE
DEFINED in MAP-MS-DataTypes	: 1877
USED in MAP-MS-DataTypes	: 89 1498 2334 2336 2353
	: 49 302
t-CSI	identifier of Named Number, 1
DEFINED in MAP-MS-DataTypes	: 2290
t-CSI	identifier of [3] T-CSI

DEFINED in MAP-MS-DataTypes : 2334

12-06	TAG R6.15 Cross Reference Listing for MAP-Proto 09:33:23 PAGE 114	col	2006-
	t-CSIidentifier o DEFINED in MAP-CH-DataTypes : 302	E [0] T-CSI	
	udubFromBusyMSidentifier o DEFINED in MAP-CH-DataTypes : 401	f Named Number,	5
	udubFromFreeMSidentifier o DEFINED in MAP-CH-DataTypes : 400	f Named Number,	4
	uesbi-Iuidentifier o DEFINED in MAP-MS-DataTypes : 562	f [21] UESBI-Iu	
	UESBI-Iutype referenDEFINED in MAP-MS-DataTypes: 826USED in MAP-MS-DataTypes: 562	ce SEQUENCE	
	uesbi-IuAidentifier o DEFINED in MAP-MS-DataTypes : 827	f [0] UESBI-IuA	
	UESBI-IuA	ce BIT STRING	
	uesbi-IuBidentifier o DEFINED in MAP-MS-DataTypes : 828	f [1] UESBI-IuB	
	UESBI-IuB	ce BIT STRING	
Securi	umts-SecurityContextDataidentifier o ityContextData DEFINED in MAP-MS-DataTypes : 370	E [1] UMTS-	
	UMTS-SecurityContextDatatype referen DEFINED in MAP-MS-DataTypes : 377 USED in MAP-MS-DataTypes : 370	ce SEQUENCE	
	unauthorisedMessageOriginatoridentifier o DEFINED in MAP-ER-DataTypes : 115	E [1] NULL	
	unauthorizedCallSessionRelatedExternalClidentifier o DEFINED in MAP-ER-DataTypes : 355	f Named Number,	7
	unauthorizedCallSessionUnrelatedExternalidentifier o DEFINED in MAP-ER-DataTypes : 354	f Named Number,	6
ERROR,	unauthorizedLCSClientinformation , Information Object DEFINED in MAP-Errors : 471	object referenc	е
	USED in MAP-LocationServiceOpe : 31 83 USED in MAP-Errors : 87		
Unauth	unauthorizedLCSClient-Diagnosticidentifier o horizedLCSClient-Diagnostic DEFINED in MAP-ER-DataTypes : 342	E [0]	
	UnauthorizedLCSClient-Diagnostictype referen DEFINED in MAP-ER-DataTypes : 346	ce ENUMERATED	

USED in MAP-ER-DataTypes : 342 UnauthorizedLCSClient-Param.....type reference SEQUENCE DEFINED in MAP-ER-DataTypes : 341
USED in MAP-Errors : 141
USED in MAP-ER-DataTypes : 50 141 473 $unauthorized \verb|PrivacyClass.....identifier of Named Number, 5$ DEFINED in MAP-ER-DataTypes : 353 unauthorizedRequestingNetwork.....information object reference ERROR, Information Object DEFINED in MAP-Errors FINED in MAP-Errors : 465
USED in MAP-LocationServiceOpe : 30 65 82 98 USED in MAP-Errors 86 UnauthorizedRequestingNetwork-Param....type reference SEQUENCE DEFINED in MAP-ER-DataTypes : 337
USED in MAP-Errors : 140
USED in MAP-ER-DataTypes : 49 467

unavailabilityCause.....identifier of [21]

UnavailabilityCause

DEFINED in MAP-CH-DataTypes : 175

UnavailabilityCause.....type reference ENUMERATED

DEFINED in MAP-CH-DataTypes : 186

12-06		R6.15			Reference	e Listin	ng	for MAP	-Proto	ocol		2006-
		USED	in	MAP-CH	-DataTypes	S	:	175				
					 -DataTypes				fier o	of Named	d Numbe	er, 0
	Unex	kpectedI	Data	Param.				.type re	eferer	nce SEQU	JENCE	
	Ι				-DataTypes							
				MAP-Er:			:		174			
		USED	ın	MAP-ER	-DataTypes	5	:	22				
ERROR,	, Info	ormation	n Ob	ject				.informa	ation	object	refere	ence
	Ι	DEFINED					:	172				
240	254		in 286		bileServio	ceOpera	:		179		203	226
411	423	445	460	1				308	322	350	372	384
411	425	113	400	,				476	491	502		
		USED	in	MAP-Ope	erationAnd	Mainte	:	26	60		87	
		USED	in	MAP-Ca	llHandling	gOperat	:	32	87	111	127	140
155	165	180	194	:								
		HCED	in	MAD Cit	onlomontar	arconti		208 36	0.7	115	122	1 = 4
173	189	203	218		oplementar	yservi	:	36	97	115	133	154
173	100	203	210	,				234	259	271	289	
		USED	in	MAP-Sho	ortMessage	eServic	:	30	72	88	102	120
132	148											
					oup-Call-C			26	52			
				MAP-Lo	cationServ	/iceOpe	:	26 16	61	76	96	
		OSED	111	MAP-EL.	LOIS		•	10				
	Unic	dentifie	edSu	ıbParam				.type re	eferer	nce SEQU	JENCE	
	Ι				-DataTypes		:	216				
					rors		:		218			
		USED	ın	MAP-ER	-DataTypes	5	:	27				
ERROR,		dentifie ormation			er			.informa	ation	object	refere	ence
	Ι	DEFINED					:	216				
					bileServic	-		85		412	424	
					erationAnd				62	77		
					llHandling ortMessage			49 33	139 104			
					cationServ			35	78			
				MAP-Er:		-	:	25				
11011								.value	refere	ence SS-	-Code,	
'1011(DEFINED	in	MAP-SS	-Code		:	161				
ERROR,	, Info	ormation	n Ob	ject				.informa	ation	object	refere	ence
	Ι	DEFINED				. ·	:	401	- د د		0.5.5	
				MAP-Suj	oplementar			49 68	190	207	222	
		USED	TII	MAP-EI.	LOID		:	00				
ERROR,	, Info	ormation	n Ob	ject				.informa	ation	object	refere	ence
	Ι	DEFINED				_	:	223				
		USED	in	MAP-Mol	bileServic	ceOpera	:	86	398			

	USED	in	MAP-Errors	:	26				
	unknownMSC.				.informa	tion	object	refere	nce
ERROR,	Information	Ol	oject						
	DEFINED	in	MAP-Errors	:	213				
	USED	in	MAP-MobileServiceOpera	:	84	352			
			MAP-Errors	:	24				
	unknownOrUn	rea	achableLCSClient		.informa	tion	object	refere	nce
ERROR,	Information	Ol	oject						
	DEFINED	in	MAP-Errors	:	483				
	USED	in	MAP-LocationServiceOpe	:	34	99			
	USED	in	MAP-Errors	:	89				
	UnknownOrUn	rea	achableLCSClient-Param.		.type re	eferen	ce SEQU	JENCE	
	DEFINED	in	MAP-ER-DataTypes	:	378				
	USED	in	MAP-Errors	:	143	485			
	USED	in	MAP-ER-DataTypes	:	52				
			eCentre			ier o	f Named	l Numbe	er, 3
	DEFINED	in	MAP-ER-DataTypes	:	143				
			iber		.informa	tion	object	refere	nce
ERROR,	Information		=						
			MAP-Errors						
			MAP-MobileServiceOpera	:	83	180	204	227	255
269	287 309	373	3						
503					385	446	461	477	492
303	USED	in	MAP-OperationAndMainte	:	28	88			
			MAP-CallHandlingOperat		35		153	182	196
			MAP-SupplementaryServi		37				
			MAP-ShortMessageServic		32		121	150	
			MAP-LocationServiceOpe		28			100	
			MAP-Errors		22	0.5	<i>J</i> ,		
	0000			•					

 $unknown Subscriber \texttt{Diagnostic}......identifier \ of \\ Unknown Subscriber \texttt{Diagnostic}$

```
TAG R6.15 Cross Reference Listing for MAP-Protocol
                                                                      2006-
12-06 09:33:23 PAGE 116
                                     :
         DEFINED in MAP-ER-DataTypes
                                             202
      {\tt UnknownSubscriberDiagnostic...............type\ reference\ {\tt ENUMERATED}}
         DEFINED in MAP-ER-DataTypes : 204
USED in MAP-ER-DataTypes : 202
      UnknownSubscriberParam.....type reference SEQUENCE
         DEFINED in MAP-ER-DataTypes : 199
USED in MAP-Errors : 113 202
USED in MAP-ER-DataTypes : 25
      unstructuredSS-Notify.....information object reference
OPERATION, Information Object
         DEFINED in MAP-SupplementaryServi : 211
                                             79 131
20
            USED in MAP-Protocol
            USED in MAP-SupplementaryServi :
      unstructuredSS-Request.....information object reference
OPERATION, Information Object
         DEFINED in MAP-SupplementaryServi : 194
            USED in MAP-Protocol : 78 131
USED in MAP-SupplementaryServi : 19
      updateGprsLocation.....information object reference
OPERATION, Information Object
         DEFINED in MAP-MobileServiceOpera : 219
            USED in MAP-Protocol : 20 122
            USED in MAP-MobileServiceOpera :
      UpdateGprsLocationArg.....type reference SEQUENCE
         DEFINED in MAP-MS-DataTypes : 442
            USED in MAP-MobileServiceOpera : 119
            USED in MAP-MS-DataTypes :
      UpdateGprsLocationRes.....type reference SEQUENCE
         DEFINED in MAP-MS-DataTypes : 468
USED in MAP-MobileServiceOpera : 120 223
            USED in MAP-MS-DataTypes :
      updateLocation.....information object reference
OPERATION, Information Object
         DEFINED in MAP-MobileServiceOpera : 171
            USED in MAP-Protocol :
            USED in MAP-MobileServiceOpera : 15
      UpdateLocationArg.....type reference SEQUENCE
         DEFINED in MAP-MS-DataTypes : 222

USED in MAP-MobileServiceOpera : 111 173
            USED in MAP-MS-DataTypes :
      UpdateLocationRes.....type reference SEQUENCE
         DEFINED in MAP-MS-DataTypes : 276

USED in MAP-MobileServiceOpera : 112
            USED in MAP-MS-DataTypes :
                                              17
      \label{lem:updateProcedure......identifier of Named Number, 0} \\
         DEFINED in MAP-MS-DataTypes :
      uplinkAttached......identifier of [6] NULL
         DEFINED in MAP-GR-DataTypes : 124
```

uplinkFreeidentifier of [3] NULL DEFINED in MAP-GR-DataTypes : 57	
uplinkRejectCommandidentifier of [2] NULL DEFINED in MAP-GR-DataTypes : 87	
uplinkReleaseCommandidentifier of [4] NULL DEFINED in MAP-GR-DataTypes : 89	
uplinkReleaseIndicationidentifier of [1] NULL DEFINED in MAP-GR-DataTypes : 86	
uplinkReleaseIndicationidentifier of [1] NULL DEFINED in MAP-GR-DataTypes : 96	
uplinkRequestidentifier of [0] NULL DEFINED in MAP-GR-DataTypes : 95	
uplinkRequestAckidentifier of [0] NULL DEFINED in MAP-GR-DataTypes : 85	
uplinkSeizedCommandidentifier of [3] NULL DEFINED in MAP-GR-DataTypes : 88	
urlidentifier of Named Number	·, 3

DEFINED in MAP-LCS-DataTypes 206	12-06	TAG R6.1			Reference	e Listi	ng	for MA	P-Pro	toca	ol		2006-
DEFINED in MAP-SS-DataTypes		DEFINED	in	MAP-LCS	S-DataType	es	:	206					
USED in MAP-SS-DataTypes : 20 ussd-Busy										ence	e SEQU	ENCE	
DEFINED in MAP-Errors										3	196	213	
DEFINED in MAP-Errors	EDDOD							.infor	matio	n ok	oject	referenc	ce
USED in MAP-SupplementaryServi : 50	ERROR,			-	rorg			4 0 4					
USED in MAP-Errors : 69 ussd-DataCodingScheme identifier of USSD-DataCodingScheme DEFINED in MAP-SS-DataTypes : 221 ussd-DataCodingScheme identifier of USSD-DataCodingScheme DEFINED in MAP-SS-DataTypes : 228 USSD-DataCodingScheme type reference OCTET STRING DEFINED in MAP-SS-DataTypes : 232 USSD in MAP-SS-DataTypes : 22 22 12 228 USSD in MAP-LCS-DataTypes : 22 27 221 228 USSD-Res type reference SEQUENCE DEFINED in MAP-SS-DataTypes : 227 USSD in MAP-SS-DataTypes : 227 USSD in MAP-SS-DataTypes : 221 ussd-String identifier of USSD-String DEFINED in MAP-SS-DataTypes : 222 USSD-String identifier of USSD-String DEFINED in MAP-SS-DataTypes : 229 USSD in MAP-SS-DataTypes : 237 USED in MAP-SS-DataTypes : 237 USED in MAP-LCS-DataTypes : 310 utranCellId identifier of Named Number, 5 DEFINED in MAP-LCS-DataTypes : 671 utranPositi										8	223		
DataCodingScheme DEFINED in MAP-SS-DataTypes 221													
ussd-DataCodingSchemeidentifier of USSD-DataCodingSchemeDEFINED in MAP-SS-DataTypes228USSD-DataCodingSchemetype reference OCTET STRINGDEFINED in MAP-SS-DataTypes232USED in MAP-SS-DataTypes22 221 228USED in MAP-LCS-DataTypes54 178 193 260USSD-Restype reference SEQUENCEDEFINED in MAP-SS-DataTypes227USED in MAP-SupplementaryServi66 185 198USED in MAP-SS-DataTypes21ussd-Stringidentifier of USSD-StringDEFINED in MAP-SS-DataTypes222ussd-Stringidentifier of USSD-StringDEFINED in MAP-SS-DataTypes229USSD-Stringtype reference OCTET STRINGDEFINED in MAP-SS-DataTypes237USED in MAP-SS-DataTypes23 222 229USED in MAP-LCS-DataTypes23 222 229USED in MAP-LCS-DataTypes310utranCellIdidentifier of Named Number, 5DEFINED in MAP-LCS-DataTypes310utranCodecListidentifier of Named Number, 0DEFINED in MAP-MS-DataTypes870utranPositioningDataidentifier of [5]UtranPositioningDataInfoidentifier of [5]UtranPositioningDataInfoidentifier of [12]UtranPositioningDataInfoidentifier of [12]UtranPositioningDataInfoidentifier of [12]UtranPositioningDataInfoidentifier of [12]	DataCo		odir	ngScheme	e			.ident:	ifier	of	USSD-		
DataCodingScheme DEFINED in MAP-SS-DataTypes 228		DEFINED	in	MAP-SS-	-DataTypes	5	:	221					
USSD-DataCodingScheme	DataCo	dingScheme							ifier	of	USSD-		
DEFINED in MAP-SS-DataTypes : 232 USED in MAP-SS-DataTypes : 22 221 228 USED in MAP-LCS-DataTypes : 54 178 193 260 USSD-Res		DEFINED	in	MAP-SS-	-DataTypes	5	:	228					
USED in MAP-SS-DataTypes : 22 221 228 USED in MAP-LCS-DataTypes : 54 178 193 260 USSD-Res										ence	e OCTE	T STRING	3
USED in MAP-LCS-DataTypes : 54 178 193 260 USSD-Res													
USSD-Res													
DEFINED in MAP-SS-DataTypes : 227 USED in MAP-SupplementaryServi : 66 185 198 USED in MAP-SS-DataTypes : 21 ussd-String		USED	in	MAP-LCS	S-DataType	es	:	54	178	8	193	260	
DEFINED in MAP-SS-DataTypes : 227 USED in MAP-SupplementaryServi : 66 185 198 USED in MAP-SS-DataTypes : 21 ussd-String		USSD-Res		. .				.type	refere	ence	e SEQU	ENCE	
USED in MAP-SS-DataTypes : 21 ussd-String		DEFINED	in	MAP-SS-	-DataTypes	3	:	227					
USED in MAP-SS-DataTypes : 21 ussd-String		USED	in	MAP-Sup	plementar	ryServi	:	66	18!	5	198		
USSD-String		USED	in	MAP-SS-	-DataTypes	5	:	21					
USSD-String		naad-Strin	7					ident:	ifier	of	- תפפוז	String	
USSD-String									IIIEI	OI	0555	bering	
USSD-String		ussd-String	a					.ident:	ifier	of	USSD-	Strina	
DEFINED in MAP-SS-DataTypes : 237 USED in MAP-SS-DataTypes : 23 222 229 USED in MAP-LCS-DataTypes : 55 188 198 264 utranCellId										0_	0000	~ ~	
DEFINED in MAP-SS-DataTypes : 237 USED in MAP-SS-DataTypes : 23 222 229 USED in MAP-LCS-DataTypes : 55 188 198 264 utranCellId		USSD-String	a					.type	refere	ence	OCTE	T STRING	3
USED in MAP-SS-DataTypes : 23 222 229 USED in MAP-LCS-DataTypes : 55 188 198 264 utranCellId													
USED in MAP-LCS-DataTypes : 55 188 198 264 utranCellId										2	229		
DEFINED in MAP-LCS-DataTypes : 310 utranCodecList												264	
DEFINED in MAP-LCS-DataTypes : 310 utranCodecList		utranCellIo	d					ident	ifier	of	Named	Number.	5
DEFINED in MAP-MS-DataTypes : 671 utranNotAllowed										0_	21000	1,411.201,	
utranNotAllowed									ifier	of	[0] C	odecList	
DEFINED in MAP-MS-DataTypes : 870 utranPositioningDataidentifier of [5] UtranPositioningDataInfo DEFINED in MAP-LCS-DataTypes : 344 utranPositioningDataidentifier of [12] UtranPositioningDataInfo DEFINED in MAP-LCS-DataTypes : 480		DEFINED	in	MAP-MS-	-DataTypes	5	:	671					
utranPositioningDataidentifier of [5] UtranPositioningDataInfo									ifier	of	Named	Number,	0
UtranPositioningDataInfo DEFINED in MAP-LCS-DataTypes : 344 utranPositioningDataidentifier of [12] UtranPositioningDataInfo DEFINED in MAP-LCS-DataTypes : 480		DEFINED	in	MAP-MS-	-DataTypes	5	:	870					
DEFINED in MAP-LCS-DataTypes : 344 utranPositioningDataidentifier of [12] UtranPositioningDataInfo DEFINED in MAP-LCS-DataTypes : 480								.ident:	ifier	of	[5]		
UtranPositioningDataInfo DEFINED in MAP-LCS-DataTypes : 480	UtranPo				S-DataType	es	:	344					
UtranPositioningDataInfo DEFINED in MAP-LCS-DataTypes : 480		utranDogit	ioni	ingData				ident:	ifior	٥f	[12]		
DEFINED in MAP-LCS-DataTypes : 480	IIt ranD						• • •	· ruellt.	TTT61	ΟL	[]		
UtranPositioningDataInfotype reference OCTET STRING	UCI AIIP(S-DataType	es	:	480					
		UtranPosit	ioni	ingDatal	Info			.type	refere	ence	e OCTE	T STRING	5

DEFINED in MAP-LCS-DataTypes	: 434
USED in MAP-LCS-DataTypes	: 344 480
uu	
DEFINED in MAP-OM-DataTypes	: 135
uui	
DEFINED in MAP-CH-DataTypes	: 269
UUI	
DEFINED in MAP-CH-DataTypes	
USED in MAP-CH-DataTypes	: 269
- 11	
uuIndicator	
DEFINED in MAP-CH-DataTypes	: 268
IIII n di nakan	town and company COMPANY
UUIndicator	
DEFINED in MAP-CH-DataTypes	
USED in MAP-CH-DataTypes	: 268
uus1	value reference SS-Code,
'10000001'B	110
DEFINED in MAP-SS-Code	: 110
uus2	value reference CC Code
'10000010'B	value leference 55-code,
	: 112
DEFINED III MAP-55-COde	: 112
uus3	walue reference SS-Codo
'10000011'B	value reference 55-code,
TOOOOTT D	

12-06	TAG R6.15 Cross Reference Listi 09:33:23 PAGE 118	g for MAP-Protocol	2006-
	DEFINED in MAP-SS-Code	114	
	uusCFInteraction DEFINED in MAP-CH-DataTypes		L
	uu-Data DEFINED in MAP-CH-DataTypes		-Data
	UU-Data DEFINED in MAP-CH-DataTypes USED in MAP-CH-DataTypes	267	CE
	valueAddedServices DEFINED in MAP-LCS-DataTypes		umber, 1
	VBSDataList DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes	1980	CE OF
	vbsGroupIndication DEFINED in MAP-MS-DataTypes	identifier of [7] NUL 1431	L
	vbsSubscriptionData DEFINED in MAP-MS-DataTypes		SDataList
	verticalCoordinateRequest DEFINED in MAP-LCS-DataTypes		L
Accura	<u> -</u>		tical-
	DEFINED in MAP-LCS-DataTypes	218	
	Vertical-Accuracy DEFINED in MAP-LCS-DataTypes USED in MAP-LCS-DataTypes	228	STRING
	VGCSDataList DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes	1983	CE OF
	vgcsGroupIndication DEFINED in MAP-MS-DataTypes		L
	vgcsSubscriptionData DEFINED in MAP-MS-DataTypes	1077	
	vlr DEFINED in MAP-MS-DataTypes	799	
	vlr DEFINED in MAP-CommonDataTypes	356	umber, 2
VlrCame	vlrCamelSubscriptionInfoelSubscriptionInfo DEFINED in MAP-MS-DataTypes	identifier of [13]	
	VlrCamelSubscriptionInfo DEFINED in MAP-MS-DataTypes USED in MAP-MS-DataTypes	1489	CE

vlr-Capabilityidentifier of [6] VLR-Capability DEFINED in MAP-MS-DataTypes : 229
VLR-Capabilitytype reference SEQUENCE DEFINED in MAP-MS-DataTypes : 235 USED in MAP-MS-DataTypes : 229 1970
vlr-Capabilityidentifier of [6] VLR-Capability DEFINED in MAP-MS-DataTypes : 1970
vlr-Numberidentifier of ISDN-AddressString DEFINED in MAP-MS-DataTypes : 225
vlr-Numberidentifier of [0] ISDN-AddressString
DEFINED in MAP-MS-DataTypes : 306
vlr-Numberidentifier of [0] ISDN-AddressString
DEFINED in MAP-MS-DataTypes : 413
vlr-numberidentifier of [1] ISDN-AddressString
DEFINED in MAP-MS-DataTypes : 2107
vmscidentifier of Named Number, 5 DEFINED in MAP-CommonDataTypes : 359

TAG R6.15 Cross Reference Listing for MAP-Protocol 12-06 09:33:23 PAGE 119	2006-
vmsc-Addressidentifier of [2] ISDN-AddressString	
DEFINED in MAP-CH-DataTypes : 160	
voiceBroadcastCallvalue reference TeleserviceC'10010010'B	ode,
DEFINED in MAP-TS-Code : 68	
VoiceBroadcastDatatype reference SEQUENCE	
DEFINED in MAP-MS-DataTypes : 1995 USED in MAP-MS-DataTypes : 1981	
	_
<pre>voiceGroupCallvalue reference TeleserviceC '10010001'B</pre>	ode,
DEFINED in MAP-TS-Code : 67	
VoiceGroupCallDatatype reference SEQUENCE	
DEFINED in MAP-MS-DataTypes : 1990	
USED in MAP-MS-DataTypes : 1984	
vplmnAddressAllowedidentifier of [19] NULL	
DEFINED in MAP-MS-DataTypes : 919	
vstkidentifier of [5] VSTK	
DEFINED in MAP-GR-DataTypes : 60	
VSTKtype reference OCTET STRING	
DEFINED in MAP-GR-DataTypes : 63 USED in MAP-GR-DataTypes : 60	
USED in MAP-GR-DataTypes : 60	
vstk-randidentifier of [6] VSTK-RAND DEFINED in MAP-GR-DataTypes : 61	
VSTK-RANDtype reference OCTET STRING	
DEFINED in MAP-GR-DataTypes : 65	
USED in MAP-GR-DataTypes : 61	
vt-BCSM-CAMEL-TDP-CriteriaListidentifier of [6] T-BCSM-CAM	EL-
TDP-CriteriaList DEFINED in MAP-MS-DataTypes : 2337	
vt-csiidentifier of Named Number,	4
DEFINED in MAP-MS-DataTypes : 1449	
vt-CSIidentifier of [7] T-CSI	
DEFINED in MAP-MS-DataTypes : 1498	
vt-csiidentifier of Named Number,	2
DEFINED in MAP-MS-DataTypes : 1728	
vt-CSIidentifier of Named Number, DEFINED in MAP-MS-DataTypes : 2291	2
vt-CSIidentifier of [5] T-CSI	
DEFINED in MAP-MS-DataTypes : 2336	
vt-IM-BCSM-CAMEL-TDP-CriteriaListidentifier of [22] T-BCSM-CATDP-CriteriaList	MEL-
DEFINED in MAP-MS-DataTypes : 2354	

	vt-IM-CSIidentifier of Named Number, 13 DEFINED in MAP-MS-DataTypes : 1458
	vt-IM-CSIidentifier of Named Number, 4 DEFINED in MAP-MS-DataTypes : 2304
	vt-IM-CSIidentifier of [21] T-CSI DEFINED in MAP-MS-DataTypes : 2353
	v-gmlc-Addressidentifier of [2] GSN-Address DEFINED in MAP-MS-DataTypes : 232
	v-gmlc-Addressidentifier of [3] GSN-Address DEFINED in MAP-MS-DataTypes : 451
	v-gmlc-Addressidentifier of [3] GSN-Address DEFINED in MAP-LCS-DataTypes : 85
	warningToneEnhancementsidentifier of Named Number, 13 DEFINED in MAP-MS-DataTypes : 1752
13	weathervalue reference LCSServiceTypeID,
	DEFINED in MAP-CommonDataTypes : 425
20	whereAmIvalue reference LCSServiceTypeID,
	DEFINED in MAP-CommonDataTypes : 432

TAG R6.15 Cross Reference Listing for MAP-Protocol 2006-12-06 09:33:23 PAGE 120 white Listed.....identifier of Named Number, 0 DEFINED in MAP-MS-DataTypes 838 wrongNetworkSignature.....identifier of Named Number, 1 DEFINED in MAP-MS-DataTypes 438 wrongPasswordAttemptsCounter.....identifier of WrongPasswordAttemptsCounter DEFINED in MAP-MS-DataTypes WrongPasswordAttemptsCounter.....type reference INTEGER DEFINED in MAP-MS-DataTypes : 2322 USED in MAP-MS-DataTypes : 2317 2391 2470 wrongPasswordAttemptsCounter.....identifier of [4] WrongPasswordAttemptsCounter DEFINED in MAP-MS-DataTypes wrongPasswordAttemptsCounter.....identifier of [3] WrongPasswordAttemptsCounter DEFINED in MAP-MS-DataTypes $wrong User Response identifier of Named Number, \ 0\\$ DEFINED in MAP-MS-DataTypes xres.....identifier of XRES DEFINED in MAP-MS-DataTypes XRES.....type reference OCTET STRING DEFINED in MAP-MS-DataTypes : 389 USED in MAP-MS-DataTypes ZoneCode.....type reference OCTET STRING DEFINED in MAP-MS-DataTypes : 1401 USED in MAP-MS-DataTypes : 1399 1430 ZoneCodeList.....type reference SEQUENCE OF DEFINED in MAP-MS-DataTypes : 1398
USED in MAP-MS-DataTypes : 66 66 1075 zoneCodesConflict......identifier of Named Number, 2

DEFINED in MAP-MS-DataTypes : 1420

Annex B (informative): Fully expanded ASN.1 sources for abstract syntaxes of MAP

Annex B is not part of the standard, it is included for information purposes only.

For every (Value)Assignment in the root ASN.1 module all the used defined types and defined values, which are defined within the ASN.1 module or imported from ASN.1 modules, are replaced by the constructs this type or value is composed of.

The fully expanded ASN.1 root module is itself a correct and equivalent representation of the MAP-Protocol.

It allows to see at all the parameters, including all nested ones for a specific operationcode or errorcode at once.

Note that for those operations which use a result without parameters the word 'RESULT' is not shown. Empty results are only defined in the ASN.1 description in clause 17.

B.1 Fully Expanded ASN.1 Source of MAP-Protocol/TCAPMessages

```
-- Expanded ASN1 Module 'MAP-MobileServiceOperations'
--SIEMENS ASN.1 Compiler
                                 R6.15 (Production 6.15)
              Date: 2006-12-06 Time: 09:29:35
MAP-MobileServiceOperations { 0 identified-organization (4) etsi (0) mobileDomain
(0) gsm-Network (1) modules (3) map-MobileServiceOperations (5) version9 (9) }
DEFINITIONS
: :=
BEGIN
EXPORTS
   updateLocation,
   cancelLocation,
  purgeMS,
   sendIdentification,
   updateGprsLocation,
   provideSubscriberInfo,
   anyTimeInterrogation,
   anyTimeSubscriptionInterrogation,
   anyTimeModification,
   noteSubscriberDataModified,
   prepareHandover,
   sendEndSignal,
   processAccessSignalling,
   forwardAccessSignalling,
   prepareSubsequentHandover,
   sendAuthenticationInfo,
   authenticationFailureReport,
   checkIMEI,
   insertSubscriberData,
   deleteSubscriberData,
   reset.
   forwardCheckSS-Indication,
```

```
restoreData,
  sendRoutingInfoForGprs,
  failureReport,
  noteMsPresentForGprs,
   noteMM-Event;
updateLocation OPERATION ::= {
  ARGUMENT SEQUENCE {
                                    OCTET STRING ( SIZE( 3 .. 8 ) ),
     imsi
                                   [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 )
     msc-Number
) ( SIZE( 1 .. 9 ) ),
                                   OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1
     vlr-Number
.. 9 ) ),
                                   [10] IMPLICIT OCTET STRING ( SIZE( 4 ) )
     lmsi
OPTIONAL,
     extensionContainer
                                   SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
            SEQUENCE {
                        MAP-EXTENSION .&extensionId ( {
               extId
                 ...}),
               extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extId } ) OPTIONAL} OPTIONAL,
         pcs-Extensions
                         [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
         ... } OPTIONAL,
      vlr-Capability
                                  [6] IMPLICIT SEQUENCE {
         supportedCamelPhases
                                                      [0] IMPLICIT BIT STRING {
           phase1 (0),
           phase2 (1),
           phase3 (2),
            phase4 (3)} (SIZE(1..16)) OPTIONAL,
                                                      SEQUENCE {
         extensionContainer
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
              SEQUENCE {
                  ext.Td
                           MAP-EXTENSION .&extensionId ( {
                     ...}),
                  extType MAP-EXTENSION .&ExtensionType ( {
                    ... } { @extId } ) OPTIONAL } OPTIONAL ,
            pcs-Extensions [1] IMPLICIT SEQUENCE {
             ... } OPTIONAL,
            ... } OPTIONAL,
         solsaSupportIndicator
                                                       [2] IMPLICIT NULL
OPTIONAL,
                                                      [1] IMPLICIT ENUMERATED {
         istSupportIndicator
           basicISTSupported ( 0 ),
istCommandSupported ( 1 ),
           ... } OPTIONAL,
         superChargerSupportedInServingNetworkEntity [3] CHOICE {
           sendSubscriberData [0] IMPLICIT NULL, subscriberDataStored [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 6 )
) } OPTIONAL,
         longFTN-Supported
                                                       [4] IMPLICIT NULL
OPTIONAL,
         supportedLCS-CapabilitySets
                                                   [5] IMPLICIT BIT STRING {
            lcsCapabilitySet1 (0 ),
            lcsCapabilitySet2 (1 ),
```

```
lcsCapabilitySet3 (2),
           lcsCapabilitySet4 (3 ) } ( SIZE( 2 .. 16 ) ) OPTIONAL,
                                                     [6] IMPLICIT BIT STRING {
        offeredCamel4CSIs
           o-csi (0),
           d-csi (1),
vt-csi (2),
           t-csi (3),
           mt-sms-csi (4),
           mg-csi (5),
           psi-enhancements (6 ) } ( SIZE( 7 .. 16 ) ) OPTIONAL } OPTIONAL ,
     informPreviousNetworkEntity [11] IMPLICIT NULL OPTIONAL, cs-LCS-NotSupportedByUE [12] IMPLICIT NULL OPTIONAL, v-gmlc-Address [2] IMPLICIT OCTET STRING ( SIZE( 5 .. 17 )
) OPTIONAL,
     add-info
                                   [13] IMPLICIT SEQUENCE {
                                   [0] IMPLICIT OCTET STRING ( SIZE( 8 ) ),
        skipSubscriberDataUpdate [1] IMPLICIT NULL OPTIONAL,
        ... } OPTIONAL }
  RESULT SEQUENCE {
                          OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1 .. 9 ) ),
     hlr-Number
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
              extId
                       MAP-EXTENSION .&extensionId ( {
                 ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extId } ) OPTIONAL} OPTIONAL,
                        [1] IMPLICIT SEQUENCE {
        pcs-Extensions
          ... } OPTIONAL,
        ... } OPTIONAL,
     add-Capability NULL OPTIONAL}
  ERRORS
     systemFailure |
     dataMissing
     unexpectedDataValue |
     unknownSubscriber
     roamingNotAllowed }
  CODE local : 2
cancelLocation OPERATION ::= {
  ARGUMENT [3] IMPLICIT SEQUENCE {
     identity imsi
                         CHOICE {
                         OCTET STRING ( SIZE( 3 .. 8 ) ),
        imsi-WithLMSI SEQUENCE {
           imsi OCTET STRING ( SIZE( 3 .. 8 ) ),
           lmsi
                     OCTET STRING ( SIZE( 4 ) ),
           ... }},
     updateProcedure ( 0 ),
        subscriptionWithdraw (1),
        ... } OPTIONAL,
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                    MAP-EXTENSION .&extensionId ( {
              extId
                 ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
```

```
...} { @extid } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
         ... } OPTIONAL,
        ... } OPTIONAL,
  RESULT
            SEQUENCE {
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
          SEQUENCE {
                      MAP-EXTENSION .&extensionId ( {
             extId
                ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extid } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
        ... } OPTIONAL,
        ... } OPTIONAL,
     ...}
  ERRORS
     dataMissing |
     unexpectedDataValue }
  CODE local : 3
purgeMS     OPERATION ::= {
  ARGUMENT [3] IMPLICIT SEQUENCE {
              OCTET STRING ( SIZE( 3 .. 8 ) ),
     imsi
                        [0] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE(
     vlr-Number
1 .. 9 ) ) OPTIONAL,
    sgsn-Number
                       [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE(
1 .. 9 ) ) OPTIONAL,
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
             extId
                      MAP-EXTENSION .&extensionId ( {
                ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
         ... } OPTIONAL,
        ... } OPTIONAL,
           SEQUENCE {
  RESULT
     freezeTMSI [0] IMPLICIT NULL OPTIONAL, freezeP-TMSI [1] IMPLICIT NULL OPTIONAL,
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
             extId MAP-EXTENSION .&extensionId ( {
               ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extid } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL,
  ERRORS
     dataMissing |
```

```
unexpectedDataValue |
     unknownSubscriber }
  CODE local : 67
sendIdentification OPERATION ::= {
  ARGUMENT SEQUENCE {
                               OCTET STRING ( SIZE( 1 .. 4 ) ),
     tmsi
     numberOfRequestedVectors INTEGER ( 1 .. 5 ) OPTIONAL, segmentationProhibited NULL OPTIONAL, extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                        MAP-EXTENSION .&extensionId ( {
              extId
                 ...}),
              extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extId } ) OPTIONAL} OPTIONAL,
                         [1] IMPLICIT SEQUENCE {
        pcs-Extensions
           ... } OPTIONAL,
        ... } OPTIONAL,
     msc-Number
                               OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1 .. 9
) ) OPTIONAL,
     previous-LAI
                                [0] IMPLICIT OCTET STRING ( SIZE( 5 ) )
OPTIONAL,
     hopCounter
                               [1] IMPLICIT INTEGER ( 0 .. 3 ) OPTIONAL}
  RESULT [3] IMPLICIT SEQUENCE {
                            OCTET STRING ( SIZE( 3 .. 8 ) ) OPTIONAL,
     authenticationSetList CHOICE {
        tripletList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 5 ) ) OF
           SEQUENCE {
  rand OCTET STRING ( SIZE( 16 ) ),
  sres OCTET STRING ( SIZE( 4 ) ),
  kc OCTET STRING ( SIZE( 8 ) ),
              ...},
        quintupletList
                         [1] IMPLICIT SEQUENCE ( SIZE( 1 .. 5 ) ) OF
           OCTET STRING ( SIZE( 16 ) ),
                         OCTET STRING ( SIZE( 16 ) ),
              ... }} OPTIONAL,
     currentSecurityContext [2] CHOICE {
        gsm-SecurityContextData [0] IMPLICIT SEQUENCE {
           kc OCTET STRING ( SIZE( 8 ) ),
                     OCTET STRING ( SIZE( 1 ) ),
           ...},
        umts-SecurityContextData
                                    [1] IMPLICIT SEQUENCE {
           ck OCTET STRING ( SIZE( 16 ) ),
                      OCTET STRING ( SIZE( 16 ) ),
                     OCTET STRING ( SIZE( 1 ) ),
           ... }} OPTIONAL,
     extensionContainer [3] IMPLICIT SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                     MAP-EXTENSION .&extensionId ( {
              extId
                 ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
```

```
...} { @extid } ) OPTIONAL} OPTIONAL.
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
         .. } OPTIONAL,
  ERRORS
     dataMissing |
     unidentifiedSubscriber }
  CODE local : 55
updateGprsLocation OPERATION ::= {
  ARGUMENT SEQUENCE {
                                 OCTET STRING ( SIZE( 3 .. 8 ) ),
     imsi
                                 OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1
     sgsn-Number
.. 9 ) ),
                                 OCTET STRING ( SIZE( 5 .. 17 ) ),
     sgsn-Address
     extensionContainer
                                 SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                       MAP-EXTENSION .&extensionId ( {
              extId
                ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL,
     sgsn-Capability
                                 [0] IMPLICIT SEQUENCE {
        solsaSupportIndicator
                                                   NULL OPTIONAL,
        extensionContainer
                                                   [1] IMPLICIT SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
              SEQUENCE {
                extId
                          MAP-EXTENSION .&extensionId ( {
                   ...}),
                 extType MAP-EXTENSION .&ExtensionType ( {
                   ...} { @extId } ) OPTIONAL} OPTIONAL,
           pcs-Extensions [1] IMPLICIT SEQUENCE {
             ... } OPTIONAL,
           ... } OPTIONAL,
        superChargerSupportedInServingNetworkEntity [2] CHOICE {
           sendSubscriberData [0] IMPLICIT NULL,
           subscriberDataStored [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 6 )
) } OPTIONAL,
        gprsEnhancementsSupportIndicator
                                                   [3] IMPLICIT NULL
OPTIONAL,
        supportedCamelPhases
                                                   [4] IMPLICIT BIT STRING {
           phase1 (0),
           phase2 (1),
           phase3 (2),
           phase4 (3 ) } ( SIZE( 1 .. 16 ) ) OPTIONAL,
                                                   [5] IMPLICIT BIT STRING {
        supportedLCS-CapabilitySets
           lcsCapabilitySet1 (0),
           lcsCapabilitySet2 (1),
           lcsCapabilitySet3 (2),
           lcsCapabilitySet4 (3)} (SIZE(2..16)) OPTIONAL,
        offeredCamel4CSIs
                                                   [6] IMPLICIT BIT STRING {
           o-csi (0),
```

```
d-csi (1),
            vt-csi (2),
            t-csi (3),
            mt-sms-csi (4),
            mg-csi (5),
            psi-enhancements (6 ) } ( SIZE( 7 .. 16 ) ) OPTIONAL,
         smsCallBarringSupportIndicator
                                                        [7] IMPLICIT NULL
OPTIONAL,
      informPreviousNetworkEntity [1] IMPLICIT NULL OPTIONAL, ps-LCS-NotSupportedByUE [2] IMPLICIT NULL OPTIONAL, v-gmlc-Address [3] IMPLICIT OCTET STRING ( SIZE( 5 .. 17 )
) OPTIONAL,
      add-info
                                     [4] IMPLICIT SEQUENCE {
                                     [0] IMPLICIT OCTET STRING ( SIZE( 8 ) ),
         skipSubscriberDataUpdate [1] IMPLICIT NULL OPTIONAL,
         ... } OPTIONAL}
   RESULT SEQUENCE {
                           OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1 .. 9 ) ),
      hlr-Number
      extensionContainer SEQUENCE {
         privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
            SEQUENCE {
                         MAP-EXTENSION .&extensionId ( {
               extId
                  ...} ) ,
               extType MAP-EXTENSION .&ExtensionType ( {
                  ...} { @extId } ) OPTIONAL} OPTIONAL,
         pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
         ... } OPTIONAL,
      add-Capability NULL OPTIONAL}
   ERRORS
      systemFailure |
      unexpectedDataValue |
      unknownSubscriber |
      roamingNotAllowed }
   CODE local : 23
provideSubscriberInfo OPERATION ::= {
   ARGUMENT SEQUENCE {
                            [0] IMPLICIT OCTET STRING ( SIZE( 3 .. 8 ) ),
      imsi
                           [1] IMPLICIT OCTET STRING ( SIZE( 4 ) ) OPTIONAL,
      lmsi
      requestedInfo [2] IMPLICIT SEQUENCE {
         locationInformation [0] IMPLICIT NULL OPTIONAL,
         subscriberState [1] IMPLICIT NULL OPTIONAL,
extensionContainer [2] IMPLICIT SEQUENCE {
            privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
               SEQUENCE {
                            MAP-EXTENSION .&extensionId ( {
                     ...} ) ,
                  extType MAP-EXTENSION .&ExtensionType ( {
                     ...} { @extId } ) OPTIONAL } OPTIONAL .
            pcs-Extensions [1] IMPLICIT SEQUENCE {
              ... } OPTIONAL,
            ... } OPTIONAL,
         currentLocation [3] IMPLICIT NULL OPTIONAL,
requestedDomain [4] IMPLICIT ENUMERATED {
            cs-Domain (0),
```

```
ps-Domain (1),
            ... } OPTIONAL,
                                [6] IMPLICIT NULL OPTIONAL,
         ms-classmark
      ms-classmark [5] IMPLICIT NULL OPTIONAL,
mnpRequestedInfo [7] IMPLICIT NULL OPTIONAL),
extensionContainer [3] IMPLICIT SEQUENCE {
         privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
            SEQUENCE {
                          MAP-EXTENSION .&extensionId ( {
                extId
                   ...}),
                extType MAP-EXTENSION .&ExtensionType ( {
                   ...} { @extid } ) OPTIONAL} OPTIONAL,
         pcs-Extensions [1] IMPLICIT SEQUENCE {
           ... } OPTIONAL,
         ... } OPTIONAL,
   RESULT
              SEQUENCE {
                            SEQUENCE {
      subscriberInfo
         locationInformation [0] IMPLICIT SEQUENCE {
            ageOfLocationInformation INTEGER ( 0 .. 32767 ) OPTIONAL, geographicalInformation [0] IMPLICIT OCTET STRING ( SIZE
                                                  [0] IMPLICIT OCTET STRING ( SIZE(
8 ) ) OPTIONAL,
            vlr-number
                                                  [1] IMPLICIT OCTET STRING ( SIZE(
1 .. 20 ) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
            locationNumber
                                                   [2] IMPLICIT OCTET STRING ( SIZE(
2 .. 10 ) ) OPTIONAL,
            cellGlobalIdOrServiceAreaIdOrLAI [3] CHOICE {
               cellGlobalIdOrServiceAreaIdFixedLength [0] IMPLICIT OCTET
STRING ( SIZE( 7 ) ),
               laiFixedLength
                                                               [1] IMPLICIT OCTET
STRING ( SIZE( 5 ) ) } OPTIONAL,
            extensionContainer
                                                  [4] IMPLICIT SEQUENCE {
                privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                   SEQUENCE {
                                MAP-EXTENSION .&extensionId ( {
                      extId
                         ...}),
                       extType MAP-EXTENSION .&ExtensionType ( {
                          ... } { @extId } ) OPTIONAL } OPTIONAL,
                pcs-Extensions [1] IMPLICIT SEQUENCE {
                  ... } OPTIONAL,
                ... } OPTIONAL,
             . . . ,
             selectedLSA-Id
                                                  [5] IMPLICIT OCTET STRING ( SIZE(
3 ) ) OPTIONAL,
            msc-Number
                                                  [6] IMPLICIT OCTET STRING ( SIZE(
1 .. 20 ) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
                                                  [7] IMPLICIT OCTET STRING ( SIZE(
            geodeticInformation
10 ) ) OPTIONAL,
            currentLocationRetrieved
                                                  [8] IMPLICIT NULL OPTIONAL,
                                                   [9] IMPLICIT NULL OPTIONAL}
            sai-Present
OPTIONAL,
         subscriberState [1] CHOICE {
  assumedIdle [0] IMPLICIT NULL,
  camelBusy [1] IMPLICIT NULL,
  netDetNotReachable ENUMERATED {
               msPurged ( 0 ),
imsiDetached ( 1 ),
restrictedArea ( 2 ),
                                  ( 0 ),
```

```
notRegistered (3)},
         notProvidedFromVLR [2] IMPLICIT NULL} OPTIONAL, extensionContainer [2] IMPLICIT SEQUENCE {
            privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
                SEQUENCE {
                              MAP-EXTENSION .&extensionId ( {
                   extId
                       ...} ) ,
                   extType MAP-EXTENSION .&ExtensionType ( {
                      ...} { @extId } ) OPTIONAL} OPTIONAL,
             pcs-Extensions [1] IMPLICIT SEQUENCE {
               ... } OPTIONAL,
             ... } OPTIONAL,
         locationInformationGPRS [3] IMPLICIT SEQUENCE {
             cellGlobalIdOrServiceAreaIdOrLAI [0] CHOICE {
                cellGlobalIdOrServiceAreaIdFixedLength [0] IMPLICIT OCTET
STRING ( SIZE( 7 ) ),
                laiFixedLength
                                                               [1] IMPLICIT OCTET
STRING ( SIZE( 5 ) ) } OPTIONAL,
                                         [1] IMPLICIT OCTET STRING ( SIZE(
            routeingAreaIdentity
6 ) ) OPTIONAL,
            geographicalInformation
                                                  [2] IMPLICIT OCTET STRING ( SIZE(
8 ) ) OPTIONAL,
                                                  [3] IMPLICIT OCTET STRING ( SIZE(
            sgsn-Number
1 .. 20 ) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
            selectedLSAIdentity
                                                  [4] IMPLICIT OCTET STRING ( SIZE(
3 ) ) OPTIONAL,
            extensionContainer
                                                  [5] IMPLICIT SEQUENCE {
               privateExtensionList [0] IMPLICIT SEQUENCE (SIZE(1..10))
OF
                   SEQUENCE {
                      extId
                                MAP-EXTENSION .&extensionId ( {
                         ...} ) ,
                       extType MAP-EXTENSION .&ExtensionType ( {
                          ...} { @extId } ) OPTIONAL} OPTIONAL,
                pcs-Extensions [1] IMPLICIT SEQUENCE {
                 ... } OPTIONAL,
                ... } OPTIONAL,
             sai-Present
                                                  [6] IMPLICIT NULL OPTIONAL,
            geodeticInformation
                                                  [7] IMPLICIT OCTET STRING ( SIZE(
10 ) ) OPTIONAL,
            currentLocationRetrieved [8] IMPLICIT NULL OPTIONAL, ageOfLocationInformation [9] IMPLICIT INTEGER ( 0 .. 32767
) OPTIONAL } OPTIONAL ,
         ps-SubscriberState [4] CHOICE {
            notProvidedFromSGSN
                                                       [0] IMPLICIT NULL,
                                                       [1] IMPLICIT NULL,
            ps-Detached
            ps-Detached [1] IMPLICIT NULL,
ps-AttachedNotReachableForPaging [2] IMPLICIT NULL,
ps-AttachedReachableForPaging [3] IMPLICIT NULL,
ps-PDP-ActiveNotReachableForPaging [4] IMPLICIT SEQUENCE (
SIZE( 1 .. 50 ) ) OF
                SEQUENCE {
                   pdp-ContextIdentifier [0] IMPLICIT INTEGER (1 .. 50 ),
pdp-ContextActive [1] IMPLICIT NULL OPTIONAL,
pdp-Type [2] IMPLICIT OCTET STRING (SIZE(2))
)),
                   pdp-Address
                                     [3] IMPLICIT OCTET STRING ( SIZE( 1
.. 16 ) ) OPTIONAL,
```

```
apn-Subscribed
                                           [4] IMPLICIT OCTET STRING ( SIZE( 2
.. 63 ) ) OPTIONAL,
                  apn-InUse
                                            [5] IMPLICIT OCTET STRING ( SIZE( 2
.. 63 ) ) OPTIONAL,
                                            [6] IMPLICIT INTEGER ( 0 .. 15 )
                  nsapi
OPTIONAL,
                                            [7] IMPLICIT OCTET STRING ( SIZE( 1
                  transactionId
.. 2 ) ) OPTIONAL,
                                            [8] IMPLICIT OCTET STRING ( SIZE ( 4
                 teid-ForGnAndGp
) ) OPTIONAL,
                  teid-ForIu
                                            [9] IMPLICIT OCTET STRING ( SIZE( 4
) ) OPTIONAL,
                  ggsn-Address
                                            [10] IMPLICIT OCTET STRING ( SIZE( 5
.. 17 ) ) OPTIONAL,
                  qos-Subscribed
                                            [11] IMPLICIT OCTET STRING ( SIZE( 1
.. 9 ) ) OPTIONAL,
                                            [12] IMPLICIT OCTET STRING ( SIZE( 1
                  qos-Requested
.. 9 ) ) OPTIONAL,
                  gos-Negotiated
                                            [13] IMPLICIT OCTET STRING ( SIZE( 1
.. 9 ) ) OPTIONAL,
                  chargingId
                                            [14] IMPLICIT OCTET STRING ( SIZE ( 4
) ) OPTIONAL,
                  chargingCharacteristics
                                           [15] IMPLICIT OCTET STRING ( SIZE( 2
) ) OPTIONAL,
                 rnc-Address
                                            [16] IMPLICIT OCTET STRING ( SIZE( 5
.. 17 ) ) OPTIONAL,
                  extensionContainer
                                           [17] IMPLICIT SEQUENCE {
                     privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ..
10 ) ) OF
                        SEQUENCE {
                           extId
                                     MAP-EXTENSION .&extensionId ( {
                              ...}),
                           extType MAP-EXTENSION .&ExtensionType ( {
                              ...} { @extId } ) OPTIONAL} OPTIONAL,
                                      [1] IMPLICIT SEQUENCE {
                     pcs-Extensions
                       ... } OPTIONAL,
                     ... } OPTIONAL,
                  qos2-Subscribed
                                           [18] IMPLICIT OCTET STRING ( SIZE( 1
.. 3 ) ) OPTIONAL,
                  qos2-Requested
                                           [19] IMPLICIT OCTET STRING ( SIZE( 1
.. 3 ) ) OPTIONAL,
                                           [20] IMPLICIT OCTET STRING ( SIZE( 1
                  gos2-Negotiated
.. 3 ) ) OPTIONAL },
           ps-PDP-ActiveReachableForPaging [5] IMPLICIT SEQUENCE (
SIZE( 1 .. 50 ) ) OF
               SEQUENCE {
                 pdp-ContextIdentifier [0] IMPLICIT INTEGER ( 1 .. 50 ),
pdp-ContextActive [1] IMPLICIT NULL OPTIONAL,
                                            [2] IMPLICIT OCTET STRING ( SIZE( 2
                  pdp-Type
) ),
                                         [3] IMPLICIT OCTET STRING ( SIZE( 1
                  pdp-Address
.. 16 ) ) OPTIONAL,
                  apn-Subscribed [4] IMPLICIT OCTET STRING ( SIZE( 2
.. 63 ) ) OPTIONAL,
                                           [5] IMPLICIT OCTET STRING ( SIZE( 2
                  apn-InUse
.. 63 ) ) OPTIONAL,
                                           [6] IMPLICIT INTEGER ( 0 .. 15 )
                  nsapi
OPTIONAL.
                  transactionId
                                           [7] IMPLICIT OCTET STRING ( SIZE( 1
.. 2 ) ) OPTIONAL,
```

```
[8] IMPLICIT OCTET STRING ( SIZE ( 4
                 teid-ForGnAndGp
) ) OPTIONAL,
                                            [9] IMPLICIT OCTET STRING ( SIZE( 4
                  teid-ForIu
) ) OPTIONAL,
                                           [10] IMPLICIT OCTET STRING ( SIZE( 5
                 ggsn-Address
.. 17 ) ) OPTIONAL,
                  qos-Subscribed
                                           [11] IMPLICIT OCTET STRING ( SIZE( 1
.. 9 ) ) OPTIONAL,
                                           [12] IMPLICIT OCTET STRING ( SIZE( 1
                  qos-Requested
.. 9 ) ) OPTIONAL,
                  qos-Negotiated
                                           [13] IMPLICIT OCTET STRING ( SIZE( 1
.. 9 ) ) OPTIONAL,
                  chargingId
                                            [14] IMPLICIT OCTET STRING ( SIZE( 4
) ) OPTIONAL,
                                           [15] IMPLICIT OCTET STRING ( SIZE( 2
                 chargingCharacteristics
) ) OPTIONAL,
                                           [16] IMPLICIT OCTET STRING ( SIZE( 5
                 rnc-Address
.. 17 ) ) OPTIONAL,
                 extensionContainer
                                           [17] IMPLICIT SEQUENCE {
                    privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ...
10 ) ) OF
                       SEQUENCE {
                          extId
                                     MAP-EXTENSION .&extensionId ( {
                             ...}),
                           extType MAP-EXTENSION .&ExtensionType ( {
                             ...} { @extId } ) OPTIONAL} OPTIONAL,
                    pcs-Extensions [1] IMPLICIT SEQUENCE {
                       ... } OPTIONAL,
                     ... } OPTIONAL,
                  qos2-Subscribed
                                          [18] IMPLICIT OCTET STRING ( SIZE( 1
.. 3 ) ) OPTIONAL,
                                           [19] IMPLICIT OCTET STRING ( SIZE( 1
                  qos2-Requested
.. 3 ) ) OPTIONAL,
                                          [20] IMPLICIT OCTET STRING ( SIZE( 1
                 qos2-Negotiated
.. 3 ) ) OPTIONAL },
           netDetNotReachable
                                                  ENUMERATED {
              msPurged (0),
              imsiDetached (1),
restrictedArea (2),
notRegistered (3)} OPTIONAL,
                                  [5] IMPLICIT OCTET STRING ( SIZE( 8 ) )
        imei
OPTIONAL,
        ms-Classmark2
                                 [6] IMPLICIT OCTET STRING ( SIZE( 3 ) )
OPTIONAL,
        qprs-MS-Class
                                  [7] IMPLICIT SEQUENCE {
           mSNetworkCapability
                                     [0] IMPLICIT OCTET STRING ( SIZE( 1 .. 8 )
),
           mSRadioAccessCapability [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 50
) ) OPTIONAL } OPTIONAL ,
        mnpInfoRes
                                 [8] IMPLICIT SEQUENCE {
           routeingNumber
                                      [0] IMPLICIT OCTET STRING ( SIZE( 1 .. 5 )
) OPTIONAL,
                                      [1] IMPLICIT OCTET STRING ( SIZE( 3 .. 8 )
            imsi
) OPTIONAL,
                                     [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 20
           msisdn
) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
           numberPortabilityStatus [3] IMPLICIT ENUMERATED {
                                                     (0),
              notKnownToBePorted
                                                     (1),
              ownNumberPortedOut
              foreignNumberPortedToForeignNetwork
                                                     (2),
```

```
(4),
              ownNumberNotPortedOut
                                                    (5) } OPTIONAL,
              foreignNumberPortedIn
           extensionContainer [4] IMPLICIT SEQUENCE {
             privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                 SEQUENCE {
                             MAP-EXTENSION .&extensionId ( {
                    extId
                       ...}),
                    extType MAP-EXTENSION .&ExtensionType ( {
                       ...} { @extId } ) OPTIONAL} OPTIONAL,
                              [1] IMPLICIT SEQUENCE {
              pcs-Extensions
                ... } OPTIONAL,
              ... } OPTIONAL,
           ... } OPTIONAL },
      extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                       MAP-EXTENSION .&extensionId ( {
              extId
                 ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
               ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL,
  ERRORS
     dataMissing |
     unexpectedDataValue }
  CODE local : 70
anyTimeInterrogation OPERATION ::= {
  ARGUMENT SEQUENCE {
     subscriberIdentity [0] CHOICE {
       imsi [0] IMPLICIT OCTET STRING ( SIZE( 3 .. 8 ) ),
        msisdn [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1 ..
9))},
     requestedInfo [1] IMPLICIT SEQUENCE {
        locationInformation [0] IMPLICIT NULL OPTIONAL,
        subscriberState [1] IMPLICIT NULL OPTIONAL,
extensionContainer [2] IMPLICIT SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
              SEQUENCE {
                          MAP-EXTENSION .&extensionId ( {
                    ...} ) ,
                 extType MAP-EXTENSION .&ExtensionType ( {
                    ...} { @extId } ) OPTIONAL} OPTIONAL,
           pcs-Extensions [1] IMPLICIT SEQUENCE {
            ... } OPTIONAL,
           ... } OPTIONAL,
        currentLocation [3] IMPLICIT NULL OPTIONAL,
requestedDomain [4] IMPLICIT ENUMERATED {
           cs-Domain (0),
ps-Domain (1),
           ... } OPTIONAL,
```

```
gsmSCF-Address [3] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE(
1 .. 9 ) ),
     extensionContainer [2] IMPLICIT SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
            SEQUENCE {
               extId
                        MAP-EXTENSION .&extensionId ( {
                  ...}),
               extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
         ... } OPTIONAL,
   RESULT
             SEQUENCE {
      subscriberInfo
                          SEQUENCE {
        locationInformation [0] IMPLICIT SEQUENCE {
           ageOfLocationInformation INTEGER ( 0 .. 32767 ) OPTIONAL, geographicalInformation [0] IMPLICIT OCTET STRING ( SIZE
                                              [0] IMPLICIT OCTET STRING ( SIZE(
8 ) ) OPTIONAL,
           vlr-number
                                               [1] IMPLICIT OCTET STRING ( SIZE(
1 .. 20 ) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
           locationNumber
                                               [2] IMPLICIT OCTET STRING ( SIZE(
2 .. 10 ) ) OPTIONAL,
           cellGlobalIdOrServiceAreaIdOrLAI [3] CHOICE {
              cellGlobalIdOrServiceAreaIdFixedLength [0] IMPLICIT OCTET
STRING ( SIZE( 7 ) ),
              laiFixedLength
                                                          [1] IMPLICIT OCTET
STRING ( SIZE( 5 ) ) } OPTIONAL,
           extensionContainer
                                              [4] IMPLICIT SEQUENCE {
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                  SEQUENCE {
                    extId
                              MAP-EXTENSION .&extensionId ( {
                       ...}),
                     extType MAP-EXTENSION .&ExtensionType ( {
                        ... } { @extId } ) OPTIONAL } OPTIONAL,
               pcs-Extensions [1] IMPLICIT SEQUENCE {
                ... } OPTIONAL,
               ... } OPTIONAL,
            . . . ,
            selectedLSA-Id
                                              [5] IMPLICIT OCTET STRING ( SIZE(
3 ) ) OPTIONAL,
            msc-Number
                                              [6] IMPLICIT OCTET STRING ( SIZE(
1 .. 20 ) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
            geodeticInformation
                                              [7] IMPLICIT OCTET STRING ( SIZE(
10 ) ) OPTIONAL,
           currentLocationRetrieved [8] IMPLICIT NULL OPTIONAL,
                                               [9] IMPLICIT NULL OPTIONAL}
            sai-Present
OPTIONAL,
        subscriberState [1] CHOICE {
  assumedIdle [0] IMPLICIT NULL,
  camelBusy [1] IMPLICIT NULL,
  netDetNotReachable ENUMERATED {
              msPurged (0), imsiDetached (1), restrictedArea (2),
```

```
notRegistered (3)},
         notProvidedFromVLR [2] IMPLICIT NULL} OPTIONAL, extensionContainer [2] IMPLICIT SEQUENCE {
            privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
                SEQUENCE {
                              MAP-EXTENSION .&extensionId ( {
                   extId
                      ...} ) ,
                   extType MAP-EXTENSION .&ExtensionType ( {
                      ...} { @extId } ) OPTIONAL} OPTIONAL,
             pcs-Extensions [1] IMPLICIT SEQUENCE {
              ... } OPTIONAL,
             ... } OPTIONAL,
         locationInformationGPRS [3] IMPLICIT SEQUENCE {
             cellGlobalIdOrServiceAreaIdOrLAI [0] CHOICE {
                cellGlobalIdOrServiceAreaIdFixedLength [0] IMPLICIT OCTET
STRING ( SIZE( 7 ) ),
                laiFixedLength
                                                               [1] IMPLICIT OCTET
STRING ( SIZE( 5 ) ) } OPTIONAL,
                                         [1] IMPLICIT OCTET STRING ( SIZE(
            routeingAreaIdentity
6 ) ) OPTIONAL,
            geographicalInformation
                                                  [2] IMPLICIT OCTET STRING ( SIZE(
8 ) ) OPTIONAL,
                                                  [3] IMPLICIT OCTET STRING ( SIZE(
            sgsn-Number
1 .. 20 ) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
            selectedLSAIdentity
                                                  [4] IMPLICIT OCTET STRING ( SIZE(
3 ) ) OPTIONAL,
            extensionContainer
                                                  [5] IMPLICIT SEQUENCE {
               privateExtensionList [0] IMPLICIT SEQUENCE (SIZE(1..10))
OF
                   SEQUENCE {
                      extId
                                MAP-EXTENSION .&extensionId ( {
                         ...} ) ,
                      extType MAP-EXTENSION .&ExtensionType ( {
                         ...} { @extId } ) OPTIONAL} OPTIONAL,
                pcs-Extensions [1] IMPLICIT SEQUENCE {
                 ... } OPTIONAL,
                ... } OPTIONAL,
             sai-Present
                                                  [6] IMPLICIT NULL OPTIONAL,
            geodeticInformation
                                                  [7] IMPLICIT OCTET STRING ( SIZE(
10 ) ) OPTIONAL,
            currentLocationRetrieved [8] IMPLICIT NULL OPTIONAL, ageOfLocationInformation [9] IMPLICIT INTEGER ( 0 .. 32767
) OPTIONAL,
         ps-SubscriberState [4] CHOICE {
            notProvidedFromSGSN
                                                      [0] IMPLICIT NULL,
            ps-Detached
                                                      [1] IMPLICIT NULL,
            ps-Detached [1] IMPLICIT NULL,
ps-AttachedNotReachableForPaging [2] IMPLICIT NULL,
ps-AttachedReachableForPaging [3] IMPLICIT NULL,
ps-PDP-ActiveNotReachableForPaging [4] IMPLICIT SEQUENCE (
SIZE( 1 .. 50 ) ) OF
                SEQUENCE {
                   pdp-ContextIdentifier [0] IMPLICIT INTEGER (1 .. 50 ),
pdp-ContextActive [1] IMPLICIT NULL OPTIONAL,
pdp-Type [2] IMPLICIT OCTET STRING (SIZE(2))
)),
                   pdp-Address
                                     [3] IMPLICIT OCTET STRING ( SIZE( 1
.. 16 ) ) OPTIONAL,
```

```
apn-Subscribed
                                           [4] IMPLICIT OCTET STRING ( SIZE( 2
.. 63 ) ) OPTIONAL,
                  apn-InUse
                                            [5] IMPLICIT OCTET STRING ( SIZE( 2
.. 63 ) ) OPTIONAL,
                                            [6] IMPLICIT INTEGER ( 0 .. 15 )
                  nsapi
OPTIONAL,
                                            [7] IMPLICIT OCTET STRING ( SIZE( 1
                  transactionId
.. 2 ) ) OPTIONAL,
                                            [8] IMPLICIT OCTET STRING ( SIZE ( 4
                 teid-ForGnAndGp
) ) OPTIONAL,
                  teid-ForIu
                                            [9] IMPLICIT OCTET STRING ( SIZE( 4
) ) OPTIONAL,
                  ggsn-Address
                                            [10] IMPLICIT OCTET STRING ( SIZE( 5
.. 17 ) ) OPTIONAL,
                  qos-Subscribed
                                            [11] IMPLICIT OCTET STRING ( SIZE( 1
.. 9 ) ) OPTIONAL,
                                            [12] IMPLICIT OCTET STRING ( SIZE( 1
                  qos-Requested
.. 9 ) ) OPTIONAL,
                  gos-Negotiated
                                            [13] IMPLICIT OCTET STRING ( SIZE( 1
.. 9 ) ) OPTIONAL,
                  chargingId
                                            [14] IMPLICIT OCTET STRING ( SIZE ( 4
) ) OPTIONAL,
                  chargingCharacteristics
                                           [15] IMPLICIT OCTET STRING ( SIZE( 2
) ) OPTIONAL,
                 rnc-Address
                                            [16] IMPLICIT OCTET STRING ( SIZE ( 5
.. 17 ) ) OPTIONAL,
                  extensionContainer
                                           [17] IMPLICIT SEQUENCE {
                     privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ..
10 ) ) OF
                        SEQUENCE {
                           extId
                                     MAP-EXTENSION .&extensionId ( {
                              ...}),
                           extType MAP-EXTENSION .&ExtensionType ( {
                              ...} { @extId } ) OPTIONAL} OPTIONAL,
                                      [1] IMPLICIT SEQUENCE {
                     pcs-Extensions
                       ... } OPTIONAL,
                     ... } OPTIONAL,
                  qos2-Subscribed
                                           [18] IMPLICIT OCTET STRING ( SIZE( 1
.. 3 ) ) OPTIONAL,
                  qos2-Requested
                                           [19] IMPLICIT OCTET STRING ( SIZE( 1
.. 3 ) ) OPTIONAL,
                                           [20] IMPLICIT OCTET STRING ( SIZE( 1
                  gos2-Negotiated
.. 3 ) ) OPTIONAL },
           ps-PDP-ActiveReachableForPaging [5] IMPLICIT SEQUENCE (
SIZE( 1 .. 50 ) ) OF
               SEQUENCE {
                 pdp-ContextIdentifier [0] IMPLICIT INTEGER ( 1 .. 50 ),
pdp-ContextActive [1] IMPLICIT NULL OPTIONAL,
                                            [2] IMPLICIT OCTET STRING ( SIZE( 2
                  pdp-Type
) ),
                                         [3] IMPLICIT OCTET STRING ( SIZE( 1
                  pdp-Address
.. 16 ) ) OPTIONAL,
                  apn-Subscribed [4] IMPLICIT OCTET STRING ( SIZE( 2
.. 63 ) ) OPTIONAL,
                                           [5] IMPLICIT OCTET STRING ( SIZE( 2
                  apn-InUse
.. 63 ) ) OPTIONAL,
                                           [6] IMPLICIT INTEGER ( 0 .. 15 )
                  nsapi
OPTIONAL.
                  transactionId
                                           [7] IMPLICIT OCTET STRING ( SIZE( 1
.. 2 ) ) OPTIONAL,
```

```
[8] IMPLICIT OCTET STRING ( SIZE ( 4
                 teid-ForGnAndGp
) ) OPTIONAL,
                                            [9] IMPLICIT OCTET STRING ( SIZE( 4
                  teid-ForIu
) ) OPTIONAL,
                                           [10] IMPLICIT OCTET STRING ( SIZE( 5
                 ggsn-Address
.. 17 ) ) OPTIONAL,
                  qos-Subscribed
                                           [11] IMPLICIT OCTET STRING ( SIZE( 1
.. 9 ) ) OPTIONAL,
                                           [12] IMPLICIT OCTET STRING ( SIZE( 1
                  qos-Requested
.. 9 ) ) OPTIONAL,
                  qos-Negotiated
                                           [13] IMPLICIT OCTET STRING ( SIZE( 1
.. 9 ) ) OPTIONAL,
                  chargingId
                                            [14] IMPLICIT OCTET STRING ( SIZE( 4
) ) OPTIONAL,
                                           [15] IMPLICIT OCTET STRING ( SIZE( 2
                 chargingCharacteristics
) ) OPTIONAL,
                                           [16] IMPLICIT OCTET STRING ( SIZE( 5
                 rnc-Address
.. 17 ) ) OPTIONAL,
                 extensionContainer
                                           [17] IMPLICIT SEQUENCE {
                    privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ...
10 ) ) OF
                       SEQUENCE {
                          extId
                                     MAP-EXTENSION .&extensionId ( {
                             ...}),
                           extType MAP-EXTENSION .&ExtensionType ( {
                             ...} { @extId } ) OPTIONAL} OPTIONAL,
                    pcs-Extensions
                                    [1] IMPLICIT SEQUENCE {
                       ... } OPTIONAL,
                     ... } OPTIONAL,
                  qos2-Subscribed
                                           [18] IMPLICIT OCTET STRING ( SIZE( 1
.. 3 ) ) OPTIONAL,
                                           [19] IMPLICIT OCTET STRING ( SIZE( 1
                  qos2-Requested
.. 3 ) ) OPTIONAL,
                                          [20] IMPLICIT OCTET STRING ( SIZE( 1
                 qos2-Negotiated
.. 3 ) ) OPTIONAL },
           netDetNotReachable
                                                  ENUMERATED {
                              (0),
              msPurged
              imsiDetached (1),
restrictedArea (2),
notRegistered (3)} OPTIONAL,
                                  [5] IMPLICIT OCTET STRING ( SIZE( 8 ) )
        imei
OPTIONAL,
        ms-Classmark2
                                 [6] IMPLICIT OCTET STRING ( SIZE( 3 ) )
OPTIONAL,
        qprs-MS-Class
                                  [7] IMPLICIT SEQUENCE {
           mSNetworkCapability
                                     [0] IMPLICIT OCTET STRING ( SIZE( 1 .. 8 )
),
           mSRadioAccessCapability [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 50
) ) OPTIONAL } OPTIONAL ,
        mnpInfoRes
                                 [8] IMPLICIT SEQUENCE {
           routeingNumber
                                      [0] IMPLICIT OCTET STRING ( SIZE( 1 .. 5 )
) OPTIONAL,
                                      [1] IMPLICIT OCTET STRING ( SIZE( 3 .. 8 )
            imsi
) OPTIONAL,
                                     [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 20
           msisdn
) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
           numberPortabilityStatus [3] IMPLICIT ENUMERATED {
                                                      (0),
              notKnownToBePorted
                                                      (1),
              ownNumberPortedOut
              foreignNumberPortedToForeignNetwork
                                                     (2),
```

```
(4),
              ownNumberNotPortedOut
              foreignNumberPortedIn
                                                    (5) } OPTIONAL,
           extensionContainer [4] IMPLICIT SEQUENCE {
             privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                 SEQUENCE {
                             MAP-EXTENSION .&extensionId ( {
                    extId
                       ...}),
                    extType MAP-EXTENSION .&ExtensionType ( {
                       ...} { @extId } ) OPTIONAL} OPTIONAL,
                              [1] IMPLICIT SEQUENCE {
              pcs-Extensions
                ... } OPTIONAL,
              ... } OPTIONAL,
           ... } OPTIONAL },
      privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                       MAP-EXTENSION .&extensionId ( {
              extId
                 ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extid } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL,
  ERRORS
     systemFailure |
     ati-NotAllowed |
     dataMissing
     unexpectedDataValue |
     unknownSubscriber }
  CODE local : 71
   }
anyTimeSubscriptionInterrogation OPERATION ::= {
  ARGUMENT SEQUENCE {
     subscriberIdentity
                               [0] CHOICE {
        imsi [0] IMPLICIT OCTET STRING ( SIZE( 3 .. 8 ) ),
        msisdn [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1 ..
9))},
     requestedSubscriptionInfo [1] IMPLICIT SEQUENCE {
        requestedSS-Info
                                                  [1] IMPLICIT SEQUENCE {
           ss-Code OCTET STF basicService CHOICE {
                             OCTET STRING ( SIZE( 1 ) ),
             bearerService [2] IMPLICIT OCTET STRING ( SIZE( 1 ) ),
teleservice [3] IMPLICIT OCTET STRING ( SIZE( 1 ) )}
OPTIONAL,
           longFTN-Supported [4] IMPLICIT NULL OPTIONAL,
                                                  [2] IMPLICIT NULL OPTIONAL,
        requestedCAMEL-SubscriptionInfo
                                                  [3] IMPLICIT ENUMERATED {
           o-CSI (0),
                        (1),
           t-CSI
           vt-CSI (2),
tif-CSI (3),
gprs-CSI (4),
mo-sms-CSI (5),
ss-CSI (6),
```

```
m-CSI ( 7 ),
d-csi ( 8 ) } OPTIONAL,
        supportedVLR-CAMEL-Phases
                                                  [4] IMPLICIT NULL OPTIONAL,
        supportedSGSN-CAMEL-Phases
                                                  [5] IMPLICIT NULL OPTIONAL,
                                                  [6] IMPLICIT SEQUENCE {
        extensionContainer
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
              SEQUENCE {
                          MAP-EXTENSION .&extensionId ( {
                 extId
                    ...}),
                 extType MAP-EXTENSION .&ExtensionType ( {
                    ...} { @extId } ) OPTIONAL} OPTIONAL,
                           [1] IMPLICIT SEQUENCE {
           pcs-Extensions
             ... } OPTIONAL,
           ... } OPTIONAL,
        additionalRequestedCAMEL-SubscriptionInfo [7] IMPLICIT ENUMERATED {
           mt-sms-CSI (0),
           mg-csi (1),
o-IM-CSI (2),
d-IM-CSI (3),
vt-IM-CSI (4),
           ... } OPTIONAL },
     qsmSCF-Address
                               [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) )
( SIZE( 1 .. 9 ) ),
     extensionContainer
                               [3] IMPLICIT SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
              extId
                       MAP-EXTENSION .&extensionId ( {
                 ...}),
              extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extId } ) OPTIONAL} OPTIONAL,
                        [1] IMPLICIT SEQUENCE {
        pcs-Extensions
          ... } OPTIONAL,
        ... } OPTIONAL,
     longFTN-Supported
                               [4] IMPLICIT NULL OPTIONAL,
     ...}
  RESULT
            SEQUENCE {
     callForwardingData [1] IMPLICIT SEQUENCE {
        forwardingFeatureList SEQUENCE (SIZE(1..32)) OF
           SEQUENCE {
                                   CHOICE {
              basicService
                ext-BearerService
                                     [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 5
) ),
                ext-Teleservice [3] IMPLICIT OCTET STRING ( SIZE( 1 .. 5
) ) } OPTIONAL,
                                    [4] IMPLICIT OCTET STRING ( SIZE( 1 .. 5
              ss-Status
) ),
             forwardedToNumber [5] IMPLICIT OCTET STRING ( SIZE( 1 .. 20
) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
              forwardedToSubaddress [8] IMPLICIT OCTET STRING ( SIZE( 1 .. 21
) ) OPTIONAL,
              forwardingOptions [6] IMPLICIT OCTET STRING ( SIZE( 1 .. 5
) ) OPTIONAL,
              noReplyConditionTime [7] IMPLICIT INTEGER ( 1 .. 100 )
OPTIONAL,
             extensionContainer [9] IMPLICIT SEQUENCE {
                privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10
) ) OF
                    SEQUENCE {
```

```
extId MAP-EXTENSION .&extensionId ( {
                           ...}),
                        extType MAP-EXTENSION .&ExtensionType ( {
                           ...} { @extid } ) OPTIONAL} OPTIONAL,
                  pcs-Extensions [1] IMPLICIT SEQUENCE {
                   ... } OPTIONAL,
                  ... } OPTIONAL,
               longForwardedToNumber [10] IMPLICIT OCTET STRING ( SIZE( 1 ..
20 ) ) ( SIZE( 1 .. 15 ) ) OPTIONAL },
        notificationToCSE NULL OPTIONAL,
extensionContainer [0] IMPLICIT SEQUENCE {
  privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
               SEQUENCE {
                            MAP-EXTENSION .&extensionId ( {
                  extId
                     ...}),
                  extType MAP-EXTENSION .&ExtensionType ( {
                    ...} { @extId } ) OPTIONAL} OPTIONAL,
           pcs-Extensions [1] IMPLICIT SEQUENCE {
             ... } OPTIONAL,
            ... } OPTIONAL,
     ... } OPTIONAL,

callBarringData [2] IMPLICIT SEQUENCE {
   callBarringFeatureList SEQUENCE ( SIZE( )
                                   SEQUENCE (SIZE(1..32)) OF
           SEQUENCE {
              basicService CHOICE {
                 ext-BearerService [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 5
) ),
                                       [3] IMPLICIT OCTET STRING ( SIZE( 1 .. 5
                ext-Teleservice
) ) } OPTIONAL,
                                   [4] IMPLICIT OCTET STRING ( SIZE( 1 .. 5 )
              ss-Status
),
               extensionContainer SEQUENCE {
                privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10
) ) OF
                     SEQUENCE {
                        extId
                                 MAP-EXTENSION .&extensionId ( {
                          ...} ) ,
                        extType MAP-EXTENSION .&ExtensionType ( {
                           ... } { @extId } ) OPTIONAL } OPTIONAL ,
                  pcs-Extensions [1] IMPLICIT SEQUENCE {
                    ... } OPTIONAL,
                  ... } OPTIONAL,
                                       NumericString (FROM
        password
("0"|"1"|"2"|"3"|"4"|"5"|"6"|"7"|"8"|"9" )) (SIZE( 4 ) ) OPTIONAL,
        wrongPasswordAttemptsCounter INTEGER ( 0 .. 4 ) OPTIONAL,
        notificationToCSE extensionContainer
                                       NULL OPTIONAL,
                                       SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
               SEQUENCE {
                 extId MAP-EXTENSION .&extensionId ( {
                     ...} ) ,
                  extType MAP-EXTENSION .&ExtensionType ( {
                     ...} { @extId } ) OPTIONAL} OPTIONAL,
```

```
[1] IMPLICIT SEQUENCE {
           pcs-Extensions
              ... } OPTIONAL,
            .. } OPTIONAL,
         ... } OPTIONAL,
     odb-Info
                                [3] IMPLICIT SEQUENCE {
                           SEQUENCE {
        odb-Data
                           BIT STRING {
           odb-GeneralData
              alloG-CallsBarred (0),
              internationalOGCallsBarred (1),
              internationalOGCallsNotToHPLMN-CountryBarred (2),
              interzonalOGCallsBarred (6 ),
              interzonalOGCallsNotToHPLMN-CountryBarred (7 ),
              interzonal OGC alls And International OGC alls Not To HPLMN-Country Barred\\
(8),
              premiumRateInformationOGCallsBarred (3 ),
              premiumRateEntertainementOGCallsBarred (4 ),
              ss-AccessBarred (5),
              allECT-Barred (9),
              chargeableECT-Barred (10),
              internationalECT-Barred (11),
              interzonalECT-Barred (12 ),
              doublyChargeableECT-Barred (13 ),
              multipleECT-Barred (14 ),
              allPacketOrientedServicesBarred (15),
              roamerAccessToHPLMN-AP-Barred (16 ),
              roamerAccessToVPLMN-AP-Barred (17 ),
              roamingOutsidePLMNOG-CallsBarred (18),
              allIC-CallsBarred (19),
              roamingOutsidePLMNIC-CallsBarred (20 ),
              roamingOutsidePLMNICountryIC-CallsBarred (21),
              roamingOutsidePLMN-Barred (22 ),
              roamingOutsidePLMN-CountryBarred (23 ),
              registrationAllCF-Barred (24),
              registrationCFNotToHPLMN-Barred (25 ),
              registrationInterzonalCF-Barred (26),
              registrationInterzonalCFNotToHPLMN-Barred (27),
              registrationInternationalCF-Barred (28)} (SIZE(15...32)),
           odb-HPLMN-Data BIT STRING {
              plmn-SpecificBarringType1 (0),
              plmn-SpecificBarringType2 (1 ),
              plmn-SpecificBarringType3 (2),
              plmn-SpecificBarringType4 (3)} (SIZE(4..32)) OPTIONAL,
           extensionContainer SEQUENCE {
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                 SEQUENCE {
                    extId
                              MAP-EXTENSION .&extensionId ( {
                    extType MAP-EXTENSION .&ExtensionType ( {
                       ...} { @extid } ) OPTIONAL} OPTIONAL,
                                  [1] IMPLICIT SEQUENCE {
              pcs-Extensions
                 ... } OPTIONAL,
              ... } OPTIONAL,
            ... },
        notificationToCSE NULL OPTIONAL,
        extensionContainer SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
              SEQUENCE {
                          MAP-EXTENSION .&extensionId ( {
                 extId
                    ...}),
```

```
extType MAP-EXTENSION .&ExtensionType ( {
                    ...} { @extId } ) OPTIONAL,
           pcs-Extensions [1] IMPLICIT SEQUENCE {
            ... } OPTIONAL,
             .. } OPTIONAL,
         ... } OPTIONAL,
     camel-SubscriptionInfo [4] IMPLICIT SEQUENCE {
           CSI [0] IMPLICIT SEQUENCE {
    o-BcsmCamelTDPDataList SEQUENCE (SIZE(1..10)) OF
        o-CST
             SEQUENCE {
                 o-BcsmTriggerDetectionPoint ENUMERATED {
                   collectedInfo (2),
                   routeSelectFailure (4)},
serviceKey
gsmSCF-Address
SIZE(1..20))(SIZE(1..9)),
                                              INTEGER ( 0 .. 2147483647 ),
                                             [0] IMPLICIT OCTET STRING (
                   continueCall (0), releaseCall (1)
                                             [1] IMPLICIT ENUMERATED {
                 defaultCallHandling
                    ... },
                 extensionContainer [2] IMPLICIT SEQUENCE {
  privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ...
10 ) ) OF
                      SEQUENCE {
                         extId
                                  MAP-EXTENSION .&extensionId ( {
                           ...} ) ,
                          extType MAP-EXTENSION .&ExtensionType ( {
                            ...} { @extid } ) OPTIONAL} OPTIONAL,
                    pcs-Extensions [1] IMPLICIT SEQUENCE {
                     ... } OPTIONAL,
                    ... } OPTIONAL,
                 ... },
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                 SEQUENCE {
                             MAP-EXTENSION .&extensionId ( {
                    extId
                      ...} ) ,
                    extType MAP-EXTENSION .&ExtensionType ( {
                      ... } { @extId } ) OPTIONAL } OPTIONAL ,
              pcs-Extensions [1] IMPLICIT SEQUENCE {
              ... } OPTIONAL,
              ... } OPTIONAL,
           camelCapabilityHandling [0] IMPLICIT INTEGER ( 1 .. 16 ) OPTIONAL,
           notificationToCSE [1] IMPLICIT NULL OPTIONAL, csiActive [2] IMPLICIT NULL OPTIONAL} OPTIONAL,
        o-BcsmCamelTDP-CriteriaList [1] IMPLICIT SEQUENCE ( SIZE( 1 ..
10 ) ) OF
           SEQUENCE {
              o-BcsmTriggerDetectionPoint ENUMERATED {
                collectedInfo (2),
                routeSelectFailure (4)},
              destinationNumberCriteria [0] IMPLICIT SEQUENCE {
                                           [0] IMPLICIT ENUMERATED {
                matchType
                   inhibiting (0),
```

```
enabling (1)},
                                            [1] IMPLICIT SEQUENCE ( SIZE( 1
                 destinationNumberList
.. 10 ) ) OF
                   OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1 .. 9 ) )
OPTIONAL,
                 destinationNumberLengthList [2] IMPLICIT SEQUENCE ( SIZE( 1
.. 3 ) ) OF
                   INTEGER ( 1 .. 15 ) OPTIONAL,
                 ... } OPTIONAL,
                                          [1] IMPLICIT SEQUENCE ( SIZE( 1 ..
              basicServiceCriteria
5 ) ) OF
                 CHOICE {
                  ext-BearerService
                                       [2] IMPLICIT OCTET STRING ( SIZE( 1
.. 5 ) ),
                   ext-Teleservice
                                        [3] IMPLICIT OCTET STRING ( SIZE( 1
.. 5 ) ) } OPTIONAL,
                                          [2] IMPLICIT ENUMERATED {
              callTypeCriteria
                forwarded (0),
notForwarded (1)}OPTIONAL,
                forwarded
              o-CauseValueCriteria
                                          [3] IMPLICIT SEQUENCE ( SIZE( 1 ...
5 ) ) OF
                OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
                                          [4] IMPLICIT SEQUENCE {
              extensionContainer
                privateExtensionList [0] IMPLICIT SEQUENCE (SIZE(1..10
) ) OF
                   SEQUENCE {
                               MAP-EXTENSION .&extensionId ( {
                      extId
                         ...} ) ,
                      extType MAP-EXTENSION .&ExtensionType ( {
                         ...} { @extId } ) OPTIONAL} OPTIONAL,
                 pcs-Extensions [1] IMPLICIT SEQUENCE {
                  ... } OPTIONAL,
                 ... } OPTIONAL } OPTIONAL ,
        d-CSI
                                          [2] IMPLICIT SEQUENCE {
           dp-AnalysedInfoCriteriaList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10
) ) OF
             SEQUENCE {
                dialledNumber OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE(
1 .. 9 ) ),
                 serviceKey INTEGER ( 0 .. 2147483647 ), gsmSCF-Address OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE(
1 .. 9 ) ),
                 defaultCallHandling ENUMERATED {
                   continueCall (0), releaseCall (1),
                 privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ..
10 ) ) OF
                      SEQUENCE { extid MAP-EXTENSION .&extensionId ( {
                           ...} ) ,
                         extType MAP-EXTENSION .&ExtensionType ( {
                            ...} { @extId } ) OPTIONAL} OPTIONAL,
                    pcs-Extensions [1] IMPLICIT SEQUENCE {
                     ... } OPTIONAL,
                    ... } OPTIONAL,
                 ... } OPTIONAL,
```

```
camelCapabilityHandling [1] IMPLICIT INTEGER ( 1 .. 16 )
OPTIONAL,
          extensionContainer
                                     [2] IMPLICIT SEQUENCE {
            privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                SEQUENCE {
                           MAP-EXTENSION .&extensionId ( {
                  extId
                     ...}),
                   extType MAP-EXTENSION .&ExtensionType ( {
                     ...} { @extId } ) OPTIONAL} OPTIONAL,
             pcs-Extensions [1] IMPLICIT SEQUENCE {
              ... } OPTIONAL,
          csi-Active [4] IMPLICIT NULL OPTIONAL,
... } OPTIONAL,
CSI
        t-CSI
           t-BcsmCamelTDPDataList SEQUENCE (SIZE(1..10)) OF
             SEQUENCE {
                t-BcsmTriggerDetectionPoint ENUMERATED {
                  termAttemptAuthorized (12),
                   ...,
                  tBusy
                                         (13),
                tNoAnswer
serviceKey
                                         (14)},
                                          INTEGER ( 0 .. 2147483647 ),
                                          [0] IMPLICIT OCTET STRING (
gsmSCF-Address
                                          [1] IMPLICIT ENUMERATED {
                  ... },
                extensionContainer
                                          [2] IMPLICIT SEQUENCE {
                  privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ..
10 ) ) OF
                     SEQUENCE { extId MAP-EXTENSION .&extensionId ( {
                          ...} ) ,
                        extType MAP-EXTENSION .&ExtensionType ( {
                          ...} { @extid } ) OPTIONAL} OPTIONAL,
                   pcs-Extensions [1] IMPLICIT SEQUENCE {
                    ... } OPTIONAL,
                   ... } OPTIONAL,
           extensionContainer SEQUENCE {
             privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                SEQUENCE {
                  extId MAP-EXTENSION .&extensionId ( {
                    ...} ) ,
                   extType MAP-EXTENSION .&ExtensionType ( {
                     ...} { @extId } ) OPTIONAL} OPTIONAL,
             pcs-Extensions [1] IMPLICIT SEQUENCE {
              ... } OPTIONAL,
             ... } OPTIONAL,
           {\tt camelCapabilityHandling} \quad \hbox{\tt [0] IMPLICIT INTEGER (1..16) OPTIONAL,}
           notificationToCSE
                                 [1] IMPLICIT NULL OPTIONAL,
```

```
csi-Active [2] IMPLICIT NULL OPTIONAL} OPTIONAL,
       t-BCSM-CAMEL-TDP-CriteriaList [4] IMPLICIT SEQUENCE ( SIZE( 1 ..
10 ) ) OF
           SEQUENCE {
             t-BCSM-TriggerDetectionPoint ENUMERATED {
                termAttemptAuthorized (12),
                                        (13),
                tBusy
             tNoAnswer
basicServiceCriteria
                                        ( 14 ) },
                                          [0] IMPLICIT SEQUENCE ( SIZE( 1
.. 5 ) ) OF
                CHOICE {
                  ext-BearerService
                                       [2] IMPLICIT OCTET STRING ( SIZE( 1
.. 5 ) ),
                  ext-Teleservice
                                       [3] IMPLICIT OCTET STRING ( SIZE( 1
.. 5 ) ) } OPTIONAL,
             t-CauseValueCriteria
                                       [1] IMPLICIT SEQUENCE ( SIZE( 1
.. 5 ) ) OF
               OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
              ... } OPTIONAL,
                                       [5] IMPLICIT SEQUENCE {
        vt-CSI
           t-BcsmCamelTDPDataList SEQUENCE (SIZE(1..10)) OF
              SEQUENCE {
                t-BcsmTriggerDetectionPoint ENUMERATED {
                   termAttemptAuthorized ( 12 ),
                   . . . ,
                   tBusv
                                           (13),
                tNoAnswer
serviceKey
                                          (14)},
                                           INTEGER ( 0 .. 2147483647 ),
gsmSCF-Address
SIZE(1..20))(SIZE(1..9)),
                                           [0] IMPLICIT OCTET STRING (
                defaultCallHandling
                  continueCall (0), releaseCall (1),
                                           [1] IMPLICIT ENUMERATED {
                   ... },
                 extensionContainer [2] IMPLICIT SEQUENCE {
                   privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ..
10 ) ) OF
                      SEQUENCE { extid MAP-EXTENSION .&extensionId ( {
                           ...} ) ,
                         extType MAP-EXTENSION .&ExtensionType ( {
                           ...} { @extid } ) OPTIONAL} OPTIONAL,
                   pcs-Extensions [1] IMPLICIT SEQUENCE {
                     ... } OPTIONAL,
                   ... } OPTIONAL,
           extensionContainer SEQUENCE {
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                 SEQUENCE {
                   extId MAP-EXTENSION .&extensionId ( {
                     ...} ) ,
                   extType MAP-EXTENSION .&ExtensionType ( {
                      ...} { @extId } ) OPTIONAL} OPTIONAL,
              pcs-Extensions [1] IMPLICIT SEQUENCE {
               ... } OPTIONAL,
              ... } OPTIONAL,
           ...,
```

```
camelCapabilityHandling [0] IMPLICIT INTEGER ( 1 .. 16 ) OPTIONAL,
           notificationToCSE
                                   [1] IMPLICIT NULL OPTIONAL,
                                   [2] IMPLICIT NULL OPTIONAL,
           csi-Active
        vt-BCSM-CAMEL-TDP-CriteriaList
                                        [6] IMPLICIT SEQUENCE ( SIZE( 1 ..
10 ) ) OF
           SEQUENCE {
              t-BCSM-TriggerDetectionPoint ENUMERATED {
                 termAttemptAuthorized (12),
                                         (13),
                 tBusy
                                         ( 14 ) },
                 tNoAnswer
                                           [0] IMPLICIT SEQUENCE ( SIZE( 1
              basicServiceCriteria
.. 5 ) ) OF
                 CHOICE {
                                        [2] IMPLICIT OCTET STRING ( SIZE( 1
                   ext-BearerService
.. 5 ) ),
                   ext-Teleservice
                                        [3] IMPLICIT OCTET STRING ( SIZE( 1
.. 5 ) ) } OPTIONAL,
              t-CauseValueCriteria
                                          [1] IMPLICIT SEQUENCE ( SIZE( 1
.. 5 ) ) OF
                OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
              ... } OPTIONAL,
        tif-CSI
                                           [7] IMPLICIT NULL OPTIONAL,
        tif-CSI-NotificationToCSE
                                           [8] IMPLICIT NULL OPTIONAL,
        aprs-CSI
                                           [9] IMPLICIT SEQUENCE {
           qprs-CamelTDPDataList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
              SEQUENCE {
                 gprs-TriggerDetectionPoint [0] IMPLICIT ENUMERATED {
                   attach
                                                            (1),
                   attachChangeOfPosition
                                                            (2),
                   pdp-ContextEstablishment
                                                            (11),
                   pdp-ContextEstablishmentAcknowledgement (12),
                   pdp-ContextChangeOfPosition
                                                            (14),
                   ... },
                                            [1] IMPLICIT INTEGER ( 0 ...
                 serviceKey
2147483647),
                                           [2] IMPLICIT OCTET STRING ( SIZE(
                 gsmSCF-Address
                defaultSessionHandling [3]
continueTransaction (0),
1 .. 20 ) ) ( SIZE( 1 .. 9 ) ),
                                         [3] IMPLICIT ENUMERATED {
                   ... },
                 extensionContainer
                                         [4] IMPLICIT SEQUENCE {
                   privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ..
10 ) ) OF
                      SEQUENCE {
                                  MAP-EXTENSION .&extensionId ( {
                         extId
                            ...}),
                         extType MAP-EXTENSION .&ExtensionType ( {
                            ...} { @extId } ) OPTIONAL} OPTIONAL,
                                        [1] IMPLICIT SEQUENCE {
                    pcs-Extensions
                      ... } OPTIONAL,
                    ... } OPTIONAL,
                 ... } OPTIONAL,
           camelCapabilityHandling [1] IMPLICIT INTEGER ( 1 .. 16 ) OPTIONAL,
                                   [2] IMPLICIT SEQUENCE {
           extensionContainer
              privateExtensionList [0] IMPLICIT SEQUENCE (SIZE(1..10))
OF
                 SEQUENCE {
                    extId MAP-EXTENSION .&extensionId ( {
```

```
...}),
                     extType MAP-EXTENSION .&ExtensionType ( {
                        ...} { @extid } ) OPTIONAL} OPTIONAL,
               pcs-Extensions [1] IMPLICIT SEQUENCE {
               ... } OPTIONAL,
               ... } OPTIONAL,
                                    [3] IMPLICIT NULL OPTIONAL,
            notificationToCSE
            csi-Active
                                      [4] IMPLICIT NULL OPTIONAL,
            ... } OPTIONAL,
         mo-sms-CST
                                              [10] IMPLICIT SEQUENCE {
            sms-CAMEL-TDP-DataList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
               SEQUENCE {
                  sms-TriggerDetectionPoint [0] IMPLICIT ENUMERATED {
   sms-CollectedInfo (1),
                     . . . ,
                     sms-DeliveryRequest (2)},
                                               [1] IMPLICIT INTEGER ( 0 ..
                  serviceKey
2147483647),
                                              [2] IMPLICIT OCTET STRING ( SIZE(
                  qsmSCF-Address
1 .. 20 ) ) ( SIZE( 1 .. 9 ) ),
                  defaultSMS-Handling [3] IMPLICIT ENUMERATED {
  continueTransaction (0),
  releaseTransaction (1),
                     ... },
                  extensionContainer [4] IMPLICIT SEQUENCE {
   privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ...
10 ) ) OF
                        SEQUENCE { extId MAP-EXTENSION .&extensionId ( {
                              ...} ) ,
                            extType MAP-EXTENSION .&ExtensionType ( {
                              ...} { @extId } ) OPTIONAL} OPTIONAL,
                     pcs-Extensions [1] IMPLICIT SEQUENCE {
                       ... } OPTIONAL,
                     ... } OPTIONAL,
                  ... } OPTIONAL,
            camelCapabilityHandling [1] IMPLICIT INTEGER ( 1 .. 16 ) OPTIONAL,
            extensionContainer [2] IMPLICIT SEQUENCE {
               privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                  SEQUENCE {
                               MAP-EXTENSION .&extensionId ( {
                     extId
                        ...}),
                     extType MAP-EXTENSION .&ExtensionType ( {
                        ...} { @extId } ) OPTIONAL} OPTIONAL,
               pcs-Extensions [1] IMPLICIT SEQUENCE {
               ... } OPTIONAL,
            ... } OPTIONAL,
notificationToCSE [3] IMPLICIT NULL OPTIONAL,
cai-Active [4] IMPLICIT NULL OPTIONAL,
            ... } OPTIONAL,
         ss-CST
                                              [11] IMPLICIT SEQUENCE {
            ss-CamelData SEQUENCE {
ss-EventList SEQUENCE (SIZE(1..10)) OF
                  OCTET STRING ( SIZE( 1 ) ),
```

```
gsmSCF-Address
                                   OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1
.. 9 ) ),
               extensionContainer [0] IMPLICIT SEQUENCE {
                 privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10
) ) OF
                     SEQUENCE {
                                   MAP-EXTENSION .&extensionId ( {
                        extId
                            ...}),
                         extType MAP-EXTENSION .&ExtensionType ( {
                            ...} { @extId } ) OPTIONAL} OPTIONAL,
                   pcs-Extensions [1] IMPLICIT SEQUENCE {
                    ... } OPTIONAL,
                   ... } OPTIONAL,
            extensionContainer SEQUENCE {
               privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                  SEQUENCE {
                               MAP-EXTENSION .&extensionId ( {
                     extId
                        ...} ) ,
                     extType MAP-EXTENSION .&ExtensionType ( {
                        ...} { @extId } ) OPTIONAL} OPTIONAL,
               pcs-Extensions [1] IMPLICIT SEQUENCE {
                ... } OPTIONAL,
               ... } OPTIONAL,
            notificationToCSE [0] IMPLICIT NULL OPTIONAL,
csi-Active [1] IMPLICIT NULL OPTIONAL) OPTIONAL,
csi - Active [1] IMPLICIT NULL OPTIONAL (12) IMPLICIT SEQUENCE (
                                              [12] IMPLICIT SEQUENCE {
         m-CSI
            mobilityTriggers SEQUENCE (SIZE(1..10))OF
              OCTET STRING ( SIZE( 1 ) ),
            serviceKey INTEGER ( 0 .. 2147483647 ),
gsmSCF-Address [0] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) (
SIZE( 1 .. 9 )),
           extensionContainer [1] IMPLICIT SEQUENCE {
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                  SEQUENCE {
                               MAP-EXTENSION .&extensionId ( {
                      extId
                        ...} ) ,
                      extType MAP-EXTENSION .&ExtensionType ( {
                        ...} { @extId } ) OPTIONAL} OPTIONAL,
                                [1] IMPLICIT SEQUENCE {
               pcs-Extensions
                 ... } OPTIONAL,
                ... } OPTIONAL,
            notificationToCSE [2] IMPLICIT NULL OPTIONAL, csi-Active [3] IMPLICIT NULL OPTIONAL,
            ... } OPTIONAL,
         extensionContainer
                                               [13] IMPLICIT SEQUENCE {
            privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
               SEQUENCE {
                  extId MAP-EXTENSION .&extensionId ( {
                      ...} ) ,
                   extType \mbox{\scriptsize MAP-EXTENSION} .&ExtensionType ( {
                      ...} { @extId } ) OPTIONAL} OPTIONAL,
```

```
pcs-Extensions
                          [1] IMPLICIT SEQUENCE {
           ... } OPTIONAL,
          ... } OPTIONAL,
        specificCSIDeletedList
                                       [14] IMPLICIT BIT STRING {
          o-csi (0 ),
          ss-csi (1),
          tif-csi (2),
          d-csi (3),
vt-csi (4),
          mo-sms-csi (5),
          m-csi (6),
          gprs-csi (7),
          t-csi (8),
          mt-sms-csi (9),
          mg-csi (10),
          o-IM-CSI (11 ),
          d-IM-CSI (12),
          vt-IM-CSI (13 )} ( SIZE( 8 .. 32 ) ) OPTIONAL,
                                        [15] IMPLICIT SEQUENCE {
       mt-sms-CSI
          sms-CAMEL-TDP-DataList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
             SEQUENCE {
               sms-TriggerDetectionPoint [0] IMPLICIT ENUMERATED {
                 sms-CollectedInfo (1),
                  sms-DeliveryRequest (2)},
               serviceKey
                                         [1] IMPLICIT INTEGER ( 0 ..
2147483647),
                                        [2] IMPLICIT OCTET STRING ( SIZE(
               gsmSCF-Address
1 .. 20 ) ) ( SIZE( 1 .. 9 ) ),
               ... },
                extensionContainer
                                       [4] IMPLICIT SEQUENCE {
                  privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ..
10 ) ) OF
                     SEQUENCE { extid MAP-EXTENSION .&extensionId ( {
                          ...} ) ,
                        extType MAP-EXTENSION .&ExtensionType ( {
                          ...} { @extid } ) OPTIONAL} OPTIONAL,
                  pcs-Extensions [1] IMPLICIT SEQUENCE {
                    ... } OPTIONAL,
                  ... } OPTIONAL,
                ... } OPTIONAL,
          camelCapabilityHandling [1] IMPLICIT INTEGER ( 1 .. 16 ) OPTIONAL,
          extensionContainer [2] IMPLICIT SEQUENCE {
             privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                SEQUENCE {
                          MAP-EXTENSION .&extensionId ( {
                  extId
                     ...} ) ,
                  extType MAP-EXTENSION .&ExtensionType ( {
                     ...} { @extid } ) OPTIONAL} OPTIONAL,
             pcs-Extensions [1] IMPLICIT SEQUENCE {
              ... } OPTIONAL,
             ... } OPTIONAL,
```

```
notificationToCSE [3] IMPLICIT NULL OPTIONAL,
                                   [4] IMPLICIT NULL OPTIONAL,
           csi-Active
           ... } OPTIONAL,
        mt-smsCAMELTDP-CriteriaList
                                          [16] IMPLICIT SEQUENCE ( SIZE( 1
.. 10 ) ) OF
           SEQUENCE {
              sms-TriggerDetectionPoint ENUMERATED {
                sms-CollectedInfo (1),
              sms-DeliveryRequest (2)},
tpdu-TypeCriterion [0] IM
                                       [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 5
) ) OF
                ENUMERATED {
                   sms-DELIVER
sms-SUBMIT-REPORT (1),
sms-STATUS-REPORT (2),
                  sms-DELIVER
                    ... } OPTIONAL,
              ... } OPTIONAL,
                                          [17] IMPLICIT SEQUENCE {
        mg-csi
           mobilityTriggers SEQUENCE (SIZE(1..10)) OF
             OCTET STRING ( SIZE( 1 ) ),
           qsmSCF-Address [0] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) (
SIZE( 1 .. 9 ) ),
          extensionContainer [1] IMPLICIT SEQUENCE {
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                 SEQUENCE {
                   extId
                            MAP-EXTENSION .&extensionId ( {
                      ...} ) ,
                    extType MAP-EXTENSION .&ExtensionType ( {
                      ...} { @extId } ) OPTIONAL} OPTIONAL,
              pcs-Extensions [1] IMPLICIT SEQUENCE {
               ... } OPTIONAL,
              ... } OPTIONAL,
           notificationToCSE [2] IMPLICIT NULL OPTIONAL, csi-Active [3] IMPLICIT NULL OPTIONAL, ... } OPTIONAL,
        o-IM-CSI
                                          [18] IMPLICIT SEQUENCE {
           o-BcsmCamelTDPDataList SEQUENCE (SIZE(1..10)) OF
              SEQUENCE {
                 o-BcsmTriggerDetectionPoint ENUMERATED {
                   collectedInfo
                                        (2),
                   routeSelectFailure (4)},
                                             INTEGER ( 0 .. 2147483647 ),
                 serviceKey
                 gsmSCF-Address
                                             [0] IMPLICIT OCTET STRING (
SIZE(1 .. 20)) (SIZE(1 .. 9)),
                 defaultCallHandling
                                         [1] IMPLICIT ENUMERATED {
                   continueCall (0), releaseCall (1),
                   ... },
                 extensionContainer
                                            [2] IMPLICIT SEQUENCE {
                   privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ..
10 ) ) OF
                      SEQUENCE {
                         extId MAP-EXTENSION .&extensionId ( {
                            ...}),
                         extType MAP-EXTENSION .&ExtensionType ( {
```

```
...} { @extId } ) OPTIONAL} OPTIONAL,
                    pcs-Extensions [1] IMPLICIT SEQUENCE {
                     ... } OPTIONAL,
                    ... } OPTIONAL,
                 ... },
           extensionContainer SEQUENCE {
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                 SEQUENCE {
                            MAP-EXTENSION .&extensionId ( {
                   extId
                      ...}),
                    extType MAP-EXTENSION .&ExtensionType ( {
                      ...} { @extid } ) OPTIONAL} OPTIONAL,
                              [1] IMPLICIT SEQUENCE {
              pcs-Extensions
                ... } OPTIONAL,
              ... } OPTIONAL,
           camelCapabilityHandling [0] IMPLICIT INTEGER ( 1 .. 16 ) OPTIONAL,
           notificationToCSE [1] IMPLICIT NULL OPTIONAL,
csiActive [2] IMPLICIT NULL OPTIONAL
                                   [2] IMPLICIT NULL OPTIONAL OPTIONAL,
           csiActive
        o-IM-BcsmCamelTDP-CriteriaList [19] IMPLICIT SEQUENCE ( SIZE( 1
.. 10 ) ) OF
           SEQUENCE {
              o-BcsmTriggerDetectionPoint ENUMERATED {
                collectedInfo (2),
                routeSelectFailure (4)},
              destinationNumberCriteria [0] IMPLICIT SEQUENCE {
                 matchType
                                            [0] IMPLICIT ENUMERATED {
                   inhibiting ( 0 ),
enabling ( 1 ) },
                 destinationNumberList
                                            [1] IMPLICIT SEQUENCE ( SIZE( 1
.. 10 ) ) OF
                   OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1 .. 9 ) )
OPTIONAL,
                 destinationNumberLengthList [2] IMPLICIT SEQUENCE ( SIZE( 1
.. 3 ) ) OF
                   INTEGER ( 1 .. 15 ) OPTIONAL,
                 ... } OPTIONAL,
              basicServiceCriteria
                                     [1] IMPLICIT SEQUENCE ( SIZE( 1 ..
5 ) ) OF
                 CHOICE {
                   ext-BearerService [2] IMPLICIT OCTET STRING ( SIZE( 1
.. 5 ) ),
                   ext-Teleservice [3] IMPLICIT OCTET STRING ( SIZE( 1
.. 5 ) ) } OPTIONAL,
              callTypeCriteria
                                         [2] IMPLICIT ENUMERATED {
                               (0),
                forwarded
                 notForwarded (1) } OPTIONAL,
              o-CauseValueCriteria
                                          [3] IMPLICIT SEQUENCE ( SIZE( 1 ...
5 ) ) OF
                OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
              extensionContainer [4] IMPLICIT SEOUENCE {
                privateExtensionList [0] IMPLICIT SEQUENCE (SIZE(1..10
) ) OF
                   SEQUENCE { extid MAP-EXTENSION .&extensionId ( {
                          ...} ) ,
                       extType MAP-EXTENSION .&ExtensionType ( {
```

```
...} { @extid } ) OPTIONAL} OPTIONAL,
                   pcs-Extensions [1] IMPLICIT SEQUENCE {
                     ... } OPTIONAL,
                   ... } OPTIONAL } OPTIONAL ,
                                              [20] IMPLICIT SEQUENCE {
            dp-AnalysedInfoCriteriaList [0] IMPLICIT SEQUENCE (SIZE(1..10
) ) OF
               SEQUENCE {
                  dialledNumber
                                       OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE(
1 .. 9 ) ),
                   serviceKey
                                        INTEGER ( 0 .. 2147483647 ),
                   serviceKey INTEGER ( 0 .. 2147483647 ), gsmSCF-Address OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE(
1 .. 9 ) ),
                   defaultCallHandling ENUMERATED {
  continueCall ( 0 ),
  releaseCall ( 1 ),
                      ... },
                   extensionContainer SEQUENCE {
                      privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ...
10 ) ) OF
                         SEQUENCE {
                                     MAP-EXTENSION .&extensionId ( {
                            extId
                              ...} ) ,
                            extType MAP-EXTENSION .&ExtensionType ( {
                              ...} { @extId } ) OPTIONAL} OPTIONAL,
                      {\tt pcs-Extensions} \hspace{1.5cm} {\tt [1]} \hspace{0.1cm} {\tt IMPLICIT} \hspace{0.1cm} {\tt SEQUENCE} \hspace{0.1cm} \big\{
                       ... } OPTIONAL,
                      ... } OPTIONAL,
                   ... } OPTIONAL,
            camelCapabilityHandling
                                          [1] IMPLICIT INTEGER ( 1 .. 16 )
OPTIONAL,
            extensionContainer
                                           [2] IMPLICIT SEQUENCE {
               privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
\bigcircF
                   SEQUENCE {
                      extId
                               MAP-EXTENSION .&extensionId ( {
                        ...} ) ,
                      extType MAP-EXTENSION .&ExtensionType ( {
                        ...} { @extId } ) OPTIONAL} OPTIONAL,
               pcs-Extensions [1] IMPLICIT SEQUENCE {
                ... } OPTIONAL,
                ... } OPTIONAL,
            notificationToCSE
                                          [3] IMPLICIT NULL OPTIONAL,
            csi-Active
                                           [4] IMPLICIT NULL OPTIONAL,
            ... } OPTIONAL,
         vt-IM-CSI
                                              [21] IMPLICIT SEQUENCE {
            t-BcsmCamelTDPDataList SEQUENCE (SIZE(1..10)) OF
                   t-BcsmTriggerDetectionPoint ENUMERATED {
                      termAttemptAuthorized (12),
                      ...,
                                                (13),
                     tBusy
                                                ( 14 ) },
                     tNoAnswer
                                                INTEGER ( 0 .. 2147483647 ),
                   serviceKey
gsmSCF-Address [0] IMPLICIT OCTET STRING SIZE(1..20)) (SIZE(1..9)), defaultCallHandling [1] IMPLICIT ENUMERATED {
                                                 [0] IMPLICIT OCTET STRING (
                     continueCall (0),
```

```
releaseCall (1),
                   ... },
                extensionContainer [2] IMPLICIT SEQUENCE {
                  privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ..
10 ) ) OF
                     SEQUENCE {
                                MAP-EXTENSION .&extensionId ( {
                       extId
                           ...}),
                        extType MAP-EXTENSION .&ExtensionType ( {
                           ...} { @extId } ) OPTIONAL} OPTIONAL,
                   pcs-Extensions [1] IMPLICIT SEQUENCE {
                    ... } OPTIONAL,
                   ... } OPTIONAL,
                ...},
           OF
                SEQUENCE {
                           MAP-EXTENSION .&extensionId ( {
                   extId
                     ...} ) ,
                   extType MAP-EXTENSION .&ExtensionType ( {
                     ...} { @extId } ) OPTIONAL} OPTIONAL,
             pcs-Extensions [1] IMPLICIT SEQUENCE {
              ... } OPTIONAL,
             ... } OPTIONAL,
          camelCapabilityHandling [0] IMPLICIT INTEGER ( 1 .. 16 ) OPTIONAL,
          notificationToCSE [1] IMPLICIT NULL OPTIONAL, csi-Active [2] IMPLICIT NULL OPTIONAL} OPTIONAL,
       vt-IM-BCSM-CAMEL-TDP-CriteriaList [22] IMPLICIT SEQUENCE ( SIZE( 1
.. 10 ) ) OF
          SEQUENCE {
             t-BCSM-TriggerDetectionPoint ENUMERATED {
               termAttemptAuthorized (12),
                tBusy
                                       (13),
                tNoAnswer
                                      (14)},
            basicServiceCriteria
                                        [0] IMPLICIT SEQUENCE ( SIZE( 1
.. 5 ) ) OF
                CHOICE {
                 ext-BearerService [2] IMPLICIT OCTET STRING ( SIZE( 1
.. 5 ) ),
                 ext-Teleservice [3] IMPLICIT OCTET STRING ( SIZE( 1
.. 5 ) ) } OPTIONAL,
                                        [1] IMPLICIT SEQUENCE ( SIZE( 1
             t-CauseValueCriteria
.. 5 ) ) OF
               OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
             ... } OPTIONAL } OPTIONAL ,
     supportedVLR-CAMEL-Phases [5] IMPLICIT BIT STRING {
        phase1 (0),
        phase2 (1),
        phase3 (2),
        phase4 (3 ) } ( SIZE( 1 .. 16 ) ) OPTIONAL,
     supportedSGSN-CAMEL-Phases [6] IMPLICIT BIT STRING {
        phase1 (0),
        phase2 (1),
        phase3 (2),
        phase4 (3 )} ( SIZE( 1 .. 16 ) ) OPTIONAL,
                              [7] IMPLICIT SEQUENCE {
     extensionContainer
```

```
privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                         MAP-EXTENSION .&extensionId ( {
              extId
                  ...}),
               extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extid } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
         ... } OPTIONAL,
     offeredCamel4CSIsInVLR [8] IMPLICIT BIT STRING {
        o-csi (0),
        d-csi (1),
        vt-csi (2),
         t-csi (3),
        mt-sms-csi (4),
        mq-csi (5),
        psi-enhancements (6 ) } ( SIZE( 7 .. 16 ) ) OPTIONAL,
     offeredCamel4CSIsInSGSN [9] IMPLICIT BIT STRING {
        o-csi (0),
        d-csi (1),
vt-csi (2),
        t-csi (3),
        mt-sms-csi (4),
        mg-csi (5),
        psi-enhancements (6 )} ( SIZE( 7 .. 16 ) ) OPTIONAL}
  ERRORS {
     atsi-NotAllowed |
     dataMissing
     unexpectedDataValue |
     unknownSubscriber |
     bearerServiceNotProvisioned |
     teleserviceNotProvisioned |
     callBarred
     illegalSS-Operation |
     ss-NotAvailable
     informationNotAvailable }
  CODE local : 62
anyTimeModification OPERATION ::= {
  ARGUMENT SEQUENCE {
                                       [0] CHOICE {
     subscriberIdentity
        imsi [0] IMPLICIT OCTET STRING ( SIZE( 3 .. 8 ) ),
        msisdn
                    [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1 ..
9))},
                                      [1] IMPLICIT OCTET STRING ( SIZE( 1 ...
     gsmSCF-Address
20 ) ) ( SIZE( 1 .. 9 ) ),
     modificationRequestFor-CF-Info [2] IMPLICIT SEQUENCE {
                                  [0] IMPLICIT OCTET STRING ( SIZE( 1 ) ),
        ss-Code
        basicService
                                  [1] CHOICE {
           ext-BearerService [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 5 ) ), ext-Teleservice [3] IMPLICIT OCTET STRING ( SIZE( 1 .. 5 ) )}
OPTIONAL,
                                 [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 5 ) )
        ss-Status
OPTIONAL,
        forwardedToNumber
                             [3] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) )
OPTIONAL,
        forwardedToSubaddress [4] IMPLICIT OCTET STRING ( SIZE( 1 .. 21 ) )
OPTIONAL,
        noReplyConditionTime [5] IMPLICIT INTEGER ( 1 .. 100 ) OPTIONAL,
```

```
modifyNotificationToCSE [6] IMPLICIT ENUMERATED {
           deactivate (0),
                         ( 1 ) } OPTIONAL,
           activate
         extensionContainer [7] IMPLICIT SEQUENCE {
  privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
               SEQUENCE {
                            MAP-EXTENSION .&extensionId ( {
                  extId
                     ...}),
                  extType MAP-EXTENSION .&ExtensionType ( {
                     ...} { @extId } ) OPTIONAL} OPTIONAL,
            pcs-Extensions [1] IMPLICIT SEQUENCE {
              ... } OPTIONAL,
            ... } OPTIONAL,
         ... } OPTIONAL,
      modificationRequestFor-CB-Info [3] IMPLICIT SEQUENCE {
        basicService
                                         [0] IMPLICIT OCTET STRING ( SIZE( 1 ) ),
          asicService [1] CHOICE {
ext-BearerService [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 5 ) ),
ext-Teleservice [3] IMPLICIT OCTET STRING ( SIZE( 1 .. 5 ) )}
                                         [1] CHOICE {
OPTIONAL,
        ss-Status
                                         [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 5
) ) OPTIONAL,
         password
                                        [3] IMPLICIT NumericString (FROM
("0"|"1"| 2"|"3"|"4"|"5"|"6"|"7"|"8"|"9" )) (SIZE( 4 ) ) OPTIONAL,
         wrongPasswordAttemptsCounter [4] IMPLICIT INTEGER ( 0 .. 4 )
OPTIONAL,
         modifyNotificationToCSE
                                       [5] IMPLICIT ENUMERATED {
           deactivate (0),
            activate (1) } OPTIONAL,
         extensionContainer [6] IMPLICIT SEQUENCE {
            privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
               SEQUENCE {
                  extId
                            MAP-EXTENSION .&extensionId ( {
                     ...}),
                  extType MAP-EXTENSION .&ExtensionType ( {
                     ...} { @extId } ) OPTIONAL} OPTIONAL,
            pcs-Extensions [1] IMPLICIT SEQUENCE {
             ... } OPTIONAL,
            ... } OPTIONAL,
         ... } OPTIONAL,
      modificationRequestFor-CSI [4] IMPLICIT SEQUENCE {
         requestedCamel-SubscriptionInfo [0] IMPLICIT ENUMERATED {
            o-CSI (0),
           t-CSI (1),

vt-CSI (2),

tif-CSI (3),

gprs-CSI (4),

mo-sms-CSI (5),

ss-CSI (6),

m-CSI (7).
            m-CSI (7),
d-csi (8)},
                                                 [1] IMPLICIT ENUMERATED {
         modifyNotificationToCSE
           deactivate ( 0 ),
activate ( 1 ) } OPTIONAL,
         modifyCSI-State
                                                     [2] IMPLICIT ENUMERATED {
           deactivate (0),
activate (1) } OPTIONAL,
                                                     [3] IMPLICIT SEQUENCE {
         extensionContainer
            privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
```

```
SEQUENCE { extid MAP-EXTENSION .&extensionId ( {
                    ...}),
                 extType
                           MAP-EXTENSION .&ExtensionType ( {
                    ...} { @extId } ) OPTIONAL} OPTIONAL,
           pcs-Extensions [1] IMPLICIT SEQUENCE {
            ... } OPTIONAL,
           ... } OPTIONAL,
        additionalRequestedCAMEL-SubscriptionInfo [4] IMPLICIT ENUMERATED {
           mt-sms-CSI (0),
mg-csi (1),
o-IM-CSI (2),
d-IM-CSI (3),
vt-IM-CSI (4),
           ... } OPTIONAL } OPTIONAL ,
                                       [5] IMPLICIT SEQUENCE {
     extensionContainer
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                        MAP-EXTENSION .&extensionId ( {
              extId
                 ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL,
     longFTN-Supported
                                       [6] IMPLICIT NULL OPTIONAL,
     modificationRequestFor-ODB-data [7] IMPLICIT SEQUENCE {
           o-data [0] IMPLICIT SEQUENCE {
odb-GeneralData BIT STRING {
        odb-data
              allOG-CallsBarred (0),
              internationalOGCallsBarred (1),
              internationalOGCallsNotToHPLMN-CountryBarred (2),
              interzonalOGCallsBarred (6),
              interzonalOGCallsNotToHPLMN-CountryBarred (7 ),
              interzonal OG Calls And International OG Calls Not To HPLMN-Country Barred\\
(8),
              premiumRateInformationOGCallsBarred (3 ),
              premiumRateEntertainementOGCallsBarred (4),
              ss-AccessBarred (5),
              allECT-Barred (9),
              chargeableECT-Barred (10),
              internationalECT-Barred (11),
              interzonalECT-Barred (12 ),
              doublyChargeableECT-Barred (13 ),
              multipleECT-Barred (14 ),
              allPacketOrientedServicesBarred (15),
              roamerAccessToHPLMN-AP-Barred (16),
              roamerAccessToVPLMN-AP-Barred (17 ),
              roamingOutsidePLMNOG-CallsBarred (18),
              allIC-CallsBarred (19),
              roamingOutsidePLMNIC-CallsBarred (20),
              roamingOutsidePLMNICountryIC-CallsBarred (21),
              roamingOutsidePLMN-Barred (22 ),
              roamingOutsidePLMN-CountryBarred (23 ),
              registrationAllCF-Barred (24),
              registrationCFNotToHPLMN-Barred (25),
              registrationInterzonalCF-Barred (26),
```

```
registrationInterzonalCFNotToHPLMN-Barred (27),
              registrationInternationalCF-Barred (28)} (SIZE(15 .. 32)),
           odb-HPLMN-Data BIT STRING {
              plmn-SpecificBarringType1 (0),
              plmn-SpecificBarringType2 (1 ),
              plmn-SpecificBarringType3 (2),
plmn-SpecificBarringType4 (3)} (SIZE(4...32)) OPTIONAL,
           extensionContainer SEQUENCE {
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                 SEQUENCE {
                            MAP-EXTENSION .&extensionId ( {
                    extId
                      ...}),
                    extType MAP-EXTENSION .&ExtensionType ( {
                      ...} { @extId } ) OPTIONAL} OPTIONAL,
                                [1] IMPLICIT SEQUENCE {
              pcs-Extensions
                 ... } OPTIONAL,
              ... } OPTIONAL,
           ... } OPTIONAL,
        modifyNotificationToCSE [1] IMPLICIT ENUMERATED {
           deactivate (0),
                       ( 1 ) } OPTIONAL,
           activate
        extensionContainer [2] IMPLICIT SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
              SEQUENCE {
                          MAP-EXTENSION .&extensionId ( {
                 extId
                   ...}),
                 extType MAP-EXTENSION .&ExtensionType ( {
                    ...} { @extid } ) OPTIONAL} OPTIONAL,
                           [1] IMPLICIT SEQUENCE {
           pcs-Extensions
             ... } OPTIONAL,
           ... } OPTIONAL,
        ... } OPTIONAL}
           SEQUENCE {
  RESULT
     ss-InfoFor-CSE [0] CHOICE {
        forwardingInfoFor-CSE [0] IMPLICIT SEQUENCE {
           ss-Code
                                 [0] IMPLICIT OCTET STRING ( SIZE( 1 ) ),
           forwardingFeatureList [1] IMPLICIT SEQUENCE ( SIZE( 1 .. 32 ) )
OF
              SEQUENCE {
                 basicService
                                       CHOICE {
                   ext-BearerService
                                        [2] IMPLICIT OCTET STRING ( SIZE( 1
.. 5 ) ),
                   ext-Teleservice [3] IMPLICIT OCTET STRING ( SIZE( 1
.. 5 ) ) } OPTIONAL,
                 ss-Status
                                       [4] IMPLICIT OCTET STRING ( SIZE( 1 ...
5)),
                                   [5] IMPLICIT OCTET STRING ( SIZE( 1 ..
                forwardedToNumber
20 ) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
                 forwardedToSubaddress [8] IMPLICIT OCTET STRING ( SIZE( 1 ..
21 ) ) OPTIONAL,
                forwardingOptions [6] IMPLICIT OCTET STRING ( SIZE( 1 ...
5 ) ) OPTIONAL,
                noReplyConditionTime [7] IMPLICIT INTEGER ( 1 .. 100 )
OPTIONAL,
                extensionContainer [9] IMPLICIT SEQUENCE {
                   privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ..
10 ) ) OF
                      SEQUENCE {
```

```
extId MAP-EXTENSION .&extensionId ( {
                              ...} ) ,
                           extType MAP-EXTENSION .&ExtensionType ( {
                              ...} { @extid } ) OPTIONAL} OPTIONAL,
                     pcs-Extensions [1] IMPLICIT SEQUENCE {
                      ... } OPTIONAL,
                     ... } OPTIONAL,
                  longForwardedToNumber [10] IMPLICIT OCTET STRING ( SIZE( 1
.. 20 ) ) ( SIZE( 1 .. 15 ) ) OPTIONAL},
           notificationToCSE [2] IMPLICIT NULL OPTIONAL,
extensionContainer [3] IMPLICIT SEQUENCE {
  privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                  SEQUENCE {
                              MAP-EXTENSION .&extensionId ( {
                     extId
                        ...} ) ,
                     extType MAP-EXTENSION .&ExtensionType ( {
               ...} { @extid } ) OPTIONAL} OPTIONAL, pcs-Extensions [1] IMPLICIT SEQUENCE {
                ... } OPTIONAL,
               ... } OPTIONAL,
            ...},
         callBarringInfoFor-CSE [1] IMPLICIT SEQUENCE {
            ss-Code
                                          [0] IMPLICIT OCTET STRING ( SIZE( 1 )
),
           callBarringFeatureList
                                           [1] IMPLICIT SEQUENCE ( SIZE( 1 ..
32 ) ) OF
               SEQUENCE {
                 basicService CHOICE {
                    ext-BearerService [2] IMPLICIT OCTET STRING ( SIZE( 1
.. 5 ) ),
                                           [3] IMPLICIT OCTET STRING ( SIZE( 1
                    ext-Teleservice
.. 5 ) ) } OPTIONAL,
                                       [4] IMPLICIT OCTET STRING ( SIZE( 1 .. 5
                 ss-Status
) ),
                 extensionContainer SEQUENCE {
                    privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ..
10 ) ) OF
                        SEQUENCE {
                                    MAP-EXTENSION .&extensionId ( {
                           extId
                           extType MAP-EXTENSION .&ExtensionType ( {
                              ...} { @extId } ) OPTIONAL} OPTIONAL,
                                      [1] IMPLICIT SEQUENCE {
                     pcs-Extensions
                       ... } OPTIONAL,
                     ... } OPTIONAL,
                                          [2] IMPLICIT NumericString ( FROM
            password
("0"|"1"|"2"|"3"|"4"|"5"|"6"|"7"|"8"|"9" )) (SIZE( 4 ) ) OPTIONAL,
            wrongPasswordAttemptsCounter [3] IMPLICIT INTEGER ( 0 .. 4 )
OPTIONAL,
            notificationToCSE [4] IMPLICIT NULL OPTIONAL, extensionContainer [5] IMPLICIT SEQUENCE {
            notificationToCSE
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                  SEQUENCE {
```

```
extId MAP-EXTENSION .&extensionId ( {
                        ...}),
                      extType MAP-EXTENSION .&ExtensionType ( {
                        ...} { @extid } ) OPTIONAL} OPTIONAL,
               pcs-Extensions [1] IMPLICIT SEQUENCE {
                 ... } OPTIONAL,
                 .. } OPTIONAL,
      ... }} OPTIONAL, camel-SubscriptionInfo [1] IMPLICIT SEQUENCE {
                                     [0] IMPLICIT SEQUENCE {
         o-CST
            o-BcsmCamelTDPDataList SEQUENCE (SIZE(1..10)) OF
               SEQUENCE {
                  o-BcsmTriggerDetectionPoint ENUMERATED {
                     collectedInfo
                                            (2),
routeSelectFailure (4)},
serviceKey INTEGER (0.2147483647),
gsmSCF-Address [0] IMPLICIT OCTET STRING (
SIZE(1.20)) (SIZE(1..9)),
defaultCallHandling [11] IMPLICIT ENUMERATES (
                     taultCallHandling
  continueCall ( 0 ),
  releaseCall ( 1 ),
                     releaseCall
                     ... },
                   extensionContainer
                                                [2] IMPLICIT SEQUENCE {
                     privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ...
10 ) ) OF
                        SEQUENCE { extId MAP-EXTENSION .&extensionId ( {
                              ...} ) ,
                            extType MAP-EXTENSION .&ExtensionType ( {
                              ...} { @extId } ) OPTIONAL} OPTIONAL,
                      pcs-Extensions [1] IMPLICIT SEQUENCE {
                       ... } OPTIONAL,
                     ... } OPTIONAL,
            extensionContainer SEQUENCE {
               privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                   SEQUENCE {
                     extId MAP-EXTENSION .&extensionId ( {
                       ...} ) ,
                      extType MAP-EXTENSION .&ExtensionType ( {
                        ...} { @extId } ) OPTIONAL} OPTIONAL,
               pcs-Extensions [1] IMPLICIT SEQUENCE {
                 ... } OPTIONAL,
               ... } OPTIONAL,
            camelCapabilityHandling [0] IMPLICIT INTEGER ( 1 .. 16 ) OPTIONAL,
            notificationToCSE [1] IMPLICIT NULL OPTIONAL, csiActive [2] IMPLICIT NULL OPTIONAL} OPTIONAL,
         o-BcsmCamelTDP-CriteriaList
                                             [1] IMPLICIT SEQUENCE ( SIZE( 1 ..
10 ) ) OF
            SEOUENCE {
               o-BcsmTriggerDetectionPoint ENUMERATED {
                  collectedInfo (2),
                  routeSelectFailure (4)},
```

```
destinationNumberCriteria [0] IMPLICIT SEQUENCE {
                                              [0] IMPLICIT ENUMERATED {
                 matchType
                   inhibiting (0),
                                (1)},
                   enabling
                 destinationNumberList
                                             [1] IMPLICIT SEQUENCE ( SIZE( 1
.. 10 ) ) OF
                   OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1 .. 9 ) )
OPTIONAL,
                 destinationNumberLengthList [2] IMPLICIT SEQUENCE ( SIZE( 1
.. 3 ) ) OF
                   INTEGER ( 1 .. 15 ) OPTIONAL,
                 ... } OPTIONAL,
              basicServiceCriteria
                                      [1] IMPLICIT SEQUENCE ( SIZE( 1 ..
5 ) ) OF
                 CHOICE {
                                        [2] IMPLICIT OCTET STRING ( SIZE( 1
                   ext-BearerService
.. 5 ) ),
                                        [3] IMPLICIT OCTET STRING ( SIZE( 1
                   ext-Teleservice
.. 5 ) ) } OPTIONAL,
              callTypeCriteria
                                           [2] IMPLICIT ENUMERATED {
                 forwarded (0),
notForwarded (1)}OPTIONAL,
                                           [3] IMPLICIT SEQUENCE ( SIZE( 1 ..
              o-CauseValueCriteria
5 ) ) OF
                 OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
              extensionContainer
                                           [4] IMPLICIT SEQUENCE {
                privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10
) ) OF
                    SEQUENCE {
                       extId
                                MAP-EXTENSION .&extensionId ( {
                          ...}),
                       extType MAP-EXTENSION .&ExtensionType ( {
                          ...} { @extId } ) OPTIONAL} OPTIONAL,
                 pcs-Extensions [1] IMPLICIT SEQUENCE {
                   ... } OPTIONAL,
                 ... } OPTIONAL } OPTIONAL ,
                                           [2] IMPLICIT SEQUENCE {
           dp-AnalysedInfoCriteriaList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10
) ) OF
              SEQUENCE {
                 dialledNumber
                                     OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE(
1 .. 9 ) ),
                 serviceKey INTEGER ( 0 .. 2147483647 ), gsmSCF-Address OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE(
1 .. 9 ) ),
                 continueCall (0), releaseCall (1),
                    ... },
                 extensionContainer SEQUENCE {
                    privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ...
10 ) ) OF
                       SEQUENCE {
                                   MAP-EXTENSION .&extensionId ( {
                          extId
                          \ldots\} ) , extType $\sf MAP-EXTENSION .&ExtensionType ( {
                             ...} { @extid } ) OPTIONAL} OPTIONAL,
                                    [1] IMPLICIT SEQUENCE {
                    pcs-Extensions
```

```
... } OPTIONAL,
                   ... } OPTIONAL,
                 ... } OPTIONAL,
           camelCapabilityHandling
                                      [1] IMPLICIT INTEGER ( 1 .. 16 )
OPTIONAL,
                                       [2] IMPLICIT SEQUENCE {
           extensionContainer
             privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                SEQUENCE {
                            MAP-EXTENSION .&extensionId ( {
                   extId
                      ...}),
                   extType MAP-EXTENSION .&ExtensionType ( {
                      ...} { @extid } ) OPTIONAL} OPTIONAL, nsions [1] IMPLICIT SEQUENCE {
              pcs-Extensions
              ... } OPTIONAL,
              ... } OPTIONAL,
                                   [3] IMPLICIT NULL OPTIONAL,
           notificationToCSE
                                       [4] IMPLICIT NULL OPTIONAL,
           csi-Active
           ... } OPTIONAL,
        t-CSI
                                       [3] IMPLICIT SEQUENCE {
           t-BcsmCamelTDPDataList SEQUENCE (SIZE(1..10)) OF
              SEQUENCE {
                t-BcsmTriggerDetectionPoint ENUMERATED {
                  termAttemptAuthorized (12),
                   tBusy
                                           (13),
                tNoAnswer
serviceKey
                                           (14)},
                                            INTEGER ( 0 .. 2147483647 ),
                gsmSCF-Address
                                            [0] IMPLICIT OCTET STRING (
SIZE(1 .. 20 ) ) ( SIZE(1 .. 9 ) ),
                defaultCallHandling
                                            [1] IMPLICIT ENUMERATED {
                   continueCall (0),
                   releaseCall
                                 (1),
                   ... },
                                            [2] IMPLICIT SEQUENCE {
                 extensionContainer
                  privateExtensionList [0] IMPLICIT SEQUENCE (SIZE(1..
10 ) ) OF
                      SEQUENCE {
                                 MAP-EXTENSION .&extensionId ( {
                        extId
                           ...} ) ,
                         extType MAP-EXTENSION .&ExtensionType ( {
                           ... } { @extid } ) OPTIONAL } OPTIONAL ,
                   pcs-Extensions [1] IMPLICIT SEQUENCE {
                    ... } OPTIONAL,
                   ... } OPTIONAL,
                 ... },
           extensionContainer SEOUENCE {
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                 SEQUENCE {
                            MAP-EXTENSION .&extensionId ( {
                   extId
                      ...} ) ,
                   extType MAP-EXTENSION .&ExtensionType ( {
                      ...} { @extid } ) OPTIONAL} OPTIONAL,
              pcs-Extensions [1] IMPLICIT SEQUENCE {
               ... } OPTIONAL,
              ... } OPTIONAL,
```

```
camelCapabilityHandling [0] IMPLICIT INTEGER ( 1 .. 16 ) OPTIONAL,
           notificationToCSE [1] IMPLICIT NULL OPTIONAL, csi-Active [2] IMPLICIT NULL OPTIONAL) OPTIONAL,
        t-BCSM-CAMEL-TDP-CriteriaList [4] IMPLICIT SEQUENCE ( SIZE( 1 ..
10 ) ) OF
           SEQUENCE {
              t-BCSM-TriggerDetectionPoint ENUMERATED {
                 termAttemptAuthorized ( 12 ),
                 . . . ,
                                         (13),
              tNoAnswer
basicServiceCriteria
                 tBusy
                                        ( 14 ) },
                                           [0] IMPLICIT SEQUENCE ( SIZE( 1
.. 5 ) ) OF
               CHOICE {
                  ext-BearerService
                                        [2] IMPLICIT OCTET STRING ( SIZE( 1
.. 5 ) ),
                                        [3] IMPLICIT OCTET STRING ( SIZE( 1
                   ext-Teleservice
.. 5 ) ) } OPTIONAL,
                                          [1] IMPLICIT SEQUENCE ( SIZE( 1
              t-CauseValueCriteria
.. 5 ) ) OF
                OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
              ... } OPTIONAL,
                                         [5] IMPLICIT SEQUENCE {
        vt-CSI
           t-BcsmCamelTDPDataList SEQUENCE (SIZE(1..10)) OF
              SEQUENCE {
                 t-BcsmTriggerDetectionPoint ENUMERATED {
                   termAttemptAuthorized (12),
                   tBusy
                                           (13),
                   tNoAnswer
                                           ( 14 ) },
                                             INTEGER ( 0 .. 2147483647 ),
                 serviceKey
                 gsmSCF-Address
                                             [0] IMPLICIT OCTET STRING (
SIZE(1 .. 20 ) ) ( SIZE(1 .. 9 ) ),
                 defaultCallHandling
                                            [1] IMPLICIT ENUMERATED {
                   continueCall (0),
                   releaseCall
                                 (1),
                   ... },
                 extensionContainer
                                             [2] IMPLICIT SEQUENCE {
                   privateExtensionList [0] IMPLICIT SEQUENCE (SIZE(1..
10 ) ) OF
                      SEQUENCE {
                                  MAP-EXTENSION .&extensionId ( \{
                         extId
                            ...} ) ,
                         extType MAP-EXTENSION .&ExtensionType ( {
                            ...} { @extId } ) OPTIONAL} OPTIONAL,
                    pcs-Extensions [1] IMPLICIT SEQUENCE {
                     ... } OPTIONAL,
                    ... } OPTIONAL,
                 ...},
           extensionContainer SEOUENCE {
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                 SEQUENCE {
                            MAP-EXTENSION .&extensionId ( {
                    extId
                      ...}),
                    extType MAP-EXTENSION .&ExtensionType ( {
                       ...} { @extId } ) OPTIONAL} OPTIONAL,
              pcs-Extensions [1] IMPLICIT SEQUENCE {
```

```
... } OPTIONAL,
               ... } OPTIONAL,
           camelCapabilityHandling [0] IMPLICIT INTEGER (1 .. 16 ) OPTIONAL, notificationToCSE [1] IMPLICIT NULL OPTIONAL, csi-Active [2] IMPLICIT NULL OPTIONAL OPTIONAL,
        vt-BCSM-CAMEL-TDP-CriteriaList
                                            [6] IMPLICIT SEQUENCE ( SIZE( 1 ..
10 ) ) OF
            SEQUENCE {
               t-BCSM-TriggerDetectionPoint ENUMERATED {
                  termAttemptAuthorized ( 12 ),
                  . . . ,
                                           (13),
                  tBusy
                  tNoAnswer
                                           ( 14 ) },
               basicServiceCriteria
                                              [0] IMPLICIT SEQUENCE ( SIZE( 1
.. 5 ) ) OF
                 CHOICE {
                    ext-BearerService
                                          [2] IMPLICIT OCTET STRING ( SIZE( 1
.. 5 ) ),
                                          [3] IMPLICIT OCTET STRING ( SIZE( 1
                    ext-Teleservice
.. 5 ) ) } OPTIONAL,
              t-CauseValueCriteria
                                             [1] IMPLICIT SEQUENCE ( SIZE( 1
.. 5 ) ) OF
                 OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
              ... } OPTIONAL,
         tif-CSI
                                             [7] IMPLICIT NULL OPTIONAL,
         tif-CSI-NotificationToCSE
                                             [8] IMPLICIT NULL OPTIONAL,
         qprs-CSI
                                             [9] IMPLICIT SEQUENCE {
           gprs-CamelTDPDataList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
               SEQUENCE {
                  gprs-TriggerDetectionPoint [0] IMPLICIT ENUMERATED {
                     attach
                                                                (1),
                     attachChangeOfPosition
                                                                (2),
                     pdp-ContextEstablishment
                                                                (11),
                     pdp-ContextEstablishmentAcknowledgement (12),
                    pdp-ContextChangeOfPosition
                                                                (14).
                    ... },
                  serviceKey
                                              [1] IMPLICIT INTEGER ( 0 ..
2147483647),
                  gsmSCF-Address
                                              [2] IMPLICIT OCTET STRING ( SIZE(
1 .. 20 ) ) ( SIZE( 1 .. 9 ) ),
                 ... },
                                              [4] IMPLICIT SEQUENCE {
                  extensionContainer
                     privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ..
10 ) ) OF
                        SEQUENCE {
                                    MAP-EXTENSION .&extensionId ( {
                              ...} ) ,
                           extType MAP-EXTENSION .&ExtensionType ( {
                              ...} { @extid } ) OPTIONAL} OPTIONAL,
                                      [1] IMPLICIT SEQUENCE {
                     pcs-Extensions
                       ... } OPTIONAL,
                     ... } OPTIONAL,
                  ... } OPTIONAL,
            camelCapabilityHandling [1] IMPLICIT INTEGER ( 1 .. 16 ) OPTIONAL, extensionContainer [2] IMPLICIT SEQUENCE {
```

```
privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                 SEQUENCE {
                            MAP-EXTENSION .&extensionId ( {
                    extId
                      ...}),
                    extType MAP-EXTENSION .&ExtensionType ( {
                      ...} { @extId } ) OPTIONAL} OPTIONAL,
              pcs-Extensions [1] IMPLICIT SEQUENCE {
              ... } OFILE
... } OPTIONAL,
                                 [3] IMPLICIT NULL OPTIONAL,
           notificationToCSE
           csi-Active
                                    [4] IMPLICIT NULL OPTIONAL,
           ... } OPTIONAL,
                                          [10] IMPLICIT SEQUENCE {
        mo-sms-CSI
           sms-CAMEL-TDP-DataList [0] IMPLICIT SEQUENCE ( SIZE(1 .. 10 ) )
OF
              SEQUENCE {
                 sms-TriggerDetectionPoint [0] IMPLICIT ENUMERATED {
   sms-CollectedInfo (1),
                   sms-DeliveryRequest (2)},
                                            [1] IMPLICIT INTEGER ( 0 ...
                 serviceKey
2147483647),
                 gsmSCF-Address
                                           [2] IMPLICIT OCTET STRING ( SIZE(
1 .. 20 ) ) ( SIZE( 1 .. 9 ) ),
                 ... },
                 extensionContainer [4] IMPLICIT SEQUENCE {
   privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ...
10 ) ) OF
                       SEQUENCE { extid MAP-EXTENSION .&extensionId ( {
                            ...} ) ,
                          extType MAP-EXTENSION .&ExtensionType ( {
                            ...} { @extId } ) OPTIONAL} OPTIONAL,
                    pcs-Extensions [1] IMPLICIT SEQUENCE {
                      ... } OPTIONAL,
                    ... } OPTIONAL,
                 ... } OPTIONAL,
           camelCapabilityHandling [1] IMPLICIT INTEGER ( 1 .. 16 ) OPTIONAL,
           extensionContainer [2] IMPLICIT SEQUENCE {
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                 SEQUENCE {
                            MAP-EXTENSION .&extensionId ( {
                      ...} ) ,
                    extType MAP-EXTENSION .&ExtensionType ( {
                      ...} { @extId } ) OPTIONAL} OPTIONAL,
              pcs-Extensions [1] IMPLICIT SEQUENCE {
              ... } OPTIONAL,
              ... } OPTIONAL,
           notificationToCSE [3] IMPLICIT NULL OPTIONAL, csi-Active [4] IMPLICIT NULL OPTIONAL,
           ... } OPTIONAL,
        ss-CSI
                                           [11] IMPLICIT SEQUENCE {
```

```
ss-CamelData SEQUENCE {
ss-EventList SEQUENCE
                                  SEQUENCE (SIZE(1..10)) OF
                 OCTET STRING ( SIZE( 1 ) ),
               qsmSCF-Address OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1
.. 9 ) ),
               extensionContainer [0] IMPLICIT SEQUENCE {
                 privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10
) ) OF
                     SEQUENCE {
                                   MAP-EXTENSION .&extensionId ( {
                         extId
                            ...} ) ,
                         extType MAP-EXTENSION .&ExtensionType ( {
                   ...} { @extId } ) OPTIONAL} OPTIONAL, pcs-Extensions [1] IMPLICIT SEQUENCE {
                    ... } OPTIONAL,
                   ... } OPTIONAL,
                ... },
            extensionContainer SEQUENCE {
               privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                   SEQUENCE {
                                MAP-EXTENSION .&extensionId ( \{
                      extId
                        ...} ) ,
                      extType MAP-EXTENSION .&ExtensionType ( {
                        ...} { @extid } ) OPTIONAL} OPTIONAL,
                pcs-Extensions [1] IMPLICIT SEQUENCE {
                 ... } OPTIONAL,
                ... } OPTIONAL,
            notificationToCSE [0] IMPLICIT NULL OPTIONAL,
csi-Active [1] IMPLICIT NULL OPTIONAL OPTIONAL,
CSI [12] IMPLICIT SEQUENCE {
                                     [12] IMPLICIT SEQUENCE {
         m-CSI
            mobilityTriggers SEQUENCE (SIZE(1..10)) OF
              OCTET STRING ( SIZE( 1 ) ),
            serviceKey INTEGER ( 0 .. 2147483647 ), gsmSCF-Address [0] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) (
SIZE( 1 .. 9 )),
            extensionContainer [1] IMPLICIT SEQUENCE {
               privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                   SEQUENCE {
                      extId MAP-EXTENSION .&extensionId ( {
                        ...} ) ,
                      extType MAP-EXTENSION .&ExtensionType ( {
                         ...} { @extid } ) OPTIONAL} OPTIONAL,
                pcs-Extensions [1] IMPLICIT SEQUENCE {
                  ... } OPTIONAL,
                ... } OPTIONAL,
         notificationToCSE [2] IMPLICIT NULL OPTIONAL, csi-Active [3] IMPLICIT NULL OPTIONAL, ... } OPTIONAL, extensionContainer [13] IMPLICIT S.
                                               [13] IMPLICIT SEQUENCE {
            privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
                SEQUENCE {
                          MAP-EXTENSION .&extensionId ( {
                   extId
                      ...}),
```

```
extType MAP-EXTENSION .&ExtensionType ( {
                      ...} { @extId } ) OPTIONAL} OPTIONAL,
            pcs-Extensions [1] IMPLICIT SEQUENCE {
             ... } OPTIONAL,
             ... } OPTIONAL,
         specificCSIDeletedList
                                               [14] IMPLICIT BIT STRING {
            o-csi (0 ),
            ss-csi (1),
            tif-csi (2),
            d-csi (3),
vt-csi (4),
            mo-sms-csi (5),
            m-csi (6),
            gprs-csi (7),
            t-csi (8),
            mt-sms-csi (9),
            mq-csi (10),
            o-IM-CSI (11 ),
            d-IM-CSI (12 ),
            vt-IM-CSI (13 )} ( SIZE( 8 .. 32 ) ) OPTIONAL,
                                               [15] IMPLICIT SEQUENCE {
         mt-sms-CSI
            sms-CAMEL-TDP-DataList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                SEQUENCE {
                   sms-TriggerDetectionPoint [0] IMPLICIT ENUMERATED {
                     sms-CollectedInfo (1),
                     sms-DeliveryRequest (2)},
                   serviceKey
                                                [1] IMPLICIT INTEGER ( 0 ..
2147483647),
                   gsmSCF-Address
                                                [2] IMPLICIT OCTET STRING ( SIZE(
1 .. 20 ) ) ( SIZE( 1 .. 9 ) ),
                   defaultSMS-Handling [3] IMPLICIT ENUMERATED {
  continueTransaction (0),
  releaseTransaction (1),
                      ... },
                   extensionContainer [4] IMPLICIT SEQUENCE {
   privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ...
10 ) ) OF
                         SEQUENCE {
                                      MAP-EXTENSION .&extensionId ( \{
                             extId
                               ...} ) ,
                             extType MAP-EXTENSION .&ExtensionType ( {
                               ...} { @extId } ) OPTIONAL} OPTIONAL,
                      pcs-Extensions [1] IMPLICIT SEQUENCE {
                         ... } OPTIONAL,
                      ... } OPTIONAL,
                   ... } OPTIONAL,
             {\tt camelCapabilityHandling} \qquad {\tt [1]} \quad {\tt IMPLICIT} \quad {\tt INTEGER} \quad (\ {\tt 1}\ \dots\ {\tt 16}\ ) \quad {\tt OPTIONAL},
            extensionContainer [2] IMPLICIT SEQUENCE {
  privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                   SEQUENCE {
                      extId MAP-EXTENSION .&extensionId ( {
                         ...}),
                      extType MAP-EXTENSION .&ExtensionType ( {
                          ...} { @extId } ) OPTIONAL} OPTIONAL,
```

```
[1] IMPLICIT SEQUENCE {
              pcs-Extensions
                 ... } OPTIONAL,
               ... } OPTIONAL,
                                     [3] IMPLICIT NULL OPTIONAL,
            notificationToCSE
            csi-Active
                                     [4] IMPLICIT NULL OPTIONAL,
            ... } OPTIONAL,
         mt-smsCAMELTDP-CriteriaList
                                            [16] IMPLICIT SEQUENCE ( SIZE( 1
.. 10 ) ) OF
            SEQUENCE {
               sms-TriggerDetectionPoint ENUMERATED {
                 sms-CollectedInfo (1),
                  sms-DeliveryRequest (2)},
                                           [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 5
               tpdu-TypeCriterion
) ) OF
                  ENUMERATED {
                    sms-DELIVER (0),
sms-SUBMIT-REPORT (1),
sms-STATUS-REPORT (2),
                   sms-DELIVER
                     ... } OPTIONAL,
               ... } OPTIONAL,
         ma-csi
                                             [17] IMPLICIT SEQUENCE {
            mobilityTriggers SEQUENCE (SIZE(1..10)) OF
              OCTET STRING ( SIZE( 1 ) ),
           serviceKey INTEGER ( 0 .. 2147483647 ), gsmSCF-Address [0] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) (
SIZE( 1 .. 9 ) ),
           extensionContainer [1] IMPLICIT SEQUENCE {
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                  SEQUENCE {
                              MAP-EXTENSION .&extensionId ( {
                     extId
                        ...} ) ,
                     extType MAP-EXTENSION .&ExtensionType ( {
                        ...} { @extId } ) OPTIONAL} OPTIONAL,
               pcs-Extensions [1] IMPLICIT SEQUENCE {
                ... } OPTIONAL,
               ... } OPTIONAL,
            notificationToCSE [2] IMPLICIT NULL OPTIONAL, csi-Active [3] IMPLICIT NULL OPTIONAL, ... } OPTIONAL, [18] IMPLICIT S
                                             [18] IMPLICIT SEQUENCE {
         o-IM-CSI
            o-BcsmCamelTDPDataList SEQUENCE (SIZE(1..10)) OF
                  o-BcsmTriggerDetectionPoint ENUMERATED {
                    collectedInfo
                  routeSelectFailure (4)},
serviceKey INT
gsmSCF-Address [0]
                                               INTEGER ( 0 .. 2147483647 ),
                                                [0] IMPLICIT OCTET STRING (
SIZE( 1 .. 20 ) ) ( SIZE( 1 .. 9 ) ),
                                               [1] IMPLICIT ENUMERATED {
                  defaultCallHandling
                    continueCall (0), releaseCall (1),
                     releaseCall
                     ...},
                  extensionContainer [2] IMPLICIT SEQUENCE {
                    privateExtensionList [0] IMPLICIT SEQUENCE (SIZE(1...
10 ) ) OF
                        SEQUENCE {
                           extId MAP-EXTENSION .&extensionId ( {
```

```
...}),
                        extType MAP-EXTENSION .&ExtensionType ( {
                          ...} { @extid } ) OPTIONAL} OPTIONAL,
                  pcs-Extensions [1] IMPLICIT SEQUENCE {
                   ... } OPTIONAL,
                   ... } OPTIONAL,
          extensionContainer SEQUENCE {
             privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                SEQUENCE {
                           MAP-EXTENSION .&extensionId ( {
                  extId
                     ...}),
                   extType MAP-EXTENSION .&ExtensionType ( {
                     ...} { @extid } ) OPTIONAL} OPTIONAL,
             pcs-Extensions [1] IMPLICIT SEQUENCE {
               ... } OPTIONAL,
             ... } OPTIONAL,
          camelCapabilityHandling [0] IMPLICIT INTEGER ( 1 .. 16 ) OPTIONAL,
          notificationToCSE [1] IMPLICIT NULL OPTIONAL,
          csiActive
                                 [2] IMPLICIT NULL OPTIONAL OPTIONAL,
       o-IM-BcsmCamelTDP-CriteriaList [19] IMPLICIT SEQUENCE ( SIZE( 1
.. 10 ) ) OF
          SEQUENCE {
             o-BcsmTriggerDetectionPoint ENUMERATED {
               collectedInfo (2),
               routeSelectFailure (4)},
             destinationNumberCriteria [0] IMPLICIT SEQUENCE {
                                         [0] IMPLICIT ENUMERATED {
                matchType
                  inhibiting (0), enabling (1)},
                destinationNumberList
                                          [1] IMPLICIT SEQUENCE ( SIZE( 1
.. 10 ) ) OF
                 OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1 .. 9 ) )
OPTIONAL,
                destinationNumberLengthList [2] IMPLICIT SEQUENCE ( SIZE( 1
.. 3 ) ) OF
                  INTEGER ( 1 .. 15 ) OPTIONAL,
                ... } OPTIONAL,
             basicServiceCriteria [1] IMPLICIT SEQUENCE ( SIZE( 1 ..
5 ) ) OF
                CHOICE {
                  ext-BearerService [2] IMPLICIT OCTET STRING ( SIZE( 1
.. 5 ) ),
                 ext-Teleservice [3] IMPLICIT OCTET STRING ( SIZE( 1
.. 5 ) ) } OPTIONAL,
               callTypeCriteria
             o-CauseValueCriteria
                                       [3] IMPLICIT SEQUENCE ( SIZE( 1 ..
5 ) ) OF
               OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
             extensionContainer
                                        [4] IMPLICIT SEQUENCE {
               privateExtensionList [0] IMPLICIT SEQUENCE (SIZE(1..10
) ) OF
                  SEQUENCE {
                     extId MAP-EXTENSION .&extensionId ( {
```

```
...} ) ,
                       extType MAP-EXTENSION .&ExtensionType ( {
                          ...} { @extid } ) OPTIONAL} OPTIONAL,
                 pcs-Extensions [1] IMPLICIT SEQUENCE {
                   ... } OPTIONAL,
                  ... } OPTIONAL } OPTIONAL ,
        d-IM-CSI
                                           [20] IMPLICIT SEQUENCE {
           dp-AnalysedInfoCriteriaList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10
) ) OF
              SEQUENCE {
                 dialledNumber
                                     OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE(
1 .. 9 ) ),
                 serviceKey
                                      INTEGER ( 0 .. 2147483647 ),
                 serviceKey INTEGER ( 0 .. 2147483647 ),
gsmSCF-Address OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE(
1 .. 9 ) ),
                 defaultCallHandling ENUMERATED {
  continueCall ( 0 ),
  releaseCall ( 1 ),
                    ... },
                 privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ..
10 ) ) OF
                       SEQUENCE { extid MAP-EXTENSION .&extensionId ( {
                            ...}),
                          extType MAP-EXTENSION .&ExtensionType ( {
                            ...} { @extId } ) OPTIONAL} OPTIONAL,
                    pcs-Extensions [1] IMPLICIT SEQUENCE {
                      ... } OPTIONAL,
                    ... } OPTIONAL,
                  ... } OPTIONAL,
           camelCapabilityHandling
                                      [1] IMPLICIT INTEGER ( 1 .. 16 )
OPTIONAL,
           extensionContainer
                                        [2] IMPLICIT SEQUENCE {
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                 SEQUENCE {
                    extId MAP-EXTENSION .&extensionId ( {
                      ...} ) ,
                    extType MAP-EXTENSION .&ExtensionType ( {
                       ...} { @extId } ) OPTIONAL} OPTIONAL,
              pcs-Extensions [1] IMPLICIT SEQUENCE {
                ... } OPTIONAL,
                                     [3] IMPLICIT NULL OPTIONAL,
[4] IMPLICIT NULL OPTIONAL,
              ... } OPTIONAL,
           notificationToCSE
           csi-Active
           CSI-ACCIVE
... } OPTIONAL,
TM CGT [21] IMPLICIT SEQUENCE {
        vt-IM-CSI
           t-BcsmCamelTDPDataList SEQUENCE (SIZE(1..10)) OF
              SEOUENCE {
                 t-BcsmTriggerDetectionPoint ENUMERATED {
                    termAttemptAuthorized (12),
                    . . . ,
                                             (13),
                    tBusy
                    tNoAnswer
                                             ( 14 ) },
                                              INTEGER ( 0 .. 2147483647 ),
                 serviceKey
```

```
gsmSCF-Address
                                             [0] IMPLICIT OCTET STRING (
SIZE(1..20)) (SIZE(1..9)),
defaultCallHandling
                                             [1] IMPLICIT ENUMERATED {
                    continueCall ( 0 ),
releaseCall ( 1 ),
                    ... },
                 extensionContainer
                                             [2] IMPLICIT SEQUENCE {
                   privateExtensionList [0] IMPLICIT SEQUENCE (SIZE(1..
10 ) ) OF
                       SEQUENCE { extId MAP-EXTENSION .&extensionId ( {
                            ...} ) ,
                          extType MAP-EXTENSION .&ExtensionType ( {
                            ...} { @extId } ) OPTIONAL} OPTIONAL,
                    pcs-Extensions [1] IMPLICIT SEQUENCE {
                     ... } OPTIONAL,
                    ... } OPTIONAL,
                 ... },
           OF
                 SEQUENCE {
                   extId
                             MAP-EXTENSION .&extensionId ( {
                      ...} ) ,
                    extType MAP-EXTENSION .&ExtensionType ( {
                      ...} { @extid } ) OPTIONAL} OPTIONAL,
              pcs-Extensions [1] IMPLICIT SEQUENCE {
               ... } OPTIONAL,
              ... } OPTIONAL,
           camelCapabilityHandling [0] IMPLICIT INTEGER ( 1 .. 16 ) OPTIONAL,
           notificationToCSE [1] IMPLICIT NULL OPTIONAL, csi-Active [2] IMPLICIT NULL OPTIONAL} OPTIONAL,
        vt-IM-BCSM-CAMEL-TDP-CriteriaList [22] IMPLICIT SEQUENCE ( SIZE( 1
.. 10 ) ) OF
           SEQUENCE {
              t-BCSM-TriggerDetectionPoint ENUMERATED {
                termAttemptAuthorized (12),
                 . . . ,
                 tBusy
                                         (13),
                 tNoAnswer
                                         (14)},
              basicServiceCriteria
                                           [0] IMPLICIT SEQUENCE ( SIZE( 1
.. 5 ) ) OF
                 CHOICE {
                   ext-BearerService [2] IMPLICIT OCTET STRING ( SIZE( 1
.. 5 ) ),
                  ext-Teleservice [3] IMPLICIT OCTET STRING ( SIZE( 1
.. 5 ) ) } OPTIONAL,
                                           [1] IMPLICIT SEQUENCE ( SIZE( 1
              t-CauseValueCriteria
.. 5 ) ) OF
                OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
              ... } OPTIONAL } OPTIONAL ,
     extensionContainer [2] IMPLICIT SEQUENCE {
   privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
              extId $\tt MAP-EXTENSION .&extensionId ( \{
                 ...}),
              extType MAP-EXTENSION .&ExtensionType ( {
```

```
...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL,
                            [3] IMPLICIT SEQUENCE {
     odb-Info
                            SEQUENCE {
        odb-Data
           odb-GeneralData
                            BIT STRING {
              allOG-CallsBarred (0),
              internationalOGCallsBarred (1),
              internationalOGCallsNotToHPLMN-CountryBarred (2),
              interzonalOGCallsBarred (6),
              interzonalOGCallsNotToHPLMN-CountryBarred (7 ),
              interzonal OGC alls And International OGC alls Not To HPLMN-Country Barred\\
(8),
              premiumRateInformationOGCallsBarred (3 ),
              premiumRateEntertainementOGCallsBarred (4 ),
              ss-AccessBarred (5),
              allECT-Barred (9),
              chargeableECT-Barred (10),
              internationalECT-Barred (11),
              interzonalECT-Barred (12),
              doublyChargeableECT-Barred (13),
              multipleECT-Barred (14),
              allPacketOrientedServicesBarred (15),
              roamerAccessToHPLMN-AP-Barred (16 ),
              roamerAccessToVPLMN-AP-Barred (17 ),
              roamingOutsidePLMNOG-CallsBarred (18 ),
              allIC-CallsBarred (19),
              roamingOutsidePLMNIC-CallsBarred (20),
              roamingOutsidePLMNICountryIC-CallsBarred (21),
              roamingOutsidePLMN-Barred (22),
              roamingOutsidePLMN-CountryBarred (23 ),
              registrationAllCF-Barred (24),
              registrationCFNotToHPLMN-Barred (25),
              registrationInterzonalCF-Barred (26),
              registrationInterzonalCFNotToHPLMN-Barred (27 ),
              registrationInternationalCF-Barred (28)} (SIZE(15...32)),
           odb-HPLMN-Data BIT STRING {
              plmn-SpecificBarringType1 (0),
              plmn-SpecificBarringType2 (1 ),
              plmn-SpecificBarringType3 (2),
              plmn-SpecificBarringType4 (3)} (SIZE(4..32)) OPTIONAL,
           extensionContainer SEQUENCE {
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                 SEOUENCE {
                    extId
                             MAP-EXTENSION .&extensionId ( {
                       ...} ) ,
                    extType MAP-EXTENSION .&ExtensionType ( {
                       ...} { @extid } ) OPTIONAL} OPTIONAL,
                                   [1] IMPLICIT SEQUENCE {
              pcs-Extensions
                 ... } OPTIONAL,
              ... } OPTIONAL,
           ... },
        notificationToCSE
                            NULL OPTIONAL,
        extensionContainer SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
              SEQUENCE {
                 extId
                          MAP-EXTENSION .&extensionId ( \{
```

```
...} ) ,
                          MAP-EXTENSION .&ExtensionType ( {
                 extType
                    ...} { @extId } ) OPTIONAL} OPTIONAL,
           pcs-Extensions [1] IMPLICIT SEQUENCE {
             ... } OPTIONAL,
           ... } OPTIONAL,
        ... } OPTIONAL }
  ERRORS
     atm-NotAllowed |
     dataMissing
     unexpectedDataValue |
     unknownSubscriber |
     bearerServiceNotProvisioned |
     teleserviceNotProvisioned |
     callBarred
     illegalSS-Operation |
     ss-SubscriptionViolation |
     ss-ErrorStatus
     ss-Incompatibility |
     informationNotAvailable }
  CODE local : 65
noteSubscriberDataModified OPERATION ::= {
  ARGUMENT SEQUENCE {
     imsi
                             OCTET STRING ( SIZE( 3 .. 8 ) ),
     msisdn
                             OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1 .. 9 )
),
     forwardingInfoFor-CSE [0] IMPLICIT SEQUENCE {
                              [0] IMPLICIT OCTET STRING ( SIZE( 1 ) ),
        ss-Code
        forwardingFeatureList [1] IMPLICIT SEQUENCE ( SIZE( 1 .. 32 ) ) OF
           SEQUENCE {
               ext-BearerService [2] IMPT
             basicService
                                     [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 5
) ),
                                     [3] IMPLICIT OCTET STRING ( SIZE( 1 .. 5
                ext-Teleservice
) ) } OPTIONAL,
                                     [4] IMPLICIT OCTET STRING ( SIZE( 1 .. 5
              ss-Status
) ),
             forwardedToNumber [5] IMPLICIT OCTET STRING ( SIZE( 1 .. 20
) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
              forwardedToSubaddress [8] IMPLICIT OCTET STRING ( SIZE( 1 .. 21
) ) OPTIONAL,
                                    [6] IMPLICIT OCTET STRING ( SIZE( 1 .. 5
             forwardingOptions
) ) OPTIONAL,
              noReplyConditionTime
                                    [7] IMPLICIT INTEGER ( 1 .. 100 )
OPTIONAL,
              extensionContainer [9] IMPLICIT SEQUENCE {
                 privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10
) ) OF
                    SEQUENCE {
                      extId \dot{} MAP-EXTENSION .&extensionId ( {
                         ...} ) ,
                       extType MAP-EXTENSION .&ExtensionType ( {
                          ...} { @extId } ) OPTIONAL} OPTIONAL,
                 pcs-Extensions [1] IMPLICIT SEQUENCE {
                  ... } OPTIONAL,
                 ... } OPTIONAL,
              ...,
```

```
longForwardedToNumber [10] IMPLICIT OCTET STRING ( SIZE( 1 ...
20 ) ) ( SIZE( 1 .. 15 ) ) OPTIONAL},
        notificationToCSE [2] IMPLICIT NULL OPTIONAL, extensionContainer [3] IMPLICIT SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
              SEQUENCE {
                           MAP-EXTENSION .&extensionId ( {
                 extId
                    ...}),
                 extType MAP-EXTENSION .&ExtensionType ( {
                    ...} { @extId } ) OPTIONAL} OPTIONAL,
           pcs-Extensions [1] IMPLICIT SEQUENCE {
             ... } OPTIONAL,
            ... } OPTIONAL,
         ... } OPTIONAL,
      callBarringInfoFor-CSE [1] IMPLICIT SEQUENCE {
                                    [0] IMPLICIT OCTET STRING ( SIZE( 1 ) ),
        ss-Code
        callBarringFeatureList
                                      [1] IMPLICIT SEQUENCE ( SIZE( 1 .. 32 )
) OF
           SEQUENCE {
              basicService CHOICE {
                 ext-BearerService [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 5
) ),
                ext-Teleservice
                                      [3] IMPLICIT OCTET STRING ( SIZE( 1 .. 5
) ) } OPTIONAL,
              ss-Status
                                  [4] IMPLICIT OCTET STRING ( SIZE( 1 .. 5 )
),
              extensionContainer SEQUENCE {
                privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10
) ) OF
                    SEQUENCE {
                                 MAP-EXTENSION .&extensionId ( {
                       extId
                          ...}),
                       extType MAP-EXTENSION .&ExtensionType ( {
                          ...} { @extId } ) OPTIONAL} OPTIONAL,
                 pcs-Extensions [1] IMPLICIT SEQUENCE {
                   ... } OPTIONAL,
                 ... } OPTIONAL,
        password
                                      [2] IMPLICIT NumericString (FROM
("0"|"1"|"2"|"3"|"4"|"5"|"6"|"7"|"8"|"9" )) (SIZE( 4 ) ) OPTIONAL,
        wrongPasswordAttemptsCounter [3] IMPLICIT INTEGER ( 0 .. 4 )
OPTIONAL,
        notificationToCSE [4] IMPLICIT NULL OPTIONAL, extensionContainer [5] IMPLICIT SEQUENCE {
        notificationToCSE
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
              SEQUENCE {
                           MAP-EXTENSION .&extensionId ( {
                    ...} ) ,
                 extType MAP-EXTENSION .&ExtensionType ( {
                    ...} { @extid } ) OPTIONAL} OPTIONAL,
           pcs-Extensions [1] IMPLICIT SEQUENCE {
              ... } OPTIONAL,
            ... } OPTIONAL,
         ... } OPTIONAL,
                            [2] IMPLICIT SEQUENCE {
      odb-Info
        o-Info [2] IMPLIC
odb-Data SEQUENCE {
           odb-GeneralData BIT STRING {
```

```
alloG-CallsBarred (0),
              internationalOGCallsBarred (1),
              internationalOGCallsNotToHPLMN-CountryBarred (2),
              interzonalOGCallsBarred (6),
              interzonalOGCallsNotToHPLMN-CountryBarred (7 ),
              interzonal OGC alls And International OGC alls Not To HPLMN-Country Barred\\
(8),
              premiumRateInformationOGCallsBarred (3 ),
              premiumRateEntertainementOGCallsBarred (4 ),
              ss-AccessBarred (5),
              allECT-Barred (9),
              chargeableECT-Barred (10),
              internationalECT-Barred (11 ),
              interzonalECT-Barred (12 ),
              doublyChargeableECT-Barred (13 ),
              multipleECT-Barred (14),
              allPacketOrientedServicesBarred (15 ),
              roamerAccessToHPLMN-AP-Barred (16),
              roamerAccessToVPLMN-AP-Barred (17 ),
              roamingOutsidePLMNOG-CallsBarred (18),
              allIC-CallsBarred (19),
              roamingOutsidePLMNIC-CallsBarred (20),
              roamingOutsidePLMNICountryIC-CallsBarred
              roamingOutsidePLMN-Barred (22),
              roamingOutsidePLMN-CountryBarred (23),
              registrationAllCF-Barred (24),
              registrationCFNotToHPLMN-Barred (25),
              registrationInterzonalCF-Barred (26),
              registrationInterzonalCFNotToHPLMN-Barred (27 ),
              registrationInternationalCF-Barred (28 )} ( SIZE( 15 .. 32 ) ),
           odb-HPLMN-Data
                           BIT STRING {
              plmn-SpecificBarringType1 (0),
              plmn-SpecificBarringType2 (1 ),
              plmn-SpecificBarringType3 (2 ),
              plmn-SpecificBarringType4 (3 )} (SIZE(4 .. 32 )) OPTIONAL,
           extensionContainer SEQUENCE {
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                 SEQUENCE {
                    extId
                             MAP-EXTENSION .&extensionId ( {
                       ...} ) ,
                    extType MAP-EXTENSION .&ExtensionType ( {
                       ... } { @extid } ) OPTIONAL } OPTIONAL ,
              pcs-Extensions
                                    [1] IMPLICIT SEQUENCE {
                 ... } OPTIONAL,
              ... } OPTIONAL,
        notificationToCSE NULL OPTIONAL,
        extensionContainer SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
              SEQUENCE {
                          MAP-EXTENSION .&extensionId ( {
                 extId
                    ...} ) ,
                 extType MAP-EXTENSION .&ExtensionType ( {
                    ...} { @extId } ) OPTIONAL} OPTIONAL,
                           [1] IMPLICIT SEQUENCE {
           pcs-Extensions
              ... } OPTIONAL,
            ... } OPTIONAL,
         ... } OPTIONAL,
```

```
camel-SubscriptionInfo [3] IMPLICIT SEQUENCE {
                                            [0] IMPLICIT SEQUENCE {
         o-CSI
            o-BcsmCamelTDPDataList SEQUENCE (SIZE(1..10)) OF
               SEQUENCE {
                  o-BcsmTriggerDetectionPoint ENUMERATED {
                    collectedInfo
                                          (2),
                    routeSelectFailure (4)},
serviceKey INTEGER ( 0 .. 2147483647 ), gsmSCF-Address [0] IMPLICIT OCTET STRING (
SIZE(1 .. 20 ) ) (SIZE(1 .. 9 )), defaultCallHandling [1] IMPLICIT ENUMERATED {
                    continueCall (0), releaseCall (1),
                     ... },
                  extensionContainer
                                               [2] IMPLICIT SEQUENCE {
                     privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ..
10 ) ) OF
                        SEQUENCE { extid MAP-EXTENSION .&extensionId ( {
                             ...} ) ,
                           extType MAP-EXTENSION .&ExtensionType ( {
                     ...} { @extId } ) OPTIONAL} OPTIONAL, pcs-Extensions [1] IMPLICIT SEQUENCE {
                       ... } OPTIONAL,
                  ... } OPTIONAL,
... },
            extensionContainer SEQUENCE {
               privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                  SEQUENCE {
                              MAP-EXTENSION .&extensionId ( {
                     extId
                       ...} ) ,
                     extType MAP-EXTENSION .&ExtensionType ( {
                       ...} { @extid } ) OPTIONAL} OPTIONAL,
               pcs-Extensions [1] IMPLICIT SEQUENCE {
                ... } OPTIONAL,
               ... } OPTIONAL,
            camelCapabilityHandling [0] IMPLICIT INTEGER ( 1 .. 16 ) OPTIONAL,
            notificationToCSE [1] IMPLICIT NULL OPTIONAL, csiActive [2] IMPLICIT NULL OPTIONAL) OPTIONAL,
         o-BcsmCamelTDP-CriteriaList
                                            [1] IMPLICIT SEQUENCE ( SIZE( 1 ..
10 ) ) OF
            SEOUENCE {
               o-BcsmTriggerDetectionPoint ENUMERATED {
                  collectedInfo
                                       (2),
                  routeSelectFailure (4)},
               destinationNumberCriteria [0] IMPLICIT SEQUENCE {
                    [0] IMPLICIT ENUMERATED {
                  matchType
                  destinationNumberList
.. 10 ) ) OF
                    OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1 .. 9 ) )
OPTIONAL,
                 destinationNumberLengthList [2] IMPLICIT SEQUENCE ( SIZE( 1
.. 3 ) ) OF
```

```
INTEGER ( 1 .. 15 ) OPTIONAL,
                 ... } OPTIONAL,
                                     [1] IMPLICIT SEQUENCE ( SIZE( 1 ..
              basicServiceCriteria
5 ) ) OF
                CHOICE {
                                       [2] IMPLICIT OCTET STRING ( SIZE( 1
                  ext-BearerService
.. 5 ) ),
                                       [3] IMPLICIT OCTET STRING ( SIZE( 1
                   ext-Teleservice
.. 5 ) ) } OPTIONAL,
                                          [2] IMPLICIT ENUMERATED {
              callTypeCriteria
                forwarded (0),
notForwarded (1)}OPTIONAL,
                                          [3] IMPLICIT SEQUENCE ( SIZE( 1 ..
              o-CauseValueCriteria
5 ) ) OF
                OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
                                          [4] IMPLICIT SEQUENCE {
              extensionContainer
                privateExtensionList [0] IMPLICIT SEQUENCE (SIZE(1..10
) ) OF
                   SEQUENCE {
                               MAP-EXTENSION .&extensionId ( {
                      extId
                         ...} ) ,
                      extType MAP-EXTENSION .&ExtensionType ( {
                         ...} { @extId } ) OPTIONAL} OPTIONAL,
                 pcs-Extensions [1] IMPLICIT SEQUENCE {
                  ... } OPTIONAL,
                 ... } OPTIONAL } OPTIONAL ,
                                          [2] IMPLICIT SEQUENCE {
           dp-AnalysedInfoCriteriaList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10
) ) OF
              SEQUENCE {
                dialledNumber
                                    OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE(
1 .. 9 ) ),
                serviceKey INTEGER ( 0 .. 2147483647 ), gsmSCF-Address OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE(
1 .. 9 ) ),
                 defaultCallHandling ENUMERATED {
                   continueCall (0),
                   releaseCall (1),
                   ... },
                 privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ...
10 ) ) OF
                      SEQUENCE {
                                  MAP-EXTENSION .&extensionId ( {
                         extId
                            ...} ) ,
                         extType MAP-EXTENSION .&ExtensionType ( {
                            ...} { @extId } ) OPTIONAL} OPTIONAL,
                                    [1] IMPLICIT SEQUENCE {
                    pcs-Extensions
                      ... } OPTIONAL,
                    ... } OPTIONAL,
                 ... } OPTIONAL,
           camelCapabilityHandling [1] IMPLICIT INTEGER ( 1 .. 16 )
OPTIONAL,
                                     [2] IMPLICIT SEQUENCE {
           extensionContainer
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                 SEQUENCE {
                    extId MAP-EXTENSION .&extensionId ( {
```

```
...}),
                    extType MAP-EXTENSION .&ExtensionType ( {
                      ...} { @extId } ) OPTIONAL} OPTIONAL,
              pcs-Extensions [1] IMPLICIT SEQUENCE {
              ... } OPTIONAL,
              ... } OPTIONAL,
                                   [3] IMPLICIT NULL OPTIONAL,
           notificationToCSE
                                      [4] IMPLICIT NULL OPTIONAL,
           csi-Active
           ... } OPTIONAL,
        t-CST
                                        [3] IMPLICIT SEQUENCE {
           t-BcsmCamelTDPDataList SEQUENCE (SIZE(1..10)) OF
              SEQUENCE {
                 t-BcsmTriggerDetectionPoint ENUMERATED {
                   termAttemptAuthorized (12),
                   tBusy
                                           (13),
                   tNoAnswer
                                           (14)},
                                             INTEGER ( 0 .. 2147483647 ),
                 serviceKey
                gsmSCF-Address
                                             [0] IMPLICIT OCTET STRING (
SIZE( 1 .. 20 ) ) ( SIZE( 1 .. 9 ) ),
                   continueCall (0), releaseCall (7)
                defaultCallHandling
                                            [1] IMPLICIT ENUMERATED {
                                 (1),
                   ... },
                 extensionContainer
                                            [2] IMPLICIT SEQUENCE {
                   privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ...
10 ) ) OF
                      SEQUENCE {
                        extId
                                  MAP-EXTENSION .&extensionId ( {
                           ...} ) ,
                         extType MAP-EXTENSION .&ExtensionType ( {
                           ...} { @extId } ) OPTIONAL} OPTIONAL,
                   pcs-Extensions [1] IMPLICIT SEQUENCE {
                    ... } OPTIONAL,
                   ... } OPTIONAL,
                 ... },
           extensionContainer SEQUENCE {
             privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                 SEQUENCE {
                            MAP-EXTENSION .&extensionId ( {
                   extId
                      ...} ) ,
                   extType MAP-EXTENSION .&ExtensionType ( {
                      ...} { @extId } ) OPTIONAL} OPTIONAL,
              pcs-Extensions [1] IMPLICIT SEQUENCE {
              ... } OPTIONAL,
              ... } OPTIONAL,
           camelCapabilityHandling [0] IMPLICIT INTEGER ( 1 .. 16 ) OPTIONAL,
           notificationToCSE [1] IMPLICIT NULL OPTIONAL, csi-Active [2] IMPLICIT NULL OPTIONAL} OPTIONAL,
        t-BCSM-CAMEL-TDP-CriteriaList [4] IMPLICIT SEQUENCE ( SIZE( 1 ..
10 ) ) OF
           SEQUENCE {
              t-BCSM-TriggerDetectionPoint ENUMERATED {
                termAttemptAuthorized ( 12 ),
                 ...,
```

```
tBusy
tNoAnswer
                                         (13),
                                         ( 14 ) },
              basicServiceCriteria
                                           [0] IMPLICIT SEQUENCE ( SIZE( 1
.. 5 ) ) OF
                CHOICE {
                  ext-BearerService
                                        [2] IMPLICIT OCTET STRING ( SIZE( 1
.. 5 ) ),
                                        [3] IMPLICIT OCTET STRING ( SIZE( 1
                   ext-Teleservice
.. 5 ) ) } OPTIONAL,
                                           [1] IMPLICIT SEQUENCE ( SIZE( 1
              t-CauseValueCriteria
.. 5 ) ) OF
                OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
              ... } OPTIONAL,
                                          [5] IMPLICIT SEQUENCE {
        vt-CSI
           t-BcsmCamelTDPDataList SEQUENCE (SIZE(1..10)) OF
              SEQUENCE {
                 t-BcsmTriggerDetectionPoint ENUMERATED {
                   termAttemptAuthorized (12),
                    . . . ,
                   tBusy
                                            (13),
                 tNoAnswer
serviceKey
                                            ( 14 ) },
                                              INTEGER ( 0 .. 2147483647 ),
                 gsmSCF-Address
                                              [0] IMPLICIT OCTET STRING (
SIZE( 1 .. 20 ) ) ( SIZE( 1 .. 9 ) ),
                 defaultCallHandling
                   continueCall (0), releaseCall
                                             [1] IMPLICIT ENUMERATED {
                    ... },
                 extensionContainer
                                             [2] IMPLICIT SEQUENCE {
                   privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ...
10 ) ) OF
                       SEQUENCE {
                                  MAP-EXTENSION .&extensionId ( {
                         extId
                            ...} ) ,
                          extType MAP-EXTENSION .&ExtensionType ( {
                            ...} { @extId } ) OPTIONAL} OPTIONAL,
                    pcs-Extensions [1] IMPLICIT SEQUENCE {
                     ... } OPTIONAL,
                    ... } OPTIONAL,
                 ... },
           extensionContainer SEQUENCE {
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                 SEQUENCE {
                            MAP-EXTENSION .&extensionId ( {
                    extId
                      ...}),
                    extType MAP-EXTENSION .&ExtensionType ( {
                      ...} { @extId } ) OPTIONAL} OPTIONAL,
              pcs-Extensions [1] IMPLICIT SEQUENCE {
               ... } OPTIONAL,
              ... } OPTIONAL,
           camelCapabilityHandling [0] IMPLICIT INTEGER ( 1 .. 16 ) OPTIONAL,
           notificationToCSE [1] IMPLICIT NULL OPTIONAL, csi-Active [2] IMPLICIT NULL OPTIONAL} OPTIONAL,
        vt-BCSM-CAMEL-TDP-CriteriaList [6] IMPLICIT SEQUENCE ( SIZE( 1 ..
10 ) ) OF
           SEQUENCE {
              t-BCSM-TriggerDetectionPoint ENUMERATED {
```

```
termAttemptAuthorized ( 12 ),
                  ...,
                                           (13),
                  tBusy
                  tNoAnswer
                                           (14)},
                                              [0] IMPLICIT SEQUENCE ( SIZE( 1
               basicServiceCriteria
.. 5 ) ) OF
                 CHOICE {
                   ext-BearerService
                                          [2] IMPLICIT OCTET STRING ( SIZE( 1
.. 5 ) ),
                                          [3] IMPLICIT OCTET STRING ( SIZE( 1
                    ext-Teleservice
.. 5 ) ) } OPTIONAL,
              t-CauseValueCriteria
                                             [1] IMPLICIT SEQUENCE ( SIZE( 1
.. 5 ) ) OF
                 OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
               ... } OPTIONAL,
         tif-CSI
                                             [7] IMPLICIT NULL OPTIONAL,
                                             [8] IMPLICIT NULL OPTIONAL,
         tif-CSI-NotificationToCSE
                                             [9] IMPLICIT SEQUENCE {
         gprs-CSI
           gprs-CamelTDPDataList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
               SEQUENCE {
                  gprs-TriggerDetectionPoint [0] IMPLICIT ENUMERATED {
                     attach
                                                                (1),
                     attachChangeOfPosition
                                                                (2),
                                                                (11),
                     pdp-ContextEstablishment
                     pdp-ContextEstablishmentAcknowledgement (12),
                    pdp-ContextChangeOfPosition
                                                                (14),
                     ... },
                  serviceKey
                                              [1] IMPLICIT INTEGER ( 0 ..
2147483647),
                  gsmSCF-Address
                                              [2] IMPLICIT OCTET STRING ( SIZE(
1 .. 20 ) ) ( SIZE( 1 .. 9 ) ),
                 ... },
                  extensionContainer [4] IMPLICIT SEQUENCE {
   privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ...
10 ) ) OF
                        SEQUENCE {
                                    MAP-EXTENSION .&extensionId ( {
                           extId
                              ...} ) ,
                           extType MAP-EXTENSION .&ExtensionType ( {
                             ...} { @extId } ) OPTIONAL} OPTIONAL,
                     pcs-Extensions [1] IMPLICIT SEQUENCE {
                       ... } OPTIONAL,
                     ... } OPTIONAL,
                  ... } OPTIONAL,
            camelCapabilityHandling [1] IMPLICIT INTEGER ( 1 .. 16 ) OPTIONAL,
extensionContainer [2] IMPLICIT SEQUENCE {
  privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                  SEQUENCE {
                    extId MAP-EXTENSION .&extensionId ( {
                       ...}),
                     extType MAP-EXTENSION .&ExtensionType ( {
                        ...} { @extId } ) OPTIONAL} OPTIONAL,
               pcs-Extensions [1] IMPLICIT SEQUENCE {
                  ... } OPTIONAL,
```

```
... } OPTIONAL,
                                   [3] IMPLICIT NULL OPTIONAL,
           notificationToCSE
                                   [4] IMPLICIT NULL OPTIONAL,
           csi-Active
           ... } OPTIONAL,
                                          [10] IMPLICIT SEQUENCE {
        mo-sms-CSI
           sms-CAMEL-TDP-DataList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
              SEQUENCE {
                 sms-TriggerDetectionPoint [0] IMPLICIT ENUMERATED {
                   sms-CollectedInfo (1),
                   sms-DeliveryRequest (2)},
                                            [1] IMPLICIT INTEGER ( 0 ..
                 serviceKey
2147483647),
                                           [2] IMPLICIT OCTET STRING ( SIZE(
                 gsmSCF-Address
                   EaultSMS-Handling [3] ContinueTransaction (0),
1 .. 20 ) ) ( SIZE( 1 .. 9 ) ),
                                           [3] IMPLICIT ENUMERATED {
                 defaultSMS-Handling
                    ... },
                 extensionContainer
                                           [4] IMPLICIT SEQUENCE {
                   privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ...
10 ) ) OF
                       SEQUENCE {
                         extId
                                  MAP-EXTENSION .&extensionId ( {
                           ...} ) ,
                         extType MAP-EXTENSION .&ExtensionType ( {
                            ...} { @extid } ) OPTIONAL} OPTIONAL,
                    pcs-Extensions [1] IMPLICIT SEQUENCE {
                     ... } OPTIONAL,
                    ... } OPTIONAL,
                 ... } OPTIONAL,
           camelCapabilityHandling [1] IMPLICIT INTEGER ( 1 \dots 16 ) OPTIONAL,
           extensionContainer [2] IMPLICIT SEQUENCE {
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                 SEQUENCE {
                   extId
                            MAP-EXTENSION .&extensionId ( {
                      ...} ) ,
                    extType MAP-EXTENSION .&ExtensionType ( {
                      ... } { @extId } ) OPTIONAL } OPTIONAL ,
              pcs-Extensions [1] IMPLICIT SEQUENCE {
                ... } OPTIONAL,
              ... } OPTIONAL,
                                 [3] IMPLICIT NULL OPTIONAL,
           notificationToCSE
           csi-Active
                                   [4] IMPLICIT NULL OPTIONAL,
           ... } OPTIONAL,
        ss-CSI
                                          [11] IMPLICIT SEQUENCE {
           ss-CamelData SEQUENCE {
   ss-EventList SEQUENCE ( SIZE( 1 .. 10 ) ) OF
                OCTET STRING ( SIZE( 1 ) ),
             gsmSCF-Address OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1
.. 9 ) ),
             extensionContainer [0] IMPLICIT SEQUENCE {
               privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10
) ) OF
                    SEQUENCE {
                       extId MAP-EXTENSION .&extensionId ( {
```

```
...} ) ,
                        extType MAP-EXTENSION .&ExtensionType ( {
                           ...} { @extid } ) OPTIONAL} OPTIONAL,
                  pcs-Extensions [1] IMPLICIT SEQUENCE {
                   ... } OPTIONAL,
                  ... } OPTIONAL,
            extensionContainer SEQUENCE {
               privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                  SEQUENCE {
                              MAP-EXTENSION .&extensionId ( {
                    extId
                        ...} ) ,
                     extType MAP-EXTENSION .&ExtensionType ( {
                        ...} { @extid } ) OPTIONAL} OPTIONAL,
               pcs-Extensions [1] IMPLICIT SEQUENCE {
               ... } OPTIONAL,
               ... } OPTIONAL,
           notificationToCSE [0] IMPLICIT NULL OPTIONAL,
csi-Active [1] IMPLICIT NULL OPTIONAL OPTIONAL,
[12] IMPLICIT SEQUENCE {
                                            [12] IMPLICIT SEQUENCE {
         m-CSI
            mobilityTriggers SEQUENCE (SIZE(1..10)) OF
             OCTET STRING ( SIZE( 1 ) ),
           serviceKey INTEGER ( 0 .. 2147483647 ),
gsmSCF-Address [0] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) (
SIZE( 1 .. 9 )),
           extensionContainer [1] IMPLICIT SEQUENCE {
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                  SEQUENCE {
                              MAP-EXTENSION .&extensionId ( {
                     extId
                       ...} ) ,
                     extType MAP-EXTENSION .&ExtensionType ( {
                       ...} { @extId } ) OPTIONAL} OPTIONAL,
               pcs-Extensions [1] IMPLICIT SEQUENCE {
               ... } OPTIONAL,
               ... } OPTIONAL,
         notificationToCSE [2] IMPLICIT NULL OPTIONAL, csi-Active [3] IMPLICIT NULL OPTIONAL, ... } OPTIONAL, extensionContainer [13] IMPLICIT S
                                             [13] IMPLICIT SEQUENCE {
            privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
               SEQUENCE {
                  extId
                           MAP-EXTENSION .&extensionId ( {
                    ...} ) ,
                  extType MAP-EXTENSION .&ExtensionType ( {
                     ...} { @extid } ) OPTIONAL} OPTIONAL,
            pcs-Extensions [1] IMPLICIT SEQUENCE {
             ... } OPTIONAL,
            ... } OPTIONAL,
         specificCSIDeletedList [14] IMPLICIT BIT STRING {
            o-csi (0),
            ss-csi (1),
            tif-csi (2),
```

```
d-csi (3),
vt-csi (4),
            mo-sms-csi (5),
            m-csi (6),
            gprs-csi (7),
            t-csi (8),
            mt-sms-csi (9),
            mg-csi (10),
            o-IM-CSI (11 ),
            d-IM-CSI (12),
            vt-IM-CSI (13 )} ( SIZE( 8 .. 32 ) ) OPTIONAL,
                                               [15] IMPLICIT SEQUENCE {
         mt-sms-CSI
            sms-CAMEL-TDP-DataList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
               SEQUENCE {
                   sms-TriggerDetectionPoint [0] IMPLICIT ENUMERATED {
   sms-CollectedInfo (1),
                      . . . ,
                      {\tt sms-DeliveryRequest} \qquad (\ 2\ )\ \big\},
                                                [1] IMPLICIT INTEGER ( 0 ..
                   serviceKey
2147483647),
                                               [2] IMPLICIT OCTET STRING ( SIZE(
                  qsmSCF-Address
1 .. 20 ) ) ( SIZE( 1 .. 9 ) ),
                  defaultSMS-Handling [3] IMPLICIT ENUMERATED {
  continueTransaction (0),
  releaseTransaction (1),
                      ... },
                   extensionContainer [4] IMPLICIT SEQUENCE {
   privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ...
10 ) ) OF
                         SEQUENCE { extid MAP-EXTENSION .&extensionId ( {
                               ...} ) ,
                            extType MAP-EXTENSION .&ExtensionType ( {
                               ...} { @extId } ) OPTIONAL} OPTIONAL,
                      pcs-Extensions [1] IMPLICIT SEQUENCE {
                        ... } OPTIONAL,
                      ... } OPTIONAL,
                   ... } OPTIONAL,
            camelCapabilityHandling [1] IMPLICIT INTEGER ( 1 .. 16 ) OPTIONAL,
            extensionContainer [2] IMPLICIT SEQUENCE {
               privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                   SEQUENCE {
                                MAP-EXTENSION .&extensionId ( {
                      extId
                         ...}),
                      extType MAP-EXTENSION .&ExtensionType ( {
                         ...} { @extid } ) OPTIONAL} OPTIONAL,
               pcs-Extensions [1] IMPLICIT SEQUENCE {
                  ... } OPTIONAL,
                ... } OPTIONAL,
            ... } OPTIONAL,
notificationToCSE [3] IMPLICIT NULL OPTIONAL,
csi-Active [4] IMPLICIT NULL OPTIONAL,
            ... } OPTIONAL,
         mt-smsCAMELTDP-CriteriaList [16] IMPLICIT SEQUENCE ( SIZE( 1
.. 10 ) ) OF
            SEOUENCE {
               sms-TriggerDetectionPoint ENUMERATED {
                  sms-CollectedInfo (1),
```

```
sms-DeliveryRequest (2)},
tpdu-TypeCriterion [0] IMI
                                       [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 5
) ) OF
                 ENUMERATED {
                   sms-DELIVER ( 0 ),
sms-SUBMIT-REPORT ( 1 ),
sms-STATUS-REPORT ( 2 ),
                  sms-DELIVER
                    ... } OPTIONAL,
              ... } OPTIONAL,
                                          [17] IMPLICIT SEQUENCE {
        mg-csi
           mobilityTriggers SEQUENCE (SIZE(1..10)) OF
             OCTET STRING ( SIZE( 1 ) ),
           serviceKey INTEGER ( 0 .. 2147483647 ), gsmSCF-Address [0] IMPLICIT OCTET STRING ( 8
                              [0] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) (
SIZE( 1 .. 9 )),
           extensionContainer [1] IMPLICIT SEQUENCE {
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                 SEQUENCE {
                             MAP-EXTENSION .&extensionId ( {
                    extId
                      ...} ) ,
                    extType MAP-EXTENSION .&ExtensionType ( {
                      ...} { @extId } ) OPTIONAL} OPTIONAL,
              pcs-Extensions [1] IMPLICIT SEQUENCE {
               ... } OPTIONAL,
              ... } OPTIONAL,
           notificationToCSE [2] IMPLICIT NULL OPTIONAL, csi-Active [3] IMPLICIT NULL OPTIONAL, ... } OPTIONAL,
           ... } OPTIONAL,
        o-IM-CSI
                                          [18] IMPLICIT SEQUENCE {
           o-BcsmCamelTDPDataList SEQUENCE (SIZE(1..10)) OF
              SEQUENCE {
                 o-BcsmTriggerDetectionPoint ENUMERATED {
                   collectedInfo (2),
                   routeSelectFailure (4)},
                 serviceKey
                                             INTEGER ( 0 .. 2147483647 ),
                 gsmSCF-Address
                                             [0] IMPLICIT OCTET STRING (
SIZE(1 .. 20)) (SIZE(1 .. 9)),
                                             [1] IMPLICIT ENUMERATED {
                 defaultCallHandling
                   continueCall (0),
                   releaseCall
                                  (1),
                    ... },
                 extensionContainer
                                             [2] IMPLICIT SEQUENCE {
                    privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ...
10 ) ) OF
                       SEQUENCE {
                                  MAP-EXTENSION .&extensionId ( \{
                            ...} ) ,
                          extType MAP-EXTENSION .&ExtensionType ( {
                            ...} { @extId } ) OPTIONAL} OPTIONAL,
                    pcs-Extensions [1] IMPLICIT SEQUENCE {
                     ... } OPTIONAL,
                    ... } OPTIONAL,
                 ... },
           OF
```

```
SEQUENCE {
                            MAP-EXTENSION .&extensionId ( {
                    extId
                      ...}),
                    extType MAP-EXTENSION .&ExtensionType ( {
                      ...} { @extId } ) OPTIONAL} OPTIONAL,
              pcs-Extensions [1] IMPLICIT SEQUENCE {
                ... } OPTIONAL,
              ... } OPTIONAL,
           camelCapabilityHandling [0] IMPLICIT INTEGER ( 1 .. 16 ) OPTIONAL,
           notificationToCSE [1] IMPLICIT NULL OPTIONAL, csiActive [2] IMPLICIT NULL OPTIONAL} OPTIONAL,
        o-IM-BcsmCamelTDP-CriteriaList [19] IMPLICIT SEQUENCE ( SIZE( 1
.. 10 ) ) OF
           SEQUENCE {
              o-BcsmTriggerDetectionPoint ENUMERATED {
                 collectedInfo (2),
                 routeSelectFailure (4)},
              destinationNumberCriteria [0] IMPLICIT SEQUENCE {
                 matchType
                                            [0] IMPLICIT ENUMERATED {
                   inhibiting (0), enabling (1)},
                 destinationNumberList
                                            [1] IMPLICIT SEQUENCE ( SIZE( 1
.. 10 ) ) OF
                  OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1 .. 9 ) )
OPTIONAL,
                destinationNumberLengthList [2] IMPLICIT SEQUENCE ( SIZE( 1
.. 3 ) ) OF
                   INTEGER ( 1 .. 15 ) OPTIONAL,
                 ... } OPTIONAL,
              basicServiceCriteria
                                     [1] IMPLICIT SEQUENCE ( SIZE( 1 ..
5 ) ) OF
                CHOICE {
                  ext-BearerService
                                      [2] IMPLICIT OCTET STRING ( SIZE( 1
.. 5 ) ),
                   ext-Teleservice
                                      [3] IMPLICIT OCTET STRING ( SIZE( 1
.. 5 ) ) } OPTIONAL,
                                         [2] IMPLICIT ENUMERATED {
              callTypeCriteria
                forwarded (0),
                notForwarded ( 1 ) } OPTIONAL,
              o-CauseValueCriteria
                                          [3] IMPLICIT SEQUENCE ( SIZE( 1 ..
5 ) ) OF
                 OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
              extensionContainer
                                         [4] IMPLICIT SEQUENCE {
                privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10
) ) OF
                    SEQUENCE {
                      extId MAP-EXTENSION .&extensionId ( {
                         ...} ) ,
                       extType MAP-EXTENSION .&ExtensionType ( {
                         ...} { @extid } ) OPTIONAL} OPTIONAL.
                 pcs-Extensions [1] IMPLICIT SEQUENCE {
                  ... } OPTIONAL,
                 ... } OPTIONAL } OPTIONAL ,
                                          [20] IMPLICIT SEQUENCE {
           dp-AnalysedInfoCriteriaList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10
) ) OF
```

```
SEQUENCE {
                dialledNumber OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE(
1 .. 9 ) ),
                 serviceKey
                                    INTEGER ( 0 .. 2147483647 ),
                 serviceKey
gsmSCF-Address
                                    OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE(
1 .. 9 ) ),
                 defaultCallHandling ENUMERATED {
                   continueCall (0), releaseCall (1),
                    ... },
                 privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ..
10 ) ) OF
                      SEQUENCE {
                                  MAP-EXTENSION .&extensionId ( \{
                         extId
                            ...} ) ,
                         extType MAP-EXTENSION .&ExtensionType ( {
                            ...} { @extId } ) OPTIONAL} OPTIONAL,
                   pcs-Extensions [1] IMPLICIT SEQUENCE {
                     ... } OPTIONAL,
                    ... } OPTIONAL,
                 ... } OPTIONAL,
           camelCapabilityHandling
                                      [1] IMPLICIT INTEGER ( 1 .. 16 )
OPTIONAL,
             tensionContainer [2] IMPLICIT SEQUENCE {
  privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
           extensionContainer
OF
                 SEQUENCE {
                   extId
                            MAP-EXTENSION .&extensionId ( {
                      ...} ) ,
                   extType MAP-EXTENSION .&ExtensionType ( {
                      ...} { @extId } ) OPTIONAL} OPTIONAL,
              pcs-Extensions [1] IMPLICIT SEQUENCE {
              ... } OPTIONAL,
              ... } OPTIONAL,
           notificationToCSE
                                      [3] IMPLICIT NULL OPTIONAL,
           csi-Active
                                       [4] IMPLICIT NULL OPTIONAL,
           ... } OPTIONAL,
                                         [21] IMPLICIT SEQUENCE {
        vt-IM-CSI
           t-BcsmCamelTDPDataList SEQUENCE (SIZE(1..10)) OF
              SEQUENCE {
                 t-BcsmTriggerDetectionPoint ENUMERATED {
                   termAttemptAuthorized (12),
                   . . . ,
                                           (13),
                   tBusy
                   tNoAnswer
                                           (14)},
                 serviceKev
                                           INTEGER ( 0 .. 2147483647 ),
gsmsCF-Address
SIZE(1..20))(SIZE(1..9)),
                                            [0] IMPLICIT OCTET STRING (
                 defaultCallHandling
                                       [1] IMPLICIT ENUMERATED {
                   continueCall (0), releaseCall (1),
                   releaseCall
                   ...},
                 extensionContainer [2] IMPLICIT SEQUENCE {
                   privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ..
10 ) ) OF
                      SEQUENCE {
                         extId MAP-EXTENSION .&extensionId ( {
```

```
...} ) ,
                        extType MAP-EXTENSION .&ExtensionType ( {
                           ...} { @extid } ) OPTIONAL} OPTIONAL,
                   pcs-Extensions [1] IMPLICIT SEQUENCE {
                    ... } OPTIONAL,
                   ... } OPTIONAL,
                ...},
           extensionContainer SEQUENCE {
             privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                SEQUENCE {
                  extId
                           MAP-EXTENSION .&extensionId ( {
                     ...}),
                   extType MAP-EXTENSION .&ExtensionType ( {
                     ...} { @extId } ) OPTIONAL} OPTIONAL,
             pcs-Extensions [1] IMPLICIT SEQUENCE {
               ... } OPTIONAL,
             ... } OPTIONAL,
           camelCapabilityHandling [0] IMPLICIT INTEGER ( 1 .. 16 ) OPTIONAL,
          notificationToCSE [1] IMPLICIT NULL OPTIONAL,
          csi-Active
                                  [2] IMPLICIT NULL OPTIONAL OPTIONAL,
       vt-IM-BCSM-CAMEL-TDP-CriteriaList [22] IMPLICIT SEQUENCE ( SIZE( 1
.. 10 ) ) OF
          SEQUENCE {
             termAttemptAuthorized (12),
                                       (13),
                tBusy
                tNoAnswer
                                       (14)},
             basicServiceCriteria
                                         [0] IMPLICIT SEQUENCE ( SIZE( 1
.. 5 ) ) OF
                CHOICE {
                                     [2] IMPLICIT OCTET STRING ( SIZE( 1
                 ext-BearerService
.. 5 ) ),
                  ext-Teleservice [3] IMPLICIT OCTET STRING ( SIZE( 1
.. 5 ) ) } OPTIONAL,
            t-CauseValueCriteria
                                        [1] IMPLICIT SEQUENCE ( SIZE( 1
.. 5 ) ) OF
               OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
             ... } OPTIONAL } OPTIONAL ,
     allInformationSent [4] IMPLICIT NULL OPTIONAL, extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                      MAP-EXTENSION .&extensionId ( {
                ...} ) ,
             extType MAP-EXTENSION .&ExtensionType ( {
               ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL,
  RESULT
           SEQUENCE {
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
          SEQUENCE {
             extId MAP-EXTENSION .&extensionId ( {
```

```
...}),
             extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
         ... } OPTIONAL,
        ... } OPTIONAL,
     ...}
  ERRORS
    dataMissing
     unexpectedDataValue
     unknownSubscriber }
  CODE local : 5
prepareHandover OPERATION ::= {
  ARGUMENT [3] IMPLICIT SEQUENCE {
                          [0] IMPLICIT OCTET STRING ( SIZE( 5 .. 7 ) )
    targetCellId
OPTIONAL,
     ho-NumberNotRequired NULL OPTIONAL,
     targetRNCId
                                [1] IMPLICIT OCTET STRING ( SIZE( 7 ) )
OPTIONAL,
     an-APDU
                                [2] IMPLICIT SEQUENCE {
        accessNetworkProtocolId ENUMERATED {
          ts3G-48006 (1),
          ts3G-25413
                       (2),
        signalInto OCTET STRING ( SIZE( 1 .. 2560 ) ), extensionContainer SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
             SEQUENCE {
                         MAP-EXTENSION .&extensionId ( {
                extId
                   ...}),
                extType MAP-EXTENSION .&ExtensionType ( {
                   ...} { @extId } ) OPTIONAL} OPTIONAL,
                         [1] IMPLICIT SEQUENCE {
           pcs-Extensions
            ... } OPTIONAL,
           ... } OPTIONAL,
        ... } OPTIONAL,
     multipleBearerRequested [3] IMPLICIT NULL OPTIONAL,
     imsi
                                [4] IMPLICIT OCTET STRING ( SIZE( 3 .. 8 ) )
OPTIONAL,
     integrityProtectionInfo [5] IMPLICIT OCTET STRING ( SIZE( 18 .. 100 )
) OPTIONAL,
                               [6] IMPLICIT OCTET STRING ( SIZE( 18 .. 100 )
     encryptionInfo
) OPTIONAL,
     radioResourceInformation [7] IMPLICIT OCTET STRING ( SIZE( 3 .. 13 ) )
OPTIONAL,
     allowedGSM-Algorithms [9] IMPLICIT OCTET STRING ( SIZE( 1 ) )
OPTIONAL,
     allowedUMTS-Algorithms [10] IMPLICIT SEQUENCE {
        integrityProtectionAlgorithms [0] IMPLICIT OCTET STRING ( SIZE( 1 ..
9 ) ) OPTIONAL,
        encryptionAlgorithms
                                      [1] IMPLICIT OCTET STRING ( SIZE( 1 ...
9 ) ) OPTIONAL,
        extensionContainer
                                     [2] IMPLICIT SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
              SEQUENCE {
                extId
                         MAP-EXTENSION .&extensionId ( \{
```

```
...}),
                 extType MAP-EXTENSION .&ExtensionType ( {
                    ...} { @extId } ) OPTIONAL} OPTIONAL,
           pcs-Extensions [1] IMPLICIT SEQUENCE {
             ... } OPTIONAL,
             .. } OPTIONAL,
         ... } OPTIONAL,
     radioResourceList
                              [11] IMPLICIT SEQUENCE ( SIZE( 1 .. 7 ) ) OF
        SEQUENCE {
           radioResourceInformation OCTET STRING ( SIZE( 3 .. 13 ) ),
                                    INTEGER ( 1 .. 255 ),
           rab-Id
           ... } OPTIONAL,
                                [8] IMPLICIT SEQUENCE {
     extensionContainer
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                       MAP-EXTENSION .&extensionId ( {
              extId
                 ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL,
      ...,
                                 [12] IMPLICIT INTEGER ( 1 .. 255 ) OPTIONAL,
     rab-Id
     bssmap-ServiceHandover
                                 [13] IMPLICIT OCTET STRING ( SIZE( 1 ) )
OPTIONAL,
                                [14] IMPLICIT OCTET STRING ( SIZE( 1 ) )
     ranap-ServiceHandover
OPTIONAL,
     bssmap-ServiceHandoverList [15] IMPLICIT SEQUENCE ( SIZE( 1 .. 7 ) ) OF
        SEQUENCE {
           bssmap-ServiceHandover OCTET STRING ( SIZE( 1 ) ),
                                  INTEGER ( 1 .. 255 ),
           rab-Id
           ... } OPTIONAL,
     asciCallReference
                                [20] IMPLICIT OCTET STRING ( SIZE( 1 .. 8 ) )
OPTIONAL,
    geran-classmark
                                [16] IMPLICIT OCTET STRING ( SIZE( 2 .. 87 )
) OPTIONAL,
     iuCurrentlyUsedCodec [17] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
OPTIONAL,
                                [18] IMPLICIT SEQUENCE {
     iuSupportedCodecsList
        utranCodecList [0] IMPLICIT SEQUENCE {
                               [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) ),
           codec1
                               [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
           codec2
OPTIONAL,
           codec3
                               [3] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
OPTIONAL,
           codec4
                               [4] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
OPTIONAL,
                               [5] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
           codec5
OPTIONAL,
                               [6] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
           codec6
OPTIONAL,
                               [7] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
           codec7
OPTIONAL,
                               [8] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
           codec8
OPTIONAL,
           extensionContainer [9] IMPLICIT SEQUENCE {
             privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                 SEQUENCE {
```

```
extId MAP-EXTENSION .&extensionId ( {
                       ...} ) ,
                    extType MAP-EXTENSION .&ExtensionType ( {
                       ...} { @extid } ) OPTIONAL} OPTIONAL,
              pcs-Extensions [1] IMPLICIT SEQUENCE {
                ... } OPTIONAL,
              ... } OPTIONAL,
           ... } OPTIONAL,
                            [1] IMPLICIT SEQUENCE {
        geranCodecList
                               [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) ),
           codec1
                               [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
           codec2
OPTIONAL,
                               [3] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
           codec3
OPTIONAL,
                               [4] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
           codec4
OPTIONAL,
           codec5
                                [5] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
OPTIONAL,
           codec6
                                [6] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
OPTIONAL,
           codec7
                                [7] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
OPTIONAL,
           codec8
                                [8] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
OPTIONAL,
           extensionContainer [9] IMPLICIT SEQUENCE {
             privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                 SEQUENCE {
                    extId
                             MAP-EXTENSION .&extensionId ( {
                      ...} ) ,
                    extType MAP-EXTENSION .&ExtensionType ( {
                      ...} { @extId } ) OPTIONAL} OPTIONAL,
              pcs-Extensions [1] IMPLICIT SEQUENCE {
               ... } OPTIONAL,
              ... } OPTIONAL,
           ... } OPTIONAL,
        extensionContainer [2] IMPLICIT SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
              SEQUENCE {
                 extId
                          MAP-EXTENSION .&extensionId ( {
                   ...}),
                 extType MAP-EXTENSION .&ExtensionType ( {
                    ... } { @extId } ) OPTIONAL } OPTIONAL ,
           pcs-Extensions [1] IMPLICIT SEQUENCE {
             ... } OPTIONAL,
           ... } OPTIONAL,
         ... } OPTIONAL,
     rab-ConfigurationIndicator [19] IMPLICIT NULL OPTIONAL,
                                 [21] IMPLICIT SEQUENCE {
        uesbi-IuA [0] IMPLICIT BIT STRING ( SIZE( 1 .. 128 ) ) OPTIONAL,
        uesbi-IuB [1] IMPLICIT BIT STRING ( SIZE( 1 .. 128 ) ) OPTIONAL,
        ... } OPTIONAL,
     imeisv
                                 [22] IMPLICIT OCTET STRING ( SIZE( 8 ) )
OPTIONAL.
     alternativeChannelType [23] IMPLICIT OCTET STRING ( SIZE( 3 .. 13 )
) OPTIONAL,
     tracePropagationList [25] IMPLICIT SEQUENCE {
```

```
[0] IMPLICIT OCTET STRING ( SIZE( 1 ...
        traceReference
2 ) ) OPTIONAL,
                                       [1] IMPLICIT INTEGER ( 0 .. 255 )
        traceType
OPTIONAL,
                                       [2] IMPLICIT OCTET STRING ( SIZE( 3 )
        traceReference2
) OPTIONAL,
        traceRecordingSessionReference [3] IMPLICIT OCTET STRING ( SIZE( 2 )
) OPTIONAL,
                                       [4] IMPLICIT ENUMERATED {
        rnc-TraceDepth
          minimum (0),
           medium
                      (1),
          medium (1), maximum (2),
           ... } OPTIONAL,
        rnc-InterfaceList
                                     [5] IMPLICIT BIT STRING {
           iu (0),
           iur (1),
iub (2),
           uu (3 )} ( SIZE( 4 .. 8 ) ) OPTIONAL,
                                [6] IMPLICIT ENUMERATED {
        msc-s-TraceDepth
          minimum (0),
           medium (1), maximum (2),
           ... } OPTIONAL,
        msc-s-InterfaceList
                                [7] IMPLICIT BIT STRING {
           a (0),
           iu (1),
mc (2),
           map-g (3),
           map-b (4),
           map-e (5),
           map-f (6),
           cap (7),
           map-d (8),
           map-c (9)} (SIZE(10..16)) OPTIONAL,
        msc-s-EventList
                               [8] IMPLICIT BIT STRING {
          mo-mtCall (0),
           mo-mt-sms (1),
           lu-imsiAttach-imsiDetach (2),
           handovers (3),
           ss (4)} (SIZE(5..16)) OPTIONAL,
        mgw-TraceDepth
                                      [9] IMPLICIT ENUMERATED {
           minimum (0),
           medium (1), maximum (2),
          ... } OPTIONAL,
                               [10] IMPLICIT BIT STRING \{
        mgw-InterfaceList
           mc (0),
           nb-up (1),
           iu-up (2)} (SIZE(3..8)) OPTIONAL,
        mqw-EventList
                                     [11] IMPLICIT BIT STRING {
         context (0)} (SIZE(1..8)) OPTIONAL,
        ... } OPTIONAL}
  RESULT [3] IMPLICIT SEQUENCE {
                                    [0] IMPLICIT OCTET STRING ( SIZE( 1 .. 20
     handoverNumber
) ) ( SIZE( 1 .. 9 ) ) OPTIONAL, relocationNumberList [1] IMPLICIT SEQUENCE ( SIZE( 1 .. 7 ) )
        SEQUENCE {
          handoverNumber OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1 .. 9 )
),
           rab-Id INTEGER ( 1 .. 255 ),
          ... } OPTIONAL,
     an-APDU
                                    [2] IMPLICIT SEQUENCE {
```

```
accessNetworkProtocolId ENUMERATED {
            ts3G-48006 (1),
            ts3G-25413
                           (2),
            ... },
         signalInfo OCTET STRING ( SIZE( 1 .. 2560 ) ), extensionContainer SEQUENCE {
            privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
               SEQUENCE {
                              MAP-EXTENSION .&extensionId ( {
                   extId
                       ...}),
                   extType MAP-EXTENSION .&ExtensionType ( {
                      ...} { @extId } ) OPTIONAL} OPTIONAL,
            pcs-Extensions [1] IMPLICIT SEQUENCE {
              ... } OPTIONAL,
             ... } OPTIONAL,
          ... } OPTIONAL,
      multicallBearerInfo [3] IMPLICIT INTEGER ( 1 .. 7 ) OPTIONAL,
multipleBearerNotSupported NULL OPTIONAL,
selectedUMTS-Algorithms [5] IMPLICIT SEQUENCE {
  integrityProtectionAlgorithm [0] IMPLICIT OCTET STRING ( SIZE( 1 ) )
OPTIONAL,
         encryptionAlgorithm
                                          [1] IMPLICIT OCTET STRING ( SIZE( 1 ) )
OPTIONAL,
         extensionContainer [2] IMPLICIT SEQUENCE {
   privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
                SEQUENCE {
                   extId
                              MAP-EXTENSION .&extensionId ( {
                     ...}),
                   extType MAP-EXTENSION .&ExtensionType ( {
                      ...} { @extId } ) OPTIONAL} OPTIONAL,
            pcs-Extensions [1] IMPLICIT SEQUENCE {
              ... } OPTIONAL,
             ... } OPTIONAL,
          ... } OPTIONAL,
      chosenRadioResourceInformation [6] IMPLICIT SEQUENCE {
         chosenChannelInfo [0] IMPLICIT OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
         chosenSpeechVersion [1] IMPLICIT OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
         ... } OPTIONAL,
                                          [4] IMPLICIT SEQUENCE {
      extensionContainer
         privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
            SEQUENCE {
               extId MAP-EXTENSION .&extensionId ( {
                  ...} ) ,
                extType MAP-EXTENSION .&ExtensionType ( {
                   ...} { @extId } ) OPTIONAL} OPTIONAL,
         pcs-Extensions [1] IMPLICIT SEQUENCE {
           ... } OPTIONAL,
         ... } OPTIONAL,
                                         [7] IMPLICIT OCTET STRING ( SIZE( 1 .. 4
      iuSelectedCodec
) ) OPTIONAL,
      iuAvailableCodecsList [8] IMPLICIT SEQUENCE {
  codec1 [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) ),
  codec2 [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
OPTIONAL,
     codec3 [3] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
OPTIONAL,
```

```
[4] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
        codec4
OPTIONAL,
                            [5] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
        codec5
OPTIONAL,
                            [6] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
        codec6
OPTIONAL,
        codec7
                            [7] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
OPTIONAL,
                            [8] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
        codec8
OPTIONAL,
        extensionContainer [9] IMPLICIT SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
              SEQUENCE {
                          MAP-EXTENSION .&extensionId ( {
                 extId
                   ...} ) ,
                 extType MAP-EXTENSION .&ExtensionType ( {
                    ...} { @extid } ) OPTIONAL} OPTIONAL,
                           [1] IMPLICIT SEQUENCE {
           pcs-Extensions
             ... } OPTIONAL,
           ... } OPTIONAL,
        ... } OPTIONAL }
  ERRORS
     systemFailure |
     dataMissing
     unexpectedDataValue |
     noHandoverNumberAvailable |
     targetCellOutsideGroupCallArea }
  CODE local : 68
sendEndSignal OPERATION ::= {
  ARGUMENT [3] IMPLICIT SEQUENCE {
     an-APDU
               SEQUENCE {
        accessNetworkProtocolId ENUMERATED {
           ts3G-48006 (1),
ts3G-25413 (2),
           ... },
        signalInfo OCTET STRING ( SIZE( 1 .. 2560 ) ), extensionContainer SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
              SEQUENCE {
                extId
                          MAP-EXTENSION .&extensionId ( {
                   ...}),
                 extType MAP-EXTENSION .&ExtensionType ( {
                    ... } { @extId } ) OPTIONAL } OPTIONAL ,
           pcs-Extensions [1] IMPLICIT SEQUENCE {
              ... } OPTIONAL,
           ... } OPTIONAL,
     extensionContainer [0] IMPLICIT SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                       MAP-EXTENSION .&extensionId ( {
              extId
                 ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
```

```
... } OPTIONAL,
        ... } OPTIONAL,
  RESULT
            SEQUENCE {
     extensionContainer [0] IMPLICIT SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                       MAP-EXTENSION .&extensionId ( {
              extId
                 ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extid } ) OPTIONAL} OPTIONAL,
                        [1] IMPLICIT SEQUENCE {
        pcs-Extensions
          ... } OPTIONAL,
        ... } OPTIONAL,
     ...}
          local : 29
  CODE
processAccessSignalling OPERATION ::= {
  ARGUMENT [3] IMPLICIT SEQUENCE {
     an-APDU
                                    SEQUENCE {
        accessNetworkProtocolId ENUMERATED {
           ts3G-48006 ( 1 ),
ts3G-25413 ( 2 ),
           ... },
        signalInfo OCTET STRING ( SIZE( 1 .. 2560 ) ), extensionContainer SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
              SEQUENCE {
                extId
                          MAP-EXTENSION .&extensionId ( {
                   ...} ) ,
                 extType MAP-EXTENSION .&ExtensionType ( {
                   ...} { @extId } ) OPTIONAL} OPTIONAL,
           pcs-Extensions [1] IMPLICIT SEQUENCE {
            ... } OPTIONAL,
           ... } OPTIONAL,
        ...},
     selectedUMTS-Algorithms [1] IMPLICIT SEQUENCE {
        integrityProtectionAlgorithm [0] IMPLICIT OCTET STRING ( SIZE( 1 ) )
OPTIONAL,
        encryptionAlgorithm
                                     [1] IMPLICIT OCTET STRING ( SIZE( 1 ) )
OPTIONAL,
        extensionContainer
                                     [2] IMPLICIT SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
              SEQUENCE {
                extId
                         MAP-EXTENSION .&extensionId ( {
                   ...} ) ,
                 extType MAP-EXTENSION .&ExtensionType ( {
                   ...} { @extid } ) OPTIONAL} OPTIONAL,
           pcs-Extensions [1] IMPLICIT SEQUENCE {
             ... } OPTIONAL,
            ... } OPTIONAL,
        ... } OPTIONAL,
     selectedGSM-Algorithm
                              [2] IMPLICIT OCTET STRING ( SIZE( 1 ) )
OPTIONAL.
     chosenRadioResourceInformation [3] IMPLICIT SEQUENCE {
        chosenChannelInfo [0] IMPLICIT OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
```

```
chosenSpeechVersion [1] IMPLICIT OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
        ... } OPTIONAL,
     selectedRab-Id
                                    [4] IMPLICIT INTEGER ( 1 .. 255 )
OPTIONAL.
                                    [0] IMPLICIT SEQUENCE {
     extensionContainer
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                       MAP-EXTENSION .&extensionId ( {
              extId
                 ...}),
              extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extId } ) OPTIONAL} OPTIONAL,
                        [1] IMPLICIT SEQUENCE {
        pcs-Extensions
          ... } OPTIONAL,
        ... } OPTIONAL,
                                    [5] IMPLICIT OCTET STRING ( SIZE( 1 .. 4
     iUSelectedCodec
) ) OPTIONAL,
     [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
        codec2
OPTIONAL,
        codec3
                            [3] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
OPTIONAL,
        codec4
                            [4] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
OPTIONAL,
                            [5] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
        codec5
OPTIONAL,
                            [6] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
        codec6
OPTIONAL,
        codec7
                            [7] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
OPTIONAL,
        codec8
                            [8] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
OPTIONAL,
        extensionContainer [9] IMPLICIT SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
             SEQUENCE {
                          MAP-EXTENSION .&extensionId ( {
                ext.Td
                   ...}),
                 extType MAP-EXTENSION .&ExtensionType ( {
                   ... } { @extId } ) OPTIONAL } OPTIONAL ,
                          [1] IMPLICIT SEQUENCE {
           pcs-Extensions
             ... } OPTIONAL,
           ... } OPTIONAL,
        ... } OPTIONAL }
  CODE
           local : 33
forwardAccessSignalling OPERATION ::= {
  ARGUMENT [3] IMPLICIT SEQUENCE {
     an-APDU
                                SEQUENCE {
        accessNetworkProtocolId ENUMERATED {
           ts3G-48006 (1),
           ts3G-25413 (2),
           ... },
                                OCTET STRING ( SIZE( 1 .. 2560 ) ),
        signalInfo
        signalInfo OCTET STRING extensionContainer SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
              SEQUENCE {
                extId
                      MAP-EXTENSION .&extensionId ( \{
```

```
...} ) ,
                          MAP-EXTENSION .&ExtensionType ( {
                 extType
                   ...} { @extId } ) OPTIONAL} OPTIONAL,
                           [1] IMPLICIT SEQUENCE {
           pcs-Extensions
             ... } OPTIONAL,
           ... } OPTIONAL,
        ... },
                               [0] IMPLICIT OCTET STRING ( SIZE( 18 .. 100 )
     integrityProtectionInfo
) OPTIONAL,
     encryptionInfo
                                [1] IMPLICIT OCTET STRING ( SIZE( 18 .. 100 )
) OPTIONAL,
                                [2] IMPLICIT ENUMERATED {
     keyStatus
        old (0),
                   (1),
        new
        ... } OPTIONAL,
                                [4] IMPLICIT OCTET STRING ( SIZE( 1 ) )
     allowedGSM-Algorithms
OPTIONAL,
     allowedUMTS-Algorithms [5] IMPLICIT SEQUENCE {
        integrityProtectionAlgorithms [0] IMPLICIT OCTET STRING ( SIZE( 1 ...
9 ) ) OPTIONAL,
       encryptionAlgorithms
                                      [1] IMPLICIT OCTET STRING ( SIZE( 1 ...
9 ) ) OPTIONAL,
        extensionContainer
                                      [2] IMPLICIT SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
              SEQUENCE {
                extId
                          MAP-EXTENSION .&extensionId ( {
                   ...}),
                 extType MAP-EXTENSION .&ExtensionType ( {
                   ...} { @extId } ) OPTIONAL} OPTIONAL,
                           [1] IMPLICIT SEQUENCE {
           pcs-Extensions
             ... } OPTIONAL,
           ... } OPTIONAL,
        ... } OPTIONAL,
     radioResourceInformation [6] IMPLICIT OCTET STRING ( SIZE( 3 .. 13 ) )
OPTIONAL,
     extensionContainer
                                [3] IMPLICIT SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                       MAP-EXTENSION .&extensionId ( {
                 ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extId } ) OPTIONAL} OPTIONAL,
                        [1] IMPLICIT SEQUENCE {
        pcs-Extensions
          ... } OPTIONAL,
        ... } OPTIONAL,
                         [7] IMPLICIT SEQUENCE ( SIZE( 1 .. 7 ) ) OF
     radioResourceList
        SEOUENCE {
           radioResourceInformation OCTET STRING ( SIZE( 3 .. 13 ) ),
                                   INTEGER ( 1 .. 255 ),
           ... } OPTIONAL,
     bssmap-ServiceHandover [9] IMPLICIT OCTET STRING ( SIZE( 1 ) )
OPTIONAL,
     ranap-ServiceHandover [8] IMPLICIT OCTET STRING ( SIZE( 1 ) )
OPTIONAL,
     bssmap-ServiceHandoverList [10] IMPLICIT SEQUENCE ( SIZE( 1 .. 7 ) ) OF
        SEQUENCE {
```

```
bssmap-ServiceHandover OCTET STRING ( SIZE( 1 ) ),
            rab-Id
                                    INTEGER ( 1 .. 255 ),
            ... } OPTIONAL,
      currentlyUsedCodec
                                 [11] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
OPTIONAL,
     iuSupportedCodecsList [12] IMPLICIT SEQU
utranCodecList [0] IMPLICIT SEQUENCE {
                                  [12] IMPLICIT SEQUENCE {
                                 [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) ),
            codec1
                                 [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
            codec2
OPTIONAL,
                                 [3] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
            codec3
OPTIONAL,
                                 [4] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
            codec4
OPTIONAL,
                                 [5] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
            codec5
OPTIONAL,
            codec6
                                 [6] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
OPTIONAL,
            codec7
                                 [7] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
OPTIONAL,
            codec8
                                 [8] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
OPTIONAL,
            extensionContainer [9] IMPLICIT SEQUENCE {
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                  SEQUENCE {
                     extId
                               MAP-EXTENSION .&extensionId ( {
                        ...}),
                     extType MAP-EXTENSION .&ExtensionType ( {
                        ...} { @extid } ) OPTIONAL} OPTIONAL,
                               [1] IMPLICIT SEQUENCE {
               pcs-Extensions
                 ... } OPTIONAL,
               ... } OPTIONAL,
            ... } OPTIONAL,
         geranCodecList
                             [1] IMPLICIT SEQUENCE {
            codec1
                                 [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) ),
            codec2
                                 [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
OPTIONAL,
            codec3
                                 [3] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
OPTIONAL,
            codec4
                                 [4] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
OPTIONAL,
            codec5
                                 [5] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
OPTIONAL,
                                 [6] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
            codec6
OPTIONAL,
            codec7
                                 [7] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
OPTIONAL,
                                 [8] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
            codec8
OPTIONAL,
            extensionContainer [9] IMPLICIT SEQUENCE {
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                  SEQUENCE {
                              MAP-EXTENSION .&extensionId ( {
                     extId
                        ...}),
                     extType MAP-EXTENSION .&ExtensionType ( {
                        ...} { @extId } ) OPTIONAL} OPTIONAL,
                                     [1] IMPLICIT SEQUENCE {
               pcs-Extensions
```

```
... } OPTIONAL,
             ... } OPTIONAL,
           ... } OPTIONAL,
        extensionContainer [2] IMPLICIT SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
             SEQUENCE {
                extId
                         MAP-EXTENSION .&extensionId ( {
                   ...}),
                extType MAP-EXTENSION .&ExtensionType ( {
                   ...} { @extId } ) OPTIONAL} OPTIONAL,
           pcs-Extensions [1] IMPLICIT SEQUENCE {
             ... } OPTIONAL,
           ... } OPTIONAL,
        ... } OPTIONAL,
     rab-ConfigurationIndicator [13] IMPLICIT NULL OPTIONAL,
                                [14] IMPLICIT OCTET STRING ( SIZE( 1 .. 4 ) )
     iuSelectedCodec
OPTIONAL,
     alternativeChannelType
                               [15] IMPLICIT OCTET STRING ( SIZE( 3 .. 13 )
) OPTIONAL,
     tracePropagationList [17] IMPLICIT SEQUENCE {
       traceReference
                                      [0] IMPLICIT OCTET STRING ( SIZE( 1 ..
2 ) ) OPTIONAL,
       traceType
                                       [1] IMPLICIT INTEGER ( 0 .. 255 )
OPTIONAL,
        traceReference2
                                       [2] IMPLICIT OCTET STRING ( SIZE( 3 )
) OPTIONAL,
        traceRecordingSessionReference
                                     [3] IMPLICIT OCTET STRING ( SIZE( 2 )
) OPTIONAL,
        rnc-TraceDepth
                                      [4] IMPLICIT ENUMERATED {
          minimum (0),
          ... } OPTIONAL,
                                     [5] IMPLICIT BIT STRING {
        rnc-InterfaceList
          iu (0),
           iur (1),
          iub (2),
          uu (3 )} ( SIZE( 4 .. 8 ) ) OPTIONAL,
        msc-s-TraceDepth
                                      [6] IMPLICIT ENUMERATED {
          minimum ( 0 ),
          medium (1), maximum (2),
          ... } OPTIONAL,
                              [7] IMPLICIT BIT STRING {
        msc-s-InterfaceList
          a (0),
           iu (1),
           mc (2),
           map-q (3),
           map-b (4),
           map-e (5),
           map-f (6),
           cap (7),
           map-d (8),
           map-c (9)} (SIZE(10..16)) OPTIONAL,
                                    [8] IMPLICIT BIT STRING {
        msc-s-EventList
          mo-mtCall (0),
           mo-mt-sms (1),
           lu-imsiAttach-imsiDetach (2),
           handovers (3),
          ss (4)} (SIZE(5..16)) OPTIONAL,
        mgw-TraceDepth
                                      [9] IMPLICIT ENUMERATED {
```

```
... } OPTIONAL,
                                  [10] IMPLICIT BIT STRING \{
        mgw-InterfaceList
           mc (0),
           nb-up (1 ),
iu-up (2 )} ( SIZE( 3 .. 8 ) ) OPTIONAL,
                                    [11] IMPLICIT BIT STRING {
        mgw-EventList
          context (0 )} ( SIZE( 1 .. 8 ) ) OPTIONAL,
        ... } OPTIONAL}
          local : 34
  CODE
   }
prepareSubsequentHandover OPERATION ::= {
  ARGUMENT [3] IMPLICIT SEQUENCE {
                                [0] IMPLICIT OCTET STRING ( SIZE( 5 .. 7 ) )
    targetCellId
OPTIONAL,
    targetMSC-Number
                                [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) )
( SIZE( 1 .. 9 ) ),
    targetRNCId
                                 [2] IMPLICIT OCTET STRING ( SIZE( 7 ) )
OPTIONAL,
     an-APDU
                                 [3] IMPLICIT SEQUENCE {
        accessNetworkProtocolId ENUMERATED {
           ts3G-48006 ( 1 ),
ts3G-25413 ( 2 ),
           ... },
        signalInfo OCTET STRING ( SIZE( 1 .. 2560 ) ), extensionContainer SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
              SEQUENCE {
                extId
                          MAP-EXTENSION .&extensionId ( {
                   ...}),
                 extType MAP-EXTENSION .&ExtensionType ( {
                    ...} { @extId } ) OPTIONAL} OPTIONAL,
           pcs-Extensions [1] IMPLICIT SEQUENCE {
            ... } OPTIONAL,
           ... } OPTIONAL,
        ... } OPTIONAL,
     selectedRab-Id [4] IMPLICIT INTEGER ( 1 .. 255 ) OPTIONAL, extensionContainer [5] IMPLICIT SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
              extId MAP-EXTENSION .&extensionId ( {
                ...}),
              extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL,
     ...,
                                [6] IMPLICIT OCTET STRING ( SIZE( 2 .. 87 ) )
     geran-classmark
OPTIONAL,
     rab-ConfigurationIndicator [7] IMPLICIT NULL OPTIONAL}
  RESULT [3] IMPLICIT SEQUENCE {
     an-APDU SEQUENCE {
        accessNetworkProtocolId ENUMERATED {
           ts3G-48006 (1),
ts3G-25413 (2),
```

```
signalInfo OCTET STRING ( SIZE( 1 .. 2560 ) ), extensionContainer SEQUENCE {
          privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
            SEQUENCE {
                        MAP-EXTENSION .&extensionId ( {
               extId
                  ...}),
                extType MAP-EXTENSION .&ExtensionType ( {
                  ...} { @extId } ) OPTIONAL} OPTIONAL,
          pcs-Extensions [1] IMPLICIT SEQUENCE {
           ... } OPTIONAL,
          ... } OPTIONAL,
        ... },
     extensionContainer [0] IMPLICIT SEQUENCE {
       privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
          SEQUENCE {
                     MAP-EXTENSION .&extensionId ( {
             extId
               ...} ) ,
             extType MAP-EXTENSION .&ExtensionType ( {
               ...} { @extid } ) OPTIONAL} OPTIONAL,
       pcs-Extensions [1] IMPLICIT SEQUENCE {
         ... } OPTIONAL,
       ... } OPTIONAL,
  ERRORS
     unexpectedDataValue |
     dataMissing
     unknownMSC
     subsequentHandoverFailure }
  CODE local : 69
sendAuthenticationInfo OPERATION ::= {
  ARGUMENT SEQUENCE {
    immediateResponsePreferred [1] IMPLICIT NULL OPTIONAL,
     re-synchronisationInfo SEQUENCE {
       rand OCTET STRING ( SIZE( 16 ) ), auts OCTET STRING ( SIZE( 14 ) ),
       ... } OPTIONAL,
     extensionContainer
                              [2] IMPLICIT SEQUENCE {
       privateExtensionList [0] IMPLICIT SEQUENCE (SIZE(1..10)) OF
          SEQUENCE {
             extId MAP-EXTENSION .&extensionId ( {
               ...} ) ,
             extType MAP-EXTENSION .&ExtensionType ( {
               ...} { @extId } ) OPTIONAL} OPTIONAL,
       pcs-Extensions [1] IMPLICIT SEQUENCE {
         ... } OPTIONAL,
        ... } OPTIONAL,
     requestingNodeType
                         [3] IMPLICIT ENUMERATED {
       vlr (0),
sgsn (1),
        ... } OPTIONAL,
```

```
[4] IMPLICIT OCTET STRING ( SIZE( 3 ) )
      requestingPLMN-Id
OPTIONAL }
              [3] IMPLICIT SEQUENCE {
   RESULT
      authenticationSetList CHOICE {
         tripletList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 5 ) ) OF
            ipletList
SEQUENCE {
  rand     OCTET STRING ( SIZE( 16 ) ),
     sres     OCTET STRING ( SIZE( 4 ) ),
  kc      OCTET STRING ( SIZE( 8 ) ),
     },
         quintupletList [1] IMPLICIT SEQUENCE ( SIZE( 1 .. 5 ) ) OF
             SEQUENCE {
  rand OCTET STRING ( SIZE( 16 ) ),
  xres OCTET STRING ( SIZE( 4 .. 16 ) ),
  ck OCTET STRING ( SIZE( 16 ) ),
  ik OCTET STRING ( SIZE( 16 ) ),
  autn OCTET STRING ( SIZE( 16 ) ),
                ... }} OPTIONAL,
      extensionContainer SEQUENCE {
         privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
             SEQUENCE {
                           MAP-EXTENSION .&extensionId ( {
                extId
                   ...} ) ,
                extType MAP-EXTENSION .&ExtensionType ( {
                   ...} { @extId } ) OPTIONAL} OPTIONAL,
         pcs-Extensions [1] IMPLICIT SEQUENCE {
           ... } OPTIONAL,
          ... } OPTIONAL,
      ...}
   ERRORS
      systemFailure |
      dataMissing
      unexpectedDataValue |
      unknownSubscriber }
   CODE local : 56
   }
authenticationFailureReport OPERATION ::= {
   ARGUMENT SEQUENCE {
                             OCTET STRING ( SIZE( 3 .. 8 ) ),
      imsi
      failureCause
                            ENUMERATED {
         wrongUserResponse ( 0 ),
         wrongNetworkSignature (1)},
      extensionContainer SEQUENCE {
         privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
             SEQUENCE {
                           MAP-EXTENSION .&extensionId ( {
                   ...} ) ,
                extType MAP-EXTENSION .&ExtensionType ( {
                   ...} { @extid } ) OPTIONAL} OPTIONAL,
         pcs-Extensions [1] IMPLICIT SEQUENCE {
           ... } OPTIONAL,
          ... } OPTIONAL,
       . . . ,
      re-attempt BOOLEAN OPTIONAL, accessType ENUMERATED {
         call (0), emergencyCall (1), locationUpdating (2),
```

```
supplementaryService (3),
                                   (4),
         shortMessage
                                   (5),
         gprsAttach
                                  (6),
         routingAreaUpdating
                                  (7),
         serviceRequest
         pdpContextActivation (8),
pdpContextDeactivation (9),
         gprsDetach
                                   ( 10 ) } OPTIONAL,
                        ( 10 ) } OPTIONAL,
OCTET STRING ( SIZE( 16 ) ) OPTIONAL,
      rand
      vlr-Number
                          [0] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE(
1 .. 9 ) ) OPTIONAL,
                          [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE(
     sgsn-Number
1 .. 9 ) ) OPTIONAL}
  RESULT SEQUENCE {
                          SEQUENCE {
      extensionContainer
         privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
            SEQUENCE {
               extId
                         MAP-EXTENSION .&extensionId ( {
                  ...} ) ,
               extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extid } ) OPTIONAL} OPTIONAL,
         pcs-Extensions [1] IMPLICIT SEQUENCE {
           ... } OPTIONAL,
         ... } OPTIONAL,
  ERRORS
      systemFailure |
      unexpectedDataValue |
     unknownSubscriber }
  CODE local : 15
checkIMEI OPERATION ::= {
  ARGUMENT SEQUENCE {
                               OCTET STRING ( SIZE( 8 ) ),
     imei
      requestedEquipmentInfo BIT STRING {
         equipmentStatus (0),
         bmuef (1 ) } ( SIZE( 2 .. 8 ) ),
      extensionContainer SEQUENCE {
         privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
            SEQUENCE {
                        MAP-EXTENSION .&extensionId ( {
                  ...} ) ,
               extType MAP-EXTENSION .&ExtensionType ( {
                  ...} { @extId } ) OPTIONAL} OPTIONAL,
                          [1] IMPLICIT SEQUENCE {
         pcs-Extensions
            ... } OPTIONAL,
         ... } OPTIONAL,
            SEQUENCE {
  RESULT
      equipmentStatus
                          ENUMERATED {
        whiteListed (0),
blackListed (1),
greyListed (2) } OPTIONAL,
lef SEQUENCE {
      bmuef
                          SEQUENCE {
        uesbi-IuA [0] IMPLICIT BIT STRING ( SIZE( 1 .. 128 ) ) OPTIONAL, uesbi-IuB [1] IMPLICIT BIT STRING ( SIZE( 1 .. 128 ) ) OPTIONAL,
         ... } OPTIONAL,
```

```
extensionContainer [0] IMPLICIT SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                       MAP-EXTENSION .&extensionId ( {
              extId
                 ...}),
              extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL,
     ...}
  ERRORS
     systemFailure |
     dataMissing
     unknownEquipment }
  CODE local
                     : 43
insertSubscriberData OPERATION ::= {
  ARGUMENT SEQUENCE {
     imsi
                                                    [0] IMPLICIT OCTET STRING
( SIZE( 3 .. 8 ) ) OPTIONAL,
     msisdn
                                               [1] IMPLICIT OCTET STRING (
SIZE(1 .. 20)) (SIZE(1 .. 9)) OPTIONAL,
     category
                                               [2] IMPLICIT OCTET STRING (
SIZE(1)) OPTIONAL,
     subscriberStatus
                                               [3] IMPLICIT ENUMERATED {
                                   ( 0 ),
        serviceGranted
        operatorDeterminedBarring ( 1 ) } OPTIONAL,
     bearerServiceList
                                               [4] IMPLICIT SEQUENCE ( SIZE(
1 .. 50 ) OF
        OCTET STRING ( SIZE( 1 .. 5 ) ) OPTIONAL,
                                               [6] IMPLICIT SEQUENCE ( SIZE(
     teleserviceList
1 .. 20 ) ) OF
       OCTET STRING ( SIZE( 1 .. 5 ) ) OPTIONAL,
     provisionedSS
                                               [7] IMPLICIT SEQUENCE ( SIZE(
1 .. 30 ) ) OF
        CHOICE {
           forwardingInfo [0] IMPLICIT SEQUENCE {
                             OCTET STRING ( SIZE( 1 ) ),
             ss-Code
              forwardingFeatureList SEQUENCE (SIZE(1..32)) OF
                 SEQUENCE {
                                        CHOICE {
                   basicService
                      ext-BearerService
                                          [2] IMPLICIT OCTET STRING ( SIZE(
1 .. 5 ) ),
                     ext-Teleservice [3] IMPLICIT OCTET STRING ( SIZE(
1 .. 5 ) ) PTIONAL,
                   ss-Status
                                         [4] IMPLICIT OCTET STRING ( SIZE( 1
.. 5 ) ),
                   forwardedToNumber [5] IMPLICIT OCTET STRING ( SIZE( 1
.. 20 ) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
                   forwardedToSubaddress [8] IMPLICIT OCTET STRING ( SIZE( 1
.. 21 ) ) OPTIONAL,
                   forwardingOptions
                                         [6] IMPLICIT OCTET STRING ( SIZE( 1
.. 5 ) ) OPTIONAL,
                   noReplyConditionTime [7] IMPLICIT INTEGER ( 1 .. 100 )
OPTIONAL,
                   extensionContainer [9] IMPLICIT SEQUENCE {
                     privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1
.. 10 ) ) OF
                         SEQUENCE {
```

```
extId
                                   MAP-EXTENSION .&extensionId ( {
                             ...} ) ,
                           extType MAP-EXTENSION .&ExtensionType ( {
                             ...} { @extid } ) OPTIONAL} OPTIONAL,
                     pcs-Extensions [1] IMPLICIT SEQUENCE {
                      ... } OPTIONAL,
                     ... } OPTIONAL,
                   longForwardedToNumber [10] IMPLICIT OCTET STRING ( SIZE(
1 .. 20 ) ) ( SIZE( 1 .. 15 ) ) OPTIONAL},
            extensionContainer [0] IMPLICIT SEQUENCE {
                privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10
) ) OF
                   SEQUENCE {
                              MAP-EXTENSION .&extensionId ( {
                     extId
                       ...} ) ,
                     extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extId } ) OPTIONAL} OPTIONAL,
pcs-Extensions [1] IMPLICIT SEQUENCE {
                ... } OPTIONAL,
                ... } OPTIONAL,
          callBarringFeatureList SEQUENCE ( SIZE( 1 \dots 32 ) ) OF
               SEQUENCE {
                  basicService CHOICE {
                    ext-BearerService [2] IMPLICIT OCTET STRING ( SIZE(
1 .. 5 ) ),
                    ext-Teleservice
                                        [3] IMPLICIT OCTET STRING ( SIZE(
1 .. 5 ) ) } OPTIONAL,
                                     [4] IMPLICIT OCTET STRING ( SIZE( 1 ..
                  ss-Status
5)),
                   extensionContainer SEQUENCE {
                    privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1
.. 10 ) ) OF
                        SEQUENCE {
                          extId MAP-EXTENSION .&extensionId ( {
                             ...} ) ,
                           extType MAP-EXTENSION .&ExtensionType ( {
                             ...} { @extId } ) OPTIONAL} OPTIONAL,
                     pcs-Extensions [1] IMPLICIT SEQUENCE {
                       ... } OPTIONAL,
                     ... } OPTIONAL,
             extensionContainer SEQUENCE {
                privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10
) ) OF
                   SEQUENCE { extid MAP-EXTENSION .&extensionId ( {
                        ...} ) ,
                     extType MAP-EXTENSION .&ExtensionType ( {
                        ...} { @extid } ) OPTIONAL} OPTIONAL,
                pcs-Extensions [1] IMPLICIT SEQUENCE {
                   ... } OPTIONAL,
```

```
... } OPTIONAL,
          cug-Info
                           [2] IMPLICIT SEQUENCE {
             cug-SubscriptionList SEQUENCE (SIZE(0..10)) OF
               SEQUENCE {
                  cug-Index
                   noCUG-Restrictions (0),
cugIC-CallBarred (1),
cugOG-CallBarred (2)},
                  basicServiceGroupList SEQUENCE (SIZE(1..32)) OF
                    CHOICE {
                       ext-BearerService
                                          [2] IMPLICIT OCTET STRING (
SIZE( 1 .. 5 )),
                                          [3] IMPLICIT OCTET STRING (
                       ext-Teleservice
SIZE( 1 .. 5 ) ) } OPTIONAL,
                  extensionContainer [0] IMPLICIT SEQUENCE {
   privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1
.. 10 ) ) OF
                       SEQUENCE {
                                  MAP-EXTENSION .&extensionId ( {
                          extId
                            ...} ) ,
                          extType MAP-EXTENSION .&ExtensionType ( {
                            ...} { @extId } ) OPTIONAL} OPTIONAL,
                     pcs-Extensions [1] IMPLICIT SEQUENCE {
                      ... } OPTIONAL,
                     ... } OPTIONAL,
                  ... },
             cug-FeatureList SEQUENCE (SIZE(1..32)) OF
               SEQUENCE {
                  basicService
                                          CHOICE {
                    ext-BearerService [2] IMPLICIT OCTET STRING ( SIZE(
1 .. 5 ) ),
                    ext-Teleservice
                                       [3] IMPLICIT OCTET STRING ( SIZE(
1 .. 5 ) ) } OPTIONAL,
                  OPTIONAL,
                  privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1
.. 10 ) ) OF
                       SEQUENCE { extid MAP-EXTENSION .&extensionId ( {
                            ...} ) ,
                          extType MAP-EXTENSION .&ExtensionType ( {
                            ...} { @extId } ) OPTIONAL} OPTIONAL,
                     pcs-Extensions [1] IMPLICIT SEQUENCE {
                       ... } OPTIONAL,
                     ... } OPTIONAL,
                  ... } OPTIONAL,
             extensionContainer [0] IMPLICIT SEQUENCE {
               privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10
) ) OF
                  SEQUENCE { extid MAP-EXTENSION .&extensionId ( {
                       ...}),
                     extType MAP-EXTENSION .&ExtensionType ( {
```

```
...} { @extid } ) OPTIONAL} OPTIONAL,
                 pcs-Extensions [1] IMPLICIT SEQUENCE {
                   ... } OPTIONAL,
                  ... } OPTIONAL,
              ss-Code
                              [3] IMPLICIT SEQUENCE {
            ss-Data
                                     OCTET STRING ( SIZE( 1 ) ),
              ss-Status
                                      [4] IMPLICIT OCTET STRING ( SIZE( 1 .. 5
)),
              ss-SubscriptionOption CHOICE {
                 cliRestrictionOption [2] IMPLICIT ENUMERATED {
                                              ( 0 ),
                    permanent
                    temporaryDefaultRestricted (1),
temporaryDefaultAllowed (2)},
              overrideCategory [1] IMPLICIT ENUMERATED {
   overrideEnabled ( 0 ),
   overrideDisabled ( 1 ) }} OPTIONAL,
basicServiceGroupList SEQUENCE ( SIZE( 1 .. 32 ) ) OF
                 CHOICE {
                    ext-BearerService [2] IMPLICIT OCTET STRING ( SIZE( 1
.. 5 ) ),
                    ext-Teleservice
                                         [3] IMPLICIT OCTET STRING ( SIZE( 1
.. 5 ) ) } OPTIONAL,
              extensionContainer [5] IMPLICIT SEQUENCE {
                 privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10
) ) OF
                    SEQUENCE {
                       extId
                                 MAP-EXTENSION .&extensionId ( {
                          ...} ) ,
                       extType MAP-EXTENSION .&ExtensionType ( {
                          ...} { @extId } ) OPTIONAL} OPTIONAL,
                 \verb"pcs-Extensions" [1] IMPLICIT SEQUENCE \{
                   ... } OPTIONAL,
                 ... } OPTIONAL,
              . . . },
                          [4] IMPLICIT SEQUENCE {
            emlpp-Info
              maximumentitledPriority INTEGER ( 0 .. 15 ),
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10
) ) OF
                    SEQUENCE {
                       extId
                                MAP-EXTENSION .&extensionId ( {
                          ...} ) ,
                       extType MAP-EXTENSION .&ExtensionType ( {
                          ...} { @extId } ) OPTIONAL} OPTIONAL,
                 pcs-Extensions [1] IMPLICIT SEQUENCE {
                    ... } OPTIONAL,
                  ... } OPTIONAL,
               ... }} OPTIONAL,
                                             [8] IMPLICIT SEQUENCE {
     odb-Data
        odb-GeneralData BIT STRING {
           allog-CallsBarred (0),
            internationalOGCallsBarred (1 ),
            internationalOGCallsNotToHPLMN-CountryBarred (2),
            interzonalOGCallsBarred (6 ),
            interzonalOGCallsNotToHPLMN-CountryBarred (7),
```

```
interzonalOGCallsAndInternationalOGCallsNotToHPLMN-CountryBarred (8
),
           premiumRateInformationOGCallsBarred (3 ),
           premiumRateEntertainementOGCallsBarred (4 ),
           ss-AccessBarred (5),
           allECT-Barred (9),
           chargeableECT-Barred (10 ),
           internationalECT-Barred (11 ),
           interzonalECT-Barred (12),
           doublyChargeableECT-Barred (13),
           multipleECT-Barred (14 ),
           allPacketOrientedServicesBarred (15 ),
           roamerAccessToHPLMN-AP-Barred (16 ),
           roamerAccessToVPLMN-AP-Barred (17 ),
           roamingOutsidePLMNOG-CallsBarred (18 ),
           allIC-CallsBarred (19),
           roamingOutsidePLMNIC-CallsBarred (20 ),
           roamingOutsidePLMNICountryIC-CallsBarred (21),
           roamingOutsidePLMN-Barred (22),
           roamingOutsidePLMN-CountryBarred (23),
           registrationAllCF-Barred (24),
           registrationCFNotToHPLMN-Barred (25 ),
           registrationInterzonalCF-Barred (26),
           registrationInterzonalCFNotToHPLMN-Barred (27),
           registrationInternationalCF-Barred (28 )} ( SIZE( 15 .. 32 ) ),
        odb-HPLMN-Data BIT STRING {
           plmn-SpecificBarringType1 (0),
           plmn-SpecificBarringType2 (1),
           plmn-SpecificBarringType3 (2),
           plmn-SpecificBarringType4 (3 ) { SIZE( 4 .. 32 ) ) OPTIONAL,
        extensionContainer SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
              SEQUENCE {
                 extId
                          MAP-EXTENSION .&extensionId ( \{
                    ...}),
                 extType MAP-EXTENSION .&ExtensionType ( {
                    ...} { @extId } ) OPTIONAL} OPTIONAL,
           pcs-Extensions
                            [1] IMPLICIT SEQUENCE {
              ... } OPTIONAL,
           ... } OPTIONAL,
        ... } OPTIONAL,
     roamingRestrictionDueToUnsupportedFeature [9] IMPLICIT NULL OPTIONAL,
     regionalSubscriptionData
                                                [10] IMPLICIT SEQUENCE (
SIZE( 1 .. 10 ) ) OF
        OCTET STRING ( SIZE( 2 ) ) OPTIONAL,
     vbsSubscriptionData
                                                [11] IMPLICIT SEQUENCE (
SIZE( 1 .. 50 ) ) OF
        SEQUENCE {
                                    OCTET STRING ( SIZE( 3 ) ),
           groupid
           broadcastInitEntitlement NULL OPTIONAL,
           extensionContainer
                                    SEOUENCE {
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                 SEQUENCE {
                             MAP-EXTENSION .&extensionId ( {
                    extId
                       ...}),
                    extType MAP-EXTENSION .&ExtensionType ( {
                       ...} { @extid } ) OPTIONAL} OPTIONAL,
                                   [1] IMPLICIT SEQUENCE {
              pcs-Extensions
```

```
... } OPTIONAL,
             ... } OPTIONAL,
           ... } OPTIONAL,
                                             [12] IMPLICIT SEQUENCE (
     vgcsSubscriptionData
SIZE( 1 .. 50 ) ) OF
       SEQUENCE {
          groupId
                            OCTET STRING ( SIZE( 3 ) ),
          extensionContainer SEQUENCE {
            privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                SEQUENCE {
                           MAP-EXTENSION .&extensionId ( {
                   extId
                     ...} ) ,
                   extType MAP-EXTENSION .&ExtensionType ( {
                     ...} { @extId } ) OPTIONAL} OPTIONAL,
                             [1] IMPLICIT SEQUENCE {
             pcs-Extensions
               ... } OPTIONAL,
             ... } OPTIONAL,
           ... } OPTIONAL,
     vlrCamelSubscriptionInfo

[0] IMPLICIT SEQUENCE {
                                             [13] IMPLICIT SEQUENCE {
           o-BcsmCamelTDPDataList SEQUENCE (SIZE(1..10)) OF
             SEOUENCE {
                o-BcsmTriggerDetectionPoint ENUMERATED {
                  collectedInfo (2),
                  routeSelectFailure (4)},
                serviceKey
                                          INTEGER ( 0 .. 2147483647 ),
                gsmSCF-Address
                                           [0] IMPLICIT OCTET STRING (
SIZE( 1 .. 20 ) ) ( SIZE( 1 .. 9 ) ),
                defaultCallHandling
                                          [1] IMPLICIT ENUMERATED {
                  continueCall (0),
                  releaseCall
                                (1),
                   ... },
                                           [2] IMPLICIT SEQUENCE {
                extensionContainer
                  privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ..
10 ) ) OF
                      SEQUENCE {
                                 MAP-EXTENSION .&extensionId ( {
                        extId
                          ...} ) ,
                        extType MAP-EXTENSION .&ExtensionType ( {
                          ... } { @extId } ) OPTIONAL } OPTIONAL ,
                   pcs-Extensions [1] IMPLICIT SEQUENCE {
                   ... } OPTIONAL,
                   ... } OPTIONAL,
                ...},
           extensionContainer SEOUENCE {
             privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                SEQUENCE {
                           MAP-EXTENSION .&extensionId ( {
                   extId
                     ...} ) ,
                   extType MAP-EXTENSION .&ExtensionType ( {
                     ...} { @extId } ) OPTIONAL} OPTIONAL,
             pcs-Extensions [1] IMPLICIT SEQUENCE {
               ... } OPTIONAL,
              ... } OPTIONAL,
```

```
camelCapabilityHandling [0] IMPLICIT INTEGER ( 1 .. 16 ) OPTIONAL,
        notificationToCSE [1] IMPLICIT NULL OPTIONAL, csiActive [2] IMPLICIT NULL OPTIONAL OPTIONAL, extensionContainer [1] IMPLICIT SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
              SEQUENCE {
                           MAP-EXTENSION .&extensionId ( {
                 extId
                    ...} ) ,
                 extType MAP-EXTENSION .&ExtensionType ( {
                    ...} { @extId } ) OPTIONAL} OPTIONAL,
           pcs-Extensions [1] IMPLICIT SEQUENCE {
             ... } OPTIONAL,
           ... } OPTIONAL,
        ss-CSI
                                        [2] IMPLICIT SEQUENCE {
           ss-CamelData SEQUENCE {
ss-EventList SEQUENCE (SIZE(1..10)) OF
                 OCTET STRING ( SIZE( 1 ) ),
              qsmSCF-Address OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1
.. 9 ) ),
              extensionContainer [0] IMPLICIT SEQUENCE {
                privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10
) ) OF
                    SEQUENCE {
                                 MAP-EXTENSION .&extensionId ( {
                       extId
                         ...} ) ,
                       extType MAP-EXTENSION .&ExtensionType ( {
                          ...} { @extid } ) OPTIONAL} OPTIONAL,
                 pcs-Extensions [1] IMPLICIT SEQUENCE {
                   ... } OPTIONAL,
                 ... } OPTIONAL,
            extensionContainer SEQUENCE {
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                 SEQUENCE {
                    extId MAP-EXTENSION .&extensionId ( {
                       ...} ) ,
                     extType MAP-EXTENSION .&ExtensionType ( {
                       ...} { @extId } ) OPTIONAL} OPTIONAL,
              pcs-Extensions [1] IMPLICIT SEQUENCE {
                ... } OPTIONAL,
              ... } OPTIONAL,
           notificationToCSE [0] IMPLICIT NULL OPTIONAL, csi-Active [1] IMPLICIT NULL OPTIONAL) OPTIONAL,
        o-BcsmCamelTDP-CriteriaList [4] IMPLICIT SEQUENCE ( SIZE( 1 .. 10
) ) OF
           SEOUENCE {
              o-BcsmTriggerDetectionPoint ENUMERATED {
                collectedInfo (2),
                 routeSelectFailure (4)},
              destinationNumberCriteria [0] IMPLICIT SEQUENCE {
                                             [0] IMPLICIT ENUMERATED {
                 matchType
                    inhibiting (0),
```

```
enabling (1)},
                                                [1] IMPLICIT SEOUENCE ( SIZE( 1
                  destinationNumberList
.. 10 ) ) OF
                    OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1 .. 9 ) )
OPTIONAL,
                  destinationNumberLengthList [2] IMPLICIT SEQUENCE ( SIZE( 1
.. 3 ) ) OF
                    INTEGER ( 1 .. 15 ) OPTIONAL,
                  ... } OPTIONAL,
               basicServiceCriteria
                                             [1] IMPLICIT SEQUENCE ( SIZE( 1 ..
5 ) ) OF
                  CHOICE {
                    ext-BearerService [2] IMPLICIT OCTET STRING ( SIZE( 1
.. 5 ) ),
                     ext-Teleservice
                                           [3] IMPLICIT OCTET STRING ( SIZE( 1
.. 5 ) ) } OPTIONAL,
                                             [2] IMPLICIT ENUMERATED {
               callTypeCriteria
                  forwarded (0),
notForwarded (1)}OPTIONAL,
                  forwarded
               o-CauseValueCriteria
                                              [3] IMPLICIT SEQUENCE ( SIZE( 1 ..
5 ) ) OF
                  OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
                  tensionContainer [4] IMPLICIT SEQUENCE {
privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10
               extensionContainer
) ) OF
                     SEQUENCE {
                                  MAP-EXTENSION .&extensionId ( {
                        extId
                           ...} ) ,
                        extType MAP-EXTENSION .&ExtensionType ( {
                            ...} { @extId } ) OPTIONAL} OPTIONAL,
                  pcs-Extensions [1] IMPLICIT SEQUENCE {
                    ... } OPTIONAL,
                  ... } OPTIONAL } OPTIONAL ,
                                         [3] IMPLICIT NULL OPTIONAL,
         tif-CSI
         m-CSI
                                         [5] IMPLICIT SEQUENCE {
            mobilityTriggers SEQUENCE (SIZE(1..10)) OF
              OCTET STRING ( SIZE( 1 ) ),
           serviceKey INTEGER ( 0 .. 2147483647 ), gsmSCF-Address [0] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) (
SIZE( 1 .. 9 )),
            extensionContainer [1] IMPLICIT SEQUENCE {
               privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                  SEQUENCE {
                     extId
                              MAP-EXTENSION .&extensionId ( {
                        ...} ) ,
                     extType MAP-EXTENSION .&ExtensionType ( {
                        ...} { @extId } ) OPTIONAL} OPTIONAL,
               pcs-Extensions [1] IMPLICIT SEQUENCE {
                 ... } OPTIONAL,
               ... } OPTIONAL,
            notificationToCSE [2] IMPLICIT NULL OPTIONAL, csi-Active [3] IMPLICIT NULL OPTIONAL, ... } OPTIONAL, ... } OPTIONAL, [6] IMPLICIT SECUEN
                                         [6] IMPLICIT SEQUENCE {
         mo-sms-CSI
            sms-CAMEL-TDP-DataList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
               SEQUENCE {
```

```
sms-TriggerDetectionPoint [0] IMPLICIT ENUMERATED {
                                         (1),
                    sms-CollectedInfo
                    sms-DeliveryRequest (2)},
                                            [1] IMPLICIT INTEGER ( 0 ..
                 serviceKey
2147483647),
                                           [2] IMPLICIT OCTET STRING ( SIZE(
                 gsmSCF-Address
                    EaultSMS-Handling [3] ContinueTransaction (0),
1 .. 20 ) ) ( SIZE( 1 .. 9 ) ),
                                           [3] IMPLICIT ENUMERATED {
                 defaultSMS-Handling
                    ... },
                 extensionContainer
                                           [4] IMPLICIT SEQUENCE {
                    privateExtensionList [0] IMPLICIT SEQUENCE (SIZE(1...
10 ) ) OF
                       SEQUENCE {
                                   MAP-EXTENSION .&extensionId ( \{
                          extId
                             ...} ) ,
                          extType MAP-EXTENSION .&ExtensionType ( {
                            ... } { @extid } ) OPTIONAL } OPTIONAL ,
                    pcs-Extensions [1] IMPLICIT SEQUENCE {
                      ... } OPTIONAL,
                    ... } OPTIONAL,
                 ... } OPTIONAL,
           camelCapabilityHandling [1] IMPLICIT INTEGER ( 1 .. 16 ) OPTIONAL, extensionContainer [2] IMPLICIT SEQUENCE {
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                 SEQUENCE {
                    extId
                             MAP-EXTENSION .&extensionId ( {
                       ...}),
                    extType MAP-EXTENSION .&ExtensionType ( {
                       ...} { @extId } ) OPTIONAL} OPTIONAL,
              pcs-Extensions [1] IMPLICIT SEQUENCE {
                ... } OPTIONAL,
              ... } OPTIONAL,
                                  [3] IMPLICIT NULL OPTIONAL,
           notificationToCSE
                                    [4] IMPLICIT NULL OPTIONAL,
           csi-Active
           CS1-ACLIVE
... } OPTIONAL,
                                    [7] IMPLICIT SEQUENCE {
        vt-CSI
           t-BcsmCamelTDPDataList SEQUENCE (SIZE(1..10)) OF
              SEQUENCE {
                 t-BcsmTriggerDetectionPoint ENUMERATED {
                   termAttemptAuthorized
                                           (12),
                    . . . ,
                                            (13),
                    tBusy
                 tNoAnswer
serviceKey
                                            (14) },
                                              INTEGER ( 0 .. 2147483647 ),
                 gsmSCF-Address
                                              [0] IMPLICIT OCTET STRING (
SIZE(1 .. 20)) (SIZE(1 .. 9)),
                                         [1] IMPLICIT ENUMERATED {
                 defaultCallHandling
                   continueCall (0), releaseCall (1),
                    ... },
                 extensionContainer
                                              [2] IMPLICIT SEQUENCE {
                    privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ..
10 ) ) OF
                       SEQUENCE {
                          extId MAP-EXTENSION .&extensionId ( {
```

```
...} ) ,
                         extType MAP-EXTENSION .&ExtensionType ( {
                            ...} { @extid } ) OPTIONAL} OPTIONAL,
                   pcs-Extensions [1] IMPLICIT SEQUENCE {
                     ... } OPTIONAL,
                    ... } OPTIONAL,
                 ... },
           extensionContainer SEQUENCE {
             privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                SEQUENCE {
                           MAP-EXTENSION .&extensionId ( \{
                   extId
                      ...} ) ,
                   extType MAP-EXTENSION .&ExtensionType ( {
                      ... } { @extId } ) OPTIONAL } OPTIONAL ,
                            [1] IMPLICIT SEQUENCE {
              pcs-Extensions
               ... } OPTIONAL,
              ... } OPTIONAL,
           {\tt camelCapabilityHandling} \quad \hbox{\tt [0] IMPLICIT INTEGER (1..16) OPTIONAL,}
           notificationToCSE [1] IMPLICIT NULL OPTIONAL, csi-Active [2] IMPLICIT NULL OPTIONAL} OPTIONAL,
        t-BCSM-CAMEL-TDP-CriteriaList [8] IMPLICIT SEQUENCE ( SIZE( 1 .. 10
) ) OF
           SEQUENCE {
             termAttemptAuthorized ( 12 ),
                ...,
                tBusy
                                        (13),
                tNoAnswer
                                       ( 14 ) },
             basicServiceCriteria
                                          [0] IMPLICIT SEQUENCE ( SIZE( 1
.. 5 ) ) OF
               CHOICE {
                  ext-BearerService [2] IMPLICIT OCTET STRING ( SIZE( 1
.. 5 ) ),
                  ext-Teleservice
                                      [3] IMPLICIT OCTET STRING ( SIZE( 1
.. 5 ) ) } OPTIONAL,
                                         [1] IMPLICIT SEQUENCE ( SIZE( 1
              t-CauseValueCriteria
.. 5 ) ) OF
               OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
              ... } OPTIONAL,
                                     [9] IMPLICIT SEQUENCE {
           dp-AnalysedInfoCriteriaList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10
) ) OF
             SEOUENCE {
                dialledNumber OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE(
1 .. 9 ) ),
                serviceKey INTEGER ( 0 .. 2147483647 ), gsmSCF-Address OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE(
1 .. 9 ) ),
                continueCall (0), releaseCall (1),
                   ... },
                privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ...
10 ) ) OF
                      SEQUENCE {
                         extId MAP-EXTENSION .&extensionId ( {
```

```
...} ) ,
                          extType MAP-EXTENSION .&ExtensionType ( {
                             ...} { @extId } ) OPTIONAL} OPTIONAL,
                    pcs-Extensions [1] IMPLICIT SEQUENCE {
                     ... } OPTIONAL,
                    ... } OPTIONAL,
                 ... } OPTIONAL,
                                       [1] IMPLICIT INTEGER ( 1 .. 16 )
           camelCapabilityHandling
OPTIONAL,
           extensionContainer
                                        [2] IMPLICIT SEQUENCE {
             privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                 SEQUENCE { extId MAP-EXTENSION .&extensionId ( {
                       ...} ) ,
                    extType MAP-EXTENSION .&ExtensionType ( {
              ...} { @extId } ) OPTIONAL} OPTIONAL,
pcs-Extensions [1] IMPLICIT SEQUENCE {
                ... } OPTIONAL,
              ... } OPTIONAL,
                                     [3] IMPLICIT NULL OPTIONAL,
           notificationToCSE
           csi-Active
                                        [4] IMPLICIT NULL OPTIONAL,
           ... } OPTIONAL,
        mt-sms-CSI
                                       [10] IMPLICIT SEQUENCE {
           sms-CAMEL-TDP-DataList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
              SEQUENCE {
                 sms-TriggerDetectionPoint [0] IMPLICIT ENUMERATED {
                   sms-CollectedInfo (1),
                    sms-DeliveryRequest (2)},
                                            [1] IMPLICIT INTEGER ( 0 ..
                 serviceKey
2147483647),
                                           [2] IMPLICIT OCTET STRING ( SIZE(
                 gsmSCF-Address
1 .. 20 ) ) ( SIZE( 1 .. 9 ) ),
                 ... },
                 extensionContainer [4] IMPLICIT SEQUENCE {
                    privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ...
10 ) ) OF
                       SEQUENCE { extid MAP-EXTENSION .&extensionId ( {
                            ...} ) ,
                          extType MAP-EXTENSION .&ExtensionType ( {
                            ...} { @extid } ) OPTIONAL} OPTIONAL,
                    pcs-Extensions [1] IMPLICIT SEQUENCE {
                      ... } OPTIONAL,
                    ... } OPTIONAL,
                 ... } OPTIONAL,
           camelCapabilityHandling [1] IMPLICIT INTEGER ( 1 .. 16 ) OPTIONAL,
extensionContainer [2] IMPLICIT SEQUENCE {
           extensionContainer [2] IMPLICIT SEQUENCE {
  privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                 SEQUENCE {
                    extId MAP-EXTENSION .&extensionId ( {
```

```
...}),
                      extType MAP-EXTENSION .&ExtensionType ( {
                         ...} { @extid } ) OPTIONAL} OPTIONAL,
               pcs-Extensions [1] IMPLICIT SEQUENCE {
                ... } OPTIONAL,
            ... } OPTIONAL,
notificationToCSE [3] IMPLICIT NULL OPTIONAL,
            csi-Active
... } OPTIONAL,
                                       [4] IMPLICIT NULL OPTIONAL,
         mt-smsCAMELTDP-CriteriaList [11] IMPLICIT SEQUENCE ( SIZE( 1 .. 10
) ) OF
            SEQUENCE {
               sms-TriggerDetectionPoint ENUMERATED {
   sms-CollectedInfo (1),
                  . . . ,
               sms-DeliveryRequest (2)},
tpdu-TypeCriterion [0] IM:
                                          [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 5
) ) OF
                  ENUMERATED {
                     sms-DELIVER ( 0 ),
sms-SUBMIT-REPORT ( 1 ),
sms-STATUS-REPORT ( 2 ),
                    sms-DELIVER
                     ... } OPTIONAL,
               ... } OPTIONAL } OPTIONAL ,
         tensionContainer [14] IMPLICIT SEQUENCE { privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
      extensionContainer
            SEQUENCE {
               extId
                         MAP-EXTENSION .&extensionId ( {
                 ...} ) ,
               extType MAP-EXTENSION .&ExtensionType ( {
                  ...} { @extid } ) OPTIONAL} OPTIONAL,
         pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
         ... } OPTIONAL,
      naea-PreferredCI
                                                         [15] IMPLICIT SEQUENCE {
         naea-PreferredCIC [0] IMPLICIT OCTET STRING ( SIZE( 3 ) ),
extensionContainer [1] IMPLICIT SEQUENCE {
            privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
               SEQUENCE {
                  extId
                             MAP-EXTENSION .&extensionId ( {
                     ...} ) ,
                  extType MAP-EXTENSION .&ExtensionType ( {
                     ...} { @extId } ) OPTIONAL} OPTIONAL,
            pcs-Extensions [1] IMPLICIT SEQUENCE {
               ... } OPTIONAL,
             ... } OPTIONAL,
         ... } OPTIONAL,
                                                        [16] IMPLICIT SEQUENCE {
      gprsSubscriptionData
         completeDataListIncluded NULL OPTIONAL,
                                    [1] IMPLICIT SEQUENCE ( SIZE( 1 .. 50 ) )
         gprsDataList
OF
            SEQUENCE {
               pdp-ContextId
                                             INTEGER ( 1 .. 50 ),
                                              [16] IMPLICIT OCTET STRING ( SIZE(
               pdp-Type
2)),
```

```
[17] IMPLICIT OCTET STRING ( SIZE(
              pdp-Address
1 .. 16 ) ) OPTIONAL,
                                          [18] IMPLICIT OCTET STRING ( SIZE(
              qos-Subscribed
3)),
              vplmnAddressAllowed
                                          [19] IMPLICIT NULL OPTIONAL,
                                           [20] IMPLICIT OCTET STRING ( SIZE(
              apn
2 .. 63 ) ),
              extensionContainer
                                          [21] IMPLICIT SEQUENCE {
                privateExtensionList [0] IMPLICIT SEQUENCE (SIZE(1..10
) ) OF
                    SEQUENCE {
                                MAP-EXTENSION .&extensionId ( {
                       extId
                         ...}),
                       extType MAP-EXTENSION .&ExtensionType ( {
                         ...} { @extId } ) OPTIONAL} OPTIONAL,
                                 [1] IMPLICIT SEQUENCE {
                 pcs-Extensions
                   ... } OPTIONAL,
                 ... } OPTIONAL,
                                          [0] IMPLICIT OCTET STRING ( SIZE( 1
              ext-QoS-Subscribed
.. 9 ) ) OPTIONAL,
              pdp-CharqingCharacteristics [1] IMPLICIT OCTET STRING ( SIZE( 2
) ) OPTIONAL,
              ext2-OoS-Subscribed
                                          [2] IMPLICIT OCTET STRING ( SIZE( 1
.. 3 ) ) OPTIONAL },
        extensionContainer [2] IMPLICIT SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
              SEQUENCE {
                 extId
                          MAP-EXTENSION .&extensionId ( {
                    ...}),
                 extType MAP-EXTENSION .&ExtensionType ( {
                    ...} { @extId } ) OPTIONAL} OPTIONAL,
           pcs-Extensions [1] IMPLICIT SEQUENCE {
             ... } OPTIONAL,
           ... } OPTIONAL,
        ... } OPTIONAL,
     roamingRestrictedInSgsnDueToUnsupportedFeature [23] IMPLICIT NULL
OPTIONAL,
                                                    [24] IMPLICIT ENUMERATED
     networkAccessMode
{
        bothMSCAndSGSN (0),
        onlyMSC (1),
        onlySGSN
                        (2),
        ... } OPTIONAL,
     lsaInformation
                                                    [25] IMPLICIT SEQUENCE {
        completeDataListIncluded NULL OPTIONAL,
        lsaOnlyAccessIndicator [1] IMPLICIT ENUMERATED {
           accessOutsideLSAsAllowed (0),
accessOutsideLSAsRestricted (1) } OPTIONAL,
        lsaDataList
                                 [2] IMPLICIT SEQUENCE ( SIZE( 1 .. 20 ) )
OF
           SEQUENCE {
              lsaIdentity
lsaAttributes
                                     [0] IMPLICIT OCTET STRING ( SIZE( 3 ) ),
              lsaIdentity
                                     [1] IMPLICIT OCTET STRING ( SIZE( 1 ) ),
              lsaActiveModeIndicator [2] IMPLICIT NULL OPTIONAL,
              extensionContainer [3] IMPLICIT SEQUENCE {
                privateExtensionList [0] IMPLICIT SEQUENCE (SIZE(1.. 10
) ) OF
                    SEQUENCE {
```

```
extId MAP-EXTENSION .&extensionId ( {
                          ...} ) ,
                       extType MAP-EXTENSION .&ExtensionType ( {
                          ...} { @extid } ) OPTIONAL} OPTIONAL,
                 pcs-Extensions [1] IMPLICIT SEQUENCE {
                   ... } OPTIONAL,
                  ... } OPTIONAL,
        ... } OPTIONAL, extensionContainer [3] IMPLICIT SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
              SEQUENCE {
                           MAP-EXTENSION .&extensionId ( \{
                 extId
                    ...} ) ,
                 extType MAP-EXTENSION .&ExtensionType ( {
                    ... } { @extId } ) OPTIONAL } OPTIONAL ,
           pcs-Extensions [1] IMPLICIT SEQUENCE {
              ... } OPTIONAL,
            ... } OPTIONAL,
         ... } OPTIONAL,
     lmu-Indicator
                                                      [21] IMPLICIT NULL
OPTIONAL,
     lcsInformation
                                                      [22] IMPLICIT SEQUENCE {
        gmlc-List
                                      [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 5 )
) OF
           OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
        lcs-PrivacyExceptionList [1] IMPLICIT SEQUENCE ( SIZE( 1 .. 4 )
) OF
           SEQUENCE {
              ss-Code
                                      OCTET STRING ( SIZE( 1 ) ),
              ss-Status
                                     OCTET STRING ( SIZE( 1 .. 5 ) ),
              notificationToMSUser [0] IMPLICIT ENUMERATED {
                 notifyLocationAllowed
                                                                  (0),
                 notifyAndVerify-LocationAllowedIfNoResponse (1),
                 notifyAndVerify-LocationNotAllowedIfNoResponse (2),
                 locationNotAllowed
                                                                   (3)}
OPTIONAL,
              externalClientList [1] IMPLICIT SEQUENCE ( SIZE( 0 .. 5 )
) OF
                 SEQUENCE {
                   clientIdentity SEQUENCE {
   externalAddress [0] IMPLICIT OCTET STRING ( SIZE( 1
.. 20 ) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
                       extensionContainer [1] IMPLICIT SEQUENCE {
                         privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE(
1 .. 10 ) ) OF
                             SEQUENCE { extid MAP-EXTENSION .&extensionId ( {
                                  ...} ) ,
                                extType MAP-EXTENSION .&ExtensionType ( {
                          ...} { @extId } ) OPTIONAL} OPTIONAL,
pcs-Extensions [1] IMPLICIT SEQUENCE {
                            ... } OPTIONAL,
                           ... } OPTIONAL,
                    gmlc-Restriction [0] IMPLICIT ENUMERATED {
  gmlc-List ( 0 ),
```

```
home-Country (1),
                       ... } OPTIONAL,
                    notificationToMSUser [1] IMPLICIT ENUMERATED {
                                                                        (0),
                       notifyLocationAllowed
                                                                        (1),
                       notifyAndVerify-LocationAllowedIfNoResponse
                       notifyAndVerify-LocationNotAllowedIfNoResponse
                                                                        (2),
                       locationNotAllowed
                                                                        (3)
} OPTIONAL,
                    extensionContainer [2] IMPLICIT SEQUENCE {
                       privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1
.. 10 ) ) OF
                          SEQUENCE {
                                      MAP-EXTENSION .&extensionId ( \{
                             extId
                                ...} ) ,
                             extType MAP-EXTENSION .&ExtensionType ( {
                                ...} { @extId } ) OPTIONAL} OPTIONAL, nsions [1] IMPLICIT SEQUENCE {
                       pcs-Extensions
                         ... } OPTIONAL,
                       ... } OPTIONAL,
                    ... } OPTIONAL,
              plmnClientList
                                      [2] IMPLICIT SEQUENCE ( SIZE( 1 .. 5 )
) OF
                 ENUMERATED {
                   broadcastService
                                                (0),
                    o-andM-HPLMN
                                                 (1),
                    o-andM-VPLMN
                                                (2),
                    anonymousLocation
                                                (3),
                    targetMSsubscribedService (4),
                    ... } OPTIONAL,
                 tensionContainer [3] IMPLICIT SEQUENCE {
  privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10
              extensionContainer
) ) OF
                    SEQUENCE {
                                MAP-EXTENSION .&extensionId ( {
                       extId
                          ...} ) ,
                       extType MAP-EXTENSION .&ExtensionType ( {
                          ...} { @extId } ) OPTIONAL} OPTIONAL,
                 pcs-Extensions [1] IMPLICIT SEQUENCE {
                   ... } OPTIONAL,
                 ... } OPTIONAL,
              ext-externalClientList [4] IMPLICIT SEQUENCE ( SIZE( 1 .. 35 )
) OF
                 SEQUENCE {
                    clientIdentity SEQUENCE {
    externalAddress [0] IMPLIO
                                           [0] IMPLICIT OCTET STRING ( SIZE( 1
.. 20 ) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
                       extensionContainer [1] IMPLICIT SEQUENCE {
                          privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE(
1 .. 10 ) ) OF
                             SEQUENCE {
                                         MAP-EXTENSION .&extensionId ( {
                                extId
                                  ...} ) ,
                                extType MAP-EXTENSION .&ExtensionType ( {
                                   ...} { @extId } ) OPTIONAL} OPTIONAL,
                          pcs-Extensions [1] IMPLICIT SEQUENCE {
```

```
... } OPTIONAL,
                             ... } OPTIONAL,
                          ... },
                       gmlc-Restriction [0] IMPLICIT ENUMERATED {
  gmlc-List (0),
  home-Country (1),
                          ... } OPTIONAL,
                       notificationToMSUser [1] IMPLICIT ENUMERATED {
                          notifyLocationAllowed
                                                                                 (0),
                          notifyAndVerify-LocationAllowedIfNoResponse (1),
notifyAndVerify-LocationNotAllowedIfNoResponse (2),
                          notifyAndVerify-LocationAllowedIfNoResponse
                                                                                 (1),
                          locationNotAllowed
                                                                                 (3)
} OPTIONAL,
                       extensionContainer [2] IMPLICIT SEQUENCE {
                          privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1
.. 10 ) ) OF
                             SEQUENCE {
                                           MAP-EXTENSION .&extensionId ( {
                                extId
                                   ...} ) ,
                                 extType MAP-EXTENSION .&ExtensionType ( {
                                   ...} { @extid } ) OPTIONAL} OPTIONAL,
                          pcs-Extensions [1] IMPLICIT SEQUENCE {
                          ... } OPTIONAL,
... } OPTIONAL,
                       ... } OPTIONAL,
                serviceTypeList
                                           [5] IMPLICIT SEQUENCE ( SIZE( 1 .. 32 )
) OF
                   SEQUENCE {
                       \begin{array}{lll} \mbox{serviceTypeIdentity} & \mbox{INTEGER ( 0 .. 127 ),} \\ \mbox{gmlc-Restriction} & \mbox{[0] IMPLICIT ENUMERATED } \end{array} \label{eq:energy}
                         gmlc-List (0),
home-Country (1),
                          ... } OPTIONAL,
                       notificationToMSUser [1] IMPLICIT ENUMERATED {
                          notifyLocationAllowed
                                                                                 (0),
                          notifyAndVerify-LocationAllowedIfNoResponse
                                                                               (1),
                          notifyAndVerify-LocationNotAllowedIfNoResponse
                                                                                (2),
                          locationNotAllowed
                                                                                 (3)
} OPTIONAL,
                       extensionContainer [2] IMPLICIT SEQUENCE {
                          privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1
.. 10 ) ) OF
                             SEQUENCE {
                                 extId
                                           MAP-EXTENSION .&extensionId ( {
                                   ...} ) ,
                                 extType MAP-EXTENSION .&ExtensionType ( {
                                   ...} { @extId } ) OPTIONAL} OPTIONAL,
                          pcs-Extensions [1] IMPLICIT SEQUENCE {
                            ... } OPTIONAL,
                          ... } OPTIONAL,
                       ... } OPTIONAL } OPTIONAL ,
                                           [2] IMPLICIT SEQUENCE ( SIZE( 1 .. 3 )
         molr-List
) OF
             SEQUENCE {
                                     OCTET STRING ( SIZE( 1 ) ),
               ss-Code
                ss-Code OCIET STRING (SIZE(1,,,, ss-Status OCTET STRING (SIZE(1...5)),
                extensionContainer [0] IMPLICIT SEQUENCE {
```

```
privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10
) ) OF
                   SEQUENCE {
                               MAP-EXTENSION .&extensionId ( {
                      extId
                         ...}),
                      extType MAP-EXTENSION .&ExtensionType ( {
                         ...} { @extId } ) OPTIONAL} OPTIONAL,
                 pcs-Extensions [1] IMPLICIT SEQUENCE {
                   ... } OPTIONAL,
                 ... } OPTIONAL,
              ... } OPTIONAL,
        add-lcs-PrivacyExceptionList [3] IMPLICIT SEQUENCE ( SIZE( 1 .. 4 )
) OF
           SEQUENCE {
             ss-Code
              ss-Code
ss-Status
                                     OCTET STRING ( SIZE( 1 ) ),
                                     OCTET STRING ( SIZE( 1 .. 5 ) ),
              notificationToMSUser
                                    [0] IMPLICIT ENUMERATED {
                notifyLocationAllowed
                                                                (0),
                notifyAndVerify-LocationAllowedIfNoResponse
                                                              (1),
                notifyAndVerify-LocationNotAllowedIfNoResponse
                locationNotAllowed
                                                                (3)}
OPTIONAL,
              externalClientList [1] IMPLICIT SEQUENCE ( SIZE( 0 .. 5 )
) OF
                SEQUENCE {
                   clientIdentity SEQUENCE {
                      externalAddress [0] IMPLICIT OCTET STRING ( SIZE( 1
.. 20 ) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
                      extensionContainer [1] IMPLICIT SEQUENCE {
                         privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE(
1 .. 10 ) ) OF
                            SEQUENCE {
                                       MAP-EXTENSION .&extensionId ( {
                               extId
                                 ...} ) ,
                               extType MAP-EXTENSION .&ExtensionType ( {
                                 ...} { @extId } ) OPTIONAL} OPTIONAL,
                         pcs-Extensions [1] IMPLICIT SEQUENCE {
                          ... } OPTIONAL,
                         ... } OPTIONAL,
                      ... },
                   gmlc-Restriction [0] IMPLICIT ENUMERATED {
                      gmlc-List (0),
home-Country (1),
                      ... } OPTIONAL,
                   notificationToMSUser [1] IMPLICIT ENUMERATED {
                                                                     (0),
                      notifyLocationAllowed
                                                                    (1),
                      notifyAndVerify-LocationAllowedIfNoResponse
                      notifyAndVerify-LocationNotAllowedIfNoResponse (2),
                      . . . ,
                      locationNotAllowed
                                                                     (3)
} OPTIONAL,
                   extensionContainer [2] IMPLICIT SEQUENCE {
                      privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1
.. 10 ) ) OF
                         SEQUENCE {
                            extId MAP-EXTENSION .&extensionId ( {
```

```
...} ) ,
                              extType MAP-EXTENSION .&ExtensionType ( {
                                 ...} { @extid } ) OPTIONAL} OPTIONAL,
                        pcs-Extensions [1] IMPLICIT SEQUENCE {
                         ... } OPTIONAL,
                          .. } OPTIONAL,
                     ... } OPTIONAL,
               plmnClientList
                                       [2] IMPLICIT SEQUENCE ( SIZE( 1 .. 5 )
) OF
                  ENUMERATED {
                    broadcastService
                                                   (0),
                     o-andM-HPLMN
                                                   (1),
                                                   (2),
                     anonymousLocation
                     o-andM-VPLMN
                     targetMSsubscribedService (4),
                     ... } OPTIONAL,
                  tensionContainer [3] IMPLICIT SEQUENCE {
  privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10
               extensionContainer
) ) OF
                     SEQUENCE { extid MAP-EXTENSION .&extensionId ( {
                           ...}),
                        extType MAP-EXTENSION .&ExtensionType ( {
                          ...} { @extId } ) OPTIONAL} OPTIONAL,
                  pcs-Extensions [1] IMPLICIT SEQUENCE {
                   ... } OPTIONAL,
                  ... } OPTIONAL,
               ext-externalClientList [4] IMPLICIT SEQUENCE ( SIZE( 1 .. 35 )
) OF
                  SEQUENCE {
                    clientIdentity SEQUENCE {
    externalAddress [0] IMPLIC
                                             [0] IMPLICIT OCTET STRING ( SIZE( 1
.. 20 ) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
                       extensionContainer [1] IMPLICIT SEQUENCE {
                          privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE(
1 .. 10 ) ) OF
                              SEQUENCE { extid MAP-EXTENSION .&extensionId ( {
                                    ...} ) ,
                                  extType MAP-EXTENSION .&ExtensionType ( {
                                    ...} { @extId } ) OPTIONAL} OPTIONAL,
                           pcs-Extensions [1] IMPLICIT SEQUENCE {
                             ... } OPTIONAL,
                           ... } OPTIONAL,
                        ...},
                     gmlc-Restriction [0] IMPLICIT ENUMERATED {
gmlc-List (0),
home-Country (1),
                        ... } OPTIONAL,
                     notificationToMSUser [1] IMPLICIT ENUMERATED {
                                                                          (0),
                        notifyLocationAllowed
                        notifyAndVerify-LocationAllowedIfNoResponse (1),
notifyAndVerify-LocationNotAllowedIfNoResponse (2),
                        . . . ,
                                                                          (3)
                        locationNotAllowed
} OPTIONAL,
                     extensionContainer [2] IMPLICIT SEQUENCE {
```

```
privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1
.. 10 ) ) OF
                          SEQUENCE {
                                      MAP-EXTENSION .&extensionId ( {
                             extId
                                ...}),
                             extType MAP-EXTENSION .&ExtensionType ( {
                                ...} { @extId } ) OPTIONAL} OPTIONAL,
                       pcs-Extensions [1] IMPLICIT SEQUENCE {
                         ... } OPTIONAL,
                         .. } OPTIONAL,
                     ... } OPTIONAL,
                                      [5] IMPLICIT SEQUENCE ( SIZE( 1 .. 32 )
              serviceTypeList
) OF
                 SEQUENCE {
                    serviceTypeIdentity INTEGER ( 0 .. 127 ),
gmlc-Restriction [0] IMPLICIT ENUMERATED {
gmlc-List ( 0 ),
                       gmlc-List (0), home-Country (1),
                       ... } OPTIONAL,
                    notificationToMSUser [1] IMPLICIT ENUMERATED {
                       notifyLocationAllowed
                                                                        (0),
                       notifyAndVerify-LocationNotAllowedIfNoResponse (1),
...,
                       locationNotAllowed
                                                                        (3)
} OPTIONAL,
                    extensionContainer [2] IMPLICIT SEQUENCE {
                       privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1
.. 10 ) ) OF
                          SEQUENCE {
                                      MAP-EXTENSION .&extensionId ( {
                             extId
                                ...} ) ,
                             extType MAP-EXTENSION .&ExtensionType ( {
                                ...} { @extId } ) OPTIONAL} OPTIONAL,
                       pcs-Extensions [1] IMPLICIT SEQUENCE {
                        ... } OPTIONAL,
                       ... } OPTIONAL,
                    ... } OPTIONAL } OPTIONAL ,
     istAlertTimer
                                                      [26] IMPLICIT INTEGER (
15 .. 255 ) OPTIONAL,
     superChargerSupportedInHLR
                                                      [27] IMPLICIT OCTET
STRING ( SIZE( 1 .. 6 ) ) OPTIONAL,
                                                      [28] IMPLICIT SEQUENCE {
     mc-SS-Info
                             [0] IMPLICIT OCTET STRING ( SIZE( 1 ) ),
        ss-Code
                             [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 5 ) ),
        ss-Status
        nbrSB
                             [2] IMPLICIT INTEGER ( 2 .. 7 ),
                             [3] IMPLICIT INTEGER (1 .. 7),
        extensionContainer [4] IMPLICIT SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
              SEQUENCE {
                          MAP-EXTENSION .&extensionId ( {
                 extType MAP-EXTENSION .&ExtensionType ( {
                    ...} { @extId } ) OPTIONAL} OPTIONAL,
           pcs-Extensions [1] IMPLICIT SEQUENCE {
             ... } OPTIONAL,
            ... } OPTIONAL,
```

```
... } OPTIONAL,
      cs-AllocationRetentionPriority
                                                       [29] IMPLICIT OCTET
STRING ( SIZE( 1 ) ) OPTIONAL,
                                                       [17] IMPLICIT SEQUENCE {
     sgsn-CAMEL-SubscriptionInfo
                                      [0] IMPLICIT SEQUENCE {
        gprs-CSI
            gprs-CamelTDPDataList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
               SEQUENCE {
                  gprs-TriggerDetectionPoint [0] IMPLICIT ENUMERATED {
                                                                 (1),
                    attach
                     attachChangeOfPosition
                                                                 (2),
                                                                 (11),
                     pdp-ContextEstablishment
                     pdp-ContextEstablishmentAcknowledgement
                                                                 (12),
                     pdp-ContextChangeOfPosition
                                               [1] IMPLICIT INTEGER ( 0 ..
                  serviceKey
2147483647),
                                               [2] IMPLICIT OCTET STRING ( SIZE(
                  gsmSCF-Address
1 .. 20 ) ) ( SIZE( 1 .. 9 ) ),
                  defaultSessionHandling [3]
continueTransaction (0),
releaseTransaction (1),
                                              [3] IMPLICIT ENUMERATED {
                     ... },
                                              [4] IMPLICIT SEQUENCE {
                  extensionContainer
                     privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ...
10 ) ) OF
                        SEQUENCE { extid MAP-EXTENSION .&extensionId ( {
                             ...} ) ,
                           extType MAP-EXTENSION .&ExtensionType ( {
                              ...} { @extId } ) OPTIONAL} OPTIONAL,
                     pcs-Extensions [1] IMPLICIT SEQUENCE {
                       ... } OPTIONAL,
                     ... } OPTIONAL,
                  ... } OPTIONAL,
            camelCapabilityHandling [1] IMPLICIT INTEGER ( 1 .. 16 ) OPTIONAL,
            extensionContainer [2] IMPLICIT SEQUENCE {
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                  SEQUENCE {
                              MAP-EXTENSION .&extensionId ( {
                     extId
                        ...} ) ,
                     extType MAP-EXTENSION .&ExtensionType ( {
                        ... } { @extId } ) OPTIONAL } OPTIONAL ,
               pcs-Extensions
                                     [1] IMPLICIT SEQUENCE {
                 ... } OPTIONAL,
               ... } OPTIONAL,
            notificationToCSE [3] IMPLICIT NULL OPTIONAL, csi-Active [4] IMPLICIT NULL OPTIONAL, ... } OPTIONAL, [1] IMPLICIT SEQUENCE {
         mo-sms-CSI
                                      [1] IMPLICIT SEQUENCE {
            sms-CAMEL-TDP-DataList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
               SEQUENCE {
                  sms-TriggerDetectionPoint [0] IMPLICIT ENUMERATED {
                    sms-CollectedInfo (1),
                     sms-DeliveryRequest (2)},
```

```
[1] IMPLICIT INTEGER ( 0 ...
                   serviceKey
2147483647),
                   gsmSCF-Address
                                                 [2] IMPLICIT OCTET STRING ( SIZE(
                   defaultSMS-Handling [3] I continueTransaction (0),
1 .. 20 ) ) ( SIZE( 1 .. 9 ) ),
                                                 [3] IMPLICIT ENUMERATED {
                      ... },
                   extensionContainer
                                                [4] IMPLICIT SEQUENCE {
                     privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ...
10 ) ) OF
                          SEQUENCE { extId MAP-EXTENSION .&extensionId ( {
                                ...} ) ,
                             extType MAP-EXTENSION .&ExtensionType ( {
                                ...} { @extid } ) OPTIONAL} OPTIONAL,
                       pcs-Extensions [1] IMPLICIT SEQUENCE {
                        ... } OPTIONAL,
                       ... } OPTIONAL,
                   ... } OPTIONAL,
             camelCapabilityHandling [1] IMPLICIT INTEGER ( 1 .. 16 ) OPTIONAL, extensionContainer [2] IMPLICIT SEQUENCE {
   privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                   SEQUENCE {
                                MAP-EXTENSION .&extensionId ( {
                      extId
                         ...} ) ,
                       extType MAP-EXTENSION .&ExtensionType ( {
                         ...} { @extid } ) OPTIONAL} OPTIONAL,
                pcs-Extensions [1] IMPLICIT SEQUENCE {
                 ... } OPTIONAL,
                ... } OPTIONAL,
         notificationToCSE [3] IMPLICIT NULL OPTIONAL, csi-Active [4] IMPLICIT NULL OPTIONAL, ... } OPTIONAL, extensionContainer [2] IMPLICIT SEQUENCE {
             privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
                SEQUENCE {
                              MAP-EXTENSION .&extensionId ( {
                   extId
                      ...} ) ,
                   extType MAP-EXTENSION .&ExtensionType ( {
                      ...} { @extId } ) OPTIONAL} OPTIONAL,
             pcs-Extensions [1] IMPLICIT SEQUENCE {
               ... } OPTIONAL,
             ... } OPTIONAL,
                                         [3] IMPLICIT SEQUENCE {
             sms-CSI [3] IMPLICIT SEQUENCE {
sms-CAMEL-TDP-DataList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                SEOUENCE {
                   sms-TriggerDetectionPoint [0] IMPLICIT ENUMERATED {
                     sms-CollectedInfo (1),
                      sms-DeliveryRequest (2)},
                                                 [1] IMPLICIT INTEGER ( 0 ..
                   serviceKey
2147483647),
```

```
gsmSCF-Address
                                             [2] IMPLICIT OCTET STRING ( SIZE(
1 .. 20 ) ) ( SIZE( 1 .. 9 ) ),
                    FaultSMS-Handling (0), continueTransaction (1),
                  defaultSMS-Handling
                                             [3] IMPLICIT ENUMERATED {
                     ... },
                  extensionContainer
                                             [4] IMPLICIT SEQUENCE {
                    privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ..
10 ) ) OF
                        SEQUENCE {
                                    MAP-EXTENSION .&extensionId ( {
                          extId
                              ...}),
                           extType MAP-EXTENSION .&ExtensionType ( {
                             ...} { @extId } ) OPTIONAL} OPTIONAL,
                    pcs-Extensions [1] IMPLICIT SEQUENCE {
                       ... } OPTIONAL,
                     ... } OPTIONAL,
                  ... } OPTIONAL,
            camelCapabilityHandling [1] IMPLICIT INTEGER ( 1 .. 16 ) OPTIONAL, extensionContainer [2] IMPLICIT SEQUENCE {
            extensionContainer
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                  SEQUENCE {
                              MAP-EXTENSION .&extensionId ( {
                    extId
                       ...}),
                     extType MAP-EXTENSION .&ExtensionType ( {
                       ...} { @extid } ) OPTIONAL} OPTIONAL,
                              [1] IMPLICIT SEQUENCE {
               pcs-Extensions
                 ... } OPTIONAL,
               ... } OPTIONAL,
            notificationToCSE
                                     [3] IMPLICIT NULL OPTIONAL,
            csi-Active
                                     [4] IMPLICIT NULL OPTIONAL,
            ... } OPTIONAL,
        mt-smsCAMELTDP-CriteriaList [4] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 )
) OF
            SEQUENCE {
              sms-TriggerDetectionPoint ENUMERATED {
                sms-CollectedInfo
                                        (1),
                  sms-DeliveryRequest (2)},
                                         [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 5
               tpdu-TypeCriterion
) ) OF
                  ENUMERATED {
                    sms-DELIVER
                    sms-DELIVER (0),
sms-SUBMIT-REPORT (1),
sms-STATUS-REPORT (2),
                    ... } OPTIONAL,
               ... } OPTIONAL,
                                      [5] IMPLICIT SEQUENCE {
            mobilityTriggers SEQUENCE (SIZE(1..10)) OF
              OCTET STRING ( SIZE( 1 ) ),
           serviceKey INTEGER ( 0 .. 2147483647 ),
gsmSCF-Address [0] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) (
SIZE( 1 .. 9 )),
           extensionContainer [1] IMPLICIT SEQUENCE {
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                  SEQUENCE {
                     extId MAP-EXTENSION .&extensionId ( {
```

```
...}),
                    extType MAP-EXTENSION .&ExtensionType ( {
                        ...} { @extId } ) OPTIONAL} OPTIONAL,
                               [1] IMPLICIT SEQUENCE {
              pcs-Extensions
                 ... } OPTIONAL,
               ... } OPTIONAL,
                              [2] IMPLICIT NULL OPTIONAL,
[3] IMPLICIT NULL OPTIONAL,
           notificationToCSE
           csi-Active
            ... } OPTIONAL } OPTIONAL ,
     chargingCharacteristics
                                                      [18] IMPLICIT OCTET
STRING ( SIZE( 2 ) ) OPTIONAL,
     accessRestrictionData
                                                      [19] IMPLICIT BIT STRING
{
        utranNotAllowed (0),
        geranNotAllowed (1 ) { ( SIZE( 2 .. 8 ) ) OPTIONAL}
  RESULT SEQUENCE {
                                    [1] IMPLICIT SEQUENCE ( SIZE( 1 .. 20 ) )
     teleserviceList
OF
        OCTET STRING ( SIZE( 1 .. 5 ) ) OPTIONAL,
                                    [2] IMPLICIT SEQUENCE ( SIZE( 1 .. 50 ) )
     bearerServiceList
OF
        OCTET STRING ( SIZE( 1 .. 5 ) ) OPTIONAL,
     ss-List
                                    [3] IMPLICIT SEQUENCE ( SIZE( 1 .. 30 ) )
OF
        OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
     odb-GeneralData
                                   [4] IMPLICIT BIT STRING {
        allog-CallsBarred (0),
         internationalOGCallsBarred (1),
        internationalOGCallsNotToHPLMN-CountryBarred (2),
         interzonalOGCallsBarred (6 ),
         interzonalOGCallsNotToHPLMN-CountryBarred (7),
         interzonalOGCallsAndInternationalOGCallsNotToHPLMN-CountryBarred (8),
        premiumRateInformationOGCallsBarred (3),
        premiumRateEntertainementOGCallsBarred (4 ),
        ss-AccessBarred (5),
        allECT-Barred (9),
        chargeableECT-Barred (10),
         internationalECT-Barred (11 ),
         interzonalECT-Barred (12 ),
        doublyChargeableECT-Barred (13 ),
        multipleECT-Barred (14),
        allPacketOrientedServicesBarred (15 ),
        roamerAccessToHPLMN-AP-Barred (16),
        roamerAccessToVPLMN-AP-Barred (17 ),
        roamingOutsidePLMNOG-CallsBarred (18),
        allIC-CallsBarred (19),
        roamingOutsidePLMNIC-CallsBarred (20),
        roamingOutsidePLMNICountryIC-CallsBarred (21),
        roamingOutsidePLMN-Barred (22),
        roamingOutsidePLMN-CountryBarred (23),
        registrationAllCF-Barred (24),
        registrationCFNotToHPLMN-Barred (25),
        registrationInterzonalCF-Barred (26),
        registrationInterzonalCFNotToHPLMN-Barred (27),
        registrationInternationalCF-Barred (28 )} ( SIZE( 15 .. 32 ) )
OPTIONAL,
      regionalSubscriptionResponse [5] IMPLICIT ENUMERATED {
                                   ( 0 ),
        networkNode-AreaRestricted
        tooManyZoneCodes
zoneCodesConflict
                                      (1),
                                      (2),
        regionalSubscNotSupported (3)} OPTIONAL,
```

```
[6] IMPLICIT BIT STRING {
     supportedCamelPhases
        phase1 (0),
        phase2 (1),
        phase3 (2),
        phase4 (3 )} ( SIZE( 1 .. 16 ) ) OPTIONAL,
                                   [7] IMPLICIT SEQUENCE {
      extensionContainer
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                        MAP-EXTENSION .&extensionId ( {
              extId
                  ...}),
              extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extid } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
         ... } OPTIONAL,
                           [8] IMPLICIT BIT STRING {
     offeredCamel4CSIs
        o-csi (0),
        d-csi (1),
vt-csi (2),
        t-csi (3),
        mt-sms-csi (4),
        mg-csi (5),
        psi-enhancements (6 ) } ( SIZE( 7 .. 16 ) ) OPTIONAL }
  ERRORS {
     dataMissing |
     unexpectedDataValue |
     unidentifiedSubscriber }
  CODE local : 7
deleteSubscriberData OPERATION ::= {
  ARGUMENT SEQUENCE {
    imsi
                                                       [0] IMPLICIT OCTET
STRING ( SIZE( 3 .. 8 ) ),
    basicServiceList
                                                       [1] IMPLICIT SEQUENCE (
SIZE( 1 .. 70 ) ) OF
        CHOICE {
          ext-BearerService [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 5 ) ), ext-Teleservice [3] IMPLICIT OCTET STRING ( SIZE( 1 .. 5 ) )}
OPTIONAL,
     ss-List
                                                       [2] IMPLICIT SEQUENCE (
SIZE( 1 .. 30 ) ) OF
        OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
     roamingRestrictionDueToUnsupportedFeature [4] IMPLICIT NULL
OPTIONAL,
     regionalSubscriptionIdentifier
                                                       [5] IMPLICIT OCTET
STRING ( SIZE( 2 ) ) OPTIONAL,
     vbsGroupIndication
                                                       [7] IMPLICIT NULL
OPTIONAL,
     vgcsGroupIndication
                                                       [8] IMPLICIT NULL
OPTIONAL.
                                                       [9] IMPLICIT NULL
     camelSubscriptionInfoWithdraw
OPTIONAL,
     extensionContainer
                                                       [6] IMPLICIT SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
              extId MAP-EXTENSION .&extensionId ( {
                 ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
```

```
...} { @extId } ) OPTIONAL} OPTIONAL,
        \verb"pcs-Extensions" [1] IMPLICIT SEQUENCE" \{
          ... } OPTIONAL,
         ... } OPTIONAL,
      gprsSubscriptionDataWithdraw
                                                        [10] CHOICE {
        allGPRSData NULL,
contextIdList SEQUENCE (SIZE(1..50)) OF
INTEGER (1..50)} OPTIONAL,
      roamingRestrictedInSgsnDueToUnsuppportedFeature [11] IMPLICIT NULL
OPTIONAL,
     lsaInformationWithdraw
                                                        [12] CHOICE {
        allLSAData NULL, lsaIdentityList SEQUENCE (SIZE(1..20)) OF
           OCTET STRING ( SIZE( 3 ) ) } OPTIONAL,
      qmlc-ListWithdraw
                                                        [13] IMPLICIT NULL
OPTIONAL,
     istInformationWithdraw
                                                        [14] IMPLICIT NULL
OPTIONAL,
                                                        [15] IMPLICIT BIT STRING
     specificCSI-Withdraw
{
        o-csi (0 ),
        ss-csi (1),
tif-csi (2),
        d-csi (3),
vt-csi (4),
        mo-sms-csi (5),
        m-csi (6),
        gprs-csi (7),
         t-csi (8),
        mt-sms-csi (9),
        mg-csi (10),
        o-IM-CSI (11 ),
         d-IM-CSI (12),
        vt-IM-CSI (13 )} ( SIZE( 8 .. 32 ) ) OPTIONAL,
      chargingCharacteristicsWithdraw
                                                       [16] IMPLICIT NULL
OPTIONAL }
  RESULT
            SEQUENCE {
      regionalSubscriptionResponse [0] IMPLICIT ENUMERATED {
        networkNode-AreaRestricted ( 0 ),
        tooManyZoneCodes
zoneCodesConflict
                                     (1),
                                     (2),
        regionalSubscNotSupported (3) OPTIONAL,
      extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
            SEQUENCE {
               extId \texttt{MAP-EXTENSION} . &extensionId ( \{
                 ...} ) ,
               extType MAP-EXTENSION .&ExtensionType ( {
                  ...} { @extId } ) OPTIONAL} OPTIONAL,
         pcs-Extensions [1] IMPLICIT SEQUENCE {
           ... } OPTIONAL,
         ... } OPTIONAL,
   ERRORS
      dataMissing |
      unexpectedDataValue |
     unidentifiedSubscriber }
   CODE local : 8
```

```
reset OPERATION ::= {
  ARGUMENT SEQUENCE {
     hlr-Number OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1 .. 9 ) ), hlr-List SEQUENCE ( SIZE( 1 .. 50 ) ) OF
       OCTET STRING ( SIZE( 3 .. 8 ) ) OPTIONAL,
      ...}
          local
   CODE
                    : 37
   }
forwardCheckSS-Indication OPERATION ::= {
  CODE local : 38
   }
restoreData OPERATION ::= {
   ARGUMENT SEQUENCE {
                          OCTET STRING ( SIZE( 3 .. 8 ) ),
      imsi
                          OCTET STRING ( SIZE( 4 ) ) OPTIONAL,
      lmsi
      extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
            SEQUENCE {
                        MAP-EXTENSION .&extensionId ( {
               extId
                 ...} ) ,
               extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extId } ) OPTIONAL} OPTIONAL,
         pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
         ... } OPTIONAL,
      vlr-Capability [6] IMPLICIT SEQUENCE {
         supportedCamelPhases
                                                      [0] IMPLICIT BIT STRING {
           phase1 (0),
           phase2 (1),
           phase3 (2),
           phase4 (3) } ( SIZE( 1 .. 16 ) ) OPTIONAL,
                                                       SEQUENCE {
         extensionContainer
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
              SEQUENCE {
                  ext.Td
                           MAP-EXTENSION .&extensionId ( {
                     ...} ) ,
                  extType MAP-EXTENSION .&ExtensionType ( {
                     ... } { @extId } ) OPTIONAL } OPTIONAL ,
            pcs-Extensions [1] IMPLICIT SEQUENCE {
             ... } OPTIONAL,
            ... } OPTIONAL,
         solsaSupportIndicator
                                                       [2] IMPLICIT NULL
OPTIONAL,
                                                      [1] IMPLICIT ENUMERATED {
         istSupportIndicator
           basicISTSupported ( 0 ), istCommandSupported ( 1 ),
           ... } OPTIONAL,
         superChargerSupportedInServingNetworkEntity [3] CHOICE {
           sendSubscriberData [0] IMPLICIT NULL, subscriberDataStored [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 6 )
) } OPTIONAL,
         longFTN-Supported
                                                       [4] IMPLICIT NULL
OPTIONAL,
         supportedLCS-CapabilitySets
                                                       [5] IMPLICIT BIT STRING {
```

```
lcsCapabilitySet1 (0),
           lcsCapabilitySet2 (1 ),
           lcsCapabilitySet3 (2),
           lcsCapabilitySet4 (3)} (SIZE(2..16)) OPTIONAL,
                                                   [6] IMPLICIT BIT STRING {
        offeredCamel4CSIs
           o-csi (0),
           d-csi (1),
           vt-csi (2),
           t-csi (3),
           mt-sms-csi (4),
           mg-csi (5),
           psi-enhancements (6)} (SIZE(7..16)) OPTIONAL} OPTIONAL}
  RESULT
           SEQUENCE {
                         OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1 .. 9 ) ),
     hlr-Number
     msNotReachable
                         NULL OPTIONAL,
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                        MAP-EXTENSION .&extensionId ( {
              extId
                 ...}),
              extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extid } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL,
  ERRORS
     systemFailure |
     dataMissing
     unexpectedDataValue |
     unknownSubscriber }
  CODE local : 57
sendRoutingInfoForGprs OPERATION ::= {
  ARGUMENT SEQUENCE {
     imsi
                         [0] IMPLICIT OCTET STRING ( SIZE( 3 .. 8 ) ),
     ggsn-Address
                        [1] IMPLICIT OCTET STRING ( SIZE( 5 .. 17 ) )
OPTIONAL,
     ggsn-Number
                        [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE(
1 .. 9 ) ),
     extensionContainer [3] IMPLICIT SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                        MAP-EXTENSION .&extensionId ( {
                 ...}),
              extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extid } ) OPTIONAL} OPTIONAL,
                             [1] IMPLICIT SEQUENCE {
        pcs-Extensions
           ... } OPTIONAL,
        ... } OPTIONAL,
  RESULT
           SEQUENCE {
                               [0] IMPLICIT OCTET STRING ( SIZE( 5 .. 17 ) ),
     sgsn-Address
                               [1] IMPLICIT OCTET STRING ( SIZE( 5 .. 17 ) )
     ggsn-Address
OPTIONAL,
     mobileNotReachableReason [2] IMPLICIT INTEGER ( 0 .. 255 ) OPTIONAL,
                               [3] IMPLICIT SEQUENCE {
     extensionContainer
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
```

```
SEQUENCE {
                      MAP-EXTENSION .&extensionId ( {
             extId
                ...}),
             extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
         ... } OPTIONAL,
        ... } OPTIONAL,
     ...}
  ERRORS
           {
    absentSubscriber
     systemFailure |
     dataMissing |
     unexpectedDataValue |
     unknownSubscriber |
     callBarred }
  CODE local
failureReport OPERATION ::= {
  ARGUMENT SEQUENCE {
     imsi
                        [0] IMPLICIT OCTET STRING ( SIZE( 3 .. 8 ) ),
     ggsn-Number
                       [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE(
1 .. 9 ) ),
    ggsn-Address
                       [2] IMPLICIT OCTET STRING ( SIZE( 5 .. 17 ) )
OPTIONAL,
     extensionContainer [3] IMPLICIT SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
          SEQUENCE {
             extId
                     MAP-EXTENSION .&extensionId ( {
               ...} ) ,
             extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
         ... } OPTIONAL,
        ... } OPTIONAL,
  RESULT SEQUENCE {
                       [0] IMPLICIT OCTET STRING ( SIZE( 5 .. 17 ) )
     ggsn-Address
OPTIONAL,
     extensionContainer [1] IMPLICIT SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
             extId MAP-EXTENSION .&extensionId ( {
               ...} ) ,
             extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extid } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL,
  ERRORS
     systemFailure |
     dataMissing
     unexpectedDataValue |
     unknownSubscriber }
  CODE local : 25
```

```
}
noteMsPresentForGprs OPERATION ::= {
  ARGUMENT SEQUENCE {
     imsi [0] IMPLICIT OCTET STRING ( SIZE( 3 .. 8 ) ), sgsn-Address [1] IMPLICIT OCTET STRING ( SIZE( 5 .. 17 ) ), ggsn-Address [2] IMPLICIT OCTET STRING ( SIZE( 5 .. 17 ) )
                          [0] IMPLICIT OCTET STRING ( SIZE( 3 .. 8 ) ),
OPTIONAL,
     extensionContainer [3] IMPLICIT SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                       MAP-EXTENSION .&extensionId ( {
              extId
                 ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extid } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL,
  RESULT
            SEQUENCE {
     extensionContainer [0] IMPLICIT SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                       MAP-EXTENSION .&extensionId ( {
              extId
                ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL,
  ERRORS
     systemFailure |
     dataMissing
     unexpectedDataValue |
     unknownSubscriber }
  CODE local : 26
   }
noteMM-Event OPERATION ::= {
  ARGUMENT SEQUENCE {
     serviceKey
                                   INTEGER ( 0 .. 2147483647 ),
     eventMet
                                   [0] IMPLICIT OCTET STRING ( SIZE( 1 ) ),
     imsi
                                    [1] IMPLICIT OCTET STRING ( SIZE( 3 .. 8 )
),
     msisdn
                                   [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 )
) (SIZE(1..9)),
     [0] IMPLICIT OCTET STRING ( SIZE( 8
) ) OPTIONAL,
                                         [1] IMPLICIT OCTET STRING ( SIZE( 1
        vlr-number
.. 20 ) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
                                         [2] IMPLICIT OCTET STRING ( SIZE( 2
        locationNumber
.. 10 ) ) OPTIONAL,
        cellGlobalIdOrServiceAreaIdOrLAI [3] CHOICE {
           cellGlobalIdOrServiceAreaIdFixedLength [0] IMPLICIT OCTET STRING
( SIZE( 7 ) ),
```

```
[1] IMPLICIT OCTET STRING
          laiFixedLength
(SIZE(5))} OPTIONAL,
        extensionContainer
                                [4] IMPLICIT SEQUENCE {
          privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
             SEQUENCE {
                         MAP-EXTENSION .&extensionId ( {
                extId
                   ...} ) ,
                extType MAP-EXTENSION .&ExtensionType ( {
                   ...} { @extId } ) OPTIONAL} OPTIONAL,
           pcs-Extensions [1] IMPLICIT SEQUENCE {
            ... } OPTIONAL,
          ... } OPTIONAL,
        selectedLSA-Id
                                        [5] IMPLICIT OCTET STRING ( SIZE( 3
) ) OPTIONAL,
                                        [6] IMPLICIT OCTET STRING ( SIZE( 1
        msc-Number
.. 20 ) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
                                        [7] IMPLICIT OCTET STRING ( SIZE( 10
        geodeticInformation
) ) OPTIONAL,
       currentLocationRetrieved
                                        [8] IMPLICIT NULL OPTIONAL,
        sai-Present
                                         [9] IMPLICIT NULL OPTIONAL}
OPTIONAL,
     supportedCAMELPhases [5] IMPLICIT BIT STRING {
        phase1 (0),
        phase2 (1 ),
phase3 (2 ),
phase4 (3 )} ( SIZE( 1 .. 16 ) ) OPTIONAL,
     extensionContainer [6] IMPLICIT SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
          SEQUENCE {
                      MAP-EXTENSION .&extensionId ( {
             extId
                ...}),
             extType MAP-EXTENSION .&ExtensionType ( {
               ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
         ... } OPTIONAL,
        ... } OPTIONAL,
     locationInformationGPRS [7] IMPLICIT SEQUENCE {
        cellGlobalIdOrServiceAreaIdOrLAI [0] CHOICE {
          cellGlobalIdOrServiceAreaIdFixedLength [0] IMPLICIT OCTET STRING
( SIZE( 7 ) ),
          laiFixedLength
                                                  [1] IMPLICIT OCTET STRING
(SIZE(5)) OPTIONAL,
        routeingAreaIdentity
                                       [1] IMPLICIT OCTET STRING ( SIZE ( 6
) ) OPTIONAL,
        geographicalInformation
                                       [2] IMPLICIT OCTET STRING ( SIZE( 8
) ) OPTIONAL,
       sgsn-Number
                                        [3] IMPLICIT OCTET STRING ( SIZE( 1
.. 20 ) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
       selectedLSAIdentity
                                        [4] IMPLICIT OCTET STRING ( SIZE( 3
) ) OPTIONAL,
        extensionContainer
                                        [5] IMPLICIT SEQUENCE {
          privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
             SEQUENCE {
                extId MAP-EXTENSION .&extensionId ( {
                   ...}),
                extType MAP-EXTENSION .&ExtensionType ( {
```

```
...} { @extId } ) OPTIONAL} OPTIONAL,
           pcs-Extensions [1] IMPLICIT SEQUENCE {
            ... } OPTIONAL,
           ... } OPTIONAL,
        sai-Present
                                          [6] IMPLICIT NULL OPTIONAL,
        geodeticInformation
                                          [7] IMPLICIT OCTET STRING ( SIZE( 10
) ) OPTIONAL,
        currentLocationRetrieved
ageOfLocationInformation
                                         [8] IMPLICIT NULL OPTIONAL,
                                          [9] IMPLICIT INTEGER ( 0 .. 32767 )
OPTIONAL,
     offeredCamel4Functionalities [8] IMPLICIT BIT STRING {
        initiateCallAttempt (0),
        splitLeg (1),
        moveLeg (2),
        disconnectLeg (3),
entityReleased (4),
        dfc-WithArgument (5),
        playTone (6),
        dtmf-MidCall (7 ),
        chargingIndicator (8),
        alertingDP (9),
        locationAtAlerting (10 ),
changeOfPositionDP (11 ),
        or-Interactions (12),
        warningToneEnhancements (13),
        cf-Enhancements (14),
        subscribedEnhancedDialledServices (15 ),
        servingNetworkEnhancedDialledServices (16 ),
        criteriaForChangeOfPositionDP (17 ),
        serviceChangeDP (18) { (SIZE(15..64)) OPTIONAL}
  RESULT SEQUENCE {
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                       MAP-EXTENSION .&extensionId ( {
              extId
                 ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL,
  ERRORS
     dataMissing
     unexpectedDataValue |
     unknownSubscriber |
     mm-EventNotSupported }
   CODE local : 89
END
--Expanded ASN1 Module 'MAP-OperationAndMaintenanceOperations'
--SIEMENS ASN.1 Compiler R6.15 (Production 6.15)
             Date: 2006-12-06 Time: 09:29:50
```

```
MAP-OperationAndMaintenanceOperations{ 0 identified-organization (4) etsi (0)
mobileDomain (0) qsm-Network (1) modules (3) map-
OperationAndMaintenanceOperations (6) version9 (9) }
DEFINITIONS
::=
BEGIN
EXPORTS
  activateTraceMode,
   deactivateTraceMode,
   sendIMSI;
activateTraceMode OPERATION ::= {
   ARGUMENT SEQUENCE {
                             [0] IMPLICIT OCTET STRING ( SIZE( 3 .. 8 ) )
     imsi
OPTIONAL,
      traceReference [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 2 ) ),
traceType [2] IMPLICIT INTEGER ( 0 .. 255 ),
omc-Id [3] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) )
      omc-Id
                             [3] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) )
OPTIONAL,
      extensionContainer [4] IMPLICIT SEQUENCE {
         privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
             SEQUENCE {
                extId
                          MAP-EXTENSION .&extensionId ( {
                   ...}),
                extType MAP-EXTENSION .&ExtensionType ( {
                    ...} { @extId } ) OPTIONAL} OPTIONAL,
         pcs-Extensions [1] IMPLICIT SEQUENCE {
           ... } OPTIONAL,
          ... } OPTIONAL,
      traceReference2 [5] IMPLICIT OCTET STRING ( SIZE( 3 ) ) OPTIONAL, traceDepthList [6] IMPLICIT SEQUENCE { msc-s-TraceDepth [0] IMPLICIT ENUMERATED {
             \mbox{minimum} \qquad \mbox{(0),}
             ... } OPTIONAL,
         mgw-TraceDepth [1] IMPLICIT ENUMERATED {
             minimum (0),
medium (1),
maximum (2),
             ... } OPTIONAL,
          sgsn-TraceDepth [2] IMPLICIT ENUMERATED {
             minimum ( 0 ),
             medium
                         (1),
             medium (1), maximum (2),
             ... } OPTIONAL,
          ggsn-TraceDepth [3] IMPLICIT ENUMERATED {
            minimum (0),
medium (1),
maximum (2),
             ... } OPTIONAL,
         rnc-TraceDepth [4] IMPLICIT ENUMERATED {
             minimum (0),
                         (1),
             medium
             maximum (2),
```

```
... } OPTIONAL,
  bmsc-TraceDepth [5] IMPLICIT ENUMERATED {
     minimum (0),
medium (1),
maximum (2),
     ... } OPTIONAL,
  ... } OPTIONAL,
                 [7] IMPLICIT BIT STRING {
traceNE-TypeList
  msc-s (0),
  mgw (1),
  sgsn (2),
  ggsn (3),
  rnc (4),
  bm-sc (5)} (SIZE(6..16)) OPTIONAL,
traceInterfaceList [8] IMPLICIT SEQUENCE {
  msc-s-List [0] IMPLICIT BIT STRING {
     a (0),
     iu (1 ),
     mc (2),
     map-g (3),
     map-b (4),
map-e (5),
map-f (6),
     cap (7),
     map-d (8),
     map-c (9 )} ( SIZE(10 .. 16 ) ) OPTIONAL,
  mgw-List [1] IMPLICIT BIT STRING {
     mc (0),
     nb-up (1),
     iu-up (2 )} ( SIZE( 3 .. 8 ) ) OPTIONAL,
  sgsn-List [2] IMPLICIT BIT STRING {
     gb (0),
     iu (1 ),
     gn (2),
     map-gr (3),
     map-gd (4),
     map-gf (5),
     gs (6),
     ge (7)} (SIZE(8..16)) OPTIONAL,
  ggsn-List [3] IMPLICIT BIT STRING {
     gn (0),
     gi (1),
     gmb (2)} (SIZE(3..8)) OPTIONAL,
  rnc-List [4] IMPLICIT BIT STRING {
     iu (0),
     iur (1),
     iub (2),
     uu (3 )} ( SIZE( 4 .. 8 ) ) OPTIONAL,
  bmsc-List [5] IMPLICIT BIT STRING {
     qmb (0)} (SIZE(1..8)) OPTIONAL,
   ... } OPTIONAL,
traceEventList [9] IMPLICIT SEQUENCE {
  msc-s-List [0] IMPLICIT BIT STRING {
     mo-mtCall (0),
     mo-mt-sms (1),
     lu-imsiAttach-imsiDetach (2),
     handovers (3),
     ss (4)} (SIZE(5..16)) OPTIONAL,
  mgw-List [1] IMPLICIT BIT STRING {
     context (0 ) } ( SIZE( 1 .. 8 ) ) OPTIONAL,
  sgsn-List [2] IMPLICIT BIT STRING {
     pdpContext (0),
     mo-mt-sms (1),
```

```
rau-gprsAttach-gprsDetach (2),
           mbmsContext (3)} (SIZE(4..16)) OPTIONAL,
        ggsn-List [3] IMPLICIT BIT STRING {
           pdpContext (0 ),
mbmsContext (1 )} ( SIZE( 2 .. 8 ) ) OPTIONAL,
        bmsc-List [4] IMPLICIT BIT STRING {
           mbmsMulticastServiceActivation (0)}(SIZE(1..8))OPTIONAL,
        ... } OPTIONAL}
  RESULT SEQUENCE {
                           [0] IMPLICIT SEQUENCE {
     extensionContainer
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
              extId
                       MAP-EXTENSION .&extensionId ( {
                ...}),
              extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extid } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL,
     traceSupportIndicator [1] IMPLICIT NULL OPTIONAL}
  ERRORS
     systemFailure |
     dataMissing
     unexpectedDataValue |
     facilityNotSupported |
     unidentifiedSubscriber |
     tracingBufferFull }
  CODE local : 50
deactivateTraceMode OPERATION ::= {
  ARGUMENT SEQUENCE {
                         [0] IMPLICIT OCTET STRING ( SIZE( 3 .. 8 ) )
     imsi
OPTIONAL,
     traceReference [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 2 ) ),
     extensionContainer [2] IMPLICIT SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
             extId MAP-EXTENSION .&extensionId ( {
                ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                 ... } { @extid } ) OPTIONAL } OPTIONAL ,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL,
                        [3] IMPLICIT OCTET STRING ( SIZE( 3 ) ) OPTIONAL}
     traceReference2
           SEQUENCE {
     extensionContainer [0] IMPLICIT SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                      MAP-EXTENSION .&extensionId ( {
              ext.Td
              \ldots\} ) , extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extId } ) OPTIONAL} OPTIONAL,
                        [1] IMPLICIT SEQUENCE {
        pcs-Extensions
```

```
... } OPTIONAL,
         ... } OPTIONAL,
  ERRORS
     systemFailure |
     dataMissing
     unexpectedDataValue |
     facilityNotSupported |
     unidentifiedSubscriber }
         local
                   : 51
  CODE
   }
sendIMSI OPERATION ::= {
  ARGUMENT OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1 .. 9 ) )
             OCTET STRING ( SIZE( 3 .. 8 ) )
  RESULT
  ERRORS
     dataMissing |
     unexpectedDataValue |
     unknownSubscriber }
  CODE
          local
END
    Expanded ASN1 Module 'MAP-CallHandlingOperations'
--SIEMENS ASN.1 Compiler
                               R6.15 (Production 6.15)
             Date: 2006-12-06 Time: 09:30:04
MAP-CallHandlingOperations { 0 identified-organization (4) etsi (0) mobileDomain
(0) qsm-Network (1) modules (3) map-CallHandlingOperations (7) version9 (9) }
DEFINITIONS
: :=
BEGIN
EXPORTS
  sendRoutingInfo,
  provideRoamingNumber,
  resumeCallHandling,
  setReportingState,
  statusReport,
  remoteUserFree,
  ist-Alert,
  ist-Command,
  releaseResources;
sendRoutingInfo OPERATION ::= {
  ARGUMENT SEQUENCE {
                                       [0] IMPLICIT OCTET STRING ( SIZE( 1 ..
     msisdn
20 ) ) ( SIZE( 1 .. 9 ) ),
     cug-CheckInfo
                                       [1] IMPLICIT SEQUENCE {
                        OCTET STRING ( SIZE( 4 ) ),
        cug-Interlock
        cug-OutgoingAccess NULL OPTIONAL,
        extensionContainer
                            SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
              SEQUENCE {
                 extId
                           MAP-EXTENSION .&extensionId ( {
```

```
...}),
                  extType MAP-EXTENSION .&ExtensionType ( {
                     ...} { @extId } ) OPTIONAL} OPTIONAL,
            pcs-Extensions [1] IMPLICIT SEQUENCE {
             ... } OPTIONAL,
              .. } OPTIONAL,
         ... } OPTIONAL,
      numberOfForwarding
                                        [2] IMPLICIT INTEGER ( 1 .. 5 )
OPTIONAL,
      interrogationType
                                        [3] IMPLICIT ENUMERATED {
        basicCall (0),
forwarding (1)},
                                         [4] IMPLICIT NULL OPTIONAL,
      or-Interrogation
                                         [5] IMPLICIT INTEGER ( 1 .. 127 )
      or-Capability
OPTIONAL,
                                        [6] IMPLICIT OCTET STRING ( SIZE( 1 ...
     gmsc-OrGsmSCF-Address
20 ) ) ( SIZE( 1 .. 9 ) ),
                                        [7] IMPLICIT OCTET STRING ( SIZE( 1 .. 8
     callReferenceNumber
) ) OPTIONAL,
     forwardingReason
     forwardingReason [8]
notReachable (0),
busy (1),
noReply (2) OPTIONAL,
basicServiceGroup [9]
                                         [8] IMPLICIT ENUMERATED {
        sicServiceGroup [9] CHOICE {
ext-BearerService [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 5 ) ),
ext-Teleservice [3] IMPLICIT OCTET STRING ( SIZE( 1 .. 5 ) )}
     OPTIONAL,
                                        [10] IMPLICIT SEQUENCE {
         gsm-0806 (2),

gsm-BSSMAP (3),

ets-300102-1 (4)},

signalInfo OCTET STRING (SIZE(1...200)),
         extensionContainer SEQUENCE {
            privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
               SEQUENCE {
                  ext.Td
                            MAP-EXTENSION .&extensionId ( {
                     ...} ) ,
                  extType MAP-EXTENSION .&ExtensionType ( {
                     ...} { @extid } ) OPTIONAL} OPTIONAL,
            pcs-Extensions [1] IMPLICIT SEQUENCE {
              ... } OPTIONAL,
            ... } OPTIONAL,
         ... } OPTIONAL,
                                        [11] IMPLICIT SEQUENCE {
      camelInfo
         supportedCamelPhases BIT STRING {
            phase1 (0),
            phase2 (1),
            phase3 (2),
            phase4 (3)} (SIZE(1..16)),
         privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
               SEQUENCE {
                            MAP-EXTENSION .&extensionId ( {
                  extId
                     ...} ) ,
                  extType MAP-EXTENSION .&ExtensionType ( {
```

```
...} { @extid } ) OPTIONAL} OPTIONAL.
            pcs-Extensions [1] IMPLICIT SEQUENCE {
             ... } OPTIONAL,
            ... } OPTIONAL,
         offeredCamel4CSIs [0] IMPLICIT BIT STRING {
            o-csi (0 ),
            d-csi (1),
            vt-csi (2),
            t-csi (3),
            mt-sms-csi (4),
            mg-csi (5),
            psi-enhancements (6 ) } ( SIZE( 7 .. 16 ) ) OPTIONAL } OPTIONAL ,
      suppressionOfAnnouncement [12] IMPLICIT NULL OPTIONAL,
extensionContainer [13] IMPLICIT SEQUENCE {
         privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
            SEQUENCE {
                         MAP-EXTENSION .&extensionId ( {
               extId
                  ...} ) ,
               extType MAP-EXTENSION .&ExtensionType ( {
                  ...} { @extId } ) OPTIONAL} OPTIONAL,
         pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
         ... } OPTIONAL,
      alertingPattern
                                         [14] IMPLICIT OCTET STRING ( SIZE( 1 ) )
OPTIONAL,
      ccbs-Call
                                         [15] IMPLICIT NULL OPTIONAL,
      supportedCCBS-Phase
NAL,
                                         [16] IMPLICIT INTEGER ( 1 .. 127 )
OPTIONAL,
      additionalSignalInfo [17 ext-ProtocolId ENUMERATED {
                                        [17] IMPLICIT SEQUENCE {
           ets-300356 (1),
            ... },
                             OCTET STRING ( SIZE( 1 .. 200 ) ),
         signalInfo
         extensionContainer SEQUENCE {
            privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
               SEQUENCE {
                  ext.Td
                            MAP-EXTENSION .&extensionId ( {
                     ...} ) ,
                  extType MAP-EXTENSION .&ExtensionType ( {
                     ...} { @extId } ) OPTIONAL} OPTIONAL,
            pcs-Extensions [1] IMPLICIT SEQUENCE {
              ... } OPTIONAL,
            ... } OPTIONAL,
         ... } OPTIONAL,
      istSupportIndicator
                                         [18] IMPLICIT ENUMERATED {
         basicISTSupported (0), istCommandSupported (1),
         ... } OPTIONAL,
      pre-pagingSupported
                                        [19] IMPLICIT NULL OPTIONAL,
      callDiversionTreatmentIndicator [20] IMPLICIT OCTET STRING ( SIZE( 1 ) )
OPTIONAL,
      longFTN-Supported
                                         [21] IMPLICIT NULL OPTIONAL,
                                         [22] IMPLICIT NULL OPTIONAL,
      suppress-VT-CSI [22] IMPLICIT NULL OPTIONAL, suppressIncomingCallBarring [23] IMPLICIT NULL OPTIONAL, gsmSCF-InitiatedCall [24] IMPLICIT NULL OPTIONAL, basicServiceGroup2 [25] CHOICE {
      suppress-VT-CSI
         ext-BearerService [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 5 ) ),
```

```
ext-Teleservice [3] IMPLICIT OCTET STRING ( SIZE( 1 .. 5 ) )}
OPTIONAL,
     networkSignalInfo2
                                   [26] IMPLICIT SEQUENCE {
                         ENUMERATED {
        protocolId
                        (1),
          gsm-0408
          gsm-0806
                         (2),
          gsm-BSSMAP
                         (3),
          ets-300102-1 (4)},
                         OCTET STRING ( SIZE( 1 .. 200 ) ),
        signalInfo
        extensionContainer SEQUENCE {
          privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
             SEQUENCE {
                         MAP-EXTENSION .&extensionId ( {
                extId
                   ...}),
                extType MAP-EXTENSION .&ExtensionType ( {
                   ... } { @extId } ) OPTIONAL } OPTIONAL ,
          pcs-Extensions [1] IMPLICIT SEQUENCE {
             ... } OPTIONAL,
           ... } OPTIONAL,
        ... } OPTIONAL}
  RESULT
           [3] IMPLICIT SEQUENCE {
    imsi
                                    [9] IMPLICIT OCTET STRING ( SIZE( 3 .. 8
) ) OPTIONAL,
     extendedRoutingInfo
                                    CHOICE {
                         CHOICE {
       routingInfo
          roamingNumber
                           OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1 .. 9 )
),
           forwardingData SEQUENCE {
             forwardedToNumber [5] IMPLICIT OCTET STRING ( SIZE( 1 .. 20
) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
             forwardedToSubaddress [4] IMPLICIT OCTET STRING ( SIZE( 1 .. 21
) ) OPTIONAL,
             forwardingOptions [6] IMPLICIT OCTET STRING ( SIZE( 1 ) )
OPTIONAL.
             extensionContainer [7] IMPLICIT SEQUENCE {
                privateExtensionList [0] IMPLICIT SEQUENCE (SIZE(1..10
) ) OF
                   SEQUENCE {
                     extId
                              MAP-EXTENSION .&extensionId ( {
                        ...}),
                      extType MAP-EXTENSION .&ExtensionType ( {
                        ... } { @extId } ) OPTIONAL } OPTIONAL ,
                pcs-Extensions [1] IMPLICIT SEQUENCE {
                  ... } OPTIONAL,
                ... } OPTIONAL,
             longForwardedToNumber [8] IMPLICIT OCTET STRING ( SIZE( 1 .. 20
) ) ( SIZE( 1 .. 15 ) ) OPTIONAL } } ,
        forwardedToNumber
                                   [5] IMPLICIT OCTET STRING ( SIZE( 1 .. 20
) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
             forwardedToSubaddress [4] IMPLICIT OCTET STRING ( SIZE( 1 .. 21
) ) OPTIONAL,
             forwardingOptions [6] IMPLICIT OCTET STRING ( SIZE( 1 ) )
OPTIONAL,
             extensionContainer [7] IMPLICIT SEQUENCE {
                privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10
) ) OF
```

```
...} ) ,
                      extType MAP-EXTENSION .&ExtensionType ( {
                         ...} { @extid } ) OPTIONAL} OPTIONAL,
                pcs-Extensions [1] IMPLICIT SEQUENCE {
                 ... } OPTIONAL,
                ... } OPTIONAL,
              longForwardedToNumber [8] IMPLICIT OCTET STRING ( SIZE( 1 .. 20
) ) ( SIZE( 1 .. 15 ) ) OPTIONAL } OPTIONAL ,
           gmscCamelSubscriptionInfo [0] IMPLICIT SEQUENCE {
                                         [0] IMPLICIT SEQUENCE {
                CSI [0] IMPLICIT SEQUENCE {
t-BcsmCamelTDPDataList SEQUENCE (SIZE(1..10)) OF
             t-CSI
                   SEQUENCE {
                      termAttemptAuthorized (12),
                         . . . .
                         tBusy
                                                (13),
                         tNoAnswer
                                                (14)},
                      serviceKey
                                                 INTEGER ( 0 .. 2147483647
),
                     gsmSCF-Address
                                                 [0] IMPLICIT OCTET STRING
( SIZE( 1 .. 20 ) ) ( SIZE( 1 .. 9 ) ),
                      defaultCallHandling
  continueCall ( 0 ),
  releaseCall ( 1 ),
                                                 [1] IMPLICIT ENUMERATED {
                        ... },
                      extensionContainer
                                                 [2] IMPLICIT SEQUENCE {
                        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE(
1 .. 10 ) ) OF
                           SEQUENCE {
                                      MAP-EXTENSION .&extensionId ( {
                              extId
                                ...} ) ,
                              extType MAP-EXTENSION .&ExtensionType ( {
                                ...} { @extId } ) OPTIONAL} OPTIONAL,
                         pcs-Extensions [1] IMPLICIT SEQUENCE {
                         ... } OPTIONAL,
                         ... } OPTIONAL,
                      ... },
                privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ...
10 ) ) OF
                      SEQUENCE {
                                 MAP-EXTENSION .&extensionId ( {
                           ...} ) ,
                         extType MAP-EXTENSION .&ExtensionType ( {
                           ...} { @extId } ) OPTIONAL} OPTIONAL,
                                   [1] IMPLICIT SEQUENCE {
                   pcs-Extensions
                    ... } OPTIONAL,
                   ... } OPTIONAL,
                camelCapabilityHandling [0] IMPLICIT INTEGER ( 1 .. 16 )
OPTIONAL,
                notificationToCSE [1] IMPLICIT NULL OPTIONAL, csi-Active [2] IMPLICIT NULL OPTIONAL}
OPTIONAL,
```

```
[1] IMPLICIT SEQUENCE {
             o-CSI
               o-BcsmCamelTDPDataList SEQUENCE (SIZE(1..10)) OF
                  SEQUENCE {
                     collectedInfo
                                          (2),
                       routeSelectFailure (4)},
                                                INTEGER ( 0 .. 2147483647
                     serviceKey
),
                                               [0] IMPLICIT OCTET STRING
                     gsmSCF-Address
( SIZE( 1 .. 20 ) ) ( SIZE( 1 .. 9 ) ),
                                               [1] IMPLICIT ENUMERATED {
                     defaultCallHandling
                       continueCall (0), releaseCall (1),
                       ... },
                     extensionContainer
                                               [2] IMPLICIT SEQUENCE {
                       privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE(
1 .. 10 ) ) OF
                          SEQUENCE {
                                     MAP-EXTENSION .&extensionId ( {
                             extId
                               ...} ) ,
                             extType MAP-EXTENSION .&ExtensionType ( {
                        ...} { @extId } ) OPTIONAL} OPTIONAL, pcs-Extensions [1] IMPLICIT SEQUENCE {
                         ... } OPTIONAL,
                        ... } OPTIONAL,
                     ...},
                10 ) ) OF
                     SEQUENCE { extid MAP-EXTENSION .&extensionId ( {
                          ...} ) ,
                        extType MAP-EXTENSION .&ExtensionType ( {
                          ...} { @extId } ) OPTIONAL} OPTIONAL,
                  pcs-Extensions [1] IMPLICIT SEQUENCE {
                   ... } OPTIONAL,
                  ... } OPTIONAL,
                camelCapabilityHandling [0] IMPLICIT INTEGER ( 1 .. 16 )
OPTIONAL,
               notificationToCSE [1] IMPLICIT NULL OPTIONAL,
               csiActive
                                      [2] IMPLICIT NULL OPTIONAL}
OPTIONAL,
             extensionContainer
                                         [2] IMPLICIT SEQUENCE {
               privateExtensionList [0] IMPLICIT SEQUENCE (SIZE(1..10
) ) OF
                  SEQUENCE {
                             MAP-EXTENSION .&extensionId ( {
                     ...}), extType MAP-EXTENSION .&ExtensionType ( {
                       ...} { @extid } ) OPTIONAL} OPTIONAL,
                pcs-Extensions [1] IMPLICIT SEQUENCE {
                 ... } OPTIONAL,
                ... } OPTIONAL,
```

```
o-BcsmCamelTDP-CriteriaList [3] IMPLICIT SEQUENCE ( SIZE( 1
.. 10 ) ) OF
                SEQUENCE {
                   collectedInfo (2),
                     routeSelectFailure (4)},
                   destinationNumberCriteria [0] IMPLICIT SEQUENCE {
                                                [0] IMPLICIT ENUMERATED {
                     matchType
                                   ( 0 ),
( 1 ) },
                        inhibiting
                        enabling
                                                [1] IMPLICIT SEQUENCE (
                     destinationNumberList
SIZE( 1 .. 10 ) ) OF
                       OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1 .. 9 ) )
OPTIONAL,
                     destinationNumberLengthList [2] IMPLICIT SEQUENCE (
SIZE( 1 .. 3 ) ) OF
                       INTEGER ( 1 .. 15 ) OPTIONAL,
                     ... } OPTIONAL,
                  basicServiceCriteria
                                       [1] IMPLICIT SEQUENCE (
SIZE( 1 .. 5 ) ) OF
                     CHOICE {
                       ext-BearerService
                                            [2] IMPLICIT OCTET STRING (
SIZE( 1 .. 5 ) ),
                       ext-Teleservice
                                            [3] IMPLICIT OCTET STRING (
SIZE( 1 .. 5 ) ) } OPTIONAL,
                   callTypeCriteria
                                             [2] IMPLICIT ENUMERATED {
                     forwarded (0),
notForwarded (1)}OPTIONAL,
                     forwarded
                   o-CauseValueCriteria
                                              [3] IMPLICIT SEQUENCE (
SIZE( 1 .. 5 ) ) OF
                     OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
                   extensionContainer
                                              [4] IMPLICIT SEQUENCE {
                     privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1
.. 10 ) ) OF
                        SEQUENCE {
                           extId
                                   MAP-EXTENSION .&extensionId ( {
                             ...} ) ,
                           extType MAP-EXTENSION .&ExtensionType ( {
                             ...} { @extId } ) OPTIONAL} OPTIONAL,
                     pcs-Extensions [1] IMPLICIT SEQUENCE {
                       ... } OPTIONAL,
                      ... } OPTIONAL } OPTIONAL ,
             t-BCSM-CAMEL-TDP-CriteriaList [4] IMPLICIT SEQUENCE ( SIZE( 1
.. 10 ) ) OF
                SEOUENCE {
                   t-BCSM-TriggerDetectionPoint ENUMERATED {
                     termAttemptAuthorized ( 12 ),
                     . . . ,
                                            (13),
                     tBusy
                     tNoAnswer
                                            (14) },
                  basicServiceCriteria
                                              [0] IMPLICIT SEQUENCE (
SIZE( 1 .. 5 ) ) OF
                     CHOICE {
                       ext-BearerService [2] IMPLICIT OCTET STRING (
SIZE( 1 .. 5 )),
                       ext-Teleservice [3] IMPLICIT OCTET STRING (
SIZE( 1 .. 5 ) ) } OPTIONAL,
                   t-CauseValueCriteria [1] IMPLICIT SEQUENCE (
SIZE( 1 .. 5 ) ) OF
```

```
OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
                    ... } OPTIONAL,
                                            [5] IMPLICIT SEQUENCE {
              d-csi
                 dp-AnalysedInfoCriteriaList [0] IMPLICIT SEQUENCE ( SIZE( 1
.. 10 ) ) OF
                    SEQUENCE {
                      dialledNumber
                                           OCTET STRING ( SIZE( 1 .. 20 ) ) (
SIZE( 1 .. 9 ) ),
                       serviceKey
                                           INTEGER ( 0 .. 2147483647 ),
                       serviceKey INTEGER ( 0 .. 2147483647 ),
gsmSCF-Address OCTET STRING ( SIZE( 1 .. 20 ) ) (
SIZE( 1 .. 9 )),
                       defaultCallHandling ENUMERATED {
                        continueCall (0), releaseCall (1),
                         ... },
                       privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE(
1 .. 10 ) ) OF
                            SEQUENCE {
                                        MAP-EXTENSION .&extensionId ( {
                               extId
                                  ...} ) ,
                               extType MAP-EXTENSION .&ExtensionType ( {
                          ...} { @extId } ) OPTIONAL} OPTIONAL, pcs-Extensions [1] IMPLICIT SEQUENCE {
                           ... } OPTIONAL,
                          ... } OPTIONAL,
                       ... } OPTIONAL,
                 camelCapabilityHandling
                                            [1] IMPLICIT INTEGER ( 1 .. 16 )
OPTIONAL,
                 extensionContainer
                                              [2] IMPLICIT SEQUENCE {
                   privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ...
10 ) ) OF
                       SEQUENCE {
                                  MAP-EXTENSION .&extensionId ( {
                          extId
                            ...} ) ,
                          extType MAP-EXTENSION .&ExtensionType ( {
                            ...} { @extId } ) OPTIONAL} OPTIONAL,
                    pcs-Extensions [1] IMPLICIT SEQUENCE {
                      ... } OPTIONAL,
                    ... } OPTIONAL,
                                           [3] IMPLICIT NULL OPTIONAL,
                 notificationToCSE
                                             [4] IMPLICIT NULL OPTIONAL,
                 csi-Active
           ... } OPTIONAL },
extensionContainer [1] IMPLICIT SEQUENCE {
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                 SEQUENCE {
                   extId MAP-EXTENSION .&extensionId ( {
                      ...} ) ,
                    extType MAP-EXTENSION .&ExtensionType ( {
                      ...} { @extId } ) OPTIONAL} OPTIONAL,
              pcs-Extensions [1] IMPLICIT SEQUENCE {
               ... } OPTIONAL,
                .. } OPTIONAL,
           ... }} OPTIONAL,
[3] IMPLICIT SEQUENCE {
     cug-CheckInfo
        cug-Interlock OCTET STRING ( SIZE( 4 ) ),
```

```
cug-OutgoingAccess NULL OPTIONAL,
          extensionContainer SEQUENCE {
             privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
                SEQUENCE {
                               MAP-EXTENSION .&extensionId ( {
                    extId
                       ...}),
                    extType MAP-EXTENSION .&ExtensionType ( {
                       ...} { @extId } ) OPTIONAL} OPTIONAL,
             pcs-Extensions [1] IMPLICIT SEQUENCE {
               ... } OPTIONAL,
             ... } OPTIONAL,
          ... } OPTIONAL,
         gSubscriptionFlag [6] IMPLICIT NULL OPTIONAL, oscriberInfo [7] IMPLICIT SEQUENCE {
locationInformation [0] IMPLICIT SEQUENCE {
      cugSubscriptionFlag
      subscriberInfo
             ageOfLocationInformation INTEGER ( 0 .. 32767 ) OPTIONAL, geographicalInformation [0] IMPLICIT OCTET STRING ( SIZE
                                                    [0] IMPLICIT OCTET STRING ( SIZE(
8 ) ) OPTIONAL,
             vlr-number
                                                    [1] IMPLICIT OCTET STRING ( SIZE(
1 .. 20 ) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
                                                    [2] IMPLICIT OCTET STRING ( SIZE(
             locationNumber
2 .. 10 ) ) OPTIONAL,
             cellGlobalIdOrServiceAreaIdOrLAI [3] CHOICE {
                cellGlobalIdOrServiceAreaIdFixedLength [0] IMPLICIT OCTET
STRING ( SIZE( 7 ) ),
                laiFixedLength
                                                                 [1] IMPLICIT OCTET
STRING ( SIZE( 5 ) ) } OPTIONAL,
                                           [4] IMPLICIT SEQUENCE {
             extensionContainer
                privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                    SEQUENCE {
                       extId
                                 MAP-EXTENSION .&extensionId ( {
                          ...} ) ,
                       extType MAP-EXTENSION .&ExtensionType ( {
                          ...} { @extId } ) OPTIONAL} OPTIONAL,
                pcs-Extensions [1] IMPLICIT SEQUENCE {
                  ... } OPTIONAL,
                ... } OPTIONAL,
             selectedLSA-Id
                                                   [5] IMPLICIT OCTET STRING ( SIZE(
3 ) ) OPTIONAL,
             msc-Number
                                                    [6] IMPLICIT OCTET STRING ( SIZE(
1 .. 20 ) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
             geodeticInformation
                                                   [7] IMPLICIT OCTET STRING ( SIZE(
10 ) ) OPTIONAL,
             currentLocationRetrieved [8] IMPLICIT NULL OPTIONAL,
                                                    [9] IMPLICIT NULL OPTIONAL}
             sai-Present
OPTIONAL,
         subscriberState [1] CHOICE {
  assumedIdle [0] IMPLICIT NULL,
  camelBusy [1] IMPLICIT NULL,
  netDetNotReachable ENUMERATED {
          msPurged (0),
imsiDetached (1),
restrictedArea (2),
notRegistered (3)},
notProvidedFromVLR [2] IMPLICIT NULL} OPTIONAL,
extensionContainer [2] IMPLICIT SEQUENCE {
             privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
```

```
SEQUENCE { extId MAP-EXTENSION .&extensionId ( {
                      ...}),
                  extType MAP-EXTENSION .&ExtensionType ( {
                      ...} { @extid } ) OPTIONAL} OPTIONAL,
            pcs-Extensions [1] IMPLICIT SEQUENCE {
              ... } OPTIONAL,
            ... } OPTIONAL,
         locationInformationGPRS [3] IMPLICIT SEQUENCE {
            cellGlobalIdOrServiceAreaIdOrLAI [0] CHOICE {
               cellGlobalIdOrServiceAreaIdFixedLength [0] IMPLICIT OCTET
STRING ( SIZE( 7 ) ),
               laiFixedLength
                                                            [1] IMPLICIT OCTET
STRING ( SIZE( 5 ) ) } OPTIONAL,
                                        [1] IMPLICIT OCTET STRING ( SIZE(
            routeingAreaIdentity
6 ) ) OPTIONAL,
            geographicalInformation
                                                [2] IMPLICIT OCTET STRING ( SIZE(
8 ) ) OPTIONAL,
                                                [3] IMPLICIT OCTET STRING ( SIZE(
            sgsn-Number
1 .. 20 ) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
                                                [4] IMPLICIT OCTET STRING ( SIZE(
            selectedLSAIdentity
3 ) ) OPTIONAL,
            extensionContainer
                                                [5] IMPLICIT SEQUENCE {
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                   SEQUENCE {
                               MAP-EXTENSION .&extensionId ( {
                     extId
                        ...} ) ,
                      extType MAP-EXTENSION .&ExtensionType ( {
                         ...} { @extId } ) OPTIONAL} OPTIONAL,
               pcs-Extensions [1] IMPLICIT SEQUENCE {
                 ... } OPTIONAL,
               ... } OPTIONAL,
            sai-Present
                                                [6] IMPLICIT NULL OPTIONAL,
            geodeticInformation
                                                [7] IMPLICIT OCTET STRING ( SIZE(
10 ) ) OPTIONAL,
            currentLocationRetrieved [8] IMPLICIT NULL OPTIONAL, ageOfLocationInformation [9] IMPLICIT INTEGER ( 0 .. 32767
) OPTIONAL } OPTIONAL ,
         ps-SubscriberState [4] CHOICE {
            notProvidedFromSGSN
                                                     [0] IMPLICIT NULL,
            ps-Detached
                                                     [1] IMPLICIT NULL,
           ps-AttachedNotReachableForPaging [2] IMPLICIT NULL,
ps-AttachedReachableForPaging [3] IMPLICIT NULL,
ps-PDP-ActiveNotReachableForPaging [4] IMPLICIT SEQUENCE (
SIZE( 1 .. 50 ) ) OF
               SEOUENCE {
                  pdp-ContextIdentifier [0] IMPLICIT INTEGER ( 1 .. 50 ),
pdp-ContextActive [1] IMPLICIT NULL OPTIONAL,
pdp-Type [2] IMPLICIT OCTET STRING ( SIZE(
                                             [2] IMPLICIT OCTET STRING ( SIZE( 2
                  pdp-Type
) ),
                                           [3] IMPLICIT OCTET STRING ( SIZE( 1
                  pdp-Address
.. 16 ) ) OPTIONAL,
                  apn-Subscribed [4] IMPLICIT OCTET STRING ( SIZE( 2
.. 63 ) ) OPTIONAL,
                  apn-InUse [5] IMPLICIT OCTET STRING ( SIZE( 2
.. 63 ) ) OPTIONAL,
```

```
[6] IMPLICIT INTEGER ( 0 .. 15 )
                  nsapi
OPTIONAL,
                                            [7] IMPLICIT OCTET STRING ( SIZE( 1
                  transactionId
.. 2 ) ) OPTIONAL,
                  teid-ForGnAndGp
                                           [8] IMPLICIT OCTET STRING ( SIZE( 4
) ) OPTIONAL,
                                            [9] IMPLICIT OCTET STRING ( SIZE( 4
                  teid-ForIu
) ) OPTIONAL,
                                            [10] IMPLICIT OCTET STRING ( SIZE( 5
                  ggsn-Address
.. 17 ) ) OPTIONAL,
                  qos-Subscribed
                                            [11] IMPLICIT OCTET STRING ( SIZE( 1
.. 9 ) ) OPTIONAL,
                  qos-Requested
                                            [12] IMPLICIT OCTET STRING ( SIZE( 1
.. 9 ) ) OPTIONAL,
                                            [13] IMPLICIT OCTET STRING ( SIZE( 1
                  qos-Negotiated
.. 9 ) ) OPTIONAL,
                                            [14] IMPLICIT OCTET STRING ( SIZE( 4
                  chargingId
) ) OPTIONAL,
                  chargingCharacteristics
                                           [15] IMPLICIT OCTET STRING ( SIZE( 2
) ) OPTIONAL,
                 rnc-Address
                                            [16] IMPLICIT OCTET STRING ( SIZE ( 5
.. 17 ) ) OPTIONAL,
                                           [17] IMPLICIT SEQUENCE {
                  extensionContainer
                     privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ..
10 ) ) OF
                        SEQUENCE {
                           extId
                                     MAP-EXTENSION .&extensionId ( {
                             ...}),
                           extType MAP-EXTENSION .&ExtensionType ( {
                              ...} { @extId } ) OPTIONAL} OPTIONAL,
                                      [1] IMPLICIT SEQUENCE {
                     pcs-Extensions
                       ... } OPTIONAL,
                     ... } OPTIONAL,
                  qos2-Subscribed
                                           [18] IMPLICIT OCTET STRING ( SIZE( 1
.. 3 ) ) OPTIONAL,
                  qos2-Requested
                                           [19] IMPLICIT OCTET STRING ( SIZE( 1
.. 3 ) ) OPTIONAL,
                  qos2-Negotiated
                                           [20] IMPLICIT OCTET STRING ( SIZE( 1
.. 3 ) ) OPTIONAL },
           ps-PDP-ActiveReachableForPaging [5] IMPLICIT SEQUENCE (
SIZE( 1 .. 50 ) ) OF
               SEQUENCE {
                 pdp-ContextIdentifier [0] IMPLICIT INTEGER ( 1 .. 50 ),
pdp-ContextActive [1] IMPLICIT NULL OPTIONAL,
                                            [2] IMPLICIT OCTET STRING ( SIZE( 2
                  pdp-Type
)),
                  pdp-Address
                                          [3] IMPLICIT OCTET STRING ( SIZE( 1
.. 16 ) ) OPTIONAL,
                  apn-Subscribed [4] IMPLICIT OCTET STRING ( SIZE( 2
.. 63 ) ) OPTIONAL,
                                           [5] IMPLICIT OCTET STRING ( SIZE( 2
                  apn-InUse
.. 63 ) ) OPTIONAL,
                                           [6] IMPLICIT INTEGER ( 0 .. 15 )
                  nsapi
OPTIONAL,
                  transactionId
                                           [7] IMPLICIT OCTET STRING ( SIZE( 1
.. 2 ) ) OPTIONAL,
                  teid-ForGnAndGp [8] IMPLICIT OCTET STRING ( SIZE( 4
) ) OPTIONAL,
                 teid-ForIu
                                           [9] IMPLICIT OCTET STRING ( SIZE ( 4
) ) OPTIONAL,
```

```
ggsn-Address
                                           [10] IMPLICIT OCTET STRING ( SIZE( 5
.. 17 ) ) OPTIONAL,
                  qos-Subscribed
                                          [11] IMPLICIT OCTET STRING ( SIZE( 1
.. 9 ) ) OPTIONAL,
                                           [12] IMPLICIT OCTET STRING ( SIZE( 1
                  qos-Requested
.. 9 ) ) OPTIONAL,
                  qos-Negotiated
                                           [13] IMPLICIT OCTET STRING ( SIZE( 1
.. 9 ) ) OPTIONAL,
                 chargingId
                                           [14] IMPLICIT OCTET STRING ( SIZE( 4
) ) OPTIONAL,
                 chargingCharacteristics
                                          [15] IMPLICIT OCTET STRING ( SIZE( 2
) ) OPTIONAL,
                 rnc-Address
                                           [16] IMPLICIT OCTET STRING ( SIZE( 5
.. 17 ) ) OPTIONAL,
                                          [17] IMPLICIT SEQUENCE {
                 extensionContainer
                    privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 ..
10 ) ) OF
                       SEQUENCE {
                                     MAP-EXTENSION .&extensionId ( {
                          extId
                             ...}),
                          extType MAP-EXTENSION .&ExtensionType ( {
                             ...} { @extId } ) OPTIONAL} OPTIONAL,
                    pcs-Extensions [1] IMPLICIT SEQUENCE {
                       ... } OPTIONAL,
                     ... } OPTIONAL,
                  qos2-Subscribed
                                          [18] IMPLICIT OCTET STRING ( SIZE( 1
.. 3 ) ) OPTIONAL,
                                          [19] IMPLICIT OCTET STRING ( SIZE( 1
                  qos2-Requested
.. 3 ) ) OPTIONAL,
                                          [20] IMPLICIT OCTET STRING ( SIZE( 1
                 qos2-Negotiated
.. 3 ) ) OPTIONAL },
                                                  ENUMERATED {
           netDetNotReachable
              msPurged ( 0 ),
              imsiDetached (1),
restrictedArea (2),
notRegistered (3)} OPTIONAL,
                                  [5] IMPLICIT OCTET STRING ( SIZE( 8 ) )
        imei
OPTIONAL,
        ms-Classmark2
                                 [6] IMPLICIT OCTET STRING ( SIZE( 3 ) )
OPTIONAL,
        gprs-MS-Class
                                 [7] IMPLICIT SEQUENCE {
           mSNetworkCapability
                                     [0] IMPLICIT OCTET STRING ( SIZE( 1 .. 8 )
),
           mSRadioAccessCapability [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 50
) ) OPTIONAL } OPTIONAL ,
        mnpInfoRes
                                 [8] IMPLICIT SEQUENCE {
           routeingNumber
                                     [0] IMPLICIT OCTET STRING ( SIZE( 1 .. 5 )
) OPTIONAL,
                                     [1] IMPLICIT OCTET STRING ( SIZE( 3 .. 8 )
            imsi
) OPTIONAL,
                                     [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 20
           msisdn
) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
           numberPortabilityStatus [3] IMPLICIT ENUMERATED {
                                                     (0),
              notKnownToBePorted
                                                     (1),
              ownNumberPortedOut
                                                     (2),
              foreignNumberPortedToForeignNetwork
              ownNumberNotPortedOut
                                                      (5) } OPTIONAL,
               foreignNumberPortedIn
            extensionContainer [4] IMPLICIT SEQUENCE {
```

```
privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                SEQUENCE {
                            MAP-EXTENSION .&extensionId ( {
                   extId
                      ...}),
                    extType MAP-EXTENSION .&ExtensionType ( {
                      ...} { @extId } ) OPTIONAL} OPTIONAL,
                              [1] IMPLICIT SEQUENCE {
              pcs-Extensions
                ... } OPTIONAL,
               .. } OPTIONAL,
           ... } OPTIONAL } OPTIONAL ,
                                     [1] IMPLICIT SEQUENCE ( SIZE( 1 .. 30 )
     ss-List
) OF
        OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
     basicService
                                     [5] CHOICE {
       ext-BearerService [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 5 ) ),
                             [3] IMPLICIT OCTET STRING ( SIZE( 1 .. 5 ) )}
        ext-Teleservice
OPTIONAL,
     forwardingInterrogationRequired [4] IMPLICIT NULL OPTIONAL,
                                     [2] IMPLICIT OCTET STRING ( SIZE( 1 ...
     vmsc-Address
20 ) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
     extensionContainer
                                    [0] IMPLICIT SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                       MAP-EXTENSION .&extensionId ( {
              extId
                ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
         ... } OPTIONAL,
        ... } OPTIONAL,
                                    [10] IMPLICIT SEQUENCE {
     naea-PreferredCI
        naea-PreferredCIC [0] IMPLICIT OCTET STRING ( SIZE( 3 ) ),
        extensionContainer [1] IMPLICIT SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
             SEQUENCE {
                         MAP-EXTENSION .&extensionId ( {
                extId
                   ...} ) ,
                 extType MAP-EXTENSION .&ExtensionType ( {
                   ... } { @extId } ) OPTIONAL } OPTIONAL ,
           pcs-Extensions [1] IMPLICIT SEQUENCE {
             ... } OPTIONAL,
           ... } OPTIONAL,
        ... } OPTIONAL,
                                    [11] IMPLICIT SEQUENCE {
     ccbs-Indicators
        ccbs-Possible [0] IMPLICIT SEQUENC.
        keepCCBS-CallIndicator [1] IMPLICIT NULL OPTIONAL,
        extensionContainer [2] IMPLICIT SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
              SEQUENCE {
                extId MAP-EXTENSION .&extensionId ( {
                    ...} ) ,
                 extType \mbox{\scriptsize MAP-EXTENSION} .&ExtensionType ( {
                    ...} { @extId } ) OPTIONAL} OPTIONAL,
```

```
[1] IMPLICIT SEQUENCE {
           pcs-Extensions
              ... } OPTIONAL,
             .. } OPTIONAL,
         ... } OPTIONAL,
     msisdn
                                       [12] IMPLICIT OCTET STRING ( SIZE( 1 ...
20 ) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
     numberPortabilityStatus
                                      [13] IMPLICIT ENUMERATED {
        notKnownToBePorted
                                               (0),
                                               (1),
        ownNumberPortedOut
                                              (2),
        foreignNumberPortedToForeignNetwork
        ownNumberNotPortedOut
                                                (4),
                                               (5) OPTIONAL,
        foreignNumberPortedIn
                                      [14] IMPLICIT INTEGER ( 15 .. 255 )
      istAlertTimer
OPTIONAL,
     supportedCamelPhasesInVMSC
                                      [15] IMPLICIT BIT STRING {
        phase1 (0),
        phase2 (1),
        phase3 (2),
phase4 (3)} (SIZE(1..16)) OPTIONAL,
     offeredCamel4CSIsInVMSC [16] IMPLICIT BIT STRING {
        o-csi (0),
        d-csi (1),
vt-csi (2),
        t-csi (3),
        mt-sms-csi (4 ),
        mg-csi (5),
        psi-enhancements (6)} (SIZE(7..16)) OPTIONAL,
     routingInfo2 [17] CHOICE {
roamingNumber OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1 .. 9 ) ),
        forwardingData SEQUENCE {
           forwardedToNumber [5] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 )
) ( SIZE( 1 .. 9 ) ) OPTIONAL,
           forwardedToSubaddress [4] IMPLICIT OCTET STRING ( SIZE( 1 .. 21 )
) OPTIONAL,
           forwardingOptions
                                  [6] IMPLICIT OCTET STRING ( SIZE( 1 ) )
OPTIONAL,
           extensionContainer [7] IMPLICIT SEQUENCE {
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                  SEQUENCE {
                             MAP-EXTENSION .&extensionId ( {
                    extId
                       ...}),
                     extType MAP-EXTENSION .&ExtensionType ( {
                       ...} { @extid } ) OPTIONAL} OPTIONAL,
              pcs-Extensions [1] IMPLICIT SEQUENCE {
                 ... } OPTIONAL,
              ... } OPTIONAL,
            longForwardedToNumber [8] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 )
) ( SIZE( 1 .. 15 ) ) OPTIONAL } } OPTIONAL,
                                       [18] IMPLICIT SEQUENCE ( SIZE( 1 .. 30
     ss-List2
        OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
     basicService2
                                       [19] CHOICE {
        ext-BearerService [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 5 ) ), ext-Teleservice [3] IMPLICIT OCTET STRING ( SIZE( 1 .. 5 ) )}
OPTIONAL,
     allowedServices
                                       [20] IMPLICIT BIT STRING {
        firstServiceAllowed (0 ),
        secondServiceAllowed (1 )} ( SIZE( 2 .. 8 ) ) OPTIONAL,
```

```
[21] IMPLICIT ENUMERATED {
     unavailabilityCause
        bearerServiceNotProvisioned (1),
        teleserviceNotProvisioned
                                      (2),
                                       (3),
        absentSubscriber
        busySubscriber
                                       (4),
                                       (5),
        callBarred
                                       (6),
        cug-Reject
         ... } OPTIONAL,
     releaseResourcesSupported
                                      [22] IMPLICIT NULL OPTIONAL
  ERRORS
     systemFailure |
     dataMissing
     unexpectedDataValue |
     facilityNotSupported |
     or-NotAllowed |
     unknownSubscriber |
     numberChanged |
     bearerServiceNotProvisioned |
     teleserviceNotProvisioned |
     absentSubscriber |
     busySubscriber |
     noSubscriberReply |
     callBarred |
     cuq-Reject |
     forwardingViolation }
  CODE local : 22
provideRoamingNumber OPERATION ::= {
  ARGUMENT SEQUENCE {
     imsi
                                               [0] IMPLICIT OCTET STRING (
SIZE( 3 .. 8 ) ),
     msc-Number
                                               [1] IMPLICIT OCTET STRING (
SIZE(1 .. 20)) (SIZE(1 .. 9)),
     msisdn
                                               [2] IMPLICIT OCTET STRING (
SIZE( 1 .. 20 ) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
     lmsi
                                               [4] IMPLICIT OCTET STRING (
SIZE(4)) OPTIONAL,
     gsm-BearerCapability
                                               [5] IMPLICIT SEQUENCE {
        n-Bearercapun
protocolId ENUM
- 0408 (1),
                            ENUMERATED {
           gsm-0408
           gsm-0806
                          (2),
        gsm-BSSMAP ( 3 ),
ets-300102-1 ( 4 ) },
signalInfo OCTET
                           OCTET STRING ( SIZE( 1 .. 200 ) ),
         extensionContainer SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
              SEQUENCE {
                           MAP-EXTENSION .&extensionId ( {
                    ...} ) ,
                 extType MAP-EXTENSION .&ExtensionType ( {
                    ...} { @extId } ) OPTIONAL} OPTIONAL,
                                 [1] IMPLICIT SEQUENCE {
           pcs-Extensions
              ... } OPTIONAL,
            ... } OPTIONAL,
         ... } OPTIONAL,
     networkSignalInfo
                                               [6] IMPLICIT SEQUENCE {
        protocolId
           gsm-0408
gsm-0806
gsm-BSSM-
                           ENUMERATED {
                         (1),
                          (2),
           gsm-BSSMAP (3),
```

```
ets-300102-1 (4)}, signalInfo OCTET S
                          OCTET STRING ( SIZE( 1 .. 200 ) ),
        extensionContainer SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
             SEQUENCE {
                         MAP-EXTENSION .&extensionId ( {
                extId
                   ...}),
                extType MAP-EXTENSION .&ExtensionType ( {
                   ...} { @extId } ) OPTIONAL} OPTIONAL,
           pcs-Extensions [1] IMPLICIT SEQUENCE {
             ... } OPTIONAL,
           ... } OPTIONAL,
        ... } OPTIONAL,
                                             [7] IMPLICIT NULL OPTIONAL,
     suppressionOfAnnouncement
     gmsc-Address
                                             [8] IMPLICIT OCTET STRING (
SIZE( 1 .. 20 ) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
                                             [9] IMPLICIT OCTET STRING (
     callReferenceNumber
SIZE(1 .. 8)) OPTIONAL,
                                             [10] IMPLICIT NULL OPTIONAL,
     or-Interrogation
                                             [11] IMPLICIT SEQUENCE {
     extensionContainer
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
             extId
                       MAP-EXTENSION .&extensionId ( {
                ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
               ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
         ... } OPTIONAL,
        ... } OPTIONAL,
     alertingPattern
                                            [12] IMPLICIT OCTET STRING (
SIZE(1)) OPTIONAL,
     ccbs-Call
                                            [13] IMPLICIT NULL OPTIONAL,
     supportedCamelPhasesInInterrogatingNode [15] IMPLICIT BIT STRING {
        phase1 (0),
        phase2 (1),
        phase3 (2),
        phase4 (3)} (SIZE(1..16)) OPTIONAL,
                                         [14] IMPLICIT SEQUENCE {
     additionalSignalInfo
        ets-300356 (1),
          ... },
                          OCTET STRING ( SIZE( 1 .. 200 ) ),
        signalInfo
        extensionContainer SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
             SEQUENCE {
                         MAP-EXTENSION .&extensionId ( {
                   ...} ) ,
                extType MAP-EXTENSION .&ExtensionType ( {
                   ...} { @extId } ) OPTIONAL} OPTIONAL,
           pcs-Extensions [1] IMPLICIT SEQUENCE {
            ... } OPTIONAL,
           ... } OPTIONAL,
        ... } OPTIONAL,
     \verb"orNotSupportedInGMSC"
                                             [16] IMPLICIT NULL OPTIONAL,
                                             [17] IMPLICIT NULL OPTIONAL,
     pre-pagingSupported
                                             [18] IMPLICIT NULL OPTIONAL,
     longFTN-Supported
```

```
suppress-VT-CSI
                                          [19] IMPLICIT NULL OPTIONAL.
     offeredCamel4CSIsInInterrogatingNode [20] IMPLICIT BIT STRING {
        o-csi (0),
        d-csi (1 ),
        vt-csi (2),
        t-csi (3),
        mt-sms-csi (4),
        mg-csi (5),
        psi-enhancements (6 ) } ( SIZE( 7 .. 16 ) ) OPTIONAL }
  RESULT SEQUENCE {
                              OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1 ..
     roamingNumber
9)),
     extensionContainer
                              SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
          SEQUENCE {
                      MAP-EXTENSION .&extensionId ( {
             extId
                ...}),
             extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extId } ) OPTIONAL} OPTIONAL,
                         [1] IMPLICIT SEQUENCE {
        pcs-Extensions
          ... } OPTIONAL,
        ... } OPTIONAL,
     releaseResourcesSupported NULL OPTIONAL}
  ERRORS
     systemFailure |
     dataMissing |
     unexpectedDataValue |
     facilityNotSupported |
     or-NotAllowed
     absentSubscriber |
     noRoamingNumberAvailable }
  CODE local : 4
resumeCallHandling OPERATION ::= {
  ARGUMENT SEQUENCE {
    callReferenceNumber
                              [0] IMPLICIT OCTET STRING ( SIZE( 1 .. 8 ) )
OPTIONAL,
     OPTIONAL,
       rwardingData [2] IMPLICIT SEQUENCE {
forwardedToNumber [5] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) (
     forwardingData
SIZE(1..9)) OPTIONAL,
       forwardedToSubaddress [4] IMPLICIT OCTET STRING ( SIZE( 1 .. 21 ) )
OPTIONAL,
        forwardingOptions [6] IMPLICIT OCTET STRING ( SIZE( 1 ) )
OPTIONAL,
        extensionContainer [7] IMPLICIT SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
             SEQUENCE {
                extId MAP-EXTENSION .&extensionId ( {
                   ...}),
                extType MAP-EXTENSION .&ExtensionType ( {
                   ...} { @extId } ) OPTIONAL} OPTIONAL,
           pcs-Extensions [1] IMPLICIT SEQUENCE {
              ... } OPTIONAL,
```

```
... } OPTIONAL,
        longForwardedToNumber [8] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) (
SIZE(1..15)) OPTIONAL) OPTIONAL,
                                 [3] IMPLICIT OCTET STRING ( SIZE( 3 .. 8 ) )
     imsi
OPTIONAL,
                           [4] IMPLICIT SEQUENCE {
     cug-CheckInfo
        g-CheckInfo [4] IMPLICIT SEQUENCE cug-Interlock OCTET STRING ( SIZE( 4 ) ),
        cug-OutgoingAccess NULL OPTIONAL,
extensionContainer SEQUENCE {
          privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
             SEQUENCE {
                          MAP-EXTENSION .&extensionId ( {
                 extId
                    ...} ) ,
                 extType MAP-EXTENSION .&ExtensionType ( {
                    ...} { @extId } ) OPTIONAL} OPTIONAL,
           pcs-Extensions [1] IMPLICIT SEQUENCE {
             ... } OPTIONAL,
           ... } OPTIONAL,
        ... } OPTIONAL,
     o-CSI
                                 [5] IMPLICIT SEQUENCE {
        CSI [5] IMPLICIT SEQUENCE {
   o-BcsmCamelTDPDataList SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEOUENCE {
             o-BcsmTriggerDetectionPoint ENUMERATED {
                collectedInfo (2),
                 routeSelectFailure (4)},
              serviceKey
                                          INTEGER ( 0 .. 2147483647 ),
                                           [0] IMPLICIT OCTET STRING ( SIZE( 1
              gsmSCF-Address
.. 20 ) ) ( SIZE( 1 .. 9 ) ),
              defaultCallHandling
                                          [1] IMPLICIT ENUMERATED {
                 continueCall (0),
                 releaseCall
                               (1),
                 ... },
                                          [2] IMPLICIT SEQUENCE {
              extensionContainer
                privateExtensionList [0] IMPLICIT SEQUENCE (SIZE(1..10
) ) OF
                    SEQUENCE {
                                MAP-EXTENSION .&extensionId ( {
                      extId
                         ...} ) ,
                       extType MAP-EXTENSION .&ExtensionType ( {
                         ...} { @extid } ) OPTIONAL} OPTIONAL,
                 pcs-Extensions [1] IMPLICIT SEQUENCE {
                  ... } OPTIONAL,
                 ... } OPTIONAL,
              ...},
        extensionContainer SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
              SEQUENCE {
                 extId MAP-EXTENSION .&extensionId ( {
                   ...} ) ,
                 extType MAP-EXTENSION .&ExtensionType ( {
                    ...} { @extId } ) OPTIONAL} OPTIONAL,
           pcs-Extensions [1] IMPLICIT SEQUENCE {
             ... } OPTIONAL,
           ... } OPTIONAL,
```

```
camelCapabilityHandling [0] IMPLICIT INTEGER ( 1 .. 16 ) OPTIONAL,
      notificationToCSE [1] IMPLICIT NULL OPTIONAL, csiActive [2] IMPLICIT NULL OPTIONAL) OPTIONAL, extensionContainer [7] IMPLICIT SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
            SEQUENCE {
                        MAP-EXTENSION .&extensionId ( {
               extId
                  ...} ) ,
               extType MAP-EXTENSION .&ExtensionType ( {
                  ...} { @extid } ) OPTIONAL} OPTIONAL,
         pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
         ... } OPTIONAL,
                                   [8] IMPLICIT NULL OPTIONAL,
      ccbs-Possible
                                   [9] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) )
      msisdn
( SIZE( 1 .. 9 ) ) OPTIONAL,
                                   [10] IMPLICIT SEQUENCE {
     uu-Data
        uuIndicator [0] IMPLICIT OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
                              [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 131 ) )
        uui
OPTIONAL,
        uusCFInteraction [2] IMPLICIT NULL OPTIONAL,
extensionContainer [3] IMPLICIT SEQUENCE {
            privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
              SEQUENCE {
                  extId
                            MAP-EXTENSION .&extensionId ( {
                    ...} ) ,
                  extType MAP-EXTENSION .&ExtensionType ( {
                    ...} { @extid } ) OPTIONAL} OPTIONAL,
            pcs-Extensions [1] IMPLICIT SEQUENCE {
             ... } OPTIONAL,
            ... } OPTIONAL,
         ... } OPTIONAL,
      allInformationSent
                                  [11] IMPLICIT NULL OPTIONAL,
      . . . ,
      d-csi
                                   [12] IMPLICIT SEQUENCE {
        dp-AnalysedInfoCriteriaList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 )
) OF
            SEQUENCE {
              dialledNumber OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1
.. 9 ) ),
              serviceKey INTEGER ( 0 .. 2147483647 ), gsmSCF-Address OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1
              serviceKey
.. 9 ) ),
               defaultCallHandling ENUMERATED {
                 continueCall (0),
releaseCall (1),
                  ... },
               privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10
) ) OF
                     SEQUENCE { extid MAP-EXTENSION .&extensionId ( {
                           ...}),
                        extType MAP-EXTENSION .&ExtensionType ( {
                           ...} { @extId } ) OPTIONAL} OPTIONAL,
                  pcs-Extensions [1] IMPLICIT SEQUENCE {
                     ... } OPTIONAL,
```

```
... } OPTIONAL,
              ... } OPTIONAL,
                                    [1] IMPLICIT INTEGER ( 1 .. 16 )
        camelCapabilityHandling
OPTIONAL,
        extensionContainer [2] IMPLICIT SEQUENCE {
   privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
              SEQUENCE {
                          MAP-EXTENSION .&extensionId ( {
                 extId
                    ...} ) ,
                 extType
                          MAP-EXTENSION .&ExtensionType ( {
                    ...} { @extId } ) OPTIONAL} OPTIONAL,
                           [1] IMPLICIT SEQUENCE {
           pcs-Extensions
             ... } OPTIONAL,
           ... } OPTIONAL,
                                     [3] IMPLICIT NULL OPTIONAL,
        notificationToCSE
                                     [4] IMPLICIT NULL OPTIONAL,
        csi-Active
        ... } OPTIONAL,
     o-BcsmCamelTDPCriteriaList [13] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
        SEQUENCE {
           o-BcsmTriggerDetectionPoint ENUMERATED {
              collectedInfo
              routeSelectFailure (4)},
           destinationNumberCriteria [0] IMPLICIT SEQUENCE {
              matchType
                                          [0] IMPLICIT ENUMERATED {
                inhibiting (0),
enabling (1)},
              destinationNumberList
                                          [1] IMPLICIT SEQUENCE ( SIZE( 1 ..
10 ) ) OF
                OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
              destinationNumberLengthList [2] IMPLICIT SEQUENCE ( SIZE( 1 ..
3 ) ) OF
                INTEGER ( 1 .. 15 ) OPTIONAL,
              ... } OPTIONAL,
           basicServiceCriteria
                                   [1] IMPLICIT SEQUENCE ( SIZE( 1 .. 5
) ) OF
              CHOICE {
               ext-BearerService
                                     [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 5
) ),
                ext-Teleservice [3] IMPLICIT OCTET STRING ( SIZE( 1 .. 5
) ) } OPTIONAL,
           callTypeCriteria
                                       [2] IMPLICIT ENUMERATED {
              forwarded (0),
              notForwarded (1) } OPTIONAL,
           . . . ,
           o-CauseValueCriteria
                                       [3] IMPLICIT SEQUENCE ( SIZE( 1 .. 5
) ) OF
              OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
           extensionContainer [4] IMPLICIT SEQUENCE {
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                 SEQUENCE {
                    extId MAP-EXTENSION .&extensionId ( {
                      ...}),
                    extType MAP-EXTENSION .&ExtensionType ( {
                       ...} { @extId } ) OPTIONAL} OPTIONAL,
              pcs-Extensions [1] IMPLICIT SEQUENCE {
                 ... } OPTIONAL,
```

```
... } OPTIONAL } OPTIONAL ,
     basicServiceGroup2 [14] CHOICE {
  ext-BearerService [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 5 ) ),
  ext-Teleservice [3] IMPLICIT OCTET STRING ( SIZE( 1 .. 5 ) )}
OPTIONAL }
           SEQUENCE {
  RESULT
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                       MAP-EXTENSION .&extensionId ( {
              extId
                 ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                ... } { @extId } ) OPTIONAL } OPTIONAL ,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
         ... } OPTIONAL,
        ... } OPTIONAL,
     ...}
  ERRORS
             {
     forwardingFailed |
     or-NotAllowed
     unexpectedDataValue |
     dataMissing }
  CODE local : 6
setReportingState OPERATION ::= {
  ARGUMENT SEQUENCE {
     imsi
                         [0] IMPLICIT OCTET STRING ( SIZE( 3 .. 8 ) )
OPTIONAL,
     ... } OPTIONAL,
     extensionContainer [3] IMPLICIT SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
             extId
                      MAP-EXTENSION .&extensionId ( {
                ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL,
           SEQUENCE {
     ccbs-SubscriberStatus [0] IMPLICIT ENUMERATED {
        ccbsNotIdle (0),
                          (1),
        ccbsIdle
        ccbsNotReachable (2),
        ... } OPTIONAL,
     extensionContainer [1] IMPLICIT SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
              extId MAP-EXTENSION .&extensionId ( {
                ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
```

```
...} { @extid } ) OPTIONAL} OPTIONAL,
       pcs-Extensions [1] IMPLICIT SEQUENCE {
        ... } OPTIONAL,
       ... } OPTIONAL,
  ERRORS
     systemFailure |
     unidentifiedSubscriber |
     unexpectedDataValue
     dataMissing
     resourceLimitation |
    facilityNotSupported }
  CODE local : 73
statusReport OPERATION ::= {
  ARGUMENT SEQUENCE {
     imsi
       (1),
          ccbsIdle
          ccbsNotReachable (2),
          ... } OPTIONAL,
       extensionContainer [1] IMPLICIT SEQUENCE {
          privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
             SEQUENCE {
                        MAP-EXTENSION .&extensionId ( {
               extId
                 ...} ) ,
                extType MAP-EXTENSION .&ExtensionType ( {
                  ...} { @extId } ) OPTIONAL} OPTIONAL,
          pcs-Extensions [1] IMPLICIT SEQUENCE {
           ... } OPTIONAL,
          ... } OPTIONAL,
        ... } OPTIONAL,
     callReportdata [2] IMPLICIT SEQUENCE {
  monitoringMode [0] IMPLICIT ENUMERATED {
          a-side (0),
b-side (1),
          ... } OPTIONAL,
                         [1] IMPLICIT ENUMERATED {
        callOutcome
          success ( 0 ),
failure ( 1 ),
busy ( 2 ),
          ... } OPTIONAL,
        extensionContainer [2] IMPLICIT SEQUENCE {
          privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
             SEQUENCE {
                        MAP-EXTENSION .&extensionId ( {
                  ...} ) ,
                extType MAP-EXTENSION .&ExtensionType ( {
                  ...} { @extId } ) OPTIONAL} OPTIONAL,
          pcs-Extensions [1] IMPLICIT SEQUENCE {
            ... } OPTIONAL,
          ... } OPTIONAL,
        ... } OPTIONAL,
     extensionContainer [3] IMPLICIT SEQUENCE {
       privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
          SEQUENCE {
```

```
extId
                    MAP-EXTENSION .&extensionId ( {
               ...}),
            extType MAP-EXTENSION .&ExtensionType ( {
               ...} { @extid } ) OPTIONAL} OPTIONAL,
       pcs-Extensions [1] IMPLICIT SEQUENCE {
        ... } OPTIONAL,
       ... } OPTIONAL,
  RESULT
           SEQUENCE {
     extensionContainer [0] IMPLICIT SEQUENCE {
      privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
         SEQUENCE {
                    MAP-EXTENSION .&extensionId ( {
            extId
               ...} ) ,
            extType MAP-EXTENSION .&ExtensionType ( {
              ...} { @extid } ) OPTIONAL} OPTIONAL.
       pcs-Extensions [1] IMPLICIT SEQUENCE {
         ... } OPTIONAL,
       ... } OPTIONAL,
  ERRORS
    unknownSubscriber |
     systemFailure |
    unexpectedDataValue |
    dataMissing }
  CODE local : 74
remoteUserFree OPERATION ::= {
  ARGUMENT SEQUENCE {
    extensionContainer SEQUENCE {
          privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
            SEQUENCE {
               extId MAP-EXTENSION .&extensionId ( {
                ...} ) ,
               extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extId } ) OPTIONAL} OPTIONAL,
          pcs-Extensions [1] IMPLICIT SEQUENCE {
           ... } OPTIONAL,
          ... } OPTIONAL,
       ccbs-Feature
ccbs-Index [0] IMPLICIT INTEGER (1 .. 5 ) OPTIONAL, b-subscriberNumber [1] IMPLICIT OCTET STRING (SIZE(1 .. 20 )) (SIZE(1 .. 9 ) ) OPTIONAL,
       b-subscriberSubaddress [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 21 ) )
OPTIONAL,
```

```
teleservice [3] IMPLICIT OCTET STRING ( SIZE( 1 ) ) } OPTIONAL,
     translatedB-Number [3] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE(
1 .. 9 ) ),
     replaceB-Number [4] IMPLICIT NULL OPTIONAL,
alertingPattern [5] IMPLICIT OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
extensionContainer [6] IMPLICIT SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
            SEQUENCE {
                        MAP-EXTENSION .&extensionId ( {
               extId
                  ...}),
               extType MAP-EXTENSION .&ExtensionType ( {
                  ... } { @extId } ) OPTIONAL } OPTIONAL ,
                          [1] IMPLICIT SEQUENCE {
        pcs-Extensions
          ... } OPTIONAL,
        ... } OPTIONAL,
      ...}
  RESULT
             SEQUENCE {
      ruf-Outcome
                           [0] IMPLICIT ENUMERATED {
                           ( 0 ),
        accepted
        noResponseFromFreeMS (2),
noResponseFromBusyMS (3),
udubFromFreeMS (4)
        rejected
        udubFromFreeMS ( 4 ),
udubFromBusyMS ( 5 ),
         ... },
      extensionContainer [1] IMPLICIT SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
            SEQUENCE {
              extId
                        MAP-EXTENSION .&extensionId ( {
                  ...} ) ,
               extType MAP-EXTENSION .&ExtensionType ( {
                  ...} { @extId } ) OPTIONAL} OPTIONAL,
         pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL,
  ERRORS {
      unexpectedDataValue |
      dataMissing |
      incompatibleTerminal |
      absentSubscriber
      systemFailure |
      busySubscriber }
  CODE local : 75
   }
ist-Alert OPERATION ::= {
  ARGUMENT SEQUENCE {
                           [0] IMPLICIT OCTET STRING ( SIZE( 3 .. 8 ) ),
      extensionContainer [1] IMPLICIT SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
            SEQUENCE {
              extId MAP-EXTENSION .&extensionId ( {
                  ...}),
               extType MAP-EXTENSION .&ExtensionType ( {
                  ...} { @extId } ) OPTIONAL} OPTIONAL,
```

```
pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
         ... } OPTIONAL,
  RESULT
            SEQUENCE {
                               [0] IMPLICIT INTEGER ( 15 .. 255 ) OPTIONAL,
     istAlertTimer
     istInformationWithdraw [1] IMPLICIT NULL OPTIONAL, callTerminationIndicator [2] IMPLICIT ENUMERATED {
       terminateCallActivityReferred ( 0 ),
terminateAllCallActivities ( 1 ),
        ... } OPTIONAL,
     extensionContainer
                              [3] IMPLICIT SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                       MAP-EXTENSION .&extensionId ( {
              extId
                 ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
     ... } OPTIONAL,
... }
          ... } OPTIONAL,
  ERRORS
     unexpectedDataValue |
     resourceLimitation |
     unknownSubscriber
     systemFailure
     facilityNotSupported }
  CODE local : 87
ist-Command OPERATION ::= {
  ARGUMENT SEQUENCE {
     imsi
                        [0] IMPLICIT OCTET STRING ( SIZE( 3 .. 8 ) ),
     extensionContainer [1] IMPLICIT SEQUENCE {
       privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
              extId
                       MAP-EXTENSION .&extensionId ( {
                ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL,
           SEQUENCE {
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
              extId $\tt MAP-EXTENSION .&extensionId ( \{
                ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
         ... } OPTIONAL,
         ... } OPTIONAL,
```

```
{
  ERRORS
    unexpectedDataValue |
     resourceLimitation |
     unknownSubscriber |
     systemFailure |
     facilityNotSupported }
  CODE local : 88
releaseResources OPERATION ::= {
  ARGUMENT SEQUENCE {
                         OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1 .. 9 ) ),
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                       MAP-EXTENSION .&extensionId ( {
              extId
                ...}),
              extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extid } ) OPTIONAL} OPTIONAL,
                          [1] IMPLICIT SEQUENCE {
        pcs-Extensions
          ... } OPTIONAL,
        ... } OPTIONAL,
  RESULT
           SEQUENCE {
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
              extId
                       MAP-EXTENSION .&extensionId ( {
                ...}),
              extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL,
  ERRORS
           {
     unexpectedDataValue |
     systemFailure }
  CODE local : 20
END
--Expanded ASN1 Module 'MAP-SupplementaryServiceOperations'
--SIEMENS ASN.1 Compiler R6.15 (Production 6.15)
            Date: 2006-12-06 Time: 09:30:23
MAP-SupplementaryServiceOperations{ 0 identified-organization (4) etsi (0)
mobileDomain (0) gsm-Network (1) modules (3) map-SupplementaryServiceOperations
(8) version9 (9) }
DEFINITIONS
::=
BEGIN
```

```
EXPORTS
  registerSS,
  eraseSS,
  activateSS,
  deactivateSS,
  interrogateSS,
  processUnstructuredSS-Request,
  unstructuredSS-Request,
  unstructuredSS-Notify,
  registerPassword,
  getPassword,
  ss-InvocationNotification,
  registerCC-Entry,
  eraseCC-Entry;
registerSS OPERATION ::= {
  ARGUMENT SEQUENCE {
     ss-Code
                             OCTET STRING ( SIZE( 1 ) ),
     basicService
                             CHOICE {
        bearerService
                          [2] IMPLICIT OCTET STRING ( SIZE( 1 ) ),
        teleservice
                          [3] IMPLICIT OCTET STRING ( SIZE( 1 ) ) } OPTIONAL,
     forwardedToNumber
                             [4] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) )
OPTIONAL,
     forwardedToSubaddress
                             [6] IMPLICIT OCTET STRING ( SIZE( 1 .. 21 ) )
OPTIONAL,
                             [5] IMPLICIT INTEGER ( 5 .. 30 ) OPTIONAL,
     noReplyConditionTime
     defaultPriority
                             [7] IMPLICIT INTEGER ( 0 .. 15 ) OPTIONAL,
                             [8] IMPLICIT INTEGER ( 1 .. 7 ) OPTIONAL,
     nbrUser
     longFTN-Supported
                             [9] IMPLICIT NULL OPTIONAL}
            CHOICE {
  RESULT
                        [0] IMPLICIT SEQUENCE {
     forwardingInfo
        ss-Code
                               OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
        forwardingFeatureList SEQUENCE (SIZE(1..13)) OF
           SEQUENCE {
              basicService
                                      CHOICE {
                 bearerService [2] IMPLICIT OCTET STRING ( SIZE( 1 ) ),
                 teleservice
                                  [3] IMPLICIT OCTET STRING ( SIZE( 1 ) )}
OPTIONAL,
                                      [4] IMPLICIT OCTET STRING ( SIZE( 1 ) )
              ss-Status
OPTIONAL,
              forwardedToNumber
                                     [5] IMPLICIT OCTET STRING ( SIZE( 1 .. 20
) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
              forwardedToSubaddress [8] IMPLICIT OCTET STRING ( SIZE( 1 .. 21
) ) OPTIONAL,
              forwardingOptions
                                     [6] IMPLICIT OCTET STRING ( SIZE( 1 ) )
OPTIONAL,
              noReplyConditionTime
                                      [7] IMPLICIT INTEGER (5 .. 30)
OPTIONAL,
              longForwardedToNumber [9] IMPLICIT OCTET STRING ( SIZE( 1 .. 20
) ) ( SIZE( 1 .. 15 ) ) OPTIONAL},
        ...},
     callBarringInfo
                       [1] IMPLICIT SEQUENCE {
                                 OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
        ss-Code
        callBarringFeatureList SEQUENCE (SIZE(1..13)) OF
           SEQUENCE {
              basicService CHOICE {
                 bearerService [2] IMPLICIT OCTET STRING ( SIZE( 1 ) ),
                 teleservice
                                   [3] IMPLICIT OCTET STRING ( SIZE( 1 ) )}
OPTIONAL,
              ss-Status [4] IMPLICIT OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
```

```
...},
                          [3] IMPLICIT SEQUENCE {
      ss-Data
                                 OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
         ss-Code
                                 [4] IMPLICIT OCTET STRING ( SIZE( 1 ) )
         ss-Status
OPTIONAL,
         ss-SubscriptionOption CHOICE {
            cliRestrictionOption [2] IMPLICIT ENUMERATED {
               permanent
                                          ( 0 ),
               temporaryDefaultRestricted (1),
temporaryDefaultAllowed (2)},
            overrideCategory [1] IMPLICIT ENUMERATED {
         overrideEnabled (0),
overrideDisabled (1) }} OPTIONAL,
basicServiceGroupList SEQUENCE (SIZE(1...13)) OF
              CHOICE {
                                 [3] IMPLICIT OCTET STRING ( SIZE( 1 ) )}
OPTIONAL,
         defaultPriority INTEGER ( 0 .. 15 ) OPTIONAL, nbrUser [5] IMPLICIT INTEGER ( 1 .. 7
                                 [5] IMPLICIT INTEGER ( 1 .. 7 ) OPTIONAL } }
         nbrUser
   ERRORS
      systemFailure |
      dataMissing
      unexpectedDataValue |
      bearerServiceNotProvisioned |
      teleserviceNotProvisioned |
      callBarred
      illegalSS-Operation |
      ss-ErrorStatus
      ss-Incompatibility }
   CODE local : 10
eraseSS OPERATION ::= {
  ARGUMENT SEQUENCE {
                OCTET STRING ( SIZE( 1 ) ),
     ss-Code
       asicService CHOICE {
  bearerService [2] IMPLICIT OCTET STRING ( SIZE( 1 ) ),
  teleservice [3] IMPLICIT OCTET STRING ( SIZE( 1 ) )} OPTIONAL,
      basicService
      longFTN-Supported [4] IMPLICIT NULL OPTIONAL}
   RESULT CHOICE {
      OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
         ss-Code
         forwardingFeatureList SEQUENCE (SIZE(1..13)) OF
            SEQUENCE {
               basicService
                                        CHOICE {
                  bearerService [2] IMPLICIT OCTET STRING ( SIZE( 1 ) ),
teleservice [3] IMPLICIT OCTET STRING ( SIZE( 1 ) )}
OPTIONAL,
                                       [4] IMPLICIT OCTET STRING ( SIZE( 1 ) )
               ss-Status
OPTIONAL,
                                    [5] IMPLICIT OCTET STRING ( SIZE( 1 .. 20
              forwardedToNumber
) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
               forwardedToSubaddress [8] IMPLICIT OCTET STRING ( SIZE( 1 .. 21
) ) OPTIONAL,
               forwardingOptions [6] IMPLICIT OCTET STRING ( SIZE( 1 ) )
OPTIONAL,
               noReplyConditionTime [7] IMPLICIT INTEGER ( 5 .. 30 )
OPTIONAL,
               . . . ,
```

```
longForwardedToNumber [9] IMPLICIT OCTET STRING ( SIZE( 1 .. 20
) ) ( SIZE( 1 .. 15 ) ) OPTIONAL},
         ...},
      callBarringInfo [1] IMPLICIT SEQUENCE {
    ss-Code OCTET STRING /
                              OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
          callBarringFeatureList SEQUENCE (SIZE(1..13)) OF
             SEQUENCE {
                 basicService CHOICE {
                   bearerService [2] IMPLICIT OCTET STRING ( SIZE( 1 ) ),
teleservice [3] IMPLICIT OCTET STRING ( SIZE( 1 ) )}
OPTIONAL,
                 ss-Status [4] IMPLICIT OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
                 ...},
                            [3] IMPLICIT SEQUENCE {
      ss-Data
          ss-Code OCTET STRING ( SIZE( 1 ) ) OPTIONAL, ss-Status [4] IMPLICIT OCTET STRING ( SIZE( 1
                                      [4] IMPLICIT OCTET STRING ( SIZE( 1 ) )
OPTIONAL,
          ss-SubscriptionOption CHOICE {
             cliRestrictionOption [2] IMPLICIT ENUMERATED {
                 permanent
                                                (0),
                 temporaryDefaultRestricted (1),
temporaryDefaultAllowed (2)},
          overrideCategory [1] IMPLICIT ENUMERATED {
   overrideEnabled (0),
   overrideDisabled (1)} OPTIONAL,
basicServiceGroupList SEQUENCE (SIZE(1..13)) OF
             CHOICE {
                bearerService [2] IMPLICIT OCTET STRING ( SIZE( 1 ) ), teleservice [3] IMPLICIT OCTET STRING ( SIZE( 1 ) )}
OPTIONAL,
          defaultPriority INTEGER ( 0 .. 15 ) OPTIONAL, nbrUser [5] IMPLICIT INTEGER ( 1 .. 7
                                    [5] IMPLICIT INTEGER ( 1 .. 7 ) OPTIONAL}}
   ERRORS
      systemFailure |
      dataMissing
      unexpectedDataValue |
      bearerServiceNotProvisioned |
      teleserviceNotProvisioned |
      callBarred
      illegalSS-Operation |
      ss-ErrorStatus }
   CODE local : 11
activateSS OPERATION ::= {
   ARGUMENT SEQUENCE {
      ss-Code OCTET STRING ( SIZE( 1 ) ),
basicService CHOICE {
  bearerService [2] IMPLICIT OCTET STRING ( SIZE( 1 ) ),
  teleservice [3] IMPLICIT OCTET STRING ( SIZE( 1 ) )} OPTIONAL,
      longFTN-Supported [4] IMPLICIT NULL OPTIONAL}
      SEQUENCE {
OPTIONAL,
```

```
[4] IMPLICIT OCTET STRING ( SIZE( 1 ) )
              ss-Status
OPTIONAL,
               forwardedToNumber [5] IMPLICIT OCTET STRING ( SIZE( 1 .. 20
) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
               forwardedToSubaddress [8] IMPLICIT OCTET STRING ( SIZE( 1 .. 21
) ) OPTIONAL,
                                       [6] IMPLICIT OCTET STRING ( SIZE( 1 ) )
               forwardingOptions
OPTIONAL,
               noReplyConditionTime
                                       [7] IMPLICIT INTEGER ( 5 .. 30 )
OPTIONAL,
               ...,
               longForwardedToNumber [9] IMPLICIT OCTET STRING ( SIZE( 1 .. 20
) ) ( SIZE( 1 .. 15 ) ) OPTIONAL},
       ...},
      callBarringInfo [1] IMPLICIT SEQUENCE {
                               OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
         ss-Code
         callBarringFeatureList SEQUENCE (SIZE(1..13)) OF
            SEQUENCE {
               basicService CHOICE {
                  bearerService [2] IMPLICIT OCTET STRING ( SIZE( 1 ) ),
                  teleservice
                                    [3] IMPLICIT OCTET STRING ( SIZE( 1 ) )}
OPTIONAL,
               ss-Status [4] IMPLICIT OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
               ...},
      ss-Data
                         [3] IMPLICIT SEQUENCE {
         ss-Code
                               OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
         ss-Status
                                 [4] IMPLICIT OCTET STRING ( SIZE( 1 ) )
OPTIONAL,
         ss-SubscriptionOption CHOICE {
            cliRestrictionOption [2] IMPLICIT ENUMERATED {
               permanent
                                          ( 0 ),
               temporaryDefaultRestricted ( 1 ),
temporaryDefaultAllowed ( 2 ) },
            overrideCategory [1] IMPLICIT ENUMERATED {
  overrideEnabled ( 0 ),
  overrideDisabled ( 1 ) }} OPTIONAL,
         CHOICE {
              bearerService [2] IMPLICIT OCTET STRING ( SIZE( 1 ) ), teleservice [3] IMPLICIT OCTET STRING ( SIZE( 1 ) )}
OPTIONAL,
         defaultPriority INTEGER ( 0 .. 15 ) OPTIONAL, nbrUser [5] IMPLICIT INTEGER ( 1 .. 7 ) OPTIONAL}}
         nbrUser
   ERRORS
            {
      systemFailure |
      dataMissing |
      unexpectedDataValue |
      bearerServiceNotProvisioned |
      teleserviceNotProvisioned |
      callBarred |
      illegalSS-Operation
      ss-ErrorStatus
      ss-SubscriptionViolation |
      ss-Incompatibility |
      negativePW-Check
      numberOfPW-AttemptsViolation }
                      : 12
   CODE
            local
deactivateSS OPERATION ::= {
   ARGUMENT SEQUENCE {
```

```
ss-Code OCTET STRING ( SIZE( 1 , , , )
basicService CHOICE {
  bearerService [2] IMPLICIT OCTET STRING ( SIZE( 1 ) ),  
  teleservice [3] IMPLICIT OCTET STRING ( SIZE( 1 ) ) } OPTIONAL,
                         OCTET STRING ( SIZE( 1 ) ),
      ss-Code
      longFTN-Supported [4] IMPLICIT NULL OPTIONAL}
  RESULT CHOICE {

forwardingInfo [0] IMPLICIT SEQUENCE {

ss-Code OCTET STRING ( String )
                           OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
         SEQUENCE {
               basicService
                                       CHOICE {
                 asicService CHOICE {
bearerService [2] IMPLICIT OCTET STRING ( SIZE( 1 ) ),
teleservice [3] IMPLICIT OCTET STRING ( SIZE( 1 ) )}
OPTIONAL,
                                         [4] IMPLICIT OCTET STRING ( SIZE( 1 ) )
               ss-Status
OPTIONAL,
                                        [5] IMPLICIT OCTET STRING ( SIZE( 1 .. 20
               forwardedToNumber
) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
               forwardedToSubaddress [8] IMPLICIT OCTET STRING ( SIZE( 1 .. 21
) ) OPTIONAL,
               forwardingOptions
                                        [6] IMPLICIT OCTET STRING ( SIZE( 1 ) )
OPTIONAL,
               noReplyConditionTime
                                        [7] IMPLICIT INTEGER ( 5 .. 30 )
OPTIONAL,
                . . . ,
               longForwardedToNumber [9] IMPLICIT OCTET STRING ( SIZE( 1 .. 20
) ) ( SIZE( 1 .. 15 ) ) OPTIONAL },
         ...},
      callBarringInfo [1] IMPLICIT SEQUENCE {
         ss-Code
                           OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
         callBarringFeatureList SEQUENCE (SIZE(1..13)) OF
            SEQUENCE {
               basicService CHOICE {
                 bearerService [2] IMPLICIT OCTET STRING ( SIZE( 1 ) ),
                  teleservice
                                    [3] IMPLICIT OCTET STRING ( SIZE( 1 ) )}
OPTIONAL,
               ss-Status [4] IMPLICIT OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
               ...},
                          [3] IMPLICIT SEQUENCE {
      ss-Data
         -Data
ss-Code
                                 OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
         ss-Status
                                  [4] IMPLICIT OCTET STRING ( SIZE( 1 ) )
OPTIONAL,
         ss-SubscriptionOption CHOICE {
            cliRestrictionOption [2] IMPLICIT ENUMERATED {
               permanent
                                         ( 0 ),
               temporaryDefaultRestricted (1),
temporaryDefaultAllowed (2)},
            overrideCategory [1] IMPLICIT ENUMERATED {
               overrideEnabled ( 0 ),
overrideDisabled ( 1 ) }} OPTIONAL,
         CHOICE {
               bearerService [2] IMPLICIT OCTET STRING ( SIZE( 1 ) ), teleservice [3] IMPLICIT OCTET STRING ( SIZE( 1 ) )}
OPTIONAL,
         defaultPriority INTEGER ( 0 .. 15 ) OPTIONAL,
                                  [5] IMPLICIT INTEGER ( 1 .. 7 ) OPTIONAL}}
         nbrUser
      systemFailure |
      dataMissing
```

```
unexpectedDataValue |
      bearerServiceNotProvisioned |
      teleserviceNotProvisioned |
      callBarred
      illegalSS-Operation |
      ss-ErrorStatus
      ss-SubscriptionViolation |
      negativePW-Check |
      numberOfPW-AttemptsViolation }
   CODE
           local
                     : 13
interrogateSS OPERATION ::= {
   ARGUMENT
                 SEQUENCE {
                            OCTET STRING ( SIZE( 1 ) ),
      ss-Code
      basicService
                           CHOICE {
         bearerService [2] IMPLICIT OCTET STRING ( SIZE( 1 ) ),
teleservice [3] IMPLICIT OCTET STRING ( SIZE( 1 ) )
                            [3] IMPLICIT OCTET STRING ( SIZE( 1 ) ) } OPTIONAL,
         teleservice
      longFTN-Supported [4] IMPLICIT NULL OPTIONAL}
   RESULT CHOICE {
      ss-Status
                                   [0] IMPLICIT OCTET STRING ( SIZE( 1 ) ),
      basicServiceGroupList
                                 [2] IMPLICIT SEQUENCE ( SIZE( 1 .. 13 ) ) OF
         CHOICE {
      bearerService [2] IMPLICIT OCTET STRING ( SIZE( 1 ) ),
  teleservice [3] IMPLICIT OCTET STRING ( SIZE( 1 ) ) },
forwardingFeatureList [3] IMPLICIT SEQUENCE ( SIZE( 1 .. 13 ) ) OF
  SEQUENCE {
         SEQUENCE {
            basicService
                                      CHOICE {
                bearerService [2] IMPLICIT OCTET STRING ( SIZE( 1 ) ),
telegrapice [3] IMPLICIT OCTET STRING ( SIZE( 1 ) )
                teleservice
                                   [3] IMPLICIT OCTET STRING ( SIZE( 1 ) )}
OPTIONAL.
                                       [4] IMPLICIT OCTET STRING ( SIZE( 1 ) )
             ss-Status
OPTIONAL.
            forwardedToNumber
                                      [5] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 )
) ( SIZE( 1 .. 9 ) ) OPTIONAL,
            forwardedToSubaddress
                                      [8] IMPLICIT OCTET STRING ( SIZE( 1 .. 21 )
) OPTIONAL,
            forwardingOptions
                                      [6] IMPLICIT OCTET STRING ( SIZE( 1 ) )
OPTIONAL,
            noReplyConditionTime
                                      [7] IMPLICIT INTEGER ( 5 .. 30 ) OPTIONAL,
                                     [9] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 )
             longForwardedToNumber
) ( SIZE( 1 .. 15 ) ) OPTIONAL},
                                   [4] IMPLICIT SEQUENCE {
      genericServiceInfo
                                      OCTET STRING ( SIZE( 1 ) ),
         ss-Status
         cliRestrictionOption
                                      ENUMERATED {
                                            (0),
            permanent
            temporaryDefaultRestricted (1),
            temporaryDefaultAllowed (2) } OPTIONAL,
         maximumEntitledPriority [0] IMPLICIT INTEGER ( 0 .. 15 ) OPTIONAL,
         defaultPriority [1] IMPLICIT INTEGER ( 0 .. 15 ) OPTIONAL, ccbs-FeatureList [2] IMPLICIT SEQUENCE ( SIZE( 1 .. 5 ) ) OF
            SEQUENCE {
                ccbs-Index
                                          [0] IMPLICIT INTEGER ( 1 .. 5 )
OPTIONAL,
                b-subscriberNumber
                                          [1] IMPLICIT OCTET STRING ( SIZE( 1 ...
20 ) ) ( SIZE( 1 .. 9 ) ) OPTIONAL,
                b-subscriberSubaddress [2] IMPLICIT OCTET STRING ( SIZE( 1 ..
21 ) ) OPTIONAL,
```

```
[3] IMPLICIT OCTET STRING ( SIZE( 1 ) )}
                teleservice
OPTIONAL,
              ... } OPTIONAL,
                                 [3] IMPLICIT INTEGER ( 2 .. 7 ) OPTIONAL,
        nbrSB
                                 [4] IMPLICIT INTEGER ( 1 .. 7 ) OPTIONAL,
        nbrUser
                                 [5] IMPLICIT INTEGER ( 1 .. 7 ) OPTIONAL } }
        nbrSN
  ERRORS {
     systemFailure |
     dataMissing
     unexpectedDataValue
     bearerServiceNotProvisioned |
     teleserviceNotProvisioned |
     callBarred
     illegalSS-Operation |
     ss-NotAvailable }
  CODE local
                     : 14
processUnstructuredSS-Request OPERATION ::= {
  ARGUMENT SEQUENCE {
     ussd-DataCodingScheme OCTET STRING ( SIZE( 1 ) ),
                           OCTET STRING ( SIZE( 1 .. 160 ) ),
     ussd-String
     alertingPattern OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
     msisdn
                            [0] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) (
SIZE(1 .. 9) ) OPTIONAL}
  RESULT SEQUENCE {
     ussd-DataCodingScheme OCTET STRING ( SIZE( 1 ) ),
                            OCTET STRING ( SIZE( 1 .. 160 ) ),
     ussd-String
     ...}
  ERRORS
     systemFailure |
     dataMissing |
     unexpectedDataValue |
     unknownAlphabet |
     callBarred }
  CODE local
                   : 59
unstructuredSS-Request OPERATION ::= {
  ARGUMENT SEQUENCE {
     ussd-DataCodingScheme OCTET STRING ( SIZE( 1 ) ),
     ussd-String
                     OCTET STRING ( SIZE( 1 .. 160 ) ),
     . . . ,
     alertingPattern OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
     msisdn
                            [0] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) (
SIZE(1..9)) OPTIONAL}
  RESULT SEQUENCE {
     ussd-DataCodingScheme OCTET STRING ( SIZE( 1 ) ),
     ussd-String
                            OCTET STRING ( SIZE( 1 .. 160 ) ),
     ...}
  ERRORS
     systemFailure |
     dataMissing |
     unexpectedDataValue |
     absentSubscriber |
     illegalSubscriber |
     illegalEquipment |
     unknownAlphabet
     ussd-Busy }
  CODE
        local
                 : 60
```

```
unstructuredSS-Notify OPERATION ::= {
  ARGUMENT
              SEQUENCE {
     ussd-DataCodingScheme OCTET STRING ( SIZE( 1 ) ),
                            OCTET STRING ( SIZE( 1 .. 160 ) ),
     ussd-String
     alertingPattern
                            OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
                            [0] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) (
     msisdn
SIZE(1 .. 9 ) ) OPTIONAL}
  RETURN RESULT
                 TRUE
  ERRORS
     systemFailure |
     dataMissing |
     unexpectedDataValue |
     absentSubscriber
     illegalSubscriber |
     illegalEquipment |
     unknownAlphabet |
     ussd-Busy }
  CODE
          local
                   : 61
registerPassword OPERATION ::= {
  ARGUMENT OCTET STRING ( SIZE( 1 ) )
  RESULT
            NumericString ( FROM ("0"|"1"|"2"|"3"|"4"|"5"|"6"|"7"|"8"|"9" ))
(SIZE( 4 ) )
  ERRORS
     systemFailure |
     dataMissing |
     unexpectedDataValue |
     callBarred |
     ss-SubscriptionViolation |
     pw-RegistrationFailure |
     negativePW-Check |
     numberOfPW-AttemptsViolation }
  CODE
        local : 17
getPassword OPERATION ::=
  ARGUMENT ENUMERATED {
     enterPW
                      (0),
     enterNewPW
                        (1),
     enterNewPW-Again (2) }
  RESULT NumericString ( FROM ("0"|"1"|"2"|"3"|"4"|"5"|"6"|"7"|"8"|"9" ))
(SIZE( 4 ) )
  CODE local : 18
   }
ss-InvocationNotification OPERATION ::= {
  ARGUMENT
              SEQUENCE {
     imsi
                             [0] IMPLICIT OCTET STRING ( SIZE( 3 .. 8 ) ),
     msisdn
                            [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) (
SIZE(1 .. 9 )),
                            [2] IMPLICIT OCTET STRING ( SIZE( 1 ) ),
     ss-Event
     ss-EventSpecification [3] IMPLICIT SEQUENCE ( SIZE( 1 .. 2 ) ) OF
        OCTET STRING ( SIZE( 1 .. 20 ) ) OPTIONAL,
     extensionContainer [4] IMPLICIT SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                        MAP-EXTENSION .&extensionId ( {
              extId
                 ...}),
              extType MAP-EXTENSION .&ExtensionType ( {
```

```
...} { @extId } ) OPTIONAL} OPTIONAL,
         pcs-Extensions [1] IMPLICIT SEQUENCE {
           ... } OPTIONAL,
          ... } OPTIONAL,
                             [5] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) (
      b-subscriberNumber
SIZE( 1 .. 9 ) ) OPTIONAL,
                               [6] IMPLICIT ENUMERATED {
      ccbs-RequestState
         request (0),
recall (1),
active (2),
completed (3),
suspended (4),
frozen (5),
deleted (6)} OPTIONAL}
   RESULT SEQUENCE {
      extensionContainer SEQUENCE {
         privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
            SEQUENCE {
                          MAP-EXTENSION .&extensionId ( {
                extId
                   ...}),
                extType MAP-EXTENSION .&ExtensionType ( {
                  ...} { @extid } ) OPTIONAL} OPTIONAL,
         pcs-Extensions [1] IMPLICIT SEQUENCE {
           ... } OPTIONAL,
         ... } OPTIONAL,
      ...}
   ERRORS
      dataMissing |
      unexpectedDataValue |
      unknownSubscriber }
   CODE local : 72
registerCC-Entry OPERATION ::= {
   ARGUMENT SEQUENCE {
     ss-Code [0] IMPLICIT OCTET STRING ( SIZE( 1 ) ),
      ccbs-Data [1] IMPLICIT SEQUENCE {
         ccbs-Feature [0] IMPLICIT SEQUENCE {
            ccbs-Index [0] IMPLICIT INTEGER ( 1 .. 5 ) OPTIONAL,
b-subscriberNumber [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 )
) ( SIZE( 1 .. 9 ) ) OPTIONAL,
            b-subscriberSubaddress [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 21 )
) OPTIONAL,
            basicServiceGroup
                                 [3] CHOICE {
              bearerService [2] IMPLICIT OCTET STRING ( SIZE( 1 ) ),
teleservice [3] IMPLICIT OCTET STRING ( SIZE( 1 ) )}
OPTIONAL,
            ...},
         translatedB-Number [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) (
SIZE(1 .. 9 )),
                              [2] IMPLICIT BIT STRING {
         serviceIndicator
            clir-invoked (0 ),
            camel-invoked (1 )} ( SIZE( 2 .. 32 ) ) OPTIONAL,
                             [3] IMPLICIT SEQUENCE {
         callInfo
                                ENUMERATED {
            protocolId
               gsm-0408
gsm-0806
                              (1),
               gsm-0806 (2),
gsm-BSSMAP (3),
ets-300102-1 (4)},
gnalInfo OCTET
                                 OCTET STRING ( SIZE( 1 .. 200 ) ),
             signalInfo
```

```
extensionContainer SEQUENCE {
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                 SEQUENCE {
                             MAP-EXTENSION .&extensionId ( {
                    extId
                       ...}),
                    extType MAP-EXTENSION .&ExtensionType ( {
                       ...} { @extId } ) OPTIONAL} OPTIONAL,
              pcs-Extensions [1] IMPLICIT SEQUENCE {
               ... } OPTIONAL,
              ... } OPTIONAL,
        gsm-0408
gsm-0806
                             (1),
           gsm-0806 (2),

gsm-BSSMAP (3),

ets-300102-1 (4)},

signalInfo OCTET STRING (SIZE(1...200)),
           extensionContainer SEQUENCE {
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                 SEQUENCE {
                             MAP-EXTENSION .&extensionId ( {
                    extId
                      ...}),
                    extType MAP-EXTENSION .&ExtensionType ( {
                      ...} { @extId } ) OPTIONAL} OPTIONAL,
              pcs-Extensions [1] IMPLICIT SEQUENCE {
                ... } OPTIONAL,
              ... } OPTIONAL,
            ...},
        ... } OPTIONAL,
  RESULT SEQUENCE {
     ccbs-Feature [0] IMPLICIT SEQUENCE {
        ccbs-Index [0] IMPLICIT INTEGER ( 1 .. 5 ) OPTIONAL,
        b-subscriberNumber
                               [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) )
( SIZE( 1 .. 9 ) ) OPTIONAL,
        b-subscriberSubaddress [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 21 ) )
OPTIONAL,
                            [3] CHOICE {
        basicServiceGroup
          bearerService [2] IMPLICIT OCTET STRING ( SIZE( 1 ) ), teleservice [3] IMPLICIT OCTET STRING ( SIZE( 1 ) )} OPTIONAL,
        ... } OPTIONAL,
  ERRORS
     systemFailure |
     dataMissing |
     unexpectedDataValue |
     callBarred
     illegalSS-Operation |
     ss-ErrorStatus
     ss-Incompatibility |
     shortTermDenial
     longTermDenial |
     facilityNotSupported }
  CODE local : 76
```

```
eraseCC-Entry OPERATION ::= {
  ARGUMENT SEQUENCE {
     ss-Code [0] IMPLICIT OCTET STRING ( SIZE( 1 ) ),
     ccbs-Index [1] IMPLICIT INTEGER ( 1 .. 5 ) OPTIONAL,
            SEQUENCE {
     ss-Code [0] IMPLICIT OCTET STRING ( SIZE( 1 ) ),
     ss-Status [1] IMPLICIT OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
  ERRORS
     systemFailure
     dataMissing
     unexpectedDataValue |
     callBarred
     illegalSS-Operation |
     ss-ErrorStatus }
  CODE local : 77
END
--Expanded ASN1 Module 'MAP-ShortMessageServiceOperations'
--SIEMENS ASN.1 Compiler R6.15 (Production 6.15)
            Date: 2006-12-06 Time: 09:30:49
MAP-ShortMessageServiceOperations { 0 identified-organization (4) etsi (0)
mobileDomain (0) gsm-Network (1) modules (3) map-ShortMessageServiceOperations
(9) version9 (9) }
DEFINITIONS
::=
BEGIN
EXPORTS
  sendRoutingInfoForSM,
  mo-ForwardSM,
  mt-ForwardSM,
  reportSM-DeliveryStatus,
  alertServiceCentre,
  informServiceCentre,
  readyForSM;
sendRoutingInfoForSM OPERATION ::= {
  ARGUMENT SEQUENCE {
                            [0] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) (
     msisdn
SIZE( 1 .. 9 )),
                            [1] IMPLICIT BOOLEAN,
     sm-RP-PRI
     serviceCentreAddress [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ),
extensionContainer [6] IMPLICIT SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                        MAP-EXTENSION .&extensionId ( {
               extId
                  ...} ) ,
               extType MAP-EXTENSION .&ExtensionType ( {
                  ...} { @extId } ) OPTIONAL} OPTIONAL,
                              [1] IMPLICIT SEQUENCE {
        pcs-Extensions
```

```
... } OPTIONAL,
        ... } OPTIONAL,
     gprsSupportIndicator [7] IMPLICIT NULL OPTIONAL,
                 [8] IMPLICIT INTEGER ( 0 .. 10 ) OPTIONAL,
[9] IMPLICIT OCTET STRING ( SIZE( 1 .. 12 ) )
     sm-RP-MTI
     sm-RP-SMEA
OPTIONAL }
            SEQUENCE {
  RESULT
     imsi
                          OCTET STRING ( SIZE( 3 .. 8 ) ),
     locationInfoWithLMSI [0] IMPLICIT SEQUENCE {
  networkNode-Number [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) (
SIZE( 1 .. 9 )),
                           OCTET STRING ( SIZE( 4 ) ) OPTIONAL,
        lmsi
        extensionContainer SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
              SEQUENCE {
                          MAP-EXTENSION .&extensionId ( {
                 extId
                    ...} ) ,
                 extType MAP-EXTENSION .&ExtensionType ( {
                    ...} { @extId } ) OPTIONAL} OPTIONAL,
           pcs-Extensions [1] IMPLICIT SEQUENCE {
             ... } OPTIONAL,
           ... } OPTIONAL,
        SIZE( 1 .. 9 )),
          sgsn-Number [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) (
SIZE( 1 .. 9 ) ) } OPTIONAL },
     extensionContainer [4] IMPLICIT SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
              extId
                       MAP-EXTENSION .&extensionId ( {
                 ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL,
  ERRORS
     systemFailure |
     dataMissing |
     unexpectedDataValue |
     facilityNotSupported |
     unknownSubscriber
     teleserviceNotProvisioned |
     callBarred |
     absentSubscriberSM }
  CODE
          local : 45
mo-ForwardSM OPERATION ::= {
  ARGUMENT SEQUENCE {
     sm-RP-DA
                          CHOICE {
        imsi
                                   [0] IMPLICIT OCTET STRING ( SIZE( 3 .. 8 )
),
        lmsi
                                   [1] IMPLICIT OCTET STRING ( SIZE( 4 ) ),
```

```
serviceCentreAddressDA [4] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 )
),
                                  [5] IMPLICIT NULL },
        noSM-RP-DA
                          CHOICE {
     sm-RP-OA
                                  [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 )
        msisdn
) ( SIZE( 1 .. 9 ) ),
                                 [4] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 )
        serviceCentreAddressOA
),
        noSM-RP-OA
                                  [5] IMPLICIT NULL },
                        OCTET STRING ( SIZE( 1 .. 200 ) ),
     sm-RP-UI
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                       MAP-EXTENSION .&extensionId ( {
              extId
                 ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extId } ) OPTIONAL} OPTIONAL,
                        [1] IMPLICIT SEQUENCE {
        pcs-Extensions
          ... } OPTIONAL,
        ... } OPTIONAL,
     imsi
                         OCTET STRING ( SIZE( 3 .. 8 ) ) OPTIONAL}
   RESULT
           SEQUENCE {
     sm-RP-UI
                         OCTET STRING ( SIZE( 1 .. 200 ) ) OPTIONAL,
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
              extId
                       MAP-EXTENSION .&extensionId ( {
                 ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL,
      ...}
   ERRORS
     systemFailure |
     unexpectedDataValue |
     facilityNotSupported |
     sm-DeliveryFailure }
   CODE local : 46
mt-ForwardSM OPERATION ::= {
   ARGUMENT SEQUENCE {
     sm-RP-DA
                          CHOICE {
                                  [0] IMPLICIT OCTET STRING ( SIZE( 3 .. 8 )
        imsi
),
                                  [1] IMPLICIT OCTET STRING ( SIZE( 4 ) ),
                                  [4] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 )
        serviceCentreAddressDA
),
       noSM-RP-DA
                                  [5] IMPLICIT NULL },
     sm-RP-OA
                          CHOICE {
                                  [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 )
        msisdn
) ( SIZE( 1 .. 9 ) ),
        serviceCentreAddressOA
                                 [4] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 )
),
        noSM-RP-OA
                                  [5] IMPLICIT NULL},
                        OCTET STRING ( SIZE( 1 .. 200 ) ),
     sm-RP-UI
```

```
moreMessagesToSend NULL OPTIONAL,
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                       MAP-EXTENSION .&extensionId ( {
              extId
                 ...}),
              extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL,
  RESULT
            SEQUENCE {
                         OCTET STRING ( SIZE( 1 .. 200 ) ) OPTIONAL,
     sm-RP-UI
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
              extId
                       MAP-EXTENSION .&extensionId ( {
                 ...}),
              extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extid } ) OPTIONAL} OPTIONAL,
        pcs-Extensions
                       [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL,
     ...}
  ERRORS
     systemFailure |
     dataMissing |
     unexpectedDataValue
     facilityNotSupported |
     unidentifiedSubscriber |
     illegalSubscriber |
     illegalEquipment |
     subscriberBusyForMT-SMS |
     sm-DeliveryFailure
     absentSubscriberSM }
  CODE local : 44
reportSM-DeliveryStatus OPERATION ::= {
  ARGUMENT SEQUENCE {
     msisdn
                                            OCTET STRING ( SIZE( 1 .. 20 ) )
(SIZE(1..9)),
     serviceCentreAddress
                                            OCTET STRING ( SIZE( 1 .. 20 ) ),
     sm-DeliveryOutcome
                                            ENUMERATED {
        memoryCapacityExceeded ( 0 ),
                                (1),
        absentSubscriber
                                (2)},
        successfulTransfer
                                            [0] IMPLICIT INTEGER ( 0 .. 255 )
     absentSubscriberDiagnosticSM
OPTIONAL,
     extensionContainer
                                            [1] IMPLICIT SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
              extId
                      MAP-EXTENSION .&extensionId ( {
                 ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extId } ) OPTIONAL} OPTIONAL,
```

```
pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL,
     gprsSupportIndicator
                                            [2] IMPLICIT NULL OPTIONAL,
                                            [3] IMPLICIT NULL OPTIONAL,
     deliveryOutcomeIndicator
     additionalSM-DeliveryOutcome
                                            [4] IMPLICIT ENUMERATED {
        \label{lem:memoryCapacityExceeded} \mbox{ ( 0 ),}
        absentSubscriber (1), successfulTransfer (2)} OPTIONAL,
     additionalAbsentSubscriberDiagnosticSM [5] IMPLICIT INTEGER ( 0 .. 255 )
OPTIONAL }
  RESULT
           SEQUENCE {
     storedMSISDN
                        OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1 .. 9 ) )
OPTIONAL,
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
              extId
                        MAP-EXTENSION .&extensionId ( {
                 ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL,
  ERRORS
     dataMissing |
     unexpectedDataValue |
     unknownSubscriber
     messageWaitingListFull }
  CODE local : 47
alertServiceCentre OPERATION ::= {
  ARGUMENT SEQUENCE {
    msisdn
                           OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1 .. 9 )
),
     serviceCentreAddress OCTET STRING ( SIZE( 1 .. 20 ) ),
     . . . }
  RETURN RESULT
                  TRUE
  ERRORS {
     systemFailure
     dataMissing |
     unexpectedDataValue }
  CODE local : 64
informServiceCentre OPERATION ::= {
  ARGUMENT SEQUENCE {
                                           OCTET STRING ( SIZE( 1 .. 20 ) )
     storedMSISDN
( SIZE( 1 .. 9 ) ) OPTIONAL,
     mw-Status
                                           BIT STRING {
        sc-AddressNotIncluded (0),
        mnrf-Set (1),
        mcef-Set (2),
        mnrg-Set (3 ) } ( SIZE( 6 .. 16 ) ) OPTIONAL,
     extensionContainer
                                            SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
              extId MAP-EXTENSION .&extensionId ( {
```

```
...}),
              extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
         ... } OPTIONAL,
        ... } OPTIONAL,
     absentSubscriberDiagnosticSM INTEGER ( 0 .. 255 ) OPTIONAL, additionalAbsentSubscriberDiagnosticSM [0] IMPLICIT INTEGER ( 0 .. 255 )
OPTIONAL }
           local : 63
  CODE
readyForSM OPERATION ::= {
  ARGUMENT SEQUENCE {
                          [0] IMPLICIT OCTET STRING ( SIZE( 3 .. 8 ) ),
     imsi
                        ENUMERATED {
     alertReason
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
             extId
                      MAP-EXTENSION .&extensionId ( {
               ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
         ... } OPTIONAL,
        ... } OPTIONAL,
  RESULT
           SEQUENCE {
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
             extId
                      MAP-EXTENSION .&extensionId ( {
                ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
         ... } OPTIONAL,
        ... } OPTIONAL,
  ERRORS
     dataMissing
     unexpectedDataValue |
     facilityNotSupported |
     unknownSubscriber }
  CODE local : 66
END
-- Expanded ASN1 Module 'MAP-Group-Call-Operations'
--SIEMENS ASN.1 Compiler R6.15 (Production 6.15)
```

```
Date: 2006-12-06 Time: 09:31:01
MAP-Group-Call-Operations { 0 identified-organization (4) etsi (0) mobileDomain
(0) gsm-Network (1) modules (3) map-Group-Call-Operations (22) version9 (9) }
DEFINITIONS
::=
BEGIN
EXPORTS
  prepareGroupCall,
   sendGroupCallEndSignal,
   forwardGroupCallSignalling,
   processGroupCallSignalling;
prepareGroupCall OPERATION ::= {
   ARGUMENT SEQUENCE {
      teleservice OCTET STRING ( SIZE( 1 .. 5 ) ),
asciCallReference OCTET STRING ( SIZE( 1 .. 8 ) ),
codec-Info OCTET STRING ( SIZE( 5 .. 10 ) ),
cipheringAlgorithm OCTET STRING ( SIZE( 1 ) ),
groupKeyNumber-Vk-Id [0] IMPLICIT INTEGER ( 0 .. 15 ) OPTIONAL,

[11] IMPLICIT OCTET STRING ( SIZE( 8 ) ) OP
                               OCTET STRING ( SIZE( 1 .. 5 ) ),
                             [1] IMPLICIT OCTET STRING ( SIZE( 8 ) ) OPTIONAL,
      groupKey
                               [2] IMPLICIT INTEGER ( 0 .. 15 ) OPTIONAL,
      priority
      uplinkFree [3] IMPLICIT NULL OPTIONAL, extensionContainer [4] IMPLICIT SEQUENCE {
          privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
             SEQUENCE {
                extId
                           MAP-EXTENSION .&extensionId ( {
                    ...}),
                 extType MAP-EXTENSION .&ExtensionType ( {
                    ...} { @extid } ) OPTIONAL} OPTIONAL,
          pcs-Extensions [1] IMPLICIT SEQUENCE {
            ... } OPTIONAL,
          ... } OPTIONAL,
      vstk
                               [5] IMPLICIT OCTET STRING ( SIZE( 16 ) ) OPTIONAL,
      vstk-rand
                               [6] IMPLICIT OCTET STRING ( SIZE( 5 ) ) OPTIONAL}
   RESULT SEQUENCE {
      groupCallNumber
                            OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1 .. 9 ) ),
      extensionContainer SEQUENCE {
          privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
             SEQUENCE {
                            MAP-EXTENSION .&extensionId ( {
                    ...} ) ,
                 extType MAP-EXTENSION .&ExtensionType ( {
                    ...} { @extid } ) OPTIONAL} OPTIONAL,
                             [1] IMPLICIT SEQUENCE {
          pcs-Extensions
             ... } OPTIONAL,
          ... } OPTIONAL,
      systemFailure |
      noGroupCallNumberAvailable |
      unexpectedDataValue }
   CODE local : 39
```

```
}
sendGroupCallEndSignal OPERATION ::= {
  ARGUMENT SEQUENCE {
                        OCTET STRING ( SIZE( 3 .. 8 ) ) OPTIONAL,
     imsi
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
          SEQUENCE {
                      MAP-EXTENSION .&extensionId ( {
             extId
                ...}),
             extType MAP-EXTENSION .&ExtensionType ( {
               ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
         ... } OPTIONAL,
        ... } OPTIONAL,
  RESULT
            SEQUENCE {
                       SEQUENCE {
     extensionContainer
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
          SEQUENCE {
             extId
                      MAP-EXTENSION .&extensionId ( {
                ...} ) ,
             extType MAP-EXTENSION .&ExtensionType ( {
               ...} { @extid } ) OPTIONAL } OPTIONAL .
        pcs-Extensions [1] IMPLICIT SEQUENCE {
         ... } OPTIONAL,
        ... } OPTIONAL,
     ...}
          local : 40
  CODE
processGroupCallSignalling OPERATION ::= {
  ARGUMENT SEQUENCE {
     uplinkRequest [0] IMPLICIT NULL OPTIONAL,
     uplinkReleaseIndication [1] IMPLICIT NULL OPTIONAL,
     releaseGroupCall [2] IMPLICIT NULL OPTIONAL, extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
             extId
                     MAP-EXTENSION .&extensionId ( {
               ...} ) ,
             extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL,
         local : 41
  CODE
forwardGroupCallSignalling OPERATION ::= {
  ARGUMENT SEQUENCE {
                            OCTET STRING ( SIZE( 3 .. 8 ) ) OPTIONAL,
```

```
uplinkReleaseCommand [4] IMPLICIT NULL OPTIONAL,
extensionContainer SEQUENCE {
         privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
             SEQUENCE {
                extId
                           MAP-EXTENSION .&extensionId ( {
                    ...}),
                extType MAP-EXTENSION .&ExtensionType ( {
                    ...} { @extid } ) OPTIONAL} OPTIONAL,
          pcs-Extensions [1] IMPLICIT SEQUENCE {
            ... } OPTIONAL,
          ... } OPTIONAL,
         ateAttributes [5] IMPLICIT SEQUENCE {
downlinkAttached [5] IMPLICIT NULL OPTIONAL,
uplinkAttached [6] IMPLICIT NULL OPTIONAL,
dualCommunication [7] IMPLICIT NULL OPTIONAL,
callOriginator [8] IMPLICIT NULL OPTIONAL OPTIONAL OPTIONAL }
local : 42
      stateAttributes
   CODE
END
-- Expanded ASN1 Module 'MAP-LocationServiceOperations'
--SIEMENS ASN.1 Compiler R6.15 (Production 6.15)
             Date: 2006-12-06 Time: 09:31:13
MAP-LocationServiceOperations { 0 identified-organization (4) etsi (0)
mobileDomain (0) qsm-Network (1) modules (3) map-LocationServiceOperations (24)
version9 (9) }
DEFINITIONS
: :=
BEGIN
EXPORTS
  provideSubscriberLocation,
   sendRoutingInfoForLCS,
   subscriberLocationReport;
sendRoutingInfoForLCS OPERATION ::= {
   ARGUMENT SEQUENCE {
                              [0] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE(
     mlcNumber
1 .. 9 ) ),
                             [1] CHOICE {
      targetMS
                       [0] IMPLICIT OCTET STRING ( SIZE( 3 .. 8 ) ),
         imsi
         msisdn
                       [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1 ..
9))},
      extensionContainer [2] IMPLICIT SEQUENCE {
         privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
             SEQUENCE {
                           MAP-EXTENSION .&extensionId ( {
                extId
                    ...} ) ,
                extType MAP-EXTENSION .&ExtensionType ( {
                    ... } { @extId } ) OPTIONAL } OPTIONAL ,
```

```
pcs-Extensions [1] IMPLICIT SEQUENCE {
                    ... } OPTIONAL,
                  ... } OPTIONAL,
                        SEQUENCE {
     RESULT
          networkNode-Number OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OCTET CONTROL

OC
9))},
           lcsLocationInfo
                                                                          OCTET STRING ( SIZE( 1 .. 20 ) ) (
SIZE( 1 .. 9 ) ),
                                                                              [0] IMPLICIT OCTET STRING ( SIZE( 4 ) )
                 lmsi
OPTIONAL,
                 extensionContainer
                                                                             [1] IMPLICIT SEQUENCE {
                      privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
                            SEQUENCE {
                                                     MAP-EXTENSION .&extensionId ( {
                                  extId
                                       ...}),
                                  extType MAP-EXTENSION .&ExtensionType ( {
                                        ...} { @extid } ) OPTIONAL} OPTIONAL,
                       pcs-Extensions [1] IMPLICIT SEQUENCE {
                         ... } OPTIONAL,
                       ... } OPTIONAL,
                 SIZE( 1 .. 9 )),
                     sgsn-Number [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) (
SIZE( 1 .. 9 ) ) } OPTIONAL,
                 supportedLCS-CapabilitySets [4] IMPLICIT BIT STRING {
                       lcsCapabilitySet1 (0),
                       lcsCapabilitySet2 (1 ),
                      lcsCapabilitySet3 (2),
                      lcsCapabilitySet4 (3 ) { (SIZE( 2 .. 16 ) ) OPTIONAL,
                 additional-LCS-CapabilitySets [5] IMPLICIT BIT STRING {
                      lcsCapabilitySet1 (0),
                       lcsCapabilitySet2 (1 ),
                       lcsCapabilitySet3 (2),
                       lcsCapabilitySet4 (3 )} ( SIZE( 2 .. 16 ) ) OPTIONAL},
           extensionContainer [2] IMPLICIT SEQUENCE {
                 privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
                       SEQUENCE {
                                              MAP-EXTENSION .&extensionId ( {
                                  ...} ) ,
                            extType MAP-EXTENSION .&ExtensionType ( {
                                 ...} { @extId } ) OPTIONAL} OPTIONAL,
                 pcs-Extensions [1] IMPLICIT SEQUENCE {
                     ... } OPTIONAL,
                 ... } OPTIONAL,
           v-gmlc-Address [3] IMPLICIT OCTET STRING ( SIZE( 5 .. 17 ) )
OPTIONAL,
           h-gmlc-Address [4] IMPLICIT OCTET STRING ( SIZE( 5 .. 17 ) )
OPTIONAL,
                                      [5] IMPLICIT OCTET STRING ( SIZE( 5 .. 17 ) )
           ppr-Address
OPTIONAL,
```

```
additional-v-qmlc-Address [6] IMPLICIT OCTET STRING ( SIZE( 5 .. 17 ) )
OPTIONAL }
  ERRORS
     systemFailure |
     dataMissing |
     unexpectedDataValue |
     facilityNotSupported |
     unknownSubscriber |
     absentSubscriber |
     unauthorizedRequestingNetwork }
  CODE local : 85
provideSubscriberLocation OPERATION ::= {
  ARGUMENT SEQUENCE {
                          SEQUENCE {
     locationType
        locationEstimateType [0] IMPLICIT ENUMERATED {
                                       ( 0 ),
           currentLocation
                                      (1),
           currentOrLastKnownLocation
           initialLocation
                                         (2),
           . . . .
           activateDeferredLocation
                                      (3),
           cancelDeferredLocation
                                        (4)},
        deferredLocationEventType [1] IMPLICIT BIT STRING {
           msAvailable (0),
           enteringIntoArea (1),
           leavingFromArea (2),
           beingInsideArea (3)} (SIZE(1..16)) OPTIONAL},
     mlc-Number OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE( 1 .. 9 ) ), lcs-ClientID [0] IMPLICIT SEQUENCE {
        s-ClientID [0] IMPLICIT SEQUENCE {
lcsClientType [0] IMPLICIT ENUMERATED {
           emergencyServices ( 0 ),
valueAddedServices ( 1 ),
                                     (1),
           plmnOperatorServices (2),
           lawfulInterceptServices ( 3 ),
           ... },
        lcsClientExternalID [1] IMPLICIT SEQUENCE {
           externalAddress [0] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) (
SIZE(1 .. 9 ) ) OPTIONAL,
           extensionContainer [1] IMPLICIT SEQUENCE {
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                 SEQUENCE {
                             MAP-EXTENSION .&extensionId ( {
                    extId
                    extType MAP-EXTENSION .&ExtensionType ( {
                       ...} { @extid } ) OPTIONAL} OPTIONAL,
                                    [1] IMPLICIT SEQUENCE {
              pcs-Extensions
                 ... } OPTIONAL,
               ... } OPTIONAL,
            ... } OPTIONAL,
        lcsClientDialedByMS [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) )
OPTIONAL,
        lcsClientInternalID [3] IMPLICIT ENUMERATED {
           broadcastService
                                       (0),
                                        (1),
           o-andM-HPLMN
           o-andM-VPLMN
                                       (2),
                                       (3),
           anonymousLocation
           targetMSsubscribedService (4),
            ... } OPTIONAL,
```

```
( SIZE( 1 .. 63 ) ),
          lcs-FormatIndicator [3] IMPLICIT ENUMERATED {
             logicalName (0),
e-mailAddress (1),
msisdn (2),
                            (3),
             url (3),
sipUrl (4),
             url
             ... } OPTIONAL } OPTIONAL ,
                           [5] IMPLICIT OCTET STRING ( SIZE( 2 .. 63 ) )
        lcsAPN
OPTIONAL,
       ( SIZE( 1 .. 63 ) ),
           . . . ,
          lcs-FormatIndicator [2] IMPLICIT ENUMERATED {
  logicalName ( 0 ),
             e-mailAddress (1),
             msisdn
                            (2),
             url
                            (3),
                            (4),
             ... } OPTIONAL } OPTIONAL } OPTIONAL ,
     privacyOverride [1] IMPLICIT NULL OPTIONAL,
     imsi
                        [2] IMPLICIT OCTET STRING ( SIZE( 3 .. 8 ) )
OPTIONAL,
    msisdn
                        [3] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) (
SIZE(1 .. 9)) OPTIONAL,
                         [4] IMPLICIT OCTET STRING ( SIZE( 4 ) ) OPTIONAL,
     imei
                         [5] IMPLICIT OCTET STRING ( SIZE( 8 ) ) OPTIONAL,
     lcs-Priority [6] IMPLICIT OCTET STRIN
lcs-QoS [7] IMPLICIT SEQUENCE {
                        [6] IMPLICIT OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
       horizontal-accuracy
                                [0] IMPLICIT OCTET STRING ( SIZE( 1 ) )
OPTIONAL,
       verticalCoordinateRequest [1] IMPLICIT NULL OPTIONAL,
       vertical-accuracy [2] IMPLICIT OCTET STRING ( SIZE( 1 ) )
OPTIONAL,
       responseTime
                               [3] IMPLICIT SEQUENCE {
          responseTimeCategory ENUMERATED {
            lowdelay (0), delaytolerant (1),
             ... },
           ... } OPTIONAL,
       extensionContainer [4] IMPLICIT SEQUENCE {
          privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
             SEQUENCE {
                        MAP-EXTENSION .&extensionId ( {
                  ...} ) ,
                extType MAP-EXTENSION .&ExtensionType ( {
                  ...} { @extId } ) OPTIONAL} OPTIONAL,
          pcs-Extensions [1] IMPLICIT SEQUENCE {
            ... } OPTIONAL,
           ... } OPTIONAL,
        ... } OPTIONAL,
     extensionContainer [8] IMPLICIT SEQUENCE {
       privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
          SEQUENCE {
```

```
extId
                           MAP-EXTENSION .&extensionId ( {
                    ...} ) ,
                 extType MAP-EXTENSION .&ExtensionType ( {
                    ...} { @extid } ) OPTIONAL} OPTIONAL,
          pcs-Extensions [1] IMPLICIT SEQUENCE {
            ... } OPTIONAL,
          ... } OPTIONAL,
      supportedGADShapes [9] IMPLICIT BIT STRING {
          ellipsoidPoint (0),
          ellipsoidPointWithUncertaintyCircle (1 ),
          ellipsoidPointWithUncertaintyEllipse (2),
          polygon (3),
          ellipsoidPointWithAltitude (4),
          ellipsoidPointWithAltitudeAndUncertaintyElipsoid (5),
          ellipsoidArc (6)} (SIZE(7..16)) OPTIONAL,
      lcs-ReferenceNumber [10] IMPLICIT OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
lcsServiceTypeID [11] IMPLICIT INTEGER ( 0 .. 127 ) OPTIONAL,
lcsCodeword [12] IMPLICIT SEQUENCE {
  dataCodingScheme [0] IMPLICIT OCTET STRING ( SIZE( 1 ) ),
  lcsCodewordString [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 160 ) ) (
SIZE( 1 .. 20 )),
         ... } OPTIONAL,
      lcs-PrivacyCheck [13] IMPLICIT SEQUENCE {
          callSessionUnrelated [0] IMPLICIT ENUMERATED {
             allowedWithoutNotification ( 0 ),
             allowedWithNotification (1),
allowedIfNoResponse (2),
             allowedIfNoResponse (2), restrictedIfNoResponse (3),
             notAllowed
                                               (4),
             ... },
          callSessionRelated [1] IMPLICIT ENUMERATED {
             allowedWithoutNotification ( 0 ),
             allowedWithNotification (1), allowedIfNoResponse (2),
             allowedIfNoResponse (2), restrictedIfNoResponse (3), (4),
             notAllowed
                                              (4),
            ... } OPTIONAL,
          ... } OPTIONAL,
      areaList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
                 SEQUENCE {
                       eaType [0] IMPLICIT ENUMERATED {
  countryCode (0),
  plmnId (1),
                    areaType
                       locationAreaId (2),
routingAreaId (3),
cellGlobalId (4),
                       . . . ,
                       utranCellId (5)},
                    areaIdentification [1] IMPLICIT OCTET STRING ( SIZE( 2 .. 7
)),
                    ...},
          occurrenceInfo [1] IMPLICIT ENUMERATED {
             oneTimeEvent
                             ( 0 ),
             multipleTimeEvent ( 1 ),
             ... } OPTIONAL,
          intervalTime [2] IMPLICIT INTEGER ( 1 .. 32767 ) OPTIONAL,
          ... } OPTIONAL,
```

```
h-qmlc-Address [15] IMPLICIT OCTET STRING ( SIZE( 5 .. 17 ) )
OPTIONAL }
             SEQUENCE {
  RESULT
                                      OCTET STRING ( SIZE( 1 .. 20 ) ),
      locationEstimate
     ageOfLocationEstimate
                                       [0] IMPLICIT INTEGER ( 0 .. 32767 )
OPTIONAL,
                                       [1] IMPLICIT SEQUENCE {
     extensionContainer
         privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
            SEQUENCE {
                        MAP-EXTENSION .&extensionId ( {
               extId
                  ...}),
               extType MAP-EXTENSION .&ExtensionType ( {
                  ...} { @extId } ) OPTIONAL} OPTIONAL,
         pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
         ... } OPTIONAL,
                                       [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 91
      add-LocationEstimate
) ) OPTIONAL,
     deferredmt-lrResponseIndicator [3] IMPLICIT NULL OPTIONAL,
      geranPositioningData
                                      [4] IMPLICIT OCTET STRING ( SIZE( 2 .. 10
) ) OPTIONAL,
     utranPositioningData
                                       [5] IMPLICIT OCTET STRING ( SIZE( 3 .. 11
) ) OPTIONAL,
                                       [6] CHOICE {
     cellIdOrSai
        cellGlobalIdOrServiceAreaIdFixedLength
                                                   [0] IMPLICIT OCTET STRING (
SIZE( 7 ) ),
        laiFixedLength
                                                     [1] IMPLICIT OCTET STRING (
SIZE(5))} OPTIONAL,
     sai-Present [7] IMPLICIT NULL OPTIONAL,
accuracyFulfilmentIndicator [8] IMPLICIT ENUMERATED {
  requestedAccuracyFulfilled ( 0 ),
         requestedAccuracyNotFulfilled (1),
        ... } OPTIONAL}
   ERRORS
     systemFailure |
      dataMissing
      unexpectedDataValue |
      facilityNotSupported |
      unidentifiedSubscriber |
      illegalSubscriber |
      illegalEquipment |
      absentSubscriber
      unauthorizedRequestingNetwork |
      unauthorizedLCSClient |
      positionMethodFailure }
   CODE local : 83
   }
subscriberLocationReport OPERATION ::= {
               SEQUENCE {
                                    ENUMERATED {
      lcs-Event
                                   ( 0 ),
         emergencyCallOrigination
         emergencyCallRelease
                                    (1),
                                     (2),
         mo-lr
         . . . ,
         deferredmt-lrResponse (3)},
s-ClientID SEQUENCE {
lcsClientType [0] IMPLICIT ENUMERATED {
      lcs-ClientID
            emergencyServices (0),
            valueAddedServices
                                      (1),
```

```
plmnOperatorServices ( 2 ),
lawfulInterceptServices ( 3 ),
            ... },
         lcsClientExternalID [1] IMPLICIT SEQUENCE {
            externalAddress [0] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) (
SIZE(1 .. 9 ) OPTIONAL,
           extensionContainer [1] IMPLICIT SEQUENCE {
               privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                  SEQUENCE {
                     extId
                              MAP-EXTENSION .&extensionId ( {
                        ...}),
                     extType MAP-EXTENSION .&ExtensionType ( {
                        ...} { @extId } ) OPTIONAL} OPTIONAL,
               pcs-Extensions [1] IMPLICIT SEQUENCE {
                  ... } OPTIONAL,
               ... } OPTIONAL,
            ... } OPTIONAL,
         lcsClientDialedByMS [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) )
OPTIONAL,
         lcsClientInternalID [3] IMPLICIT ENUMERATED {
            broadcastService ( 0 ),
            o-andM-HPLMN
                                         (1),
                                        (2),
            o-andM-VPLMN
            anonymousLocation
                                        (3),
            targetMSsubscribedService (4),
            ... } OPTIONAL,
         lcsClientName [4] IMPLICIT SEQUENCE {
  dataCodingScheme [0] IMPLICIT OCTET STRING ( SIZE( 1 ) ),
  nameString [2] IMPLICIT OCTET STRING ( SIZE( 1 .. 160 ) )
( SIZE( 1 .. 63 ) ),
            lcs-FormatIndicator [3] IMPLICIT ENUMERATED {
               logicalName ( 0 ),
               e-mailAddress (1),
               msisdn
                               (2),
               url
                               (3),
              sipUrl (3),
               ... } OPTIONAL } OPTIONAL ,
                              [5] IMPLICIT OCTET STRING ( SIZE( 2 .. 63 ) )
         lcsAPN
OPTIONAL,
         lcsRequestorID [6] IMPLICIT SEQUENCE {
           dataCodingScheme [0] IMPLICIT OCTET STRING ( SIZE( 1 ) ), requestorIDString [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 160 ) )
( SIZE( 1 .. 63 ) ),
            lcs-FormatIndicator [2] IMPLICIT ENUMERATED {
               logicalName ( 0 ),
e-mailAddress ( 1 ),
               msisdn
                                (2),
               url
                                (3),
                        (4),
              sipUrl
               ... } OPTIONAL } OPTIONAL },
      lcsLocationInfo SEQUENCE {
        networkNode-Number
                                         OCTET STRING ( SIZE( 1 .. 20 ) ) (
SIZE( 1 .. 9 )),
         lmsi
                                         [0] IMPLICIT OCTET STRING ( SIZE( 4 ) )
OPTIONAL,
         extensionContainer
                                        [1] IMPLICIT SEQUENCE {
            privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
```

```
SEQUENCE {
                           MAP-EXTENSION .&extensionId ( {
                 extId
                    ...}),
                           MAP-EXTENSION .&ExtensionType ( {
                 extType
                    ...} { @extId } ) OPTIONAL} OPTIONAL,
                            [1] IMPLICIT SEQUENCE {
           pcs-Extensions
              ... } OPTIONAL,
            ... } OPTIONAL,
         gprsNodeIndicator
                                        [2] IMPLICIT NULL OPTIONAL,
        SIZE( 1 .. 9 ) ),
           9 ) ),
sgsn-Number    [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) (
SIZE( 1 .. 9 ) )} OPTIONAL,
        supportedLCS-CapabilitySets [4] IMPLICIT BIT STRING {
           lcsCapabilitySet1 (0 ),
lcsCapabilitySet2 (1 ),
lcsCapabilitySet3 (2 ),
lcsCapabilitySet4 (3 )} ( SIZE( 2 .. 16 ) ) OPTIONAL,
        additional-LCS-CapabilitySets [5] IMPLICIT BIT STRING {
           lcsCapabilitySet1 (0),
           lcsCapabilitySet2 (1 ),
lcsCapabilitySet3 (2 ),
lcsCapabilitySet4 (3 )} ( SIZE( 2 .. 16 ) ) OPTIONAL},
                                   [0] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 )
     msisdn
) ( SIZE( 1 .. 9 ) ) OPTIONAL,
     imsi
                                   [1] IMPLICIT OCTET STRING ( SIZE( 3 .. 8 ) )
OPTIONAL,
                                   [2] IMPLICIT OCTET STRING ( SIZE( 8 ) )
     imei
OPTIONAL,
     na-ESRD
                                   [3] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 )
) ( SIZE( 1 .. 9 ) ) OPTIONAL,
     na-ESRK
                                   [4] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 )
) ( SIZE( 1 .. 9 ) ) OPTIONAL,
     locationEstimate
                                  [5] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 )
) OPTIONAL,
     ageOfLocationEstimate
                                  [6] IMPLICIT INTEGER ( 0 .. 32767 )
OPTIONAL,
     slr-ArgExtensionContainer [7] IMPLICIT SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE (SIZE(1..10)) OF
           SEQUENCE {
                        MAP-EXTENSION .&extensionId ( {
                 ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                 ... } { @extId } ) OPTIONAL } OPTIONAL ,
         slr-Arq-PCS-Extensions [1] IMPLICIT SEQUENCE {
           na-ESRK-Request [0] IMPLICIT NULL OPTIONAL OPTIONAL,
         ... } OPTIONAL,
     add-LocationEstimate
                                  [8] IMPLICIT OCTET STRING ( SIZE( 1 .. 91 )
) OPTIONAL,
     deferredmt-lrData [9] IMPLICIT SEQUENCE {
         deferredLocationEventType BIT STRING {
           msAvailable (0),
           enteringIntoArea (1),
           leavingFromArea (2),
           beingInsideArea (3)} (SIZE(1..16)),
```

```
terminationCause
                           [0] IMPLICIT ENUMERATED {
                                                (0),
           normal
           errorundefined
                                                (1),
                                                (2),
           internalTimeout
                                                (3),
           congestion
                                                (4),
           mt-lrRestart
           privacyViolation
                                                (5),
           shapeOfLocationEstimateNotSupported
                                               ( 6 ) } OPTIONAL,
        lcsLocationInfo [1] IMPLICIT SEQUENCE {
                                         OCTET STRING ( SIZE( 1 .. 20 ) ) (
           networkNode-Number
SIZE( 1 .. 9 ) ),
           lmsi
                                          [0] IMPLICIT OCTET STRING ( SIZE( 4
) ) OPTIONAL,
                                          [1] IMPLICIT SEQUENCE {
           extensionContainer
              privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) )
OF
                 SEQUENCE {
                            MAP-EXTENSION .&extensionId ( {
                    extId
                      ...} ) ,
                    extType MAP-EXTENSION .&ExtensionType ( {
                      ...} { @extId } ) OPTIONAL} OPTIONAL,
              pcs-Extensions [1] IMPLICIT SEQUENCE {
                ... } OPTIONAL,
              ... } OPTIONAL,
           gprsNodeIndicator
additional-Number
                                          [2] IMPLICIT NULL OPTIONAL,
                                          [3] CHOICE {
             msc-Number [0] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) (
SIZE( 1 .. 9 )),
             sgsn-Number [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) (
SIZE( 1 .. 9 ) ) } OPTIONAL,
           supportedLCS-CapabilitySets [4] IMPLICIT BIT STRING {
              lcsCapabilitySet1 (0),
              lcsCapabilitySet2 (1 ),
              lcsCapabilitySet3 (2),
              lcsCapabilitySet4 (3 ) { (SIZE( 2 .. 16 ) ) OPTIONAL,
           additional-LCS-CapabilitySets [5] IMPLICIT BIT STRING {
              lcsCapabilitySet1 (0),
              lcsCapabilitySet2 (1 ),
              lcsCapabilitySet3 (2),
              lcsCapabilitySet4 (3 )} ( SIZE( 2 .. 16 ) ) OPTIONAL} OPTIONAL,
        ... } OPTIONAL,
                          [10] IMPLICIT OCTET STRING ( SIZE( 1 ) )
     lcs-ReferenceNumber
OPTIONAL,
     geranPositioningData
                                 [11] IMPLICIT OCTET STRING ( SIZE( 2 .. 10 )
) OPTIONAL,
                                 [12] IMPLICIT OCTET STRING ( SIZE( 3 .. 11 )
     utranPositioningData
) OPTIONAL,
                                  [13] CHOICE {
     cellIdOrSai
        cellGlobalIdOrServiceAreaIdFixedLength
                                                [0] IMPLICIT OCTET STRING (
SIZE(7)),
       laiFixedLength
                                                 [1] IMPLICIT OCTET STRING (
SIZE(5))} OPTIONAL,
                          [14] IMPLICIT OCTET STRING ( SIZE( 5 .. 17 )
     h-gmlc-Address
) OPTIONAL,
     lcsServiceTypeID
sai-Present
                                [15] IMPLICIT INTEGER ( 0 .. 127 ) OPTIONAL,
                                 [17] IMPLICIT NULL OPTIONAL,
     sai-Present
     pseudonymIndicator
                                 [18] IMPLICIT NULL OPTIONAL,
     accuracyFulfilmentIndicator [19] IMPLICIT ENUMERATED {
        requestedAccuracyFulfilled
                                       (0),
```

```
requestedAccuracyNotFulfilled (1),
  ... } OPTIONAL}
RESULT SEQUENCE {
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                        MAP-EXTENSION .&extensionId ( {
              extId
                 ...}),
              extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
         ... } OPTIONAL,
      . . . ,
                         [0] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE(
     na-ESRK
1 .. 9 ) ) OPTIONAL,
                          [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) ) ( SIZE(
     na-ESRD
1 .. 9 ) ) OPTIONAL}
  ERRORS
     systemFailure |
     dataMissing |
     resourceLimitation |
     unexpectedDataValue |
     unknownSubscriber
     unauthorizedRequestingNetwork |
     unknownOrUnreachableLCSClient }
  CODE local : 86
F.ND
            Expanded ASN1 Module 'MAP-Errors'
--SIEMENS ASN.1 Compiler R6.15 (Production 6.15)
             Date: 2006-12-06 Time: 09:31:23
MAP-Errors { 0 identified-organization (4) etsi (0) mobileDomain (0) qsm-Network
(1) modules (3) map-Errors (10) version9 (9) }
DEFINITIONS
::=
BEGIN
EXPORTS
  systemFailure,
  dataMissing,
  unexpectedDataValue,
  facilityNotSupported,
  incompatibleTerminal,
  resourceLimitation,
  unknownSubscriber,
  numberChanged,
  unknownMSC,
  unidentifiedSubscriber,
  unknownEquipment,
  roamingNotAllowed,
   illegalSubscriber,
  illegalEquipment,
```

```
bearerServiceNotProvisioned,
  teleserviceNotProvisioned,
  noHandoverNumberAvailable,
  subsequentHandoverFailure,
  targetCellOutsideGroupCallArea,
  tracingBufferFull,
  or-NotAllowed,
  noRoamingNumberAvailable,
  busySubscriber,
  noSubscriberReply,
  absentSubscriber,
  callBarred,
  forwardingViolation,
  forwardingFailed,
  cug-Reject,
  ati-NotAllowed,
  atsi-NotAllowed,
  atm-NotAllowed,
  informationNotAvailable,
  illegalSS-Operation,
  ss-ErrorStatus,
  ss-NotAvailable,
  ss-SubscriptionViolation,
  ss-Incompatibility,
  unknownAlphabet,
  ussd-Busy,
  pw-RegistrationFailure,
  negativePW-Check,
  numberOfPW-AttemptsViolation,
  shortTermDenial,
  longTermDenial,
  subscriberBusyForMT-SMS,
  sm-DeliveryFailure,
  messageWaitingListFull,
  absentSubscriberSM,
  noGroupCallNumberAvailable,
  unauthorizedRequestingNetwork,
  unauthorizedLCSClient,
  positionMethodFailure,
  unknownOrUnreachableLCSClient,
  mm-EventNotSupported;
systemFailure ERROR ::=
  PARAMETER CHOICE {
     networkResource
                                       ENUMERATED {
        plmn
                           (0),
        hlr
                           (1),
        vlr
                           (2),
                           (3),
        pvlr
        controllingMSC
                           (4),
                           (5),
         vmsc
                           (6),
         eir
                           (7),
     extensibleSystemFailureParam
                                       SEQUENCE {
        networkResource
                                     ENUMERATED {
            plmn
                              (0),
                              (1),
           hlr
                              (2),
            vlr
                              (3),
            pvlr
                              (4),
            controllingMSC
            vmsc
                              (5),
            eir
                              (6),
```

```
rss ( 7 ) } OPTIONAL, extensionContainer SEQUENCE {
                                 SEQUENCE {
           privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
             SEQUENCE {
                          MAP-EXTENSION .&extensionId ( {
                extId
                   ...}),
                 extType MAP-EXTENSION .&ExtensionType ( {
                   ...} { @extId } ) OPTIONAL} OPTIONAL,
           pcs-Extensions [1] IMPLICIT SEQUENCE {
            ... } OPTIONAL,
           ... } OPTIONAL,
        additionalNetworkResource [0] IMPLICIT ENUMERATED {
           sgsn (0),
           ggsn (1),
gmlc (2),
gsmSCF (3),
nplr (4),
auc (5),
           auc (5 /,
... } OPTIONAL}}
  CODE
           local : 34
dataMissing ERROR ::= {
  PARAMETER SEQUENCE {
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
              extId
                       MAP-EXTENSION .&extensionId ( {
                ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
         ... } OPTIONAL,
        ... } OPTIONAL,
     ...}
  CODE
           local : 35
unexpectedDataValue ERROR ::= {
  PARAMETER SEQUENCE {
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                      MAP-EXTENSION .&extensionId ( {
                ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
               ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL,
     ...}
         local : 36
  CODE
facilityNotSupported ERROR ::= {
  PARAMETER SEQUENCE {
```

```
SEQUENCE {
     extensionContainer
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                       MAP-EXTENSION .&extensionId ( {
              extId
                 ...}),
              extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extid } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
         ... } OPTIONAL,
        ... } OPTIONAL,
     shapeOfLocationEstimateNotSupported [0] IMPLICIT NULL OPTIONAL,
neededLcsCapabilityNotSupportedInServingNode [1] IMPLICIT NULL OPTIONAL}
  CODE local : 21
incompatibleTerminal ERROR ::= {
  PARAMETER SEQUENCE {
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
              extId
                       MAP-EXTENSION .&extensionId ( {
                ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions
                       [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
       ... } OPTIONAL,
  CODE
           local : 28
resourceLimitation ERROR ::= {
  PARAMETER SEQUENCE {
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
             extId MAP-EXTENSION .&extensionId ( {
                ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL,
         local : 51
  CODE
unknownSubscriber ERROR ::= {
  PARAMETER SEQUENCE {
     extensionContainer
                                 SEOUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
             extId MAP-EXTENSION .&extensionId ( {
                ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
```

```
...} { @extId } ) OPTIONAL} OPTIONAL,
       \verb"pcs-Extensions" [1] IMPLICIT SEQUENCE" \{
        ... } OPTIONAL,
       ... } OPTIONAL,
     (0),
       imsiUnknown
       gprsSubscriptionUnknown
                              (1),
       . . . ,
                              ( 2 ) } OPTIONAL}
       npdbMismatch
  CODE local : 1
  }
numberChanged ERROR ::=
  PARAMETER SEQUENCE {
    extensionContainer SEQUENCE {
       privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
          SEQUENCE {
                     MAP-EXTENSION .&extensionId ( {
             extId
               ...} ) ,
             extType MAP-EXTENSION .&ExtensionType ( {
              ...} { @extId } ) OPTIONAL} OPTIONAL,
       pcs-Extensions [1] IMPLICIT SEQUENCE {
         ... } OPTIONAL,
       ... } OPTIONAL,
     ...}
  CODE
          local : 44
unknownMSC ERROR ::= {
  CODE local : 3
unidentifiedSubscriber ERROR ::= {
  PARAMETER SEQUENCE {
    extensionContainer SEQUENCE {
       privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
          SEQUENCE {
            extId MAP-EXTENSION .&extensionId ( {
               ...} ) ,
             extType MAP-EXTENSION .&ExtensionType ( {
               ...} { @extid } ) OPTIONAL} OPTIONAL,
       pcs-Extensions [1] IMPLICIT SEQUENCE {
         ... } OPTIONAL,
       ... } OPTIONAL,
        local : 5
  CODE
unknownEquipment ERROR ::= {
  CODE local : 7
roamingNotAllowed ERROR ::= {
  PARAMETER SEQUENCE {
     roamingNotAllowedCause ENUMERATED {
       plmnRoamingNotAllowed (0),
       operatorDeterminedBarring (3)},
```

```
extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
          SEQUENCE {
                      MAP-EXTENSION .&extensionId ( {
             extId
                ...}),
             extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extid } ) OPTIONAL} OPTIONAL,
                       [1] IMPLICIT SEQUENCE {
        pcs-Extensions
         ... } OPTIONAL,
        ... } OPTIONAL,
     ...}
          local : 8
  CODE
illegalSubscriber ERROR ::= {
  PARAMETER SEQUENCE {
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
          SEQUENCE {
                      MAP-EXTENSION .&extensionId ( {
             extId
               ...} ) ,
             extType MAP-EXTENSION .&ExtensionType ( {
               ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions
                      [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
       ... } OPTIONAL,
     ...}
  CODE
         local : 9
illegalEquipment ERROR ::= {
  PARAMETER SEQUENCE {
     extensionContainer SEQUENCE {
       privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
          SEQUENCE {
             extId
                      MAP-EXTENSION .&extensionId ( {
                ...} ) ,
             extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
       ... } OPTIONAL,
     ...}
         local : 12
  CODE
bearerServiceNotProvisioned ERROR ::= {
  PARAMETER SEQUENCE {
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
          SEQUENCE {
             extId MAP-EXTENSION .&extensionId ( {
                ...} ) ,
             extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extId } ) OPTIONAL} OPTIONAL,
```

```
[1] IMPLICIT SEQUENCE {
        pcs-Extensions
          ... } OPTIONAL,
        ... } OPTIONAL,
          local : 10
  CODE
teleserviceNotProvisioned ERROR ::= {
  PARAMETER SEQUENCE {
    extensionContainer SEQUENCE {
       privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
          SEQUENCE {
             extId
                      MAP-EXTENSION .&extensionId ( {
                ...} ) ,
             extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
         ... } OPTIONAL,
        ... } OPTIONAL,
     ...}
  CODE
          local : 11
noHandoverNumberAvailable ERROR ::= {
  CODE local : 25
subsequentHandoverFailure ERROR ::= {
  CODE local : 26
targetCellOutsideGroupCallArea ERROR ::= {
  PARAMETER SEQUENCE {
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
          SEQUENCE {
                      MAP-EXTENSION .&extensionId ( {
                ...} ) ,
             extType MAP-EXTENSION .&ExtensionType ( {
               ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
         ... } OPTIONAL,
        ... } OPTIONAL,
     ...}
  CODE
          local : 42
tracingBufferFull ERROR ::= {
  PARAMETER SEQUENCE {
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
          SEQUENCE {
                      MAP-EXTENSION .&extensionId ( {
             ext.Td
             \ldots\} ) , extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
```

```
... } OPTIONAL,
        ... } OPTIONAL,
  CODE
           local : 40
noRoamingNumberAvailable ERROR ::= {
  PARAMETER SEQUENCE {
    extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                       MAP-EXTENSION .&extensionId ( {
              extId
                 ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                 ... } { @extId } ) OPTIONAL } OPTIONAL ,
                        [1] IMPLICIT SEQUENCE {
        pcs-Extensions
          ... } OPTIONAL,
        ... } OPTIONAL,
     ...}
           local : 39
   CODE
absentSubscriber ERROR ::= {
  PARAMETER SEQUENCE {
        tensionContainer SEQUENCE {
  privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
     extensionContainer
           SEQUENCE {
              extId
                       MAP-EXTENSION .&extensionId ( {
                ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL,
     absentSubscriberReason [0] IMPLICIT ENUMERATED {
        imsiDetach ( 0 ),
        restrictedArea (1),
noPageResponse (2),
        ...,
  busySubscriber ERROR ::= {
  PARAMETER SEQUENCE {
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
              extId \tt `MAP-EXTENSION .\&extensionId ( {}
                ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
        \dots \} \ \{ \ @extId \ \ \} \ ) \ OPTIONAL \} \ OPTIONAL, \\ pcs-Extensions \ \ [1] \ IMPLICIT \ SEQUENCE \ \{
          ... } OPTIONAL,
         ... } OPTIONAL,
```

```
ccbs-Possible [0] IMPLICIT NULL OPTIONAL, ccbs-Busy [1] IMPLICIT NULL OPTIONAL}
CODE local : 45
noSubscriberReply ERROR ::= {
  PARAMETER SEQUENCE {
     extensionContainer SEQUENCE {
       privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
          SEQUENCE {
                      MAP-EXTENSION .&extensionId ( {
             extId
                ...} ) ,
             extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
         ... } OPTIONAL,
        ... } OPTIONAL,
     ...}
          local : 46
  CODE
callBarred ERROR ::= {
  PARAMETER CHOICE {
     privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
             SEQUENCE {
                extId
                        MAP-EXTENSION .&extensionId ( \{
                  ...} ) ,
                extType MAP-EXTENSION .&ExtensionType ( {
                   ...} { @extId } ) OPTIONAL} OPTIONAL,
          pcs-Extensions [1] IMPLICIT SEQUENCE {
            ... } OPTIONAL,
          ... } OPTIONAL,
        unauthorisedMessageOriginator [1] IMPLICIT NULL OPTIONAL } }
  CODE
         local : 13
  }
forwardingViolation ERROR ::= {
  PARAMETER SEQUENCE {
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
          SEQUENCE {
             extId MAP-EXTENSION .&extensionId ( {
             extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
         ... } OPTIONAL,
        ... } OPTIONAL,
```

```
CODE
        local
forwardingFailed ERROR ::= {
  PARAMETER SEQUENCE {
    extensionContainer SEQUENCE {
       privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
          SEQUENCE {
                     MAP-EXTENSION .&extensionId ( {
            extId
               ...} ) ,
             extType MAP-EXTENSION .&ExtensionType ( {
               ...} { @extid } ) OPTIONAL} OPTIONAL,
       pcs-Extensions [1] IMPLICIT SEQUENCE {
        ... } OPTIONAL,
       ... } OPTIONAL,
     ...}
         local : 47
  CODE
cug-Reject ERROR ::= {
  PARAMETER SEQUENCE {
    (0),
       incomingCallsBarredWithinCUG
       subscriberNotMemberOfCUG
                                                  (1),
       requestedBasicServiceViolatesCUG-Constraints (5),
       calledPartySS-InteractionViolation
                                                 (7) } OPTIONAL,
     extensionContainer SEQUENCE {
       privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
          SEQUENCE {
                     MAP-EXTENSION .&extensionId ( {
             extId
               ...}),
             extType MAP-EXTENSION .&ExtensionType ( {
               ...} { @extId } ) OPTIONAL} OPTIONAL,
       pcs-Extensions [1] IMPLICIT SEQUENCE {
        ... } OPTIONAL,
       ... } OPTIONAL,
     ...}
          local : 15
  CODE
or-NotAllowed ERROR ::=
  PARAMETER SEQUENCE {
     extensionContainer SEQUENCE {
       privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
          SEQUENCE {
                     MAP-EXTENSION .&extensionId ( {
               ...} ) ,
             extType MAP-EXTENSION .&ExtensionType ( {
               ...} { @extId } ) OPTIONAL} OPTIONAL,
       pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
       ... } OPTIONAL,
     ...}
         local : 48
  CODE
```

```
ati-NotAllowed ERROR ::= {
  PARAMETER SEQUENCE {
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
          SEQUENCE {
                      MAP-EXTENSION .&extensionId ( {
             extId
                ...}),
             extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extid } ) OPTIONAL} OPTIONAL,
                       [1] IMPLICIT SEQUENCE {
        pcs-Extensions
         ... } OPTIONAL,
        ... } OPTIONAL,
     ...}
          local : 49
  CODE
atsi-NotAllowed ERROR ::= {
  PARAMETER SEQUENCE {
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
          SEQUENCE {
             extId
                      MAP-EXTENSION .&extensionId ( {
               ...} ) ,
             extType MAP-EXTENSION .&ExtensionType ( {
               ...} { @extid } ) OPTIONAL} OPTIONAL,
        pcs-Extensions
                       [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
       ... } OPTIONAL,
  CODE
          local : 60
atm-NotAllowed ERROR ::= {
  PARAMETER SEQUENCE {
     extensionContainer SEQUENCE {
       privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
          SEQUENCE {
                     MAP-EXTENSION .&extensionId ( {
             extId
               ...} ) ,
             extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extid } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
       ... } OPTIONAL,
         local : 61
  CODE
informationNotAvailable ERROR ::= {
  PARAMETER SEQUENCE {
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
          SEQUENCE {
             extId MAP-EXTENSION .&extensionId ( {
                ...} ) ,
             extType MAP-EXTENSION .&ExtensionType ( {
```

```
...} { @extid } ) OPTIONAL} OPTIONAL,
       \verb"pcs-Extensions" [1] IMPLICIT SEQUENCE" \{
         ... } OPTIONAL,
        ... } OPTIONAL,
          local : 62
  CODE
illegalSS-Operation ERROR ::= {
  PARAMETER SEQUENCE {
    extensionContainer SEQUENCE {
       privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
          SEQUENCE {
                      MAP-EXTENSION .&extensionId ( {
             extId
                ...} ) ,
             extType MAP-EXTENSION .&ExtensionType ( {
               ...} { @extId } ) OPTIONAL} OPTIONAL,
       pcs-Extensions [1] IMPLICIT SEQUENCE {
         ... } OPTIONAL,
       ... } OPTIONAL,
  CODE
          local : 16
ss-ErrorStatus ERROR ::= {
  PARAMETER OCTET STRING ( SIZE( 1 ) )
  CODE local : 17
ss-NotAvailable ERROR ::= {
  PARAMETER SEQUENCE {
     extensionContainer SEQUENCE {
       privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
          SEQUENCE {
             extId
                     MAP-EXTENSION .&extensionId ( {
               ...} ) ,
             extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extId } ) OPTIONAL} OPTIONAL,
       pcs-Extensions [1] IMPLICIT SEQUENCE {
         ... } OPTIONAL,
       ... } OPTIONAL,
     ...}
        local : 18
  CODE
ss-SubscriptionViolation ERROR ::= {
  PARAMETER SEQUENCE {
     extensionContainer SEQUENCE {
       privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
          SEQUENCE {
             extId MAP-EXTENSION .&extensionId ( {
               ...} ) ,
             extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
```

```
... } OPTIONAL,
  CODE local : 19
ss-Incompatibility ERROR ::= {
  PARAMETER SEQUENCE {
     ss-Code [1] IMPLICIT OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
basicService CHOICE {
     ss-Code
      bearerService [2] IMPLICIT OCTET STRING ( SIZE( 1 ) ),
teleservice [3] IMPLICIT OCTET STRING ( SIZE( 1 ) )} OPTIONAL,
       teleservice
     ss-Status [4] IMPLICIT OCTET STRING ( SIZE( 1 ) ) OPTIONAL,
     ...}
  CODE local : 20
unknownAlphabet ERROR ::= {
  CODE local : 71
ussd-Busy ERROR ::= {
  CODE local : 72
pw-RegistrationFailure ERROR ::= {
  PARAMETER ENUMERATED {
   undetermined (0),
invalidFormat (1),
newPasswordsMismatch (2)}
  CODE local : 37
negativePW-Check ERROR ::= {
  CODE local : 38
numberOfPW-AttemptsViolation ERROR ::= {
  CODE local : 43
shortTermDenial ERROR ::= {
  PARAMETER SEQUENCE {
   . . . }
  CODE local : 29
longTermDenial ERROR ::= {
  PARAMETER SEQUENCE {
   ...}
  CODE local : 30
subscriberBusyForMT-SMS ERROR ::= {
  PARAMETER SEQUENCE {
     privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
          SEQUENCE {
             extId MAP-EXTENSION .&extensionId ( {
             extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extId } ) OPTIONAL} OPTIONAL,
```

```
[1] IMPLICIT SEQUENCE {
        pcs-Extensions
          ... } OPTIONAL,
        ... } OPTIONAL,
     gprsConnectionSuspended NULL OPTIONAL}
  CODE local : 31
sm-DeliveryFailure ERROR ::= {
  PARAMETER SEQUENCE {
    sm-EnumeratedDeliveryFailureCause ENUMERATED {
       memoryCapacityExceeded (0),
equipmentProtocolError (1),
equipmentNotSM-Equipped (2),
unknownServiceCentre (3),
        sc-Congestion
                                    (4),
        invalidSME-Address
                                    (5),
        subscriberNotSC-Subscriber (6)}
                                       OCTET STRING ( SIZE( 1 .. 200 ) )
     diagnosticInfo
OPTIONAL,
     extensionContainer
                                       SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
              extId
                      MAP-EXTENSION .&extensionId ( {
                ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
       ... } OPTIONAL,
          local : 32
  CODE
messageWaitingListFull ERROR ::= {
  PARAMETER SEQUENCE {
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
              extId MAP-EXTENSION .&extensionId ( {
                ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL,
         local : 33
  CODE
absentSubscriberSM ERROR ::= {
  PARAMETER SEQUENCE {
                                            INTEGER ( 0 .. 255 ) OPTIONAL,
     absentSubscriberDiagnosticSM
     extensionContainer
                                            SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                    MAP-EXTENSION .&extensionId ( {
              extId
                 ...} ) ,
```

```
extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extid } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
         ... } OPTIONAL,
        ... } OPTIONAL,
     additionalAbsentSubscriberDiagnosticSM [0] IMPLICIT INTEGER ( 0 .. 255 )
OPTIONAL }
          local : 6
  CODE
   }
\verb|noGroupCallNumberAvailable ERROR ::= \{ \\
  PARAMETER SEQUENCE {
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                       MAP-EXTENSION .&extensionId ( {
              extId
                 ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extid } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL,
   CODE
           local : 50
unauthorizedRequestingNetwork ERROR ::= {
  PARAMETER SEQUENCE {
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
              extId
                       MAP-EXTENSION .&extensionId ( {
                 ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL,
      ...}
         local : 52
   CODE
unauthorizedLCSClient ERROR ::= {
  PARAMETER SEQUENCE {
     unauthorizedLCSClient-Diagnostic [0] IMPLICIT ENUMERATED {
        noAdditionalInformation
                                                        (0),
        clientNotInMSPrivacyExceptionList
                                                        (1),
        callToClientNotSetup
                                                        (2),
        privacyOverrideNotApplicable
                                                        (3),
        disallowedByLocalRegulatoryRequirements
        unauthorizedPrivacyClass
                                                        (5),
        unauthorizedCallSessionUnrelatedExternalClient ( 6 ),
unauthorizedCallSessionRelatedExternalClient ( 7 ) } OPTIONAL,
                               [1] IMPLICIT SEQUENCE {
      extensionContainer
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
```

```
extId MAP-EXTENSION .&extensionId ( {
                ...}),
             extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extid } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
         ... } OPTIONAL,
        ... } OPTIONAL,
  CODE
          local : 53
positionMethodFailure ERROR ::= {
  PARAMETER SEQUENCE {
     positionMethodFailure-Diagnostic [0] IMPLICIT ENUMERATED {
       congestion
                                               (0),
        insufficientResources
                                                (1),
                                                (2),
        insufficientMeasurementData
        inconsistentMeasurementData
        locationProcedureNotCompleted
        locationProcedureNotSupportedByTargetMS
        goSNotAttainable
        positionMethodNotAvailableInNetwork
        positionMethodNotAvailableInLocationArea ( 8 ),
        ... } OPTIONAL,
     extensionContainer
                                    [1] IMPLICIT SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
          SEQUENCE {
             extId
                      MAP-EXTENSION .&extensionId ( {
               ...} ) ,
             extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
         ... } OPTIONAL,
       ... } OPTIONAL,
     ...}
  CODE
          local : 54
unknownOrUnreachableLCSClient ERROR ::= {
  PARAMETER SEQUENCE {
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
          SEQUENCE {
             extId MAP-EXTENSION .&extensionId ( {
               ...} ) ,
             extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extid } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
       ... } OPTIONAL,
        local : 58
  CODE
mm-EventNotSupported ERROR ::= {
  PARAMETER SEQUENCE {
    extensionContainer SEQUENCE {
```

```
privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
            SEQUENCE {
              extId
                        MAP-EXTENSION .&extensionId ( {
                 ·
...} ) ,
               extType MAP-EXTENSION .&ExtensionType ( {
         ...} { @extid } ) OPTIONAL} OPTIONAL,
pcs-Extensions [1] IMPLICIT SEQUENCE {
     ... } OPTIONAL,
... }
          ... } OPTIONAL,
         local : 59
   CODE
   }
END
```

B.2 Fully Expanded ASN.1 Source of MAP-DialogueInformation

```
Expanded ASN1 Module 'MAP-DialogueInformation'
--SIEMENS ASN.1 Compiler R6.15 (Production 6.15)
             Date: 2006-12-06 Time: 09:31:39
MAP-DialogueInformation { 0 identified-organization (4) etsi (0) mobileDomain (0)
gsm-Network (1) modules (3) map-DialogueInformation (3) version9 (9) }
DEFINITIONS
: :=
BEGIN
EXPORTS
  map-DialogueAS,
  MAP-DialoguePDU;
map-DialogueAS OBJECT IDENTIFIER ::= { ccitt (0) identified-organization (4)
etsi (0) mobileDomain (0) qsm-Network (1) 1 map-DialoquePDU (1) version1 (1) }
MAP-DialoguePDU ::= CHOICE {
                   [0] IMPLICIT SEQUENCE {
     destinationReference [0] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) )
OPTIONAL,
     originationReference [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) )
OPTIONAL,
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                       MAP-EXTENSION .&extensionId ( {
              extId
                 ...}),
              extType MAP-EXTENSION .&ExtensionType ( {
                 ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL },
  map-accept
                       [1] IMPLICIT SEQUENCE {
     extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                       MAP-EXTENSION .&extensionId ( {
              extId
                 ...} ) ,
              extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extId } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL },
                      [2] IMPLICIT SEQUENCE {
  map-close
     ...,
```

```
extensionContainer SEQUENCE {
     privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
        SEQUENCE {
                     MAP-EXTENSION .&extensionId ( {
           extId
              ...}),
           extType MAP-EXTENSION .&ExtensionType ( {
              ...} { @extId } ) OPTIONAL} OPTIONAL,
     pcs-Extensions [1] IMPLICIT SEQUENCE {
       ... } OPTIONAL,
      ... } OPTIONAL },
map-refuse [3] IMPLICIT SEQUENCE {
                          ENUMERATED {
  reason
     noReasonGiven
                                   ( 0 ),
     invalidDestinationReference (1),
invalidOriginatingReference (2)},
  extensionContainer
                                 SEQUENCE {
     privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
        SEQUENCE {
                    MAP-EXTENSION .&extensionId ( {
           extId
              ...} ) ,
           extType MAP-EXTENSION .&ExtensionType ( {
              ...} { @extId } ) OPTIONAL} OPTIONAL,
     pcs-Extensions [1] IMPLICIT SEQUENCE {
       ... } OPTIONAL,
      ... } OPTIONAL,
  alternativeApplicationContext OBJECT IDENTIFIER OPTIONAL },
map-userAbort [4] IMPLICIT SEQUENCE {
  map-UserAbortChoice CHOICE {
     userSpecificReason[0] IMPLICIT NULL,userResourceLimitation[1] IMPLICIT NULL,resourceUnavailable[2] IMPLICIT ENUMERATED {
     shortTermResourceLimitation (0),
longTermResourceLimitation (1)},
applicationProcedureCancellation [3] IMPLICIT ENUMERATED {
        \label{eq:handoverCancellation} \text{ ( 0 ),}
        handovercance::
radioChannelRelease
                                    (1),
        networkPathRelease
                                     (2),
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
        SEQUENCE {
                    MAP-EXTENSION .&extensionId ( {
              ...} ) ,
           extType MAP-EXTENSION .&ExtensionType ( {
              ...} { @extId } ) OPTIONAL} OPTIONAL,
     pcs-Extensions [1] IMPLICIT SEQUENCE {
        ... } OPTIONAL,
... } OPTIONAL },
map-providerAbort [5] IMPLICIT SEQUENCE {
  abnormalDialogue ( 0 ),
invalidPDU ( 1 ) },
```

```
extensionContainer SEQUENCE {
        privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
           SEQUENCE {
                       MAP-EXTENSION .&extensionId ( {
              extId
                 ...}),
              extType MAP-EXTENSION .&ExtensionType ( {
                ...} { @extid } ) OPTIONAL} OPTIONAL,
        pcs-Extensions [1] IMPLICIT SEQUENCE {
          ... } OPTIONAL,
        ... } OPTIONAL } }
MAP-OpenInfo ::= SEQUENCE {
  destinationReference [0] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) )
OPTIONAL.
  originationReference [1] IMPLICIT OCTET STRING ( SIZE( 1 .. 20 ) )
OPTIONAL,
  . . . .
  extensionContainer SEQUENCE {
     privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
        SEQUENCE {
           extId
                    MAP-EXTENSION .&extensionId ( {
             ...} ) ,
           extType MAP-EXTENSION .&ExtensionType ( {
             ...} { @extId } ) OPTIONAL} OPTIONAL,
     pcs-Extensions [1] IMPLICIT SEQUENCE {
       ... } OPTIONAL,
     ... } OPTIONAL}
MAP-AcceptInfo ::= SEQUENCE {
  extensionContainer SEQUENCE {
     privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
        SEQUENCE {
           extId
                    MAP-EXTENSION .&extensionId ( {
              ...}),
           extType MAP-EXTENSION .&ExtensionType ( {
             ...} { @extid } ) OPTIONAL} OPTIONAL,
     pcs-Extensions [1] IMPLICIT SEQUENCE {
      ... } OPTIONAL,
     ... } OPTIONAL }
MAP-CloseInfo ::= SEQUENCE {
  extensionContainer SEQUENCE {
     privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
        SEQUENCE {
           extId $\tt MAP\textsubseteq} .&extensionId ( \{
             ...} ) ,
           extType MAP-EXTENSION .&ExtensionType ( {
             ...} { @extId } ) OPTIONAL} OPTIONAL,
     pcs-Extensions [1] IMPLICIT SEQUENCE {
       ... } OPTIONAL,
      ... } OPTIONAL}
```

```
MAP-RefuseInfo ::= SEQUENCE {
                                   ENUMERATED {
  reason
                                    ( 0 ),
     noReasonGiven
                                     (1),
      invalidDestinationReference
                                  (2)},
      invalidOriginatingReference
   extensionContainer
                                   SEQUENCE {
      privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
         SEQUENCE {
                      MAP-EXTENSION .&extensionId ( {
            extId
               ...}),
            extType MAP-EXTENSION .&ExtensionType ( {
               ...} { @extId } ) OPTIONAL} OPTIONAL,
                       [1] IMPLICIT SEQUENCE {
      pcs-Extensions
        ... } OPTIONAL,
      ... } OPTIONAL,
   alternativeApplicationContext OBJECT IDENTIFIER OPTIONAL}
Reason ::= ENUMERATED {
   noReasonGiven
                                  (0),
   invalidDestinationReference
                                  (1),
   invalidOriginatingReference ( 2 ) }
MAP-UserAbortInfo ::= SEQUENCE {
  map-UserAbortChoice CHOICE {
     userSpecificReason
                                           [0] IMPLICIT NULL,
                                          [1] IMPLICIT NULL,
     userResourceLimitation
                                           [2] IMPLICIT ENUMERATED {
      resourceUnavailable
        shortTermResourceLimitation (0), longTermResourceLimitation (1)},
      applicationProcedureCancellation [3] IMPLICIT ENUMERATED {
         handoverCancellation ( 0 ),
         radioChannelRelease
                                      (1),
                                      (2),
         networkPathRelease
         callRelease
                                      (3),
        associatedProcedureFailure (4),
tandemDialogueRelease (5),
remoteOperationsFailure (6)}},
   privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
         SEQUENCE {
                      MAP-EXTENSION .&extensionId ( {
            extType MAP-EXTENSION .&ExtensionType ( {
               ...} { @extid } ) OPTIONAL} OPTIONAL,
                      [1] IMPLICIT SEQUENCE {
      pcs-Extensions
        ... } OPTIONAL,
      ... } OPTIONAL}
MAP-UserAbortChoice ::= CHOICE {
  userSpecificReason
                                       [0] IMPLICIT NULL,
   userResourceLimitation
                                        [1] IMPLICIT NULL,
                                        [2] IMPLICIT ENUMERATED {
   resourceUnavailable
  shortTermResourceLimitation (0),
longTermResourceLimitation (1)},
applicationProcedureCancellation [3] IMPLICIT ENUMERATED {
     handoverCancellation (0), radioChannelRelease (1),
```

```
networkPathRelease (2),
                                      (3),
      callRelease
      associatedProcedureFailure (4),
tandemDialogueRelease (5),
remoteOperationsFailure (6)}
ResourceUnavailableReason ::= ENUMERATED {
   shortTermResourceLimitation ( 0 ),
longTermResourceLimitation ( 1 ) }
ProcedureCancellationReason ::= ENUMERATED {
  handoverCancellation (0),
  radioChannelRelease (1),
networkPathRelease (2),
  callRelease (3),
associatedProcedureFailure (4),
tandemDialogueRelease (5),
remoteOperationsFailure (6)}
MAP-ProviderAbortInfo ::= SEQUENCE {
   abnormalDialogue (0),
invalidPDU (1)},
      invalidPDU
      tensionContainer SEQUENCE {
privateExtensionList [0] IMPLICIT SEQUENCE ( SIZE( 1 .. 10 ) ) OF
   extensionContainer
         SEQUENCE {
            extId
                      MAP-EXTENSION .&extensionId ( {
               ...} ) ,
             extType MAP-EXTENSION .&ExtensionType ( {
               ...} { @extId } ) OPTIONAL} OPTIONAL,
      pcs-Extensions [1] IMPLICIT SEQUENCE {
        ... } OPTIONAL,
      ... } OPTIONAL}
MAP-ProviderAbortReason ::= ENUMERATED {
  abnormalDialogue (0),
   invalidPDU (1) }
END
```

Annex C (informative): Message Segmentation Mechanisms

Various segmentation mechanisms are in use to overcome the problem where a MAP parameter carried in an Invoke, Result (or Error) component is too long to fit into a single SCCP UDT message. These mechanisms are:

C.1 SCCP segmentation

Instead of one UDT message several XUDT messages are used according to

Signalling Connection Control Part, Signalling System no. 7 ITU-T recommendation (07/96) Q.711 to Q.716 ("White Book SCCP").

This mechanism may be used for all MAP messages. If no segmentation mechanism at the TCAP or MAP level is available, this is the only remaining possibility.

This mechanism has no impact on the MAP provider level and above; the MAP provider sees the parameter as being sent in a single segment.

It should be noted that not all SCCP transit nodes (world wide) currently support the transfer of XUDT messages. Therefore XUDT messages may be lost without notice, depending on the route the message takes. The routes which successive messages take between two end points can differ because of load balancing. It is therefore recommended that this mechanism is used only for:

- a) messages which do not cross PLMN boundaries (when the PLMN operator ensures that all SCCP transit nodes within his PLMN support White Book SCCP)
- b) messages with low priority i.e. loss of the message does not result in serious misoperation.

It should be noted that the decision whether or not a message crosses PLMN boundaries needs to be taken at the MAP application level; it is therefore based on the message's operation code rather than on the SCCP called party address, i.e. only messages which never cross PLMN boundaries due to the type of message (SendIdentification, SendRoutingInfo without OR, AnyTimeInterrogation, ...) can be regarded as not crossing PLMN boundaries.

C.2 TCAP segmentation

At the TCAP level the following segmentation mechanisms are available:

C.2.1 Empty Begin

In a dialogue with AC version >1 the first forward message (Begin) must contain a Dialogue Portion. Instead of sending the Dialogue Portion and the Component Portion in the first forward message, an empty Begin (i.e. without a Component Portion) is sent, followed (after successful dialogue establishment) by a Continue message which can carry a longer Component Portion since no Dialogue Portion is present in the second forward message.

C.2.2 Empty Continue

In a dialogue with AC version >1 the first backward message (Continue / End) must contain a Dialogue Portion. Instead of sending the Dialogue Portion and the Component Portion in the first backward message, an empty Continue (i.e. without a Component Portion) is sent, followed by a Continue/End message which can carry a longer Component Portion since no Dialogue Portion is present in the second backward message.

C.2.3 TC-Result-NL

A Result component may be segmented into one or several Result-Not-Last components followed by a Result-Last component. As specified in subclause 15.6.3, the MAP user parameter shall be split so that each segment is compatible with the type defined for the parameter of the result of the associated operation.

Note that this segmentation mechanism runs the risk that the message carrying the Result-Last component arrives before the message carrying a Result-Not-Last component which results in failure. The use of SCCP class 1 "Sequence guaranteed", which raises the chance of in sequence delivery, is recommended.

C.3 MAP Segmentation

At the MAP level the following segmentation mechanisms are available:

C.3.1 Invoke without explicit indication

An Invoke component may be segmented into several Invoke components. These may be sent in burst mode (in which case SCCP class 1 is recommended) or in acknowledged mode. The receiving node does not get an indication of whether or not more segments will be received, so it must not close the dialogue. The MAP user parameter shall be split so that each segment is compatible with the type defined for the parameter of the invoke of the associated operation.

C.3.2 Invoke with explicit indication

An Invoke component may be segmented into several Invoke components sent in acknowledged mode. Each component contains at the MAP level an indication of whether or not subsequent components will follow. The receiving node terminates the dialogue when the last component is received. The MAP user parameter shall be split so that each segment is compatible with the type defined for the parameter of the invoke of the associated operation.

C.3.3 Result

A Result (last) component may be segmented into several Result (last) components sent in acknowledged mode where a new (empty) Invoke component serves as an acknowledgment. The last segment is not acknowledged. The MAP user parameter shall be split so that each segment is compatible with the type defined for the parameter of the result of the associated operation.

The following tables show the applicability of the mechanisms described above:

AC Version 4:

Parameter	SCCP-	Empty Begin Empty		TC-Result-NL	Invoke without	Invoke with	Result
	segmentation		Continue		indication	indication	
ResumeCallHandlingArg	allowed	not allowed	n.a.	n.a.	not allowed	recommended	n.a.

AC Version 3:

Parameter	SCCP- segmentation	Empty Begin	Empty Continue	TC-Result-NL	Invoke without indication	Invoke with indication	Result
InsertSubscriberDataArg	risky	not allowed	n.a.	n.a.	recommended	n.a.	n.a.
SendIdentificationRes	allowed	n.a.	not allowed	not allowed	n.a.	n.a.	recommended
PrepareHO-Arg	allowed	not allowed	n.a.	n.a.	not allowed	n.a.	n.a.
PrepareHO-Res	allowed	n.a.	recommended	not recommended	n.a.	n.a.	not allowed
ProcessAccessSignalling-Arg	allowed	n.a.	n.a.	n.a.	not allowed	n.a.	n.a.
ForwardAccessSignalling-Arg	allowed	n.a.	n.a.	n.a.	not allowed	n.a.	n.a.
PrepareSubsequentHO-Arg	allowed	n.a.	n.a.	n.a.	not allowed	n.a.	n.a.
PrepareSubsequentHO-Res	allowed	n.a.	n.a	not recommended	n.a.	n.a.	not allowed
SendAuthenticationInfoRes	risky	n.a.	not allowed	not allowed	n.a.	n.a.	recommended
ProvideSubscriberInfoRes	allowed	n.a.	not allowed	not recommended	n.a.	n.a.	not allowed
AnyTimeInterrogationRes	allowed	n.a.	not allowed	not recommended	n.a.	n.a.	not allowed
AnyTimeModificationRes	allowed	n.a.	not allowed	recommended	n.a.	n.a.	not allowed
AnyTimeSubscriptionInterrogationRes	allowed	n.a.	not allowed	recommended	n.a.	n.a.	not allowed
noteSubscriberDataModifiedArg	allowed	not allowed	n.a.	n.a.	not allowed	recommended	n.a.
SendRoutingInfoRes	allowed	n.a.	not allowed	recommended	n.a.	n.a.	not allowed
MO-ForwardSM-Arg	risky	recommended	n.a.	n.a.	not allowed	n.a.	n.a.
MT-ForwardSM-Arg	risky	recommended	n.a.	n.a.	not allowed	n.a.	n.a.

1293 AC Version 2:

Parameter	SCCP- segmentation	Empty Begin	Empty Continue	TC-Result-NL	Invoke without indication	Invoke with indication	Result
InsertSubscriberDataArg	risky	not allowed	not allowed	n.a.	recommended	n.a.	n.a.
SendIdentificationRes	allowed	n.a.	not allowed	not recommended	n.a.	n.a.	not allowed
SendAuthenticationInfoRes	risky	n.a.	not allowed	not recommended	n.a.	n.a.	not allowed
ForwardSM-Arg	risky	recommended	n.a.	n.a.	not allowed	n.a.	n.a.
PrepareHO-Res	allowed	n.a.	recommended	not recommended	n.a.	n.a.	not allowed

AC Version 1:

Parameter	SCCP- segmentation	Empty Begin	Empty Continue	TC-Result-NL	Invoke without indication	Invoke with indication	Result
InsertSubscriberDataArg	risky	n.a.	n.a.	n.a.	recommended	n.a.	n.a.
SentParameterList	risky	n.a.	n.a.	recommended	n.a.	n.a.	not allowed

In the tables above the keywords "recommended", "allowed", "risky", "not recommended", "not allowed" and "n.a." are used as follows:

"recommended"

indicates that the normative part of this specification explicitly specifies the use of this mechanism for the parameter in question;

"allowed"

indicates that the normative part of this specification allows the use of this mechanism for the sending node and mandates support of this mechanism for the receiving node;

"risky"

indicates that the mechanism is "allowed". However, the use of this mechanism for the parameter in question may result in serious misoperation because SCCP transit nodes are not guaranteed to support XUDT messages.

"not recommended"

indicates that the normative part of this specification does not explicitly specify the use of this mechanism for the parameter in question.

"not allowed"

indicates that the normative part of this specification implicitly prohibits the use of this mechanism for the parameter in question.

"n.a."

indicates that the mechanism is not applicable for the parameter in question.

Annex D (informative): Void

Annex E (informative): Change History

SMG#	TDoc	SPEC	VERS	CR	REV	PHAS E	CAT	SUBJECT	NEW_VERS	WORKITEM
04	N2-99227	29.002	3.0.0	A002	3	R98	Α	Use of E interface	3.1.0	
04	N2-99578	29.002	3.0.0	A003		R98	В	Introduction of TIF-CSI for Call Deflection	3.1.0	
04	N2-99233	29.002	3.0.0	A004		R98	Α	Clarification in ASN.1 encoding of O-CSI and T-CSI	3.1.0	
04	N2-99269	29.002	3.0.0	A005		R98	С	Introduction of MSISDN in USSD operation	3.1.0	
04	N2-99650	29.002	3.0.0	A006		R98	Α	Modification of the O-CSI ASN.1 structure	3.1.0	
04	N2-99250	29.002	3.0.0	A007		R98	Α	Adding of MAP_DELIMITER_req to the Status report operation	3.1.0	
04	N2-99628	29.002	3.0.0	A008		R98	Α	Correction to the Purge MS "Detailed procedure in the HLR"	3.1.0	
04	N2-99677	29.002	3.0.0	A009		R98	Α	Adding of MNP-indicator to the SRI ack	3.1.0	
04	N2-99228	29.002	3.0.0	A010		R98	F	New subscription options for call forwarding	3.1.0	
04	N2-99585	29.002	3.0.0	A011		R98	С	Adding the support of ANSI SCCP which is required in North America (World Zone 1)	3.1.0	
04	N2-99515	29.002	3.0.0	A012		R98	Α	Introduction of 3-digit MNCs correction	3.1.0	
04	N2-99520	29.002	3.0.0	A013		R98	F	Export of NAEA-CIC	3.1.0	
04	N2-99548	29.002	3.0.0	A014		R98	D	Clarification to text to identify how the LSA data relevant in the current VPLMN can be determined	3.1.0	
04	3C99-468	29.002	3.0.0	A015		R97	F	Alignment with 04.80	3.1.0	
04	N2-99519	29.002	3.0.0	A016		R98	Α	VBS data	3.1.0	
04	N2-99461	29.002	3.0.0	A017		R98	F	Introduction of Data Missing error to the Resume Call Handling	3.1.0	
04	N2-99583	29.002	3.0.0	A018		R97	F	Removal of 3-digit MNCs	3.1.0	
04	N2-99676	29.002	3.0.0	A019		R98	A	Corrections of mapping from MAP service to TC service	3.1.0	
04	3C99-206	29.002	3.0.0	A020		R98	В	Introduction of UUS service to Resume Call Handling	3.1.0	
05	N2-99906	29.002	3.1.0	021		R99	A	Clarification on VLR CAMEL Subscription Info	3.2.0	CAMEL Phase 2
05	N2-99908	29.002	3.1.0	022		R99	Α	Clarification on DestinationNumberCriteria	3.2.0	CAMEL Phase 2
05	N2-99910	29.002	3.1.0	023		R99	Α	Removal of TDP-Criteria from RCH	3.2.0	CAMEL Phase 2
05	N2-99934	29.002	3.1.0	025		R99	A	Various corrections related to GGSN-HLR Interface.	3.2.0	GPRS
05	N2-99936	29.002	3.1.0	034		R99	A	Update Location handling for GPRS- only subscription	3.2.0	GPRS
05	N2-99938	29.002	3.1.0	035		R99	A	Correction of OP & AC definitions for NoteMS-PresentForGPRS	3.2.0	GPRS
05	N2-99952	29.002	3.1.0	036		R99	A	Removal of redundant information from RCH	3.2.0	TEI
05 05	N2-99956 N2-99964	29.002	3.1.0	026 024	1	R99 R99	A	OR capability IE in PRN GMSC-CAMEL phase 2 support IE in PRN	3.2.0 3.2.0	CAMEL Phase 2
05	N2-99A19	29.002	3.1.0	028		R99	Α	Alignment of 29.002 with 02.67	3.2.0	eMLPP
05	N2-99A45	29.002	3.1.0	029	1	R99	В	Non-CAMEL IST implementation	3.2.0	IST
05	N2-99B57	29.002	3.1.0	027	2	R99	В	Addition of the information elements and the ASN.1 definitions for Prepaging	3.2.0	Pre-Paging
05	N2-99C27	29.002	3.1.0	042		R99	Α	Clarification on 'Supported CAMEL Phases' in ISD ack	3.2.0	CAMEL Phase 2
05	N2-99C78	29.002	3.1.0	044		R99	Α	Editing error correction on VLR capabilities	3.2.0	SoLSA
05	N2-99D06	29.002	3.1.0	043	1	R99	Α	Addition of exception handling to the CancellationType	3.2.0	GPRS
05	N2-99D33	29.002	3.1.0	046		R99	Α	Clarification of LR-REJECT cause corresponding to RoamingRestrictionDueTo UnsupportedFeature	3.2.0	TEI

SMG#	TDoc	SPEC	VERS	CR	REV	PHAS E	CAT	SUBJECT	NEW_VERS	WORKITEM
05	N2-99D35	29.002	3.1.0	047		R99		Clarification of returning the MSISDN in SRIack	3.2.0	MNP
06	N2-99G06	29.002	3.2.0	033	3	R99	С	Introduction of the Super-Charger Concept in TS 29.002	3.3.0	Super Charger
06	N2-99G18	29.002	3.2.0	032	2	R99	С	Introduction of White Book SCCP in MAP	3.3.0	TEI
06	N2-99G50	29.002	3.2.0	070		R99	Α	Addition of GGSN number for the SRIforGPRS	3.3.0	GPRS
06	N2-99J88	29.002	3.2.0	075	1	R99	В	Introduction of Follow Me	3.3.0	Follow Me
06	N2-99K12		3.2.0	077		R99	Α	Use of SSN for GPRS	3.3.0	GPRS USSD & Follow Me
06	N2-99K24 N2-99K52	29.002	3.2.0	069	1	R99 R99	A C	Correction of the USSD procedure in the HLR. MAP Impacts for Location Services	3.3.0	Location Services
								(LCS)		
06	N2-99K58		3.2.0	045	4	R99	В	Authentication Enhancements	3.3.0	Security
06	N2-99K60		3.2.0	050	5	R99	С	QoS-Subscribed field modification	3.3.0	QoS enhancements
06	N2-99L20 N2-99J52	29.002	3.2.0	073	1	R99 R99	C	Introduction of CAMEL Phase 3 in 3GPP TS 29.002 Restructuring of MAP Location	3.3.0	CAMEL Phase 3
00	142-99002	29.002	3.2.0	074		N99		Management Procedures for the Circuit Switched Domain	3.3.0	
06	N2-99J92	29.002	3.2.0	068		R99	В	Update of SDLs to support Super- Charger	3.3.0	Super-Charger
			3.3.0					New version created to fix a CR implementation error	3.3.1	
07	N2B00043 6	29.002	3.3.1	048	5	R99	В	Introduction of Multicall	3.4.0	Multicall
07	N2B00031 9		3.3.1	059	1	R99	В	Alternative solution for ALR	3.4.0	CAMEL phase 3
07	N2B00046 1		3.3.1	063	4	R99	В	MNP Database Mismatch	3.4.0	MNP
07	N2B00037 5	29.002	3.3.1	066	5	R99	В	Addition of the FTN-AddressString	3.4.0	Call Forwarding Enhancements
07	N2B00045 6		3.3.1	079	4	R99	С	Correction of SS Invocation Notification for CCBS	3.4.0	CAMEL Phase 3
07	N2A00002 3		3.3.1	080		R99	F	Corrections to ATSI, ATM, NCSD	3.4.0	CAMEL Phase 3
07	N2B00004 6	29.002	3.3.1	083		R99	Α	Privacy notification/verification for call related privacy class	3.4.0	Location Services (LCS)
07	N2B00014 2	29.002	3.3.1	084	2	R99	В	Addition of CS Allocation/retention priority	3.4.0	QoS enhancements
07	N2B00014 4		3.3.1	086	1	R99	D	Editorial cleanup of 29.002	3.4.0	TEI
07	N2B00010 0		3.3.1	087		R99	Α	Correction of LSA information	3.4.0	SoLSA
07	N2B00006 7		3.3.1	089		R99	F	Security interworking between release 99 and pre-99 MSC/VLRs	3.4.0	Security
07	N2B00011 3	29.002	3.3.1	090	1	R99	В	Improving GPRS charging efficiency	3.4.0	GPRS
07	N2B00012 0		3.3.1	094	2	R99	С	QoS-Subscribed field enhancements	3.4.0	QoS enhancements
07	N2B00032 2 N2B00019		3.3.1	095	1	R99 R99	В	RANAP support on the E-interface UMTS Authentication	3.4.0	Handover Security
07	1 N2B00046		3.3.1	100	5	R99	С	Support of 3G Handover, including	3.4.0	Multicall
07	6 N2B00037	29.002	3.3.1	100	1	R99	В	Multicall Introduction of Service Area	3.4.0	TEI
07	2 N2B00038		3.3.1	102	2	R99	F	Identification Clarification on Authentication Info	3.4.0	Security
07	0 N2B00033		3.3.1	103	1	R99	В	Retrieval Addition of UMTS security to MAP B	3.4.0	Security
07	0 N2B00024	29.002	3.3.1	104		R99	F	interface Re-Synchronisation Info	3.4.0	UMTS Security
07	4 N2B00032	29.002	3.3.1	105	1	R99	С	Introduction of additional service	3.4.0	Handover
07	4 N2B00028	29.002	3.3.1	107		R99	D	parameters for inter-system handover Removal of architectural information from clause 4	3.4.0	TEI

SMG#	TDoc	SPEC	VERS	CR	REV	PHAS E	CAT	SUBJECT	NEW_VERS	WORKITEM
07	N2- 000454	29.002	3.3.1	110	1	R99	В	Introduction of Authentication Failure Report	3.4.0	Security
07	N2B00035 7	29.002	3.3.1	111		R99	В	Use of MAP private extensions to implement region-specific requirements	3.4.0	TEI
07	N2B00047 0	29.002	3.3.1	112		R99	Α	Prioritisation of MAP application context related to VGCS/VBS	3.4.0	ASCI Phase 2
07	N2B00047 2	29.002	3.3.1	113		R99	F	Correction of SS-Codes for LCS	3.4.0	LCS
08	N4- 000098	29.002	3.4.0	115	1	R99	F	Minor corrections to CAMEL3 NSDC/ATM/ATSI information flows	3.5.0	CAMEL Phase 3
08	N4- 000094	29.002	3.4.0	117	1	R99	Α	Using DSD to delete CCBS-B from the subscriber	3.5.0	CCBS
08	N4- 000089	29.002	3.4.0	118	1	R99	F	Indication in PRN of support of Long FTNs	3.5.0	CF enhancements
08	N4- 000073	29.002	3.4.0	120	1	R99	F	QoS-Subscribed field enhancements	3.5.0	QoS enhancements
08	N4- 000050	29.002	3.4.0	121		R99	F	Correction of introduction of additional service parameters for inter-system handover	3.5.0	Handover/Relocation
08	N4- 000100	29.002	3.4.0	122	2	R99	С	Proposed information flow on NSDC	3.5.0	CAMEL Phase 3
08	N4- 000321	29.002	3.4.0	124	3	R99	С	CAMEL Subscription Info	3.5.0	CAMEL Phase 3
08	N4- 000068	29.002	3.4.0	125		R99	Α	Clarification to GMLC List definition	3.5.0	LCS
08	N4- 000320	29.002	3.4.0	127	1	R99	F	Optionality of parameters in d-csi and in sms-csi	3.5.0	CAMEL Phase 3
08	N4- 000209	29.002	3.4.0	130		R99	F	Version 3 tags for handover messages	3.5.0	Handover
08	N4- 000211	29.002	3.4.0	132		R99	Α	Correction of version handling at dialogue establishment	3.5.0	TEI
08	N4- 000357	29.002	3.4.0	133	1	R99	F	Various corrections and/or cleanup to 29.002	3.5.0	TEI
08	N4- 000217	29.002	3.4.0	134		R99	Α	Correction of errors in Figure 25.1/1: Macro Receive_Open_Ind	3.5.0	TEI
08	N4- 000326	29.002	3.4.0	135	1	R99	В	Addition of charging characteristics per PDP context	3.5.0	TEI
08	N4- 000264	29.002	3.4.0	138		R99	F	Clarification of SAI-ack segmentation procedure	3.5.0	Security
08	N4- 000392	29.002	3.4.0	139	1	R99	Α	Indication of unsupported position method	3.5.0	LCS
08	N4- 000276	29.002	3.4.0	141		R99	Α	Clarification for ReportSM- DeliveryStatus operation	3.5.0	GPRS
08	N4- 000349	29.002	3.4.0	142	1	R99	С	Addition of a parameter in the subsequent Handover from UMTS to GSM with Multicall	3.5.0	Multicall
08	N4- 000278	29.002	3.4.0	143		R99	D	Editorial correction to MSC-A handover SDLs	3.5.0	Multicall
08	N4- 000378	29.002	3.4.0	144	1	R99	Α	Use of NAM parameter with MAP- INSERT-SUBSCRIBER-DATA service between HLR and SGSN	3.5.0	GPRS
08	N4- 000293	29.002	3.4.0	145		R99	F	Addition of state attributes in Forward group call signalling	3.5.0	ASCI
08	N4- 000294	29.002	3.4.0	146		R99	F	New user error "target cell outside group call area" in MAP Prepare Handover message	3.5.0	ASCI
08	N4- 000374	29.002	3.4.0	149		R99	Α	Correction to the description of MAP-MO-Forward-Short-Message service	3.5.0	TEI
08	N4- 000407	29.002	3.5.0	148	4	R00	В	Changes to MAP for secure transport of MAP messages	4.0.0	Security
08		29.002	4.0.0			R00		Version 4.0.1 created to allow inclusion of automatic update of Annexes A and B and of section 17	4.0.1	
09	N4- 000543	29.002	4.0.1	152	1	R00	F	Clarifications for secure MAP transport	4.1.0	Core Network Security
09	N4- 000539	29.002	4.0.1	153	1	R00	D	Generalization of version handling text in clause 18.2.4	4.1.0	TEI
09	N4- 000491	29.002	4.0.1	158		R00	Α	Deletion of informative Annexe C	4.1.0	TEI
09	N4- 000540	29.002	4.0.1	159		R00	Α	Aligning 29.002 with 25.413 (UTRAN lu Interface RANAP Signalling)	4.1.0	Handover

SMG#	TDoc	SPEC	VERS	CR	REV	PHAS E	CAT	SUBJECT	NEW_VERS	WORKITEM
09	N4- 000541	29.002	4.0.1	160		R00	Α	AUTS and AUTN parameter length	4.1.0	Security
09	N4- 000744	29.002	4.0.1	161	2	R00	Α	Clarification on Authentication Failure Report ack	4.1.0	Security
09	N4- 000666	29.002	4.0.1	163	1	R00	Α	Correction on Location Information	4.1.0	CAMEL phase 3
09	N4- 000777	29.002	4.0.1	174	2	R00	Α	Optionality of parameters in GPRS- CSI	4.1.0	CAMEL phase 3
09	N4- 000788	29.002	4.0.1	176	1	R00	Α	Correction to QoS indication	4.1.0	LCS
09	N4- 000747	29.002	4.0.1	178	1	R00	Α	Clarification of use of Radio Resource Information	4.1.0	Handover
09	N4- 000750	29.002	4.0.1	180	2	R00	Α	Correction to MSC-A handover SDLs	4.1.0	TEI
09	N4- 000736	29.002	4.0.1	182		R00	Α	Removal of LSAldentity from NoteMM- EventArg	4.1.0	CAMEL phase 3
09	N4- 000772	29.002	4.0.1	184		R00	Α	LCS Support for CAMEL Phase 3	4.1.0	LCS
09	N4- 000751	29.002	4.0.1	186	1	R00	Α	Correction to MSC-A handover SDLs	4.1.0	TEI
09	N4- 000779	29.002	4.0.1	188		R00	Α	Clarification for segmentation of D-CSI and SMS-CSI	4.1.0	CAMEL phase 3
10	N4- 000912	29.002	4.0.1	166	3	Rel-4	Α	Corrections and clarifications for USSD procedures on the HLR - gsmSCF interface	4.2.0	USSD
10	N4- 000908	29.002	4.1.0	191	1	Rel-4	A	Corrections of ISD data structure for CAMEL phase 3	4.2.0	CAMEL phase 3
10	N4- 001069	29.002	4.1.0	193	2	Rel-4	Α	USSD Corrections for Follow Me	4.2.0	USSD
10	N4- 001071	29.002	4.1.0	196	1	Rel-4	Α	GSM to 3G Handover: MAP parameter Target Cell ID	4.2.0	Handover
10	N4-	29.002	4.1.0	198		Rel-4	Α	ASN.1 description of targetCellId	4.2.0	Handover
10	000921 N4- 001073	29.002	4.1.0	200	1	Rel-4	Α	IMSI in MAP_PREPARE_HANDOVER	4.2.0	Handover
10	N4- 001076	29.002	4.1.0	208	1	Rel-4	Α	Alignment of the Target RNC-ID	4.2.0	Handover
10	N4- 001089	29.002	4.1.0	211	1	Rel-4	Α	Export of GSN-Address data type	4.2.0	CAMEL phase 3
10	N4- 001095	29.002	4.1.0	212		Rel-4	Α	Transport of long RANAP messages on MAP-E interface	4.2.0	Handover
-	-	29.002	4.2.0	-	-	Rel-4	-	Automatic update of annexes A and B	4.2.1	-
11	N4- 010036	29.002	4.2.1	206	1	Rel-4	Α	Correction to LCS application context	4.3.0	LCS
11	N4- 010276	29.002	4.2.1	215	2	Rel-4	В	Add parameters to ISD and SRI for GPRS to handle ODB for PS	4.3.0	ODB enhancements
11	N4- 010033	29.002	4.2.1	217		Rel-4	Α	Correction to maximum number of RAB's	4.3.0	Multicall
11	N4- 010198	29.002	4.2.1	222	2	Rel-4	В	PS domain support for LCS Release 4	4.3.0	LCS
11	N4- 010058	29.002	4.2.1	224		Rel-4	Α	Failure of Update GPRS Location when HLR is not reachable	4.3.0	GPRS R97
11	N4- 010287	29.002	4.2.1	231	1	Rel-4	В	Extension of call related privacy class for LCS Release 4	4.3.0	LCS
11	N4- 010375	29.002	4.2.1	232	2	Rel4	В	Maximum number of LCS Clients	4.3.0	LCS
11	N4- 010261	29.002	4.2.1	234		Rel-4	В	MAP over IP according to SIGTRAN	4.3.0	SS7IP
11	N4- 010465	29.002	4.2.1	236	1	Rel-4	В	Requesting node type in authentication set request	4.3.0	SEC1-EHCS
11	N4- 010360	29.002	4.2.1	246		Rel-4	А	Adding EXPORT definition for LSAIdentity	4.3.0	Camel 3

SMG#	TDoc	SPEC	VERS	CR	REV	PHAS E	CAT	SUBJECT	NEW_VERS	WORKITEM
11	N4- 010361	29.002	4.2.1	247		Rel-4	A	Removing duplicate parameters from ss-CSI	4.3.0	CAMEL 3
11	N4- 010362	29.002	4.2.1	248		Rel-4	Α	Correction to description of SS- CSI in HLR to VLR information flow	4.3.0	CAMEL 3
11	N4- 010365	29.002	4.2.1	250		Rel-4	Α	GSM to UMTS handover: addition of MAP parameter RNC ID	4.3.0	Handover
11	N4- 010393	29.002	4.2.1	252		Rel-4	Α	Clarification of the use of multicall bearer information	4.3.0	Multicall
11	N4- 010428	29.002	4.2.1	258		Rel-4	Α	Adding EXPORT definition for GeographicalInformation	4.3.0	Camel 3
11	N4- 010446	29.002	4.2.1	260		Rel-4	Α	Failure of Authentication Parameter GPRS when HLR is not reachable	4.3.0	GPRS R97
11	N4- 010484	29.002	4.2.1	262	1	Rel-4	Α	Correction to D-CSI	4.3.0	CAMEL 3
12	N4- 010728	29.002	4.3.0	239	4	Rel-4	Α	Addition of selected UMTS algorithm indication to the handover procedures	4.4.0	Handover
12	N4- 010730	29.002	4.3.0	241	4	Rel-4	А	Addition of allowed GSM algorithms indication to the handover procedures	4.4.0	Handover
12	N4- 010733	29.002	4.3.0	244	4	Rel-4	Α	Addition of allowed UMTS algorithm indication to the handover procedures	4.4.0	Handover
12	N4- 010735	29.002	4.3.0	245	4	Rel-4	Α	Addition of selected GSM algorithm indication to the handover procedures	4.4.0	Handover
12	N4- 010739	29.002	4.3.0	254	2	Rel-4	Α	Addition of radio resource list to the handover procedures	4.4.0	Multicall
12	NP- 010247	29.002	4.3.0	256	3	Rel-4	Α	Addition of GSM channel type and GSM chosen channel indications to handover procedures	4.4.0	Handover
12	N4- 010787	29.002	4.3.0	264	3	Rel-4	Α	Add support in MAP for all shapes defined in 23.032	4.4.0	LCS
12	N4- 010633	29.002	4.3.0	270	1	Rel-4	Α	Correction to description of RNCId parameter	4.4.0	Handover
12	N4- 010635	29.002	4.3.0	272	1	Rel-4	Α	Correction to Encryption Information and Integrity Protection parameters	4.4.0	Handover
12	N4- 010767	29.002	4.3.0	279	3	Rel-4	Α	Essential drawbacks on services due to introduction of Super- Charger function	4.4.0	TEI
12	N4- 010741	29.002	4.3.0	283	1	Rel-4	Α	Introduction of selected Rab-id to the Process Access Signalling operation	4.4.0	Multicall
12	N4- 010673	29.002	4.3.0	285		Rel-4	Α	Mistake in the definition of Authentication Failure Report Application Context	4.4.0	SEC
12	N4- 010551	29.002	4.3.0	266		Rel-4	А	Add support in MAP for Ellipsoid Point	4.4.0	LCS
12	N4- 010778	29.002	4.3.0	168	5	Rel-4	С	Security Header modification	4.4.0	Security
12	N4- 010785	29.002	4.3.0	267	3	Rel-4	С	Additional Parameters in Authentication Failure Report	4.4.0	SEC1 - EHCS
12	N4- 010783	29.002	4.3.0	268	3	Rel-4	F	MS presence notification procedure for LCS	4.4.0	LCS1

SMG#	TDoc	SPEC	VERS	CR	REV	PHAS E	CAT	SUBJECT	NEW_VERS	WORKITEM
12	N4- 010790	29.002	4.3.0	289	2	Rel-4	F	Component level granularity of protection	4.4.0	SEC1
		29.002	4.4.0			Rel-4		Corrupted headers fixed	4.4.1	
13	N4- 010840	29.002	4.4.1	290		Rel-4	F	Clarifications on long forwarded- to numbers	4.5.0	TEI4
13	N4- 010929	29.002	4.4.1	291	1	Rel-4	F	Corrections for Deferred MT-LR	4.5.0	LCS1
13	N4- 010930	29.002	4.4.1	292	2	Rel-4	F	Clarifications on SupportedLCS- CapabilitySets	4.5.0	LCS1
13	N4- 010958	29.002	4.4.1	295	2	Rel4	F	Corrections on the introduction of LCS for PS domain	4.5.0	LCS1
13	N4- 010970	29.002	4.4.1	302	2	Rel-4	F	Additional SGSN related values to Access Type	4.5.0	SEC1-EHCS
13	N4- 010976	29.002	4.4.1	306		Rel-4	Α	Addition of data type definitions to EXPORT statements for the usage in CAP	4.5.0	CAMEL3
13	N4- 011017	29.002	4.4.1	307	2	Rel-4	Α	Minimum MAP application context for intersystem MSC handover from GSM to UMTS	4.5.0	Handover
13	N4- 011019	29.002	4.4.1	309	2	Rel-4	Α	Minimum MAP application context for intersystem MSC handover from UMTS to GSM	4.5.0	Handover
13	N4- 010845	29.002	4.4.1	277	1	Rel4	F	Correction on the SDL of NW initiated USSD operations	4.5.0	TEI
13		29.002	4.4.1			Rel-4		Editorial Clean up	4.5.0	
14	N4- 011031	29.002	4.5.0	313		Rel-4	Α	Clarification on LCS parameters in MAP	4.6.0	LCS1
14	N4- 011043	29.002	4.5.0	314		Rel-4	F	Handling of linked operations in the MAP protocol machine	4.6.0	TEI4
14	N4- 011285	29.002	4.5.0	316		Rel-4	F	Corrections on the SDL diagrams for LCS	4.6.0	LCS1
14	N4- 011198	29.002	4.5.0	318	1	Rel-4	Α	Indication of deletion of CSI in Notify Subscriber Data Change	4.6.0	CAMEL3
14	N4- 011074	29.002	4.5.0	320		Rel-4	А	Correct length of Add- GeographicalInformation	4.6.0	LCS
14	N4- 011091	29.002	4.5.0	322		Rel-4	Α	Clarify encoding of RNC Id	4.6.0	Handover
14	N4- 011094	29.002	4.5.0	324		Rel-4	A	Clarify encoding of RANAP parameters in MAP	4.6.0	Handover
14	N4- 011097	29.002	4.5.0	325		Rel-4	F	Clarifications on long forwarded-to numbers	4.6.0	TEI4
14	N4- 011227	29.002	4.5.0	331	1	Rel-4	Α	Clarification of methodology for maintaining data consistency in Supercharger	4.6.0	TEI
14	N4- 011173	29.002	4.5.0	334		Rel-4	Α	Addition of RAB ID to Prepare Handover procedure	4.6.0	Multicall
14	N4- 011175	29.002	4.5.0	336		Rel-4	Α	Correction to the Allowed GSM Algorithms parameter	4.6.0	Handover
14	N4- 011177	29.002	4.5.0	337	1	Rel-4	F	Correction of references	4.6.0	TEI4
14	N4- 011190	29.002	4.5.0	339		Rel-4	Α	CUG-Info is not exported from 29.002	4.6.0	CAMEL3
14	N4- 011209	29.002	4.5.0	341		Rel-4	Α	Clarification on NSCD when data is withdrawn	4.6.0	CAMEL phase 3
14	N4- 011211	29.002	4.5.0	343		Rel-4	Α	Clarification of sending CAMEL information in stand alone ISD case	4.6.0	CAMEL phase 3
14	N4- 011262	29.002	4.5.0	344		Rel-4	F	Correction of the priority for 'SRI for LCS'	4.6.0	LCS1

SMG#	TDoc	SPEC	VERS	CR	REV	PHAS E	CAT	SUBJECT	NEW_VERS	WORKITEM
14	N4- 011273	29.002	4.5.0	347		Rel-4	Α	ASN.1 correction	4.6.0	CAMEL
14	N4- 011437	29.002	4.5.0	349	2	Rel-4	F	Handling of MNRR in the HLR & SMS-GMSC	4.6.0	TEI4
14	N4- 011433	29.002	4.5.0	354	1	Rel-4	Α	Minimum MAP application context for G2G inter-MSC handover	4.6.0	Handover
14	N4- 011439	29.002	4.5.0	359	2	Rel-4	Α	Alignment of parameter lengths with those prescribed in 08.08	4.6.0	TEI
14	N4- 011423	29.002	4.5.0	360	1	Rel-4	F	Aligning the security header elements with TS33.200	4.6.0	TEI-4
14	N4- 011394	29.002	4.5.0	364		Rel-4	Α	Syntax error in the ATM result and ATSI result	4.6.0	CAMEL phase 3
14	N4- 011381	29.002	4.6.0	355	1	Rel-5	В	LCS Capability Handling for UE"s	5.0.0	TEI5
15	N4- 020300	29.002	5.0.0	368	4	Rel-5	В	Collective CAMEL Phase 4 CR	5.1.0	CAMEL4
15	N4- 020013	29.002	5.0.0	373		Rel-5	Α	Inclusion of complete ODB data in ATSI and NSDC	5.1.0	CAMEL3
15	N4- 020266	29.002	5.0.0	381	2	Rel-5	В	Introduction of the 'Requestor ID'	5.1.0	LCS1
15	N4- 020068	29.002	5.0.0	386		Rel-5	Α	Correction to AC version of gprsLocationInfoRetrievalContext	5.1.0	TEI4
15	N4- 020248	29.002	5.0.0	390	1	Rel-5	Α	Incomplete description of Restore Data parameters	5.1.0	TEI4
15	N4- 020183	29.002	5.0.0	403		Rel-5	Α	Clarification on CODEC-Info	5.1.0	TEI
15	N4- 020250	29.002	5.0.0	407	1	Rel-5	Α	ODB alignment	5.1.0	TEI4
16	N4- 020530	29.002	5.1.0	428	2	Rel-5	Α	LCS: error handling if shape not supported by GMLC	5.2.0	LCS1
16	N4- 020622	29.002	5.1.0	453		Rel-5	Α	Addition of Radio Resource List to the Forward Access Signalling operation	5.2.0	Multicall
16	N4- 020641	29.002	5.1.0	460		Rel-5	Α	Clarification on Resume Call Handling	5.2.0	TEI
16	N4- 020746	29.002	5.1.0	440	2	Rel-5	Α	Clarification on SendAuthenticationInfo	5.2.0	TEI
16	N4- 020750	29.002	5.1.0	446	1	Rel-5	Α	Addition of Service Handover parameters to MAP Handover messages	5.2.0	Handover
16	N4- 020318	29.002	5.1.0	398		Rel-5	С	Check of NAM and Requesting Node Type on receipt of SendAuthenticationInfo	5.2.0	TEI4
16	N4- 020333	29.002	5.1.0	410		Rel-5	Α	Handling the MNRR flag in the HLR & SMS-GMSC	5.2.0	TEI4
16	N4- 020499	29.002	5.1.0	420	1	Rel-5	Α	Clarfication of introducing Session related and unrelated class	5.2.0	LCS1-PS
16	N4- 020511	29.002	5.1.0	430	1	Rel-5	Α	Corrections on the introduction of LCS for PS domain	5.2.0	LCS
16	N4- 020743	29.002	5.1.0	448	1	Rel-5	Α	Corrections in SS-code chapter	5.2.0	TEI
16	N4- 020408	29.002	5.1.0	423		Rel-5	С	Clarification of handling of MT-SMS-TPDU-Type and SMS-TDP	5.2.0	CAMEL4
16	N4- 020410	29.002	5.1.0	425		Rel-5	Α	Clarify conditions to trigger restart of MTLR-Deferred procedure	5.2.0	LCS1
16	N4- 020468	29.002	5.1.0	414	1	Rel-5	F	Corrections to the handling of Any Time Interrogation and Provide Subscriber Info	5.2.0	CAMEL4

SMG#	TDoc	SPEC	VERS	CR	REV	PHAS E	CAT	SUBJECT	NEW_VERS	WORKITEM
16	N4- 020476	29.002	5.1.0	435	1	Rel-5	D	Change PS-connected in PS-PDPactive	5.2.0	CAMEL4
16	N4- 020483	29.002	5.1.0	422	1	Rel-5	F	Triggering of gsmSCF for MT- SMS-CSI	5.2.0	CAMEL4
16	N4- 020485	29.002	5.1.0	408	2	Rel-5	С	Transferring the MS classmark & IMEI to the gsmSCF	5.2.0	CAMEL4
16	N4- 020543	29.002	5.1.0	441		Rel-5	F	Correction of Object Identifiers for ASN.1 modules	5.2.0	TEI
16	N4- 020608	29.002	5.1.0	450		Rel-5	С	Enhancement to LCS in the PS domain	5.2.0	LCS
16	N4- 020623	29.002	5.1.0	454		Rel-5	F	Addition of Location Information GPRS to Note MM Event operation	5.2.0	CAMEL4-NMM
16	N4- 020703	29.002	5.1.0	421	4	Rel-5	В	LCS: Codeword and Service Type	5.2.0	LCS1
16	N4- 020756	29.002	5.1.0	436	2	Rel-5	В	Splitting of CAMEL phase 4	5.2.0	CAMEL4
17	N4- 021001	29.002	5.2.0	437	3	Rel-5	F	Compatible upgrade to ASN.1:1997 of 29.002	5.3.0	TEI
17	NP- 020399	29.002	5.2.0	462	2	Rel-5	F	Introduction of GERAN classmark	5.3.0	TEI
17	N4- 020841	29.002	5.2.0	465		Rel-5	F	Clarification on Call Deflection	5.3.0	Call Deflection
17	N4- 021040	29.002	5.2.0	470	1	Rel-5	F	Correction to the usage of "Roaming not allowed" error	5.3.0	TEI5
17	N4- 021041	29.002	5.2.0	471	1	Rel-5	Α	Clarifications on Send Identification	5.3.0	TEI
17	N4- 021094	29.002	5.2.0	479	2	Rel-5	С	Handling of partial implementations of CAMEL phase 4	5.3.0	CAMEL4
17	N4- 021047	29.002	5.2.0	480		Rel-5	С	Removal of ChargingNotification feature	5.3.0	CAMEL4
17	N4- 020810	29.002	5.2.0	481		Rel-5	В	CR29.002-443 (rel5) on extensions to ATM for CAMEL control of IMS	5.3.0	IMS-CAMEL
17	N4- 020809	29.002	5.2.0	482		Rel-5	В	CR to 29.002 for the support of the MAP Si interface	5.3.0	IMS-CAMEL
18	N4- 021290	29.002	5.3.0	499		Rel-5	Α	Correction to segmentation of O-CSI and T-CSI	5.4.0	CAMEL3
18	N4- 021418	29.002	5.3.0	508		Rel-5	Α	ODB correction	5.4.0	CAMEL3
18	N4- 021563	29.002	5.3.0	511	1	Rel-5	A	Addtion of reference number to deferred location request procedure	5.4.0	LCS1
18	N4- 021573	29.002	5.3.0	516	2	Rel-5	А	Correction to the Service Handover parameters	5.4.0	Multicall
18	N4- 021299	29.002	5.3.0	442	3	Rel-5	F	Description of MT SM delivery via two serving nodes	5.4.0	TEI5
18	N4- 021294	29.002	5.3.0	474	2	Rel-5	F	Correction of handling of MT- SMS in the SGSN	5.4.0	CAMEL4
18	N4- 021124	29.002	5.3.0	475		Rel-5	F	ODB and CB for SMS	5.4.0	TEI5
18	N4- 021153	29.002	5.3.0	486		Rel-5	F	Correction of IMEI check for SGSN	5.4.0	TEI5
18	N4- 021467	29.002	5.3.0	489	5	Rel-5	F	Available codecs list and selected codec indication	5.4.0	TEI5
18	N4- 021194	29.002	5.3.0	490		Rel-5	F	Clarification of the use of Requested CAMEL Subscription Info parameters	5.4.0	CAMEL4

SMG#	TDoc	SPEC	VERS	CR	REV	PHAS E	CAT	SUBJECT	NEW_VERS	WORKITEM
18	N4- 021252	29.002	5.3.0	495		Rel-5	F	Correction to RCH – adding O- CSI trigger criteria	5.4.0	CAMEL4
18	N4- 021264	29.002	5.3.0	496		Rel-5	F	Additional MM-Code for MG-CSI	5.4.0	CAMEL4
18	N4- 021296	29.002	5.3.0	497	1	Rel-5	F	Additional handling of partial implementations of CAMEL phase 4	5.4.0	CAMEL4
18	N4- 021383	29.002	5.3.0	512		Rel-5	F	Correcion of Codeword Handling	5.4.0	LCS1-PS
18	N4- 021443	29.002	5.3.0	513		Rel-5	F	Reference to TS 23.078 in TS 29.002 regarding handling of VMSC address is missing	5.4.0	CAMEL4
18	N4- 021524	29.002	5.3.0	521	1	Rel-5	F	Editorial clean-up	5.4.0	TEI5
18	N4- 021531	29.002	5.3.0	522		Rel-5	F	Introduction of the CHOICE element 'netDetNotReachable' for PS-SubscriberState	5.4.0	CAMEL4
18	N4- 021260	29.002	5.4.0	491	1	Rel-6	В	Addition of LCS Format Indicator to LCS Client ID	6.0.0	LCS2
18	N4- 021504	29.002	5.4.0	517	2	Rel-6	В	Addition of V-GMLC Address to the Update Location and Update GPRS Location requests	6.0.0	LCS2
18	N4- 021567	29.002	5.4.0	518	3	Rel-6	В	Addition of V-GMLC and H-GMLC Addresses to the Send Routing Info for LCS response	6.0.0	LCS2
18-	N4- 021506	29.002	5.4.0	519	2	Rel-6	В	Addition of PPR Address to the Send Routing Info for LCS response	6.0.0	LCS2
19	N4- 030234	29.002	6.0.0	509	3	Rel-6	С	Introduction of Call Barring for SMS in PS domain	6.1.0	TEI6
19	N4- 030325	29.002	6.0.0	524	3	Rel-6	Α	Clean-up of SMS procedures chapter	6.1.0	TEI5
19	NP- 030068	29.002	6.0.0	545	2	Rel-6	А	Correction to interactions between CAMEL control of MO SMS and barring	6.1.0	CAMEL3
19	N4- 030061	29.002	6.0.0	526		Rel-6	F	Incrementing ASN.1 module versions	6.1.0	TEI6
19	N4- 030063	29.002	6.0.0	528		Rel-6	Α	LCS diagnostic alignment	6.1.0	LCS1
19	N4- 030054	29.002	6.0.0	529		Rel-6	F	Addition of LCS Capability Set 4	6.1.0	LCS2
19	N4- 030301	29.002	6.0.0	533	1	Rel-6	Α	Correction to the definitions of Radio Resource List and BSSMAP Service Handover List	6.1.0	Multicall
19	N4- 030305	29.002	6.0.0	541	2	Rel-6	А	Handover of Group Calls where MSC-B has bearer established	6.1.0	TEI
19	N4- 030287	29.002	6.0.0	551	1	Rel-6	Α	Change of SS-Code List description for Insert Subscriber Data	6.1.0	TEI
19	N4- 030289	29.002	6.0.0	559	1	Rel-6	Α	Missing of 'Continue Monitoring message' in SDL 21.7_3.2	6.1.0	TEI5
19	N4- 030297	29.002	6.0.0	563	1	Rel-6	Α	Alignment of TS 29.002 with TS 23.107 regarding QoS subscribed data	6.1.0	TEI5
19	N4- 030222	29.002	6.0.0	566	1	Rel-6	F	Introduction of MSC Number as a new parameter in MAP-SEND-IDENTIFICATION operation	6.1.0	LCS2
20	N4- 030692	29.002	6.1.0	536	2	Rel-6	Α	Additional SGSN Related Access Type – Detach	6.2.0	SEC1-EHCS

SMG#	TDoc	SPEC	VERS	CR	REV	PHAS E	CAT	SUBJECT	NEW_VERS	WORKITEM
20	N4- 030658	29.002	6.1.0	568	4	Rel-6	A	Addition of Positioning Data IE to Provide Subscriber Location and Send Location Report	6.2.0	LCS
20	N4- 030638	29.002	6.1.0	574	1	Rel-6	F	Provision of SDL diagrams and removal of redundant text in chapter 25	6.2.0	TEI6
20	N4- 030713	29.002	6.1.0	595	2	Rel-6	А	Removal of redundant text from 29.002 Chapter 23	6.2.0	TEI5
20	N4- 030439	29.002	6.1.0	599		Rel-6	Α	LCS Client external ID	6.2.0	LCS
20	N4- 030682	29.002	6.1.0	607	1	Rel-6	F	Provision of SDL diagrams and removal of redundant text in chapter 22	6.2.0	TEI5
20	N4- 030608	29.002	6.1.0	608	1	Rel-6	В	Addition of LCS capability sets to MAP_SRI_for_LCS response	6.2.0	LCS2
20	N4- 030647	29.002	6.1.0	612	1	Rel-6	Α	Enhancement of the CheckIMEI operation to retrieve the BMUEF	6.2.0	Late UE
20	N4- 030678	29.002	6.1.0	619	1	Rel-6	A	Correction to naming of PRN parameter	6.2.0	CAMEL4
20	N4- 030609	29.002	6.1.0	624	1	Rel-6	F	Addition of Privacy Check Related Action to Provide Subscriber Location request	6.2.0	LCS2
20	N4- 030642	29.002	6.1.0	610	1	Rel-6	Α	Transfer of UE-specific behaviour bitmap at handover	6.2.0	Late UE
20	N4- 030601	29.002	6.1.0	633		Rel-6	Α	Missing SMSs over MSC even if the MS is capable of such sending	6.2.0	TEI5
21	N4- 031043	29.002	6.2.0	584	2	Rel-6	Α	Correction to MAP Process Secure_MAP_DSM SDLs	6.3.0	MAP Security
21	N4- 031053	29.002	6.2.0	664	1	Rel-6	Α	Correction of encoding description of Group-Id	6.3.0	ASCI
21	N4- 030828	29.002	6.2.0	657		Rel-6	Α	Reduce maximum length of 'LCS Requestor ID' and 'LCS Codeword'.	6.3.0	LCS2
21	N4- 030922	29.002	6.2.0	647	1	Rel-6	Α	UESBI -IU format	6.3.0	LATE-UE
21	N4- 031069	29.002	6.2.0	616	3	Rel-6	Α	Incorrect Charging with MNP	6.3.0	CAMEL4
21	N4- 031057	29.002	6.2.0	660	2	Rel-6	Α	Notification of the 2 nd BSG in case of Late CF with OR	6.3.0	SCUDIF
21	N4- 031059	29.002	6.2.0	614	3	Rel-6	Α	HLR Interrogation for SCUDIF calls	6.3.0	SCUDIF
21	N4- 030785	29.002	6.2.0	644		Rel-6	D	Removal of tables in section 7.6	6.3.0	TEI6
21	N4- 030806	29.002	6.2.0	649		Rel-6	F	Correction of References	6.3.0	TEI
21	N4- 030815	29.002	6.2.0	648		Rel-6	D	Correction of wrong AC name in the table in 17.1.6	6.3.0	TEI6
21	N4- 030824	29.002	6.2.0	654		Rel-6	В	New LCS Service Types	6.3.0	LCS
21	N4- 030951	29.002	6.2.0	671		Rel-6	D	SS-Barring Category	6.3.0	TEI
21	N4- 031006	29.002	6.2.0	650	1	Rel-6	F	Add SGSN, GGSN, GMLC, gsmSCF, NPLR and AuC to network resource parameter	6.3.0	TEI6
21	N4- 0301038	29.002	6.2.0	645	1	Rel-6	В	Introduction of North American Interim Location Based Routing of Emergency Call	6.3.0	LCS2
21	N4- 031065	29.002	6.2.0	674		Rel-6	F	Positioning Data for UTRAN LCS	6.3.0	LCS2

SMG#	TDoc	SPEC	VERS	CR	REV	PHAS E	CAT	SUBJECT	NEW_VERS	WORKITEM
21	N4- 030953	29.002	6.2.0	637	1	Rel-6	A	Provision of SDL diagrams and removal of redundant text in chapter 19	6.3.0	TEI5
21	N4- 030745	29.002	6.2.0	639		Rel-6	Α	Provision of SDL diagrams and removal of redundant text in chapter 20	6.3.0	TEI5
21	N4- 030747	29.002	6.2.0	641		Rel-6	Α	Provision of SDL diagrams and removal of redundant text in chapter 21	6.3.0	TEI5
21	N4- 030748	29.002	6.2.0	642		Rel-6	F	Removal of SIWF description	6.3.0	TEI6
21	N4- 030749	29.002	6.2.0	643		Rel-6	D	Deletion of redundant Annex D	6.3.0	TEI6
22	N4- 031098	29.002	6.3.0	677		Rel-6	В	Enhancements for the Partial Implementation for "Change of position procedure armed with criteria"	6.4.0	TEI6
22	N4- 031135	29.002	6.3.0	687		Rel-6	В	Collective CR for Rel-6 Enhanced Dialled Services	6.4.0	EDCAMEL
22	N4- 031274	29.002	6.3.0	648	2	Rel-6	D	Message Segmentation Mechanisms	6.4.0	TEI6
22	N4- 031315	29.002	6.3.0	703		Rel-6	В	Addition of requesting PLMN-ID to Send Authentication Info Request	6.4.0	TEI6
22	N4- 031372	29.002	6.3.0	680	2	Rel-6	F	Addition of CGI to LCS procedures	6.4.0	LCS2
22	N4- 031373	29.002	6.3.0	696	2	Rel-6	F	Include v-gmlc parameter in RESTORE DATA MAP message	6.4.0	LCS2
22	N4- 031365	29.002	6.3.0	702	2	Rel-6	В	Deferred MT-LR Area Event	6.4.0	LCS2
22	N4- 031132	29.002	6.3.0	686		Rel-6	Α	More spare bits for CAMEL4 enhancements	6.4.0	CAMEL4
22	N4- 031163	29.002	6.3.0	692		Rel-6	Α	Clarification on D-CSI segmentation	6.4.0	CAMEL4
22	N4- 031342	29.002	6.3.0	676	2	Rel-6	Α	MNP correction for prepaid charging	6.4.0	MNP
22	N4- 031338	29.002	6.3.0	695	1	Rel-6	Α	Remove reduntant option for retrieval of routeing information in figure 21.2.3	6.4.0	TEI5
22	N4- 031108	29.002	6.3.0	679		Rel-6	F	Modification of description for conditions on inclusion of Positioning Data	6.4.0	LCS2
22	N4- 031317	29.002	6.3.0	689	2	Rel-6	Α	HSDPA impacts to MAP	6.4.0	HSDPA
22	NP- 030533	29.002	6.3.0	704		Rel-6	F	EXPORT data types to CAP (Change of position armed with criteria)	6.4.0	TEI6
23	N4- 040310	29.002	6.4.0	668	3	Rel-6	А	Codec Modification/ Mid-Call Codec Negotiation after Inter- MSC Relocation	6.5.0	OoBTC
23	N4- 040193	29.002	6.4.0	670	2	Rel-6	A	Correction of Inter-MSC SRSN Relocation procedure	6.5.0	OoBTC
23	N4- 040249	29.002	6.4.0	701	3	Rel-6	В	Introduction of Presence Stage 3 (Ph, Pc and Pg) to the MAP interface	6.5.0	PRESNC
23	N4- 040333	29.002	6.4.0	708	2	Rel-6	F	Correction to Insert Subscriber Data message for LCS SS	6.5.0	LCS
23	N4- 040328	29.002	6.4.0	709	1	Rel-6	F	SCCP segmentation for Inter PLMN MAP message	6.5.0	TEI6

SMG#	TDoc	SPEC	VERS	CR	REV	PHAS E	CAT	SUBJECT	NEW_VERS	WORKITEM
23	N4- 040327	29.002	6.4.0	711	2	Rel-6	F	Inclusion of UTRAN Positioning Data parameter	6.5.0	LCS2
23	N4- 040284	29.002	6.4.0	717	1	Rel-6	В	Include administrative restriction subscription parameter	6.5.0	TEI6
23	N4- 040340	29.002	6.4.0	720	2	Rel-6	Α	Add new Unavailability cause for SCUDIF	6.5.0	SCUDIF
23	N4- 040171	29.002	6.4.0	721		Rel-6	F	CR implemented by fault	6.5.0	TEI6
23	N4- 040182	29.002	6.4.0	724		Rel-6	F	Removal of R-GMLC Address	6.5.0	LCS2
23	N4- 040322	29.002	6.4.0	725	1	Rel-6	В	MO-LR Service Identity support	6.5.0	LCS2
23	N4- 040267	29.002	6.4.0	726	1	Rel-6	В	CAMEL4 SCUDIF notification during active call for prepay	6.5.0	SCCAMEL
24	N4- 040520	29.002	6.5.0	731		Rel-6	F	Introduction of North American Interim Location Based Routing of Emergency Call	6.6.0	LCS2
24	N4- 040585	29.002	6.5.0	735		Rel-6	F	Modify IMEI parameter usage definition in MAP-PSL and MAP-SLR	6.6.0	TEI6
24	N4- 040600	29.002	6.5.0	736		Rel-6	F	Addition of SAI-Present indication to the LCS procedures	6.6.0	LCS2
24	N4- 040601	29.002	6.5.0	737		Rel-6	F	Clarification on the use of MSISDN parameter for Follow Me functionality	6.6.0	TAI6
24	N4-04732	29.002	6.5.0	734	1	Rel-6	F	Add Additional V-GMLC parameter in MAP-SRI-INFO-FOR-LCS	6.6.0	LCS2
24	N4- 040736	29.002	6.5.0	718	6	Rel-6	В	Addition of IMEISV to Update Location Procedure for ADD function	6.6.0	TEI6
25	N4- 040929	29.002	6.6.0	739		Rel-6	В	Export of UU-Data data type	6.7.0	TEI6
25	N4- 041021	29.002	6.6.0	743		Rel-6	D	Wrong SDL flow page implemented	6.7.0	TEI6
25	N4- 041128	29.002	6.6.0	732	2	Rel-6	В	Pre-Paging Resource Optimization	6.7.0	TEI6
26	N4- 041272	29.002	6.7.0	747		Rel-6	F	Incorrect Implementation of CR 731	6.8.0	LCS2
26	N4- 041477	29.002	6.7.0	752		Rel-6	F	Correction to the service response parameters of ATI	6.8.0	TEI6
26	N4- 041662	29.002	6.7.0	746	1	Rel-6	В	Introducing VGCS/VBS ciphering	6.8.0	SECGKYV
26	N4- 041683	29.002	6.7.0	757	2	Rel-6	F	Clarification about returning authentication data for a subscriber (GSM or UMTS)	6.8.0	TEI6
26	N4- 041684	29.002	6.7.0	748	1	Rel-6	F	LCS Capability Handling for UE"s	6.8.0	TEI6
26	N4- 041685	29.002	6.7.0	753	1	Rel-6	F	Enable NA-ESRD Provision from a GMLC for E911 Location in North America	6.8.0	LCS2
26	N4- 041641	29.002	6.7.0	740	2	Rel-6	В	SMS Fraud countermeasures	6.8.0	TEI6
27	N4- 050212	29.002	6.8.0	749	1	Rel-6	В	Management Based Activation Impacts	6.9.0	OEM-TRACE
27	N4- 050369	29.002	6.8.0	761	1	Rel-6-	F	Addition of LAI to SendIdentification Request	6.9.0	TEI6
27	N4- 050430	29.002	6.8.0	760	1	Rel-6	F	Subscribed Charging Characteristics	6.9.0	TEI6

SMG#	TDoc	SPEC	VERS	CR	REV	PHAS E	CAT	SUBJECT	NEW_VERS	WORKITEM
27	N4- 050444	29.002	6.8.0	759	1	Rel-6	С	Addition of TCAP-Handshake for MO-ForwardSM	6.9.0	TEI6
27	N4- 050446	29.002	6.8.0	745	2	Rel-6	В	Introduction of Hop Counter for Send Identification	6.9.0	TEI6
27	N4- 050463	29.002	6.8.0	738	8	Rel-6	F	Rel-6 trace management additions to trace activation and deactivation procedures	6.9.0	OEM-Trace
27	N4- 050467	29.002	6.8.0	763	2	Rel-6	F	Pseudonym indicator support in MO-LR	6.9.0	LCS2
28	C4- 050737	29.002	6.9.0	769	1	Rel-6	F	Correction to Trace parameters to allow trace at the BM-SC	6.10.0	OAM-Trace
28	C4- 050832	29.002	6.9.0	770	6	Rel-6	F	Full RANAP support of network initiated SCUDIF	6.10.0	TEI6
28	C4- 050895	29.002	6.9.0	766	2	Rel-6	F	Clarification on the use of Access Restriction Data parameter	6.10.0	TEI5
29	C4- 051335	29.002	6.10.0	779	2	Rel-6	F	Correction on misalignment with stage 2 for Location Services	6.11.0	TEI6
30	C4- 051774	29.002	6.11.0	782	2	Rel-6	F	Addition of UMTS Trace parameters to handover procedure	6.12.0	TEI6
								2006-01: Editorial correction to typo in history table.	6.12.1	
31	C4- 060319	29.002	6.12.1	793	1	Rel-6	F	Addition of UMTS Trace parameters to handover procedure	6.13.0	TEI6
32	C4- 060705	29.002	6.13.0	0806	1	Rel-6	Α	Removal of MAPsec material	6.14.0	SEC7-TCAP
34	C4- 061888	29.002	6.14.0	0833	1	Rel-6	F	Add Accuracy Fulfillment Indicator parameter to MAP SLR for deferred MT-LR	6.15.0	LCS2
37	C4- 071280	29.002	6.15.0	0872	1	Rel-6	Α	NPI for the call forwarding to number	6.16.0	TEI4
48	C4- 101233	29.002	6.16.0	0968		Rel-6	F	CR implementation CR 642	6.17.0	TEI6

History

Document history		
V6.8.0	December 2004	Publication
V6.9.0	March 2005	Publication
V6.10.0	June 2005	Publication
V6.11.0	September 2005	Publication
V6.12.1	January 2006	Publication
V6.13.0	March 2006	Publication
V6.14.0	June 2006	Publication
V6.15.0	December 2006	Publication
V6.16.0	October 2007	Publication
V6.17.0	July 2010	Publication